



## Sybase Control Center for Replication

**3.1**

DOCUMENT ID: DC01677-01-0310-02

LAST REVISED: October 2011

Copyright © 2011 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

To order additional documents, U.S. and Canadian customers should call Customer Fulfillment at (800) 685-8225, fax (617) 229-9845.

Customers in other countries with a U.S. license agreement may contact Customer Fulfillment via the above fax number. All other international customers should contact their Sybase subsidiary or local distributor. Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase trademarks can be viewed at the Sybase trademarks page at <http://www.sybase.com/detail?id=1011207>. Sybase and the marks listed are trademarks of Sybase, Inc. ® indicates registration in the United States of America.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP AG in Germany and in several other countries all over the world.

Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

All other company and product names mentioned may be trademarks of the respective companies with which they are associated.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568.

# Contents

<b>About Sybase Control Center for Replication .....</b>	<b>1</b>
New Features in Sybase Control Center for Replication .....	1
Replication Environment .....	3
Compatibility Matrix .....	4
User Interface Overview .....	5
Toolbar Icons .....	6
Status Icons .....	6
Common Display Options .....	7
Style and Syntax Conventions .....	10
Accessibility Features .....	11
Sybase Control Center Accessibility Information .....	12
<b>Get Started .....</b>	<b>13</b>
Quick Start for an Evaluation .....	13
Get Started in a Production Environment .....	20
Launching Sybase Control Center .....	50
Registering the ODBC Driver in Windows .....	51
Starting and Stopping Sybase Control Center in Windows .....	51
Starting and Stopping Sybase Control Center in UNIX .....	53
Configuring Memory Usage .....	56
scc Command .....	59
Logging in to Sybase Control Center .....	62
Logging out of Sybase Control Center .....	63
Setting Up Security .....	63
Security .....	64
Configuring Authentication for Windows .....	65
Configuring a Pluggable Authentication Module (PAM) for UNIX .....	66
Configuring an LDAP Authentication Module .....	67

- Mapping Sybase Control Center Roles to LDAP  
or OS Groups .....76
- Encrypting a Password .....77
- Configuring Ports .....77
- Configuring the E-mail Server .....79
- Configuring the Automatic Logout Timer .....80
- User Authorization .....81
  - Assigning a Role to a Login or a Group .....81
  - Removing a Role from a Login or a Group .....82
  - Adding a Group .....83
  - Removing a Group .....83
  - Adding a Login Account to a Group .....84
  - Removing a Login Account from a Group .....84
  - Adding a Login Account to the System .....85
  - Removing a Login Account from the System .....86
  - Modifying a User Profile .....86
  - Logins, Roles, and Groups .....87
- Configure .....89**
  - Registering a Replication Server, Replication Agent,  
or Mirror Replication Agent .....90
  - Importing Resources for Batch Registration .....91
  - Creating a Perspective .....93
  - Adding a Resource to a Perspective .....93
  - Configuring a Login Account to Monitor Replication .....93
    - Roles or Permissions to Set Up Replication
    - Monitoring Accounts .....94
  - Authenticating a Login Account for a Managed  
Resource .....94
  - Setting Up the Latency Monitoring Process .....95
    - Latency Monitoring Process .....96
  - Setting Up Statistics Collection .....97
    - About Statistics .....98
    - Replication Data Collections .....99
    - Key Performance Indicators and Key  
Performance Areas for Replication .....100

Setting Replication Parameters .....	117
Configuring Replication Server and Replication Agent Parameters .....	117
Configuring Connection Parameters for Replication Server .....	118
Configuring Logical Connection Parameters for Replication Server .....	118
Configuring Route Parameters for Replication Server .....	119
Configuring Adaptive Server RepAgent Thread Parameters .....	120
Configuring Replication Server to Gather Zero Values for Counters .....	120
Creating an Alert .....	121
Replication Alerts .....	124
Alert Types, Severities, and States for Replication .....	129
Alert-Triggered Scripts .....	132
Substitution Parameters for Scripts .....	132
Optional Configuration Steps .....	134
<b>Manage and Monitor .....</b>	<b>137</b>
Heat Chart .....	137
Displaying Resource Availability .....	137
Historical Performance Monitoring .....	138
Graphing Performance Counters .....	138
Manage Sybase Control Center .....	139
Administration Console .....	140
Job Scheduling .....	140
Alerts .....	145
Resources .....	153
Perspectives .....	156
Views .....	157
Repository .....	158
Logging .....	164
Sybase Control Center Console .....	169

Manage and Monitor the Replication Environment .....	172
Availability Monitoring .....	172
Replication Latency .....	187
<b>Troubleshoot Sybase Control Center for Replication ....</b>	<b>191</b>
Collection Job for Adaptive Server Fails .....	191
Data on Dashboards or Charts Is Missing .....	191
No Data Is Returned for Performance Counters	
Collection Job .....	191
Same Data Is Displayed for Two or More Adaptive	
Server Collection Job Executions .....	192
Servers Are Missing in the Topology View .....	192
Servers, Routes, or Connections Display an Unknown	
Status .....	192
Some Connector Lines Do Not Display a Status Icon	
.....	192
Topology Display Is Incorrect When Two Replication	
Servers With the Same Name Are Registered .....	193
Topology View Displays Blank Canvas .....	193
Topology View Takes a Long Time to Display .....	193
Unable to Retrieve Topology Relationship Data or	
Server Objects .....	193
Problems with Basic Sybase Control Center	
Functionality .....	194
Cannot Log In .....	194
Sybase Control Center Fails to Start .....	194
Browser Refresh (F5) Causes Logout .....	194
Alerts Are Not Generated .....	195
Performance Statistics Do Not Cover Enough	
Time .....	195
Resetting the Online Help .....	195
Data Collections Fail to Complete .....	196
Memory Warnings at Startup .....	196
OutOfMemory Errors .....	196
<b>Glossary: Sybase Control Center for Replication .....</b>	<b>199</b>
<b>Index .....</b>	<b>203</b>

# About Sybase Control Center for Replication

Sybase<sup>®</sup> Control Center for Replication is a Web-based solution that replaces Replication Monitoring Services (RMS), a middle-tier server, in monitoring the status and availability of servers in a replication environment.

Sybase Control Center for Replication allows you to monitor and manage large, complex, and geographically dispersed replication environments. It lets you search, sort, and filter servers and component objects to support a larger environment than what the current Replication Manager and Replication Monitoring Services can handle.

Sybase Control Center for Replication provides status information at a glance, using server monitors and a heat chart for displaying the availability or status of a specific server. The server monitors display high-level information, such as server version and platform. The server monitors also display critical performance counters to aid you in troubleshooting replication performance.

To help you control the flow of data and configure replication parameters to improve server performance, Sybase Control Center for Replication provides a quick administration tool that you can easily access through every replication monitor.

In addition to the monitors, Sybase Control Center for Replication provides a topology view that graphically displays the servers, the connections between servers, data flow in the environment, and replication path's sources and targets. Graphs and charts are also available for monitoring performance counters.

You can set user roles to limit access to different features and servers in your environment, therefore providing better data security.

## New Features in Sybase Control Center for Replication

A brief description for each new and enhanced feature, and links to associated topics.

**Table 1. New and enhanced Sybase Control Center for Replication features**

Feature	Topics
Administration Console – manage existing resources and create new ones. Column-based filtering lets you display only the objects you are interested in.	Various topics, including: <i>Browsing and Managing Resources</i> on page 140 <i>Common Display Options</i> on page 7

## About Sybase Control Center for Replication

Feature	Topics
Testing scripts – test the execution of alert-triggered scripts to make sure they work as expected.	<p><i>Creating an Alert</i> on page 121</p> <p><i>Testing an Alert-triggered Script</i> on page 148</p>
Automatic logout – a Sybase Control Center administrator can configure the logout timer to end users' login sessions after a specified period of idleness.	<p><i>Configuring the Automatic Logout Timer</i> on page 80</p> <p><i>Logging out of Sybase Control Center</i> on page 63</p>
Multiple object selection – in the Perspective Resources view, Resource Explorer, and Administration Console, you can select and perform operations on several objects simultaneously.	Various topics, including <i>Unregistering a Resource</i> on page 154
Memory management – use environment variables to control Sybase Control Center's memory use. A new console command, <b>info -m</b> , displays memory usage data.	<p><i>Configuring Memory Usage</i> on page 56</p> <p><i>info Command</i> on page 170</p>
Configure alerts on child objects (such as routes and paths) that are components of managed resources.	<i>Creating an Alert</i> on page 121
Determine the source, target, and the path of the data flow anywhere in the replication environment through replication tracing.	<i>Replication Tracing</i> on page 173
Control data flow and configure replication parameters to resolve performance issues using the Quick Admin tool.	<p><i>Data Flow Control</i> on page 176</p> <p><i>Setting Replication Parameters</i> on page 117</p>
Set up the latency monitoring process to monitor the performance of the replication environment.	<i>Setting Up the Latency Monitoring Process</i> on page 95
Hide connection thread status in a warm standby environment and in an environment with a non-Adaptive Server primary database to avoid providing misleading information.	<i>Hiding Connection Thread Status</i> on page 180
Monitor the RepAgent thread in an Adaptive Server, either single instance or shared disk cluster.	<i>Displaying RepAgent Thread Status in Adaptive Server</i> on page 185
View Sybase IQ servers in the replication topology as part of the replication environment. <hr/> <b>Note:</b> Sybase Control Center for Replication supports Sybase IQ only as a replicate database. <hr/>	<i>Replication Topology</i> on page 173
Monitor additional Replication Server statistics for queues and Data Server Interface (DSI) thread.	<i>Graphing Performance Counters</i> on page 138



Feature	Topics
View information about logical connections associated with a Replication Server.	<i>Displaying Logical Connection Status</i> on page 178
Check the status bar for information of what is currently happening in the monitoring view, as well as warning and error messages. Launch the Sybase Control Center log viewer through the button in the left side of the status bar.	<i>Replication Monitors</i> on page 175
Maximize or minimize a chart view in a replication monitor view.	<i>Replication Monitors</i> on page 175

## Replication Environment

---

A replication environment is a set of servers—including Replication Servers, data servers, and Replication Agents—that participate in replication.

A replication environment does not need to contain all the server types in a replication system domain. It can be a subset of the replication domain identified by the ID Server. In the replication system, one Replication Server® serves as the ID Server. The ID Server assigns unique ID numbers to every Replication Server and database in the system. The ID Server also maintains version information for the system.

These are the servers that you can monitor in your Sybase Control Center replication environment:

- **Data Server**— a database within a data server may act as the source (primary database) of transaction data or may be the destination (replicate or standby database) of transaction data.
- **Replication Agent™ for Adaptive Server® Enterprise (ASE)** – is embedded within an Adaptive Server Enterprise and is called RepAgent Thread. The RepAgent Thread reads the transaction data from the primary database transaction log and sends it to Replication Server for distribution to the replicate databases.
- **Replication Server** – receives the replicated transaction data from a replication agent or another Replication Server, converts it into SQL, and applies the SQL to the replicate or standby databases. Replication Server delivers operational data across complex and broadly distributed data-infrastructures in near real-time. The primary and replicate databases can be Sybase or non-Sybase data servers.
- **Replication Agent** – reads the primary database transactions from database transaction logs, then sends those transactions to Replication Server for distribution to the replicate databases. Replication Agents allow non-Sybase data servers to act as the primary data servers in a replication system based on Sybase replication technology.
- **Mirror Replication Agent** – a component in a Mirror Activator disaster recovery environment and, in conjunction with a storage replication system, reads the primary

## About Sybase Control Center for Replication

database transactions from mirror log devices, then sends those transactions to Replication Server for distribution to the standby databases. The Mirror Activator provides an integrated disaster recovery solution with:

- Standby databases protected from disk corruption (by logical, not literal, replication).
- Synchronous replication, with zero data loss and guaranteed data integrity (transaction consistency).
- Complete coverage for databases, as well as non-database systems.
- **Sybase IQ** – a highly optimized analytics server that works with diverse data, including unstructured data and different data sources. It serves as a replicate database in the replication environment.

The replication environment also includes:

- **Components** – are objects in a server in a replication environment. Examples of components in a Replication Server are connections, routes, and queues.
- **Replication path** – is the set of servers through which transactions pass when moving from the primary to the replicate database.

### See also

- *Data Flow Control* on page 176
- *Replication Servers* on page 177
- *Replication Agents* on page 184
- *Replication Paths* on page 187
- *Compatibility Matrix* on page 4

## Compatibility Matrix

---

Know the version of the replication environment servers that are compatible with Sybase Control Center.

Server	Version
Replication Server	12.6 or later
Replication Agent	15.0 or later
Mirror Replication Agent	15.0 or later

Server	Version
Adaptive Server Enterprise	15.0.2 or later for Sybase Control Center for Adaptive Server, which offers full monitoring capabilities.  15.0.3 or later for Adaptive Server Cluster Edition monitoring.  12.5.4 or later for Sybase Control Center for Replication, which monitors only the RepAgent threads in the registered Adaptive Server.
Sybase IQ	monitoring: 15.1 ESD #2.1 and later  administration: 15.3 and later


**See also**

- *Replication Environment* on page 3
- *Data Flow Control* on page 176
- *Replication Servers* on page 177
- *Replication Agents* on page 184
- *Replication Paths* on page 187
- *Resources* on page 153
- *Registering a Replication Server, Replication Agent, or Mirror Replication Agent* on page 90

## User Interface Overview

This illustration labels important elements of the Sybase Control Center user interface so you can identify them when they appear in other help topics.










**Figure 1: Sybase Control Center User Interface**



## Toolbar Icons

Describes the icons in the Sybase Control Center toolbar for launching and managing views.

**Table 2. Toolbar icons**







Icon	Name	Description
	<b>Show/Hide Perspective Resources View</b>	Displays or minimizes the Perspective Resources view, which lists registered resources in this perspective.
	<b>Launch Resource Explorer</b>	Opens the resource explorer, which lists reachable resources (both registered and unregistered).
	<b>Launch Heat Chart</b>	Opens the perspective heat chart, which gives a status overview of the registered resources in this perspective.
	<b>Close All Open Views</b>	Closes all open and minimized views.
	<b>Minimize All Views</b>	Minimizes all open views.
	<b>Restore All Minimized Views</b>	Returns all minimized views to their original size.
	<b>Cascade All Open Views</b>	Arranges open views to overlap each other.
	<b>Tile All Open Views Vertically</b>	Arranges open views in a vertical manner.
	<b>Tile All Open Views Horizontally</b>	Arranges open views in a horizontal manner.

## Status Icons

Sybase Control Center uses icons to indicate the status of resources and key performance indicators (KPIs).




Resource status icons indicate the condition of each resource in the heat chart. In addition, they are used as badges (small overlays) on server icons in both the heat chart and the Perspective Resources view. The Perspective Resources view also has a Status column that displays the same status as the badge in English text.

**Table 3. Resource status icons: Perspective Resources view and heat chart**

Icon	Status	Description
	Running	Resource is up and running
	Pending	State is changing—check again
	Stopped	Resource has been shut down
	Warning	Resource has encountered a potentially harmful situation
	Error	Resource has encountered a serious problem
	Unknown	Resource is unreachable—state cannot be determined

The heat chart uses KPI status icons to indicate the health of the KPIs it displays.

**Table 4. KPI status icons: heat chart**

Icon	Status	Description
	Normal	Value of performance indicator is within the normal range
	Warning	Value of performance indicator is in the warning range
	Critical	Value of performance indicator is in the critical range

## Common Display Options

Use data display features to view resource status and to sort, search by resource name and type, and rearrange status information.

### *Column Options*












The Administration Console, Perspective Resources view, Resource Explorer, Alert Monitor, heat chart, and other views in Sybase Control Center—including those in product modules—use a tabular grid format to display information about managed resources. You can use options provided by the grid format to sort and organize displayed data.

**Table 5. Column Sorting Options**

Sorting Option	Description
Simple column-based sorting	Click a column name to sort the table based on that column in ascending or descending order. The arrow in the column's sorting tab (to the right of the column name) points up when data is sorted in ascending order or down when data is sorted in descending order.
Reversing the order of a column-based sort	Click a column's sorting tab to reverse its sort from ascending to descending order or vice versa.
Nested sorting based on multiple columns	Click the column name for the primary sort. For subsidiary sorts, click the column's sorting tab. Choose the columns for subsidiary sorts in the order you want to apply them. After you click a sorting tab, it displays its sorting level (1 for the primary sort, 2 for the secondary sort, and so on).
Rearranging columns	Move columns by dragging and dropping them.

The figure below shows a table of servers sorted first by resource type; within type by software version; and within version by server name. The Type and Name columns sort in ascending order and the Version column sorts in descending order.

**Figure 2: Resources sorted by type, version, and name**

	Name	3 ▲	Type	1 ▲	Version	2 ▼
	mira8		ASE Server		15.0.2	
	mira9		ASE Server		15.0.2	
	LondonDR		ASE Server, Replication Only		12.5	
	LondonEx		ASE Server, Replication Only		12.5	
	NYEx		ASE Server, Replication Only		12.5	
	lint10dev_mpx		IQ Multiplex		15.3.0.6038	
	lint10dev_mpx		IQ Multiplex		15.3.0.6038	
	sun7bar_iqdemo		IQ Multiplex		15.3.0.6035	
	lamd6supt_r2		IQ Server		15.3.0.6038	
	lint10dev_cn		IQ Server		15.3.0.6038	
	lint10dev_r1		IQ Server		15.3.0.6038	


### *Filter by Column*

The Administration Console provides a filtering field at the top of each column. Enter a filtering term to narrow the range of objects displayed. For example:

- Enter the name of a server at the top of the Name column to display only that server, database, group, or other named object. The display changes as you enter each character, so you might not need to enter the entire name.
- Enter a version number at the top of the Version column to display only servers running that software version.

You can filter on multiple columns; for example, in a listing of servers, use the Status column to display only running servers, then use the Version column to display running servers using the desired software version. Delete the filtering terms to return to the original display.

### *Full Screen Mode*


To increase the screen area available in Sybase Control Center for views and perspectives, click the  icon at the upper-right corner of the perspective area. Click the icon again to return to the original screen configuration.

---

**Tip:** To increase the screen area available to SCC, press **F11** to switch Internet Explorer or Firefox to full screen mode. Press **F11** again to return to the original browser configuration.

---

### *Maximize a Section of a View*

Some areas within views have a square minimize/maximize icon () in the upper-right corner. Click the icon to expand that area to fill the entire view. Click the icon again to restore the area to its former size.

### *View Menu*

The Perspective Resources view, the Resource Explorer, the Alert Monitor, and the heat chart each have a View menu. From the View menu, you can:

- Display the filtering tool for searches. (In the heat chart, the Filter option also displays the column selection tool.)
- Toggle between an icon view and a detail view of your resources (Perspective Resources view only)
- Refresh the display (Resource Explorer only)

---

**Note:** For these tasks, use the View menu in the view window, not the application-level View menu.

---

### **See also**

- *Resources* on page 153
- *Registering a Replication Server, Replication Agent, or Mirror Replication Agent* on page 90

## Style and Syntax Conventions

---

A reference to the fonts and special characters used to express command syntax and to represent elements of system output and user input.

**Table 6. Style Conventions**

Key	Definition
<code>monospaced(fixed-width)</code>	<ul style="list-style-type: none"> <li>• SQL and program code</li> <li>• Commands to be entered exactly as shown</li> <li>• File names</li> <li>• Directory names</li> </ul>
<i>italic monospaced</i>	In SQL or program code snippets, placeholders for user-specified values (see example below).
<i>italic</i>	<ul style="list-style-type: none"> <li>• File and variable names</li> <li>• Cross-references to other topics or documents</li> <li>• In text, placeholders for user-specified values (see example below)</li> <li>• Glossary terms in text</li> </ul>
<b>bold sans serif</b>	<ul style="list-style-type: none"> <li>• Command, function, stored procedure, utility, class, and method names</li> <li>• Glossary entries (in the Glossary)</li> <li>• Menu option paths</li> <li>• In numbered task or procedure steps, user-interface (UI) elements that you click, such as buttons, check boxes, icons, and so on</li> </ul>

A placeholder represents a system- or environment-specific value that you supply. For example:

```
installation directory\start.bat
```

where *installation directory* is where the application is installed.



**Table 7. Syntax Conventions**

Key	Definition
{ }	Curly braces indicate that you must choose at least one of the enclosed options. Do not type the braces when you enter the command.
[ ]	Brackets mean that choosing one or more of the enclosed options is optional. Do not type the brackets when you enter the command.
( )	Parentheses are to be typed as part of the command.
	The vertical bar means you can select only one of the options shown.
,	The comma means you can choose as many of the options shown as you like, separating your choices with commas that you type as part of the command.
...	An ellipsis (three dots) means you may repeat the last unit as many times as you need. Do not include ellipses in the command.

## Accessibility Features

---

Accessibility ensures access to electronic information for all users, including those with disabilities.

Documentation for Sybase products is available in an HTML version that is designed for accessibility.

Vision impaired users can navigate through the online document with an adaptive technology such as a screen reader, or view it with a screen enlarger.

Sybase HTML documentation has been tested for compliance with accessibility requirements of Section 508 of the U.S Rehabilitation Act. Documents that comply with Section 508 generally also meet non-U.S. accessibility guidelines, such as the World Wide Web Consortium (W3C) guidelines for Web sites.

---

**Note:** You may need to configure your accessibility tool for optimal use. Some screen readers pronounce text based on its case; for example, they pronounce ALL UPPERCASE TEXT as initials, and MixedCase Text as words. You might find it helpful to configure your tool to announce syntax conventions. Consult the documentation for your tool.

---

For information about how Sybase supports accessibility, see the Sybase Accessibility site: <http://www.sybase.com/products/accessibility>. The site includes links to information about Section 508 and W3C standards.

You may find additional information about accessibility features in the product documentation.

## Sybase Control Center Accessibility Information

---

Sybase Control Center uses the Adobe Flex application.

For the most current information about Adobe Flex keyboard shortcuts, see [http://livedocs.adobe.com/flex/3/html/help.html?content=accessible\\_5.html](http://livedocs.adobe.com/flex/3/html/help.html?content=accessible_5.html).

---

**Note:** To use Sybase Control Center with JAWS for Windows screen reading software effectively, download and install the appropriate Adobe scripts. See [www.adobe.com](http://www.adobe.com).

---

# Get Started

Set up Sybase Control Center.

## Quick Start for an Evaluation

---

(Optional) Get started using Sybase Control Center quickly if you do not need the full set of security features. This simplified process is suitable for a small-scale, temporary evaluation or proof-of-concept project, or for checking your installation.

### Prerequisites

Install Sybase Control Center.

### Task

Use these tasks to start Sybase Control Center, log in, register and authenticate a server, and monitor that server.

---

**Note:** After completing the tasks below and confirming that SCC is working, set up SCC for a production environment if you intend to continue using it.

---

**1. *Registering the ODBC Driver in Windows***

In Windows, run scc.bat with administrative privileges to register the ODBC driver.

**2. *Launching Sybase Control Center***

Use the scc command to start Sybase Control Center.

**3. *Getting Started After Installing***

Perform postinstallation testing and configuration.

**4. *Registering a Replication Server, Replication Agent, or Mirror Replication Agent***

Register a resource (for example, a server that can be monitored) to make Sybase Control Center aware of it and its connection information.

**5. *Configuring a Login Account to Monitor Replication***

Use the security configuration options to add one or more roles to a Sybase Control Center login account or to a group. Roles enable users to perform tasks such as monitoring servers or administering Sybase Control Center.

**6. *Authenticating a Login Account for a Managed Resource***

Specify the login account Sybase Control Center will use when it connects to your server or agent to collect monitoring data or manage the resource.

**7. *Displaying Resource Availability***

## Get Started

Use the heat chart to view availability information on the servers in the current perspective.

### 8. *Displaying Replication Server Status*

View the most recent Replication Server statistics. Sybase Control Center automatically updates the page when new status and statistical values are collected.

### 9. *Displaying Replication Agent Status*

Review high-level server availability by viewing the Replication Agent or Mirror Replication Agent status.

### See also

- *Get Started in a Production Environment* on page 20

## Registering the ODBC Driver in Windows

In Windows, run **scc.bat** with administrative privileges to register the ODBC driver.

When Sybase Control Center starts for the first time on a Windows machine, it registers its ODBC driver. Because the automatic registration of the ODBC driver edits the registry settings, you must execute **scc.bat** using elevated administrative privileges. If you launch for the first time without adequate privileges, Sybase Control Center generates an error and fails to start.

In Windows Vista, Windows 2008, and Windows 7, you must use the **Run as administrator** setting to launch Sybase Control Center even if you already have administrative privileges. This process is described below.

In other versions of Windows, you must be logged in as an administrator to start Sybase Control Center for the first time. You need not follow the steps below.

1. In Windows Vista, Windows 2008, or Windows 7, open the command prompt window with administrative privileges:
  - Select **Start > All Programs > Accessories**. Right-click **Command Prompt** and select **Run as administrator**.
  - Alternatively, enter **cmd** in the Start Menu search box and press **Shift+Ctrl+Enter**.
2. Run **scc.bat**.

## Launching Sybase Control Center

Use the **scc** command to start Sybase Control Center.

### Prerequisites

Install Adobe Flash Player in the browser you will use for Sybase Control Center.

## Task

### 1. Start Sybase Control Center.

- Windows – navigate to `<install_location>\SCC-3_2\bin` and double-click **scc.bat**.
- UNIX – execute **scc.sh**.

Messages on the progress of the launch appear in a command window. When Sybase Control Center is running, the command window becomes the Sybase Control Center console; you can issue commands to get status information on SCC and its ports, plug-ins, and services.

### 2. Open a Web browser and enter `https://<hostname>:8283/scc`.

## Getting Started After Installing

Perform postinstallation testing and configuration.

### Prerequisites

Start Sybase Control Center.

## Task

### 1. Install Adobe Flash Player 10.1 or later in the Web browser you will use to connect to Sybase Control Center.

Flash Player is a free plug-in. You can download the latest version from <http://get.adobe.com/flashplayer/>.

If Flash Player is already installed but you are not sure which version you have, go to the Adobe test site at <http://adobe.com/shockwave/welcome>. Click the link that says **Test your Adobe Flash Player installation**. The version information box on the next page that appears displays your Flash Player version.

### 2. To connect to Sybase Control Center, direct your browser to:

`https://<scc_server_hostname>:8283/scc`

---

**Note:** If you changed the default HTTPS port during installation, use the new port number instead of 8283.

---

- ### 3. If you see an error about the security certificate, add Sybase Control Center to your browser's trusted sites zone (Internet Explorer) or add a security exception (Firefox).
- ### 4. Log in. Sybase Control Center has two default login accounts:

- sccadmin – for initial configuration and setting up permanent authentication.
- sccuser – for testing.

Neither of these accounts requires a password.

---

**Note:** The sccadmin and sccuser accounts and the simple login module on which they are based are not intended for use in a production environment. Sybase recommends that you pass authentication responsibility to your operating system or to LDAP, as described in the *Sybase Control Center > Get Started > Setting Up Security* section of the online help.

Sybase further recommends that you disable sccadmin and sccuser as soon as you have set up and tested authentication, and that you set passwords on the accounts if you do not plan to set up and test authentication right away.

---

5. (Optional) Configure passwords or disable sccadmin and sccuser—see the *Sybase Control Center Installation Guide* for instructions.

## **Registering a Replication Server, Replication Agent, or Mirror Replication Agent**

Register a resource (for example, a server that can be monitored) to make Sybase Control Center aware of it and its connection information.

1. In the Resource Explorer, select **Resources > Register**.
2. Specify:

**Table 8. New resource type details**

Field	Description
Resource Name	(Required) Name of the resource to register. Enter the actual name of the server, using uppercase and lowercase letters. If the name registered in Sybase Control Center does not exactly match the server name, some monitoring functions, including the topology view, do not work.
Resource Type	Select a resource type: <ul style="list-style-type: none"><li>• ASE Server, Replication Only (12.5.0.0) – monitor only the RepAgent threads for an Adaptive Server that is older than version 15.0.2.0. Choose this type for an Adaptive Server that is part of a replication environment.</li><li>• Replication Agent (15.5.0.0) – monitor Replication Agent.</li><li>• Replication Server (15.5.0.0) – monitor Replication Server.</li></ul>
Description	A brief description to help you identify the resource.

3. Click **Next**.
4. Specify the connection information for your resource:

**Table 9. New resource connection details**

Field	Description
Server Host Name/Host Name	Local host name
Port Number	Local host port number
RSSD Host Name	(Required) Name of the RSSD host
RSSD Port Number	(Required) RSSD host port number

---

**Note:** **RSSD Host Name** and **RSSD Port Number** are required only if you are registering a Replication Server.

---

5. Click **Next**.
6. (Optional) Click **Add this resource to the current perspective**. You must add a resource to a perspective (not necessarily the current perspective) before you can manage or monitor it.
7. (Optional) Click **Open the resource explorer to view this new resource**. (This option is not present when the Resource Explorer is open.)
8. Click **Finish**.

## Configuring a Login Account to Monitor Replication

Use the security configuration options to add one or more roles to a Sybase Control Center login account or to a group. Roles enable users to perform tasks such as monitoring servers or administering Sybase Control Center.

### **Prerequisites**

You must have administrative privileges (sccAdminRole) to perform this task. To assign a monitoring role for a server, first register the server.

### **Task**

Assign the repMonitor and repAdminRole to any login account to perform monitoring and management tasks in Sybase Control Center.

1. From the menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Click **Logins** or **Groups**.
4. Select the login account or group to which you want to assign a role.
5. Click the **Roles** tab.
6. From the **Available roles for resource** list, select the role, then click **Add**.  
For example, to grant administrative privileges, add the SCC Service:sccAdminRole.

If a role appears in the **Has following roles** list, it means the account or group has already been configured with that role.

7. Click **OK**.

### **Authenticating a Login Account for a Managed Resource**

Specify the login account Sybase Control Center will use when it connects to your server or agent to collect monitoring data or manage the resource.

Perform this task for each resource registered with Sybase Control Center.

---

**Note:** You can also authenticate a server during administrative tasks like creating an alert or a collection job.

---

1. Connect a browser to Sybase Control Center and log in.
2. If the Perspective Resources view is not open, click the **Show/Hide Perspective Resources View** icon in the toolbar.
3. In the Perspective Resources view, select your resource and select **Resource > Authenticate** from the view menu.
4. Select **Use my current SCC login** or **Specify different credentials**.
5. If you chose **Specify different credentials**, enter the login and password for Sybase Control Center to use to connect to your resource.
6. If the selected server is a Replication Server, also enter the RSSD user name and password.
7. Click **OK** to save and exit the dialog.

### **Displaying Resource Availability**

Use the heat chart to view availability information on the servers in the current perspective.

1. From the application menu bar, select **View > Open > Heat Chart**.
2. (Optional) To display tools for filtering (narrowing the list of resources in the heat chart) or changing the columns, select **View > Filter** from the Perspective Heat Chart menu bar. The Filter and Column tools appear in the left pane.
3. (Optional) To use filtering, select **View > Filter** from the view's menu bar and enter a search term in the **Filter string** field.

The search term can be any string that appears in the tabular portion of the heat chart, such as the name, or part of the name, of a server or a resource type (ASE Server, for example).

4. (Optional) Select a filtering setting:
  - **Match case** – search for resources whose displayed data includes the search term, including uppercase and lowercase letters; or
  - **Exact match** – search for resources whose displayed data includes an item identical to the search term.



5. (Optional) Select a column from the **Filter on** list to restrict your search to that column.
6. (Optional) Click **Columns** to customize your heat chart.
7. (Optional) Unselect any column that should not appear in your heat chart.
8. (Optional) Click the sorting arrow in the column headers to sort the column values in either ascending or descending order.
9. (Optional) Click the resource's row and pull down the menu to the right of the resource name to view options for the selected resource.
10. (Optional) To resize the Filter and Columns tools pane, move your mouse over the border between the tools pane and the resource table. When the mouse cursor changes to a resize icon, click and drag the border to the left or the right.
11. (Optional) To hide the Filter and Columns tools, unselect **View > Filter**.

## Displaying Replication Server Status

View the most recent Replication Server statistics. Sybase Control Center automatically updates the page when new status and statistical values are collected.

### **Prerequisites**

Register and add all the servers to be monitored to the Perspective Resources view, authenticate them, and verify that you have permission to perform this task.

### **Task**

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.  
The Replication Server monitor view appears, with the Overview as the default display.
2. (Optional) To maximize or minimize a window within the monitor view, click the maximize or restore window icon in its right corner.

---

**Note:** You can also view the server status through the status badges on the server icons in the Perspective Resources, Perspective Heat Chart, Resource Explorer, and Replication Topology views.

---

## Displaying Replication Agent Status

Review high-level server availability by viewing the Replication Agent or Mirror Replication Agent status.

### **Prerequisites**

Register and add all the servers to be monitored to the Perspective Resources view, authenticate them, and verify that you have permission to perform this task.

### Task

1. From the Perspective Resources view, select a Replication Agent and click **Resource > Monitor**.

The monitor view appears displaying high-level information, which includes the status of the selected Replication Agent.

2. (Optional) To maximize or minimize a window within the monitor view, click the maximize or restore window icon in its right corner.

## Get Started in a Production Environment

---

Perform a complete set-up of Sybase Control Center, including configuration of user authentication and other one-time set-up tasks.

1. *Starting and Stopping Sybase Control Center in Windows*

There are several ways to start and stop Sybase Control Center or the SCC agent. You can start manually, which is useful for testing and troubleshooting, or set the service to start automatically and to restart in case of failure.

2. *Starting and Stopping Sybase Control Center in UNIX*

You can start Sybase Control Center or the SCC agent manually, which is useful for testing and troubleshooting, or you can set up a service to start automatically and to restart in case of failure.

3. *Configuring Memory Usage*

(Optional) Determine whether you need to configure how much memory Sybase Control Center uses, and if so which configuration method to use.

4. *Logging in to Sybase Control Center*

Enter the Sybase Control Center Web console.

5. *Setting Up Security*

Configure login authentication and map roles.

6. *Configuring the E-mail Server*

(Optional) Specify the e-mail server for Sybase Control Center to use to send e-mail alert notifications.

7. *Configuring the Automatic Logout Timer*

(Optional) Set Sybase Control Center to end login sessions when users are inactive for too long.

8. *User Authorization*

The authorization mechanism in Sybase Control Center employs login accounts and task-based roles.

## 9. *Configure*

Configure login accounts, statistics collection, and other replication monitoring options.

### **Starting and Stopping Sybase Control Center in Windows**

There are several ways to start and stop Sybase Control Center or the SCC agent. You can start manually, which is useful for testing and troubleshooting, or set the service to start automatically and to restart in case of failure.

This topic applies to both Sybase Control Center (the server) and the Sybase Control Center agent that runs on each product server managed by SCC.

If you run Sybase Control Center or the SCC agent manually, you must issue a command every time you start or shut down. If you run as a service (which is recommended), you can configure Windows to automatically start and restart Sybase Control Center or the SCC agent. These are the options:

- Use the **scc.bat** command to start Sybase Control Center or the SCC agent manually. The command gives you access to the Sybase Control Center console, which you can use to shut down and to display information about services, ports, system properties, and environment variables. You can also use **scc.bat** to change the logging level for troubleshooting purposes. Using **scc.bat** prevents you from taking advantage of the automatic start and restart features available to services.
- Use the Services list under the Windows Control Panel to start, stop, and configure the Sybase Control Center service.
- Use the **net start** and **net stop** commands. This is another way to run Sybase Control Center or the SCC agent as a service.

---

**Note:** To start or stop Sybase Control Center as a service, you must have selected **Yes** in the installer to install Sybase Control Center as a service.

---

The installer attempts to start Sybase Control Center or the SCC agent as a service and configures the service to restart automatically. Before starting, check the Windows Services list for a Sybase Control Center service.

Here are the steps for each option:

- **Start Sybase Control Center or the SCC agent:**
  - a) (Skip this step for the SCC agent.) If you are starting Sybase Control Center for the first time in Windows Vista, Windows 2008, or Windows 7, set the **Run as Administrator** option on the command prompt so that Sybase Control Center can register its ODBC driver. (This is necessary even if you are logged in as an administrator.)
  - b) Enter:
 

```
%SYBASE%\SCC-3_2\bin\scc.bat
```
- **Stop Sybase Control Center or the SCC agent:**

a) Enter:

```
%SYBASE%\SCC-3_2\bin\scc.bat --stop
```

---

**Note:** You can also enter **shutdown** at the `scc-console>` prompt.

---

- **Start or stop from the Windows Control Panel; configure automatic start and restart:**

- Open the Windows Control Panel.
- Select **Administrative Tools > Services**.
- Locate Sybase Control Center 3.2. If the service is running, the status column displays “Started.”
- To start or stop the service, right-click **Sybase Control Center 3.2** and choose **Start** or **Stop**.
- To configure automatic starting, double-click the service.
- To set the service to automatically start when the machine starts, change the **Startup type** to Automatic.
- To restart the service in case of failure, choose the **Recovery** tab and change the First, Second, and Subsequent failures to Restart Service.
- Click **Apply** to save the modifications and close the dialog.

- **Start or stop the Sybase Control Center service (controlling either Sybase Control Center or the SCC agent) from the Windows command line:**

a) To start the service, enter:

```
net start "sybase control center 3.2"
```

```
The Sybase Control Center 3.2 service is starting.....  
The Sybase Control Center 3.2 service was started  
successfully.
```

b) To stop the service, enter:

```
net stop "sybase control center 3.2"
```

```
The Sybase Control Center 3.2 service is stopping.....  
The Sybase Control Center 3.2 service was stopped  
successfully.
```

## Starting and Stopping Sybase Control Center in UNIX

You can start Sybase Control Center or the SCC agent manually, which is useful for testing and troubleshooting, or you can set up a service to start automatically and to restart in case of failure.

This topic applies to both Sybase Control Center (the server) and the Sybase Control Center agent that runs on each product server managed by SCC.

If you start Sybase Control Center or the SCC agent on a managed server manually, you must issue a command every time you want to start or stop it. If you run Sybase Control Center or the

SCC agent as a service (which is recommended), you can configure the service to start and restart automatically. These are the options:

- Use the **scc.sh** script to start Sybase Control Center or the SCC agent manually. You can do this in two ways:
  - Run **scc.sh** in the foreground to get access to the Sybase Control Center console, which you can use to shut down and to display information about services, ports, system properties, and environment variables.
  - Run **scc.sh** in the background to suppress the console.

You can use **scc.sh** to run Sybase Control Center at a nondefault logging level for troubleshooting. When you start manually with **scc.sh**, you cannot take advantage of the automatic start and restart features available to services.

- Use the **sccd** script to configure a service that starts Sybase Control Center or the SCC agent automatically.

Here are the steps for each option:

- **Before you start Sybase Control Center or the SCC agent for the first time, set environment variables.** Do this only once.
  - a) Change to the Sybase directory (the parent of the Sybase Control Center installation directory).
  - b) Execute one of the following to set environment variables.

Bourne shell:

```
. SYBASE.sh
```

C shell:

```
source SYBASE.csh
```

- **Run Sybase Control Center or the SCC agent in the foreground.**

Running in the foreground is a method of manually starting; you must issue commands to stop and restart Sybase Control Center or the SCC agent when you use this method.

- a) To start Sybase Control Center or the SCC agent and drop into the console when the start-up sequence is finished, enter:

```
$SYBASE/SCC-3_2/bin/scc.sh
```

- **Run Sybase Control Center or the SCC agent in the background.**

You can use **nohup**, **&**, and **>** to run Sybase Control Center or the SCC agent in the background, redirect output and system error to a file, and suppress the SCC console. Sybase recommends that you do this from the Sybase Control Center `bin` directory.

Running in the background is a method of manually starting; you must issue commands to stop and restart Sybase Control Center or the SCC agent when you use this method.

- a) Execute a command similar to the sample below that matches your shell. Both sample commands direct output to the file `scc-console.out`. If the output file already exists, you might need to use additional shell operators to append to or truncate the file.

For Bourne shell (sh) or Bash:

```
cd <SCC-install-dir>/bin; nohup ./scc.sh 2>&1 > scc-console.out &
```

For C shell:

```
cd <SCC-install-dir>/bin; nohup ./scc.sh >& scc-console.out &
```

- **Shut down Sybase Control Center or the SCC agent.**

a) To shut down from the `scc-console>` prompt, enter:

```
shutdown
```

---

**Warning!** Do not enter **shutdown** at a UNIX prompt; it shuts down the operating system.

---

To shut down from the UNIX command line, enter:

```
$SYBASE/SCC-3_2/bin/scc.sh --stop
```

- **Configure Sybase Control Center or the SCC agent to run as a service.**

A UNIX service is a daemon process that starts automatically after the machine is started and runs in the background. UNIX installations of Sybase Control Center include a shell script, **sccd**, which you can use to configure the Sybase Control Center service. (Some UNIX platforms supply tools that make service configuration easier; Linux **chkconfig** is an example.)

---

**Note:** Sybase recommends that if you are not familiar with the process of setting up services in UNIX, you delegate this task to a system administrator or consult the system administration documentation for your UNIX platform.

---

a) Copy `$SYBASE/SCC-3_2/bin/sccd` into this directory:

- AIX (SCC agent only): `/etc/rc.d/init.d`
- HP-UX (SCC agent only): `/sbin/init.d`
- All other platforms: `/etc/init.d`

b) Open `sccd` and edit the line that sets the SYBASE variable. Set it to the location of your Sybase installation (that is, the parent of `SCC-3_2`, the Sybase Control Center installation directory).

c) In Linux, execute these commands to configure the service to run in run levels 2, 3, 4, and 5:

```
/usr/sbin/chkconfig --add sccd  
/usr/sbin/chkconfig --level 2345 sccd
```

You can test the `sccd` script with `/usr/sbin/service sccd status`. (The **service** command accepts these options: `start` | `stop` | `status` | `restart`.)

d) On non-Linux platforms, locate this directory:

- AIX (SCC agent only): `/etc/rc.d/rc<X>.d`
- HP-UX (SCC agent only): `/sbin/rc<X>.d`

- Solaris: `/etc/rc<X>.d`

Where `<X>` is the run level (for example, 3). Make two soft links in the directory for your platform and set the links to point to:

- AIX (SCC agent only): `/etc/rc.d/init.d/sccd: S90sccd` and `/etc/rc.d/init.d/sccd: K10sccd`
- HP-UX (SCC agent only): `/sbin/init.d/sccd: S90sccd` and `/sbin/init.d/sccd: K10sccd`
- Solaris: `/etc/init.d/sccd: S90sccd` and `/etc/init.d/sccd: K10sccd`

The `S90sccd` link starts the service and the `K10sccd` link stops the service. The two-digit numbers in the links indicate the start and stop priorities of the service.

- e) Use the `S90sccd` and `K10sccd` links to test starting and stopping the service. The links are called automatically when the machine is started or shut down.

## Configuring Memory Usage

(Optional) Determine whether you need to configure how much memory Sybase Control Center uses, and if so which configuration method to use.

It is not usually necessary to configure memory usage for Sybase Control Center. This table lists memory options you can set and circumstances under which you should consider changing them.

Modify this value	When	Guidelines
Maximum memory <ul style="list-style-type: none"> <li>• <code>SCC_MEM_MAX</code> – if you are starting SCC from the command line or running it as a UNIX service</li> <li>• <code>jvmopt=-Xmx</code> – if you are running SCC as a Windows service</li> </ul>	<ul style="list-style-type: none"> <li>• You need to prevent Sybase Control Center from using more than a given amount of memory</li> <li>• An <code>OutOfMemory</code> error says Sybase Control Center is out of heap space</li> <li>• A warning message about system memory appears during the start process</li> <li>• The machine where Sybase Control Center is installed has less than 2GB of memory. (Starting SCC on a machine with less than 2GB of memory triggers the start-up warning message about system memory.)</li> </ul>	<p>On machines with less than 2GB of memory, set maximum memory to 256MB or more.</p> <p>Default value: none. (On machines with 2GB or more of memory, maximum memory is set dynamically and is effectively limited only by the amount of system memory available.)</p>

Modify this value	When	Guidelines
Permanent memory <ul style="list-style-type: none"> <li>• <code>SCC_MEM_PERM</code> – if you are starting SCC from the command line or running it as a UNIX service</li> <li>• <code>jvmopt=-XX:MaxPermSize</code> – if you are running SCC as a Windows service</li> </ul>	An OutOfMemory error says Sybase Control Center is out of permanent generation space	Increase by 32MB increments. If you reach a value equal to twice the default and still see the OutOfMemory error, contact Sybase technical support.  Default value: 128MB

You can change memory options in two ways:

- For Sybase Control Center started from the command line – execute commands to set one or more environment variables before executing the **scc** command to start Sybase Control Center. When you use this method, your changes to the memory options last only as long as the current login session. This method is useful for testing new option values.
- For the Sybase Control Center service – modify a file used by the Sybase Control Center service. (Windows and UNIX services use different files.) When you use this method, your changes to the memory options persist—Sybase Control Center uses them every time it starts as a service.

**See also**

- *Logging in to Sybase Control Center* on page 28

**Changing a Memory Option on the Command Line**

Before you start Sybase Control Center from the command line, you can issue a command to change the value of a memory option temporarily.

Changes made using this method last only as long as the current login session. This method is useful for testing new option values.

1. If Sybase Control Center is running, shut it down.
2. Set the environment variable using a command appropriate for your operating system. Specify a size in megabytes but do not indicate the units in the command.

Windows example:

```
> set SCC_MEM_MAX=512
```

UNIX example:

```
bash$ export SCC_MEM_MAX=512
```



3. Use the **scc** command to start Sybase Control Center.

### See also

- *Changing a Memory Option for an SCC Windows Service* on page 27
- *Changing a Memory Option for an SCC UNIX Service* on page 27

### **Changing a Memory Option for an SCC Windows Service**

Add a **jvmopt** command to the `scc.properties` file to change a memory option (`-Xmx` or `-XX:MaxPermSize`) for a Sybase Control Center Windows service.

When you use this method to set memory options, your changes are permanent—Sybase Control Center uses them every time it starts as a service.

1. If Sybase Control Center is running, shut it down.
2. Open the SCC properties file:  

```
<SCC-install-directory>\SCC-3_2\bin\scc.properties
```
3. Add (or modify, if it already exists) a **jvmopt** line specifying the memory size in Java format. Use `m` for megabytes or `g` for gigabytes.

For example:

```
jvmopt=-Xmx512m
```

4. Save the file and start the Sybase Control Center Windows service.

### See also

- *Changing a Memory Option on the Command Line* on page 26
- *Changing a Memory Option for an SCC UNIX Service* on page 27

### **Changing a Memory Option for an SCC UNIX Service**

To change a memory setting for a Sybase Control Center UNIX service, add the appropriate environment variable (`SCC_MEM_MAX` or `SCC_MEM_PERM`) to the `sccd` script.

When you use this method to set memory options, your changes are permanent—Sybase Control Center uses them every time it starts as a service.

1. If Sybase Control Center is running, shut it down.
2. Open the `sccd` file: `/etc/init.d/sccd`
3. Add the environment variable at the top of the file (after the comments). Specify a size in megabytes but do not indicate the units in the command.

For example:

```
SCC_MEM_MAX=512
```

4. Save the file and start the Sybase Control Center UNIX service.

**See also**

- *Changing a Memory Option on the Command Line* on page 26
- *Changing a Memory Option for an SCC Windows Service* on page 27

## **Logging in to Sybase Control Center**

Enter the Sybase Control Center Web console.

**Prerequisites**

Install Adobe Flash Player in the browser you will use for SCC. See the *Sybase Control Center Installation Guide*.

**Task**

Sybase Control Center typically authenticates users through the operating system or an LDAP directory service. Consult your SCC administrator if you are not sure which login account to use for SCC.

---

**Note:** When logging in to a newly installed Sybase Control Center for which secure authentication has not been configured, use the sccadmin account (with no password, by default). For more information, see the *Sybase Control Center Installation Guide*.

---

1. Connect to the Sybase Control Center server. In your Web browser, enter: `https://scc-hostname:8283/scc`.
2. Enter your user name and password, and click **Login**.

---

**Tip:** If you use a Windows account to log in to SCC, enter your user name in the format `username@domain`. Omit top-level domain extensions such as `.com` or `.net`—for example, enter `fred@sybase`, not `fred@sybase.com`.

---

**See also**

- *Configuring Memory Usage* on page 25

## **Setting Up Security**

Configure login authentication and map roles.

Read about security and follow these procedures before you configure Sybase Control Center product modules.

---

**Note:** These security topics are intended for use in a production environment. If you are evaluating or testing SCC, see the *Installation Guide* for instructions on getting started quickly.

---

1. *Security*

Sybase Control Center can authenticate user logins through an LDAP server, through the operating system, or both.

## 2. *Configuring Authentication for Windows*

Authentication through the Windows operating system is enabled by default, but it requires some configuration. First, set Sybase Control Center to create an account when a Windows user logs in to Sybase Control Center.

## 3. *Configuring a Pluggable Authentication Module (PAM) for UNIX*

Set up Sybase Control Center to support username and password login using accounts on the UNIX operating system. Optionally, have Sybase Control Center create an account when a UNIX user first logs in to Sybase Control Center.

## 4. *Configuring an LDAP Authentication Module*

Configure an LDAP authentication module for Sybase Control Center by editing the security properties file to point to the correct LDAP server.

## 5. *Mapping Sybase Control Center Roles to LDAP or OS Groups*

To grant Sybase Control Center privileges to users who are authenticated through LDAP or the operating system, associate roles used in Sybase Control Center with groups in LDAP or the operating system.

## 6. *Encrypting a Password*

Use the `passencrypt` utility to encrypt passwords and other values that must be kept secure while stored in text files.

## 7. *Configuring Ports*

(Optional) Use the `scc -port` command to assign Sybase Control Center services to new ports.

## See also

- *Configuring the E-mail Server* on page 44

## **Security**

Sybase Control Center can authenticate user logins through an LDAP server, through the operating system, or both.

- Sybase Control Center can be configured to authenticate through any LDAP server that supports the `inetOrgPerson` (RFC 2798) schema.
- When Sybase Control Center authenticates through the operating system, it uses the operating system of the Sybase Control Center server machine (not the client).

Although you can create native user accounts in Sybase Control Center, Sybase does not recommend this approach to authentication. It is simpler and safer to configure Sybase Control Center to authenticate using existing LDAP, Windows, or UNIX login accounts.

Sybase strongly recommends that you use a common authentication provider for all Sybase products, including Sybase Control Center. A common authentication provider ensures that single sign-on works for users of Sybase Control Center and its managed servers.

Sybase Control Center requires each authenticated login account to have a predefined role. When a login is authenticated, roles for the login are retrieved by the security module and are mapped to Sybase Control Center predefined roles. Authorization is resolved through the mappings between the security module native roles and Sybase Control Center roles. You can enable mappings by creating a "sybase" group in your operating system or LDAP server and adding all Sybase Control Center users, or by modifying the Sybase Control Center `roles-map.xml` file to configure the mapping of native roles to Sybase Control Center roles. The security module authenticates the logins and authorizes access to managed resources.

Sybase Control Center provides a set of predefined login modules for authentication. All login modules are defined in the `<install_location>/SCC-3_2/conf/csi.properties` file. The syntax is defined by the Sybase Common Security Infrastructure (CSI) framework. You can configure the different login modules to customize security strength. The login modules are:

- Simple Login – defines a user name, password, and a list of roles. The default user name is “sccadmin” with a blank password and a native role of “sccAdminRole”. You can create additional accounts by adding simple login modules to `csi.properties`. However, Sybase does not recommend the use of simple login modules for authentication in production environments.

---

**Note:** Add a password for the sccadmin account as soon as possible after you install Sybase Control Center. See the *Sybase Control Center Installation Guide* for instructions.

- NT Proxy Login – delegates authentication to the underlying Windows operating system. When you log in to Sybase Control Center through an NT Proxy Login module, enter your user name in the format `username@nt-domain-name`. For example, `user@sybase`. Windows authentication is enabled by default, but it requires some configuration.
- UNIX Proxy Login – delegates authentication to the underlying UNIX or Linux operating system using Pluggable Authentication Modules (PAM). When you log in to Sybase Control Center through a UNIX PAM, enter only your user name. UNIX authentication is enabled by default, but it requires some configuration.
- LDAP Login – delegates authentication to an LDAP server you specify. When you log in to Sybase Control Center through an LDAP server, enter only your user name. LDAP authentication is not enabled by default; you must configure the login module.

### **Configuring Authentication for Windows**

Authentication through the Windows operating system is enabled by default, but it requires some configuration. First, set Sybase Control Center to create an account when a Windows user logs in to Sybase Control Center.

This task is optional. However, if you choose not to create Sybase Control Center accounts automatically as described here, you must enter them manually. Sybase Control Center needs the accounts for purposes of setting authorization (user privileges).

1. Log in to Sybase Control Center using an account with administrative privileges. (The login account or its group must have sccAdminRole.)
2. Select **Application > Administration > Security**.
3. Check the box labeled **Automatically add SCC login records for authenticated logins**.
4. Check the box labeled **Automatically grant secUserRole to newly created logins**.
5. Click **OK** to close the Security dialog.

## Next

There are two next steps:

- If you opted not to automatically create Sybase Control Center login accounts, enter each account into Sybase Control Center manually.
- Whether you add accounts automatically or manually, you must grant privileges to any login accounts that require more than basic user access. You can grant privileges by assigning Sybase Control Center roles directly to the login accounts, or by assigning the login accounts to groups and mapping Sybase Control Center roles to the groups. The group approach is generally more efficient.

## **Configuring a Pluggable Authentication Module (PAM) for UNIX**

Set up Sybase Control Center to support username and password login using accounts on the UNIX operating system. Optionally, have Sybase Control Center create an account when a UNIX user first logs in to Sybase Control Center.

1. Using a login account with root privileges, configure the pluggable authentication module for your platform:

Platform	Action
Solaris	Append the contents of the <SCC-install-dir>/utility/sunos/pam.conf file (provided with Sybase Control Center) to the /etc/pam.conf file on your Solaris platform.
Linux	Copy the <SCC-install-dir>/utility/linux/sybase-ua file (provided with Sybase Control Center) to the /etc/pam.d directory on your Linux platform.  <b>Note:</b> The sybase-ua file provided with Sybase Control Center is not compatible with the most recent SUSE Linux versions. For SUSE 11 and later, see the example at the end of this topic.

**Note:** In the table above, the portion of the path that indicates the operating system might differ slightly from what is shown.

2. (Skip if you configured a PAM before starting Sybase Control Center) Restart Sybase Control Center.
3. (Optional) If you want Sybase Control Center to create an account when a UNIX user logs in to Sybase Control Center, execute these steps. If you choose not to create Sybase Control Center accounts automatically, you must enter them manually. Sybase Control Center needs the accounts for purposes of setting authorization (user privileges).
  - a) Log in to Sybase Control Center using an account with administrative privileges (sccAdminRole).
  - b) Select **Application > Administration > Security**.
  - c) Check the box labeled **Automatically add SCC login records for authenticated logins**.
  - d) Click **OK** to close the Security dialog.

### Example: PAM for SUSE Linux 11 and later

For SUSE 11 and later, do not use the `sybase-ua` file provided with Sybase Control Center. Instead, in your `/etc/pam.d` directory, create a `sybase-ua` file that contains:

```
# sybase-ua PAM Configuration (SUSE style)
auth      include      common-auth
account   include      common-account
password  include      common-password
session   include      common-session
```

### Next

There are two next steps:

- If you opted not to automatically create Sybase Control Center login accounts, enter each account into Sybase Control Center manually.
- Whether you add accounts automatically or manually, you must also grant privileges to the login accounts. You can grant privileges by assigning Sybase Control Center roles directly to the login accounts, or by assigning the login accounts to groups and mapping Sybase Control Center roles to the groups. The group approach is generally more efficient.

### Configuring an LDAP Authentication Module

Configure an LDAP authentication module for Sybase Control Center by editing the security properties file to point to the correct LDAP server.

1. Open the `<SCC-install-dir>\conf\csi.properties` file.
2. Uncomment the LDAP module in the properties file by removing the `#` symbol at the beginning of each line (or, if necessary, add an LDAP module to the file). The sample module below specifies the LDAP server that will provide user authentication.

The sample module shows the properties used for an OpenDS LDAP server. See the example at the end for values that work for ActiveDirectory. Configuration properties you can use in the LDAP module are described in a subtopic.

Each line of the LDAP server module of the properties file must begin with "CSI.loginModule." followed by a module number. (The module number in this sample is 7.) The module number you assign must be unique in the properties file, and you must use the same module number in every line of the module.

```
CSI.loginModule.
7.options.AuthenticationSearchBase=ou=users,dc=example,dc=com
CSI.loginModule.7.options.BindDN=cn=Directory Manager
CSI.loginModule.7.options.BindPassword=secret
CSI.loginModule.7.options.DefaultSearchBase=dc=example,dc=com
CSI.loginModule.7.options.ProviderURL=ldap://localhost:10389
CSI.loginModule.
7.options.RoleSearchBase=ou=groups,dc=example,dc=com
CSI.loginModule.7.options.ServerType=openldap
CSI.loginModule.7.options.moduleName=LDAP Login Module
CSI.loginModule.7.controlFlag=sufficient
CSI.loginModule.
7.provider=com.sybase.ua.services.security.ldap.LDAPLoginModule
```

---

**Note:** Change the values of bolded lines only.

---

3. Save the file.
4. If your LDAP server's SSL certificate is signed by a nonstandard certificate authority (for example, if it is a self-signed certificate), use the **keytool** utility to configure your JVM or JDK to trust the certificate. Execute a command similar to this:

```
keytool -import -keystore <sybase-dir>/shared/JRE-6_0_6/bin/
keytool/lib/security/cacerts -file
<your cert file and path> -alias ldapcert -storepass changeit
```

## LDAP configuration values for ActiveDirectory

For an ActiveDirectory server, use these values for configuration properties in your LDAP login module:

```
ServerType: msad2K
DefaultSearchBase: dc=<domainname>,dc=<tld> or o=<company
name>,c=<country code>
E.g. dc=sybase,dc=com or o=Sybase,c=us
ProviderUrl: ldaps://<hostname>:<port>
E.g.: ldaps://myserver:636
AuthenticationFilter: (&(userPrincipalName={uid})
(objectclass=user))
BindDN: <User with read capability for all users>
BindPassword: <Password for BindDN user>
RoleFilter: (|(objectclass=groupofnames) (objectclass=group))
controlFlag: sufficient
```

## Next

There are two additional steps:

- Set up roles and passwords for LDAP

## Get Started

- Map Sybase Control Center role to LDAP groups

### See also

- *Mapping Sybase Control Center Roles to LDAP or OS Groups* on page 41

### Setting Up Roles and Passwords

Set the initial user roles and passwords required for Sybase Control Center to authenticate through an LDAP server.

### Prerequisites

Configure an LDAP authentication module.

### Task

1. Open the `<SCC-install-dir>\conf\roles-map.xml` file and add an LDAP login module.

Insert an LDAP login module similar to this at the end of the security-modules portion of the file, just before `</security-modules>`:

```
<module name="LDAP Login Module">
  <role-mapping modRole="sybase"
    uafRole="uaAnonymous,uaPluginAdmin,sccUserRole" />
  <role-mapping modRole="administrators"
    uafRole="uaAnonymous,sccAdminRole" />
</module>
```

2. Ensure that the roles defined in the LDAP repository match the roles defined in `roles-map.xml`.
3. In the `<SCC-install-dir>\conf\csi.properties` file, set the `BindPassword` and `ProviderURL` properties with values used in your deployment.  
Sybase recommends that you encrypt sensitive values before saving them in `csi.properties`.

### Next

Map Sybase Control Center roles to LDAP groups.

### See also

- *LDAP Configuration Properties* on page 35



LDAP Configuration Properties

Use these properties in your `csi.properties` file to control your LDAP service.

Property	Default Value	Description
ServerType	None	<p>Optional. The type of LDAP server you are connecting to:</p> <ul style="list-style-type: none"> <li>• <code>sunone5</code> -- SunOne 5.x OR iPlanet 5.x</li> <li>• <code>msad2k</code> -- Microsoft ActiveDirectory, Windows 2000</li> <li>• <code>nsds4</code> -- Netscape Directory Server 4.x</li> <li>• <code>openldap</code> -- OpenLDAP Directory Server 2.x</li> </ul> <p>The value you choose establishes default values for these other authentication properties:</p> <ul style="list-style-type: none"> <li>• <code>RoleFilter</code></li> <li>• <code>UserRoleMembership</code></li> <li>• <code>RoleMemberAttributes</code></li> <li>• <code>AuthenticationFilter</code></li> <li>• <code>DigestMD5Authentication</code></li> <li>• <code>UseUserAccountControl</code></li> </ul>
ProviderURL	<code>ldap://localhost:389</code>	<p>The URL used to connect to the LDAP server. Use the default value if the server is:</p> <ul style="list-style-type: none"> <li>• Located on the same machine as your product that is enabled with the common security infrastructure.</li> <li>• Configured to use the default port (389).</li> </ul> <p>Otherwise, use this syntax for setting the value:</p> <pre>ldap://&lt;hostname&gt;:&lt;port&gt;</pre>

Property	Default Value	Description
DefaultSearchBase	None	<p>The LDAP search base that is used if no other search base is specified for authentication, roles, attribution and self registration:</p> <ol style="list-style-type: none"> <li>1. <code>dc=&lt;domainname&gt;,dc=&lt;tld&gt;</code> For example, a machine in sybase.com domain would have a search base of <code>dc=sybase,dc=com</code>.</li> <li>2. <code>o=&lt;company name&gt;,c=&lt;country code&gt;</code> For example, this might be <code>o=Sybase,c=us</code> for a machine within the Sybase organization.</li> </ol>
SecurityProtocol	None	<p>The protocol to be used when connecting to the LDAP server.</p> <p>To use an encrypted protocol, use "ssl" instead "ldaps" in the url.</p> <hr/> <p><b>Note:</b> ActiveDirectory requires the SSL protocol when setting the value for the password attribute. This occurs when creating a user or updating the password of an existing user.</p> <hr/>
AuthenticationMethod	simple	<p>The authentication method to use for all authentication requests into LDAP. Legal values are generally the same as those of the <code>java.naming.security.authentication</code> JNDI property. Choose one of:</p> <ul style="list-style-type: none"> <li>• simple — For clear-text password authentication.</li> <li>• DIGEST-MD5 — For more secure hashed password authentication. This method requires that the server use plain text password storage and only works with JRE 1.4 or later.</li> </ul>

Property	Default Value	Description
AuthenticationFilter	<p>For most LDAP servers:  <code>(&amp;(uid={uid})  (object-  class=person))</code></p> <p>or</p> <p>For Active Directory  email lookups:  <code>(&amp;(userPrinci-  palName={uid})  (object-  class=user))  [ActiveDirec-  tory]</code></p> <p>For Active Directory  Windows username  lookups: <code>(&amp;(SAMAc-  count-  Name={uid})  (object-  class=user))</code></p>	<p>The filter to use when looking up the user.</p> <p>When performing a username based lookup, this filter is used to determine the LDAP entry that matches the supplied username.</p> <p>The string "{uid}" in the filter is replaced with the supplied username.</p>
AuthenticationScope	onelevel	<p>The authentication search scope. The supported values for this are:</p> <ul style="list-style-type: none"> <li>• onellevel</li> <li>• subtree</li> </ul> <p>If you do not specify a value or if you specify an invalid value, the default value is used.</p>
AuthenticationSearchBase	none	<p>The search base used to authenticate users. If this value is not specified, the LDAP DefaultSearch-Base is used.</p>

Property	Default Value	Description
BindDN	none	<p>The user DN to bind against when building the initial LDAP connection.</p> <p>In many cases, this user may need read permissions on all user records. If you do not set a value, anonymous binding is used. Anonymous binding works on most servers without additional configuration.</p> <p>However, the LDAP attributer may also use this DN to create the users in the LDAP server. When the self-registration feature is used, this user may also need the requisite permissions to create a user record. This behavior can occur if you do not set <code>useUserCredentialsToBind</code> to <code>true</code>. In this case, the LDAP attributer uses this DN to update the user attributes.</p>
BindPassword	none	<p>BindPassword is the password for BindDN, which is used to authenticate any user. BindDN and BindPassword are used to separate the LDAP connection into units.</p> <p>The <code>AuthenticationMethod</code> property determines the bind method used for this initial connection.</p> <p>If you use an encrypted the password using the CSI encryption utility, append <code>.e</code> to the property name. For example:</p> <pre>CSI.loginModule.7.options. BindPassword.e=1-AAAAEgQQOLL+LpX JO8fO9T4SrQYRC9lRT1w5ePfdczQTDs P8iACk9mDAbm3F3p5a1wXWKK8+NdJuk nc7w2nw5aGJlyG3xQ==</pre>
RoleSearchBase	none	<p>The search base used to retrieve lists of roles. If this value is not specified, the LDAP <code>DefaultSearchBase</code> is used.</p>

Property	Default Value	Description
RoleFilter	<p>For SunONE/iPlanet: (&amp;(object-class=ldapsu-bentry) (objectclass=nsroledefinition))</p> <p>For Netscape Directory Server: (object-class=groupof-names) (object-class=groupofunique-names))</p> <p>For ActiveDirectory: (object-class=groupof-names) (object-class=group))</p>	<p>The role search filter. This filter should, when combined with the role search base and role scope, return a complete list of roles within the LDAP server. There are several default values depending on the chosen server type. If the server type is not chosen or this property is not initialized, no roles are available.</p>
RoleMemberAttributes	<p>For Netscape Directory Server: member,unique-member</p>	<p>The role's member attributes defines a comma-delimited list of attributes that roles may have that define a list of DN's of people who are in the role.</p> <p>These values are cross referenced with the active user to determine the user's role list. One example of the use of this property is when using LDAP groups as placeholders for roles. This property only has a default value when the Netscape server type is chosen.</p>
RoleNameAttribute	cn	<p>The attribute for retrieved roles that is the common name of the role. If this value is "dn" it is interpreted specially as the entire dn of the role as the role name.</p>
RoleScope	onelevel	<p>The role search scope. The supported values for this are:</p> <ul style="list-style-type: none"> <li>• onellevel</li> <li>• subtree</li> </ul> <p>If you do not specify a value or if you specify an invalid value, the default value is used.</p>

Property	Default Value	Description
UserRoleMembershipAttributes	For iPlanet/SunONE: nsRoleDN  For ActiveDirectory: memberOf  For all others: none	The user's role membership attributes property is used to define an attribute that a user has that contains the DN's of all of the roles as user is a member of.  These comma-delimited values are then cross-referenced with the roles retrieved in the role search base and search filter to come up with a list of user's roles.
UserFreeformRoleMembershipAttributes	None	The "freeform" role membership attribute list. Users who have attributes in this comma-delimited list are automatically granted access to roles whose names are equal to the attribute value. For example, if the value of this property is "department" and user's LDAP record has the following values for the department attribute, { "sales", "consulting" }, then the user will be granted roles whose names are "sales" and "consulting".
Referral	ignore	The behavior when a referral is encountered. The valid values are those dictated by LdapContext, for example, "follow", "ignore", "throw".
DigestMD5AuthenticationFormat	DN  For OpenLDAP: User-name	The DIGEST-MD5 bind authentication identity format.
UseUserAccountControlAttribute	For most LDAP servers: false  For ActiveDirectory: true	The UserAccountControl attribute to be used for detecting disabled user accounts, account expirations, password expirations and so on. ActiveDirectory also uses this attribute to store the above information.
controlFlag	optional	Indicates whether authentication with this login module is sufficient to allow the user to log in, or whether the user must also be authenticated with another login module. Rarely set to anything other than "sufficient" for any login module.  <b>Note:</b> controlFlag is a generic login module option rather than an LDAP configuration property.

**See also**

- *Setting Up Roles and Passwords* on page 34

## **Mapping Sybase Control Center Roles to LDAP or OS Groups**

To grant Sybase Control Center privileges to users who are authenticated through LDAP or the operating system, associate roles used in Sybase Control Center with groups in LDAP or the operating system.

You can configure Sybase Control Center to enable users to authenticate through their local operating system or through an LDAP server. To make this type of authentication work, Sybase Control Center roles must be mapped to groups that exist in the system providing authentication (LDAP or the operating system) or in the login module.

By default, Sybase Control Center assumes there is a “sybase” group in the authenticating system and maps the LDAP or OS “sybase” group to Sybase Control Center roles to provide basic privileges. The table lists additional default mappings of LDAP and OS groups to Sybase Control Center roles.

<b>Login module</b>	<b>OS group</b>	<b>Sybase Control Center roles</b>
UNIX Proxy	root	uaAnonymous, uaAgentAdmin, uaOSAdmin
	sybase	uaAnonymous, uaPluginAdmin, sccUserRole
	user	uaAnonymous, uaUser
	guest	uaAnonymous, uaGuest
NT Proxy	Administrators	uaAnonymous, uaAgentAdmin, uaOSAdmin
	sybase	uaAnonymous, uaPluginAdmin, sccUserRole
	Users	uaAnonymous, uaUser
	Guests	uaAnonymous, uaGuest
LDAP	sybase	uaAnonymous, uaPluginAdmin, sccUserRole

There are two ways to accomplish the mapping:

- (Recommended) Add a “sybase” group to the operating system or LDAP server Sybase Control Center is using to authenticate users, and add all users who need to access Sybase Control Center to the “sybase” group.
- Configure Sybase Control Center to use an existing group in LDAP or the operating system by editing the `roles-map.xml` file. This option is described here.

1. If Sybase Control Center is running, shut it down.

2. In a text editor, open:

```
<SCC-install-directory>/conf/roles-map.xml
```

3. Locate the appropriate login module (UNIX or NT (for Windows)).

## Get Started

4. Copy the line that maps the “sybase” group and paste it into the module just above the original sybase line.
5. Change “sybase” to the name of the group in your operating system to which Sybase Control Center users belong.

For example, if the group is `SCCusers`, the new line should look like this:

```
<role-mapping modRole="SCCusers"  
uafRole="uaAnonymous,uaPluginAdmin,sccUserRole" />
```

6. Save the file and exit.
7. Start Sybase Control Center.

### See also

- *Configuring an LDAP Authentication Module on page 32*

### **Encrypting a Password**

Use the **passencrypt** utility to encrypt passwords and other values that must be kept secure while stored in text files.

You can safely store an encrypted password in a properties file. Enter the password in clear text (unencrypted) when you execute **passencrypt** and when you use the password to log in.

**passencrypt**, which is located in the Sybase Control Center bin directory, uses the DES encryption algorithm.

1. Open a command window and change to the bin directory:

Windows: `cd <SCC-install-directory>\bin`

UNIX: `cd <SCC-install-directory>/bin`

2. To encrypt a password, enter **passencrypt**. Enter your new password at the resulting prompt.  
The **passencrypt** utility encrypts the password you enter and displays the password in encrypted form.
3. Copy the encrypted password.
4. Paste the encrypted password where needed.

### **Configuring Ports**

(Optional) Use the **scc -port** command to assign Sybase Control Center services to new ports.

### **Prerequisites**

Check for port conflicts between Sybase Control Center and other software running on the same host.



## Task

Sybase Control Center cannot function properly if other services use its ports. If you discover a conflict with any port listed in the right column below, you can either reconfigure the other service's port or reconfigure Sybase Control Center as described here.

Short port name	Description	Service names	Property names	Default port number
db	Database port	ScsSADataserver Messaging Alert Scheduler	com.sybase.asa.server.port messaging.db.port alert.database.port org.quartz.data-Source.ASA.URL	3638
http	Web HTTP port	EmbeddedWebContainer	http.port	8282
https	Web HTTPS (secure HTTP) port	EmbeddedWebContainer	https.port	8283
jiniHttp	JINI HTTP server	Jini	httpPort	9092
jiniRmid	JINI Remote Method Invocation daemon	Jini	rmidPort	9095
msg	Messaging port	Messaging	messaging.port	2000
rmi	RMI port	RMI	port	9999
tds	Tabular Data Stream™ port (used to communicate with other Sybase products)	Tds	tdsPort	9998

1. Shut down Sybase Control Center.
2. Execute **scc --info ports** to display a list of Sybase Control Center services, their properties, and their assigned ports.
3. To reassign a port, enter a command in one of these formats:  

```
scc --port port-name=port-number
```

```
scc --port service-name:property-name=port-number
```

## Get Started

Use the first, simpler format unless you want to configure the database services to use different ports. (By default, they all use the same port.)

4. Start Sybase Control Center.
5. Execute **scc --info ports** again to confirm that the port has been reassigned.

### Examples

Set all four database services (data server, messaging, database alert, and scheduler) to the same port, 3639. (The database is SQL Anywhere, used by the Sybase Control Center internal repository.)

```
scc --port db=3639
```

Set only the database messaging service to port 3639.

```
scc --port Messaging:messaging.db.port=3639
```

Set the HTTP port to 9292.

```
scc --port http=9292
```

Set the Jini RMI daemon to port 9696.

```
scc --port jiniRmid=9696
```

Set the main Sybase Control Center messaging service to port 2001.

```
scc --port msg=2001
```

Set the RMI port to 9991.

```
scc --port rmi=9991
```

Set the Tabular Data Stream port to 9997.

```
scc --port tds=9997
```

---

**Note:** **scc** commands that include a port-setting option (**-p** or **--port**, for example) do not start Sybase Control Center. To start SCC, execute a separate **scc** command.

---

## Configuring the E-mail Server

(Optional) Specify the e-mail server for Sybase Control Center to use to send e-mail alert notifications.

### Prerequisites

Launch Sybase Control Center and log in using an account with administrative privileges. (The login account or its group must have sccAdminRole.)

### Task

1. From the menu bar, select **Application > Administration**.
2. Select **General Settings**.

3. Click the **E-mail** tab.
4. Enter the name of the e-mail server through which Sybase Control Center will send alert notifications.
5. Change the default e-mail server port only in consultation with your e-mail administrator.
6. (Optional) Enter an e-mail address and click **Send** to dispatch a test message.  
If the test e-mail is received, you have properly configured the server for e-mail alert notifications.
7. Click **OK** (to apply the change and close the properties dialog) or **Apply** (to apply the change and leave the dialog open).

**Next**

(Optional) Configure automatic logout.

**See also**

- *Setting Up Security* on page 28

## **Configuring the Automatic Logout Timer**

(Optional) Set Sybase Control Center to end login sessions when users are inactive for too long.

**Prerequisites**

Launch Sybase Control Center and log in using an account with administrative privileges. (The login account or its group must have sccAdminRole.)

**Task**

1. From the menu bar, select **Application > Administration**.
2. Select **General Settings**.
3. Click the **Auto-Logout** tab.
4. Enter the number of minutes after which an idle user will be automatically logged out.  
Enter 0 or leave the box empty to disable automatic logout.
5. Click **OK** (to apply the change and close the properties dialog) or **Apply** (to apply the change and leave the dialog open).

## **User Authorization**

The authorization mechanism in Sybase Control Center employs login accounts and task-based roles.

Access to Sybase Control Center is controlled by login accounts. You grant permissions to a login account by assigning predefined roles that control tasks the user can perform in Sybase Control Center, such as administration and monitoring of particular types of Sybase servers. The roles can be assigned directly to login accounts or to groups; a login account inherits the

## Get Started

roles of any group to which it belongs. Component product modules assign some roles automatically.

Sybase Control Center classifies roles as follows:

- System roles – define how a user can interact with Sybase Control Center.
- Product roles – define how a user can interact with a particular managed resource in Sybase Control Center, for example the Replication Server named RepBoston01.

---

**Note:** The tools described here are for managing SCC-enabled login accounts; you cannot use them to manage accounts and groups that are native to your managed resource.

---

### See also

- *Configure* on page 49

### **Assigning a Role to a Login or a Group**

Use the security configuration options to add one or more roles to a Sybase Control Center login account or to a group. Roles enable users to perform tasks such as monitoring servers or administering Sybase Control Center.

### **Prerequisites**

You must have administrative privileges (sccAdminRole) to perform this task. To assign a monitoring role for a server, first register the server.

### **Task**

Assign the sccAdminRole to any login account that will perform administrative tasks in Sybase Control Center.

1. From the application menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Click **Logins** or **Groups**.
4. In the table, select the login account or group to which you want to assign a role.
5. Click the **Roles** tab.
6. In the **Available roles for resource** list, select the role, then click **Add**. For example, to grant administrative privileges, add the SCC Service:sccAdminRole. To grant monitoring privileges, add the MonitorRole for the desired server and server type.

---

**Note:** Sybase Control Center product modules assign certain roles automatically, so you might not need to add a MonitorRole.

---

If a role appears in the **Has following roles** list, this account or group has already been configured with that role.

7. Click **OK**.

**See also**

- *Adding a Group* on page 47
- *Adding a Login Account to a Group* on page 47
- *Logins, Roles, and Groups* on page 48

**Adding a Group**

Use the security configuration options to create a new group.

**Prerequisites**

You must have administrative privileges (sccAdminRole) to perform this task.

**Task**

Groups can make roles easier to manage. Rather than assigning roles to individual users, assign roles to groups and add users to the groups or remove them as needed.

1. From the main menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Select **Groups**.
4. Click **Create Group**.
5. Enter a group name and a description.
6. Click **Finish**.

**See also**

- *Assigning a Role to a Login or a Group* on page 46
- *Adding a Login Account to a Group* on page 47
- *Logins, Roles, and Groups* on page 48

**Adding a Login Account to a Group**

Use the security configuration options to add one or more login accounts to a group.

**Prerequisites**

You must have administrative privileges (sccAdminRole) to perform this task.

**Task**

1. From the main menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Click **Groups**.
4. Select the group to which you want to assign an account.
5. Click the **Membership** tab.

- 6. Select the account, then click **Add**.
- 7. Click **OK**.

**See also**

- *Assigning a Role to a Login or a Group* on page 46
- *Adding a Group* on page 47
- *Logins, Roles, and Groups* on page 48

**Logins, Roles, and Groups**

Sybase Control Center includes predefined login accounts and roles.

In Sybase Control Center, a login account identifies a user who can connect to the application. An account may have roles that specify the tasks the user is allowed to perform.

Sybase Control Center is designed to delegate user authentication to the operating system or to an LDAP directory service. Delegation requires some configuration, however, so Sybase Control Center comes with two predefined login accounts. Sybase recommends using the predefined accounts only for installing and setting up Sybase Control Center. These accounts are not intended for use in a production environment.

**Table 10. Predefined accounts**

Login name	Description
sccadmin	Can use all the administration features in Sybase Control Center
sccuser	Test account with no special privileges

A role is a predefined profile that can be assigned to a login account or a group. Roles control the access rights for login accounts. Sybase Control Center comes with predefined roles that are intended for use in production environments.

**Table 11. Predefined roles**

Role	Description
sccUserRole	Provides nonadministrative access to Sybase Control Center. Required for every user.
sccAdminRole	Provides administrative privileges for managing Sybase Control Center.
aseMonitorRole*	Provides privileges to monitor the Adaptive Server environment.
iqMonitorRole*	Provides privileges to monitor the Sybase IQ environment.
repMonitorRole	Provides privileges to monitor the replication environment.

Role	Description
repAdminRole	Provides administrative privileges for managing the replication environment.

\*These monitoring roles are assigned to users automatically by Sybase Control Center product modules; it is generally not necessary to assign them manually.

A group is made up of one or more login accounts; all the accounts in a group have the roles granted to the group. In Sybase Control Center you can create groups to suit your business requirements.

### See also

- *Assigning a Role to a Login or a Group* on page 46
- *Adding a Group* on page 47
- *Adding a Login Account to a Group* on page 47

## Configure

Configure login accounts, statistics collection, and other replication monitoring options.

1. *Registering a Replication Server, Replication Agent, or Mirror Replication Agent*  
Register a resource (for example, a server that can be monitored) to make Sybase Control Center aware of it and its connection information.
2. *Importing Resources for Batch Registration*  
(Optional) Import and register multiple servers from an interfaces or sql.ini file.
3. *Creating a Perspective*  
Create a perspective in which you can add and manage resources.
4. *Adding a Resource to a Perspective*  
Add one or more resources to the current perspective.
5. *Configuring a Login Account to Monitor Replication*  
Use the security configuration options to add one or more roles to a Sybase Control Center login account or to a group. Roles enable users to perform tasks such as monitoring servers or administering Sybase Control Center.
6. *Authenticating a Login Account for a Managed Resource*  
Specify the login account Sybase Control Center will use when it connects to your server or agent to collect monitoring data or manage the resource.
7. *Setting Up the Latency Monitoring Process*  
Start the latency monitoring process for replication paths in the replication environment.
8. *Setting Up Statistics Collection*

## Get Started

Use the Properties view of your managed resource to create a data collection job and add a schedule to the job.

### 9. *Setting Replication Parameters*

Configure replication parameters to improve server performance. Sybase Control Center for Replication allows you to configure the parameters for Replication Server, Replication Agent, connection and logical connection, route, and Adaptive Server RepAgent thread.

### 10. *Creating an Alert*

Use the Add Alert wizard to create an alert instance for your resource.

### 11. *Optional Configuration Steps*

Perform additional configuration, including user authorization, alerts, data collection scheduling, backups, and setting purging options for the repository.

### See also

- *User Authorization* on page 45
- *Logins, Roles, and Groups* on page 87
- *Setting Up Security* on page 63
- *Assigning a Role to a Login or a Group* on page 81

## Launching Sybase Control Center

---

Use the **scc** command to start Sybase Control Center.

### Prerequisites

Install Adobe Flash Player in the browser you will use for Sybase Control Center.

### Task

#### 1. Start Sybase Control Center.

- Windows – navigate to `<install_location>\SCC-3_2\bin` and double-click **scc.bat**.
- UNIX – execute **scc.sh**.

Messages on the progress of the launch appear in a command window. When Sybase Control Center is running, the command window becomes the Sybase Control Center console; you can issue commands to get status information on SCC and its ports, plug-ins, and services.

#### 2. Open a Web browser and enter `https://<hostname>:8283/scc`.

### See also

- *Sybase Control Center Console* on page 169



## Registering the ODBC Driver in Windows

In Windows, run **scc.bat** with administrative privileges to register the ODBC driver.

When Sybase Control Center starts for the first time on a Windows machine, it registers its ODBC driver. Because the automatic registration of the ODBC driver edits the registry settings, you must execute **scc.bat** using elevated administrative privileges. If you launch for the first time without adequate privileges, Sybase Control Center generates an error and fails to start.

In Windows Vista, Windows 2008, and Windows 7, you must use the **Run as administrator** setting to launch Sybase Control Center even if you already have administrative privileges. This process is described below.

In other versions of Windows, you must be logged in as an administrator to start Sybase Control Center for the first time. You need not follow the steps below.

1. In Windows Vista, Windows 2008, or Windows 7, open the command prompt window with administrative privileges:
  - Select **Start > All Programs > Accessories**. Right-click **Command Prompt** and select **Run as administrator**.
  - Alternatively, enter **cmd** in the Start Menu search box and press **Shift+Ctrl+Enter**.
2. Run **scc.bat**.

### **See also**

- *Starting and Stopping Sybase Control Center in Windows* on page 51
- *Starting and Stopping Sybase Control Center in UNIX* on page 53
- *Configuring Memory Usage* on page 56
- *scc Command* on page 59

## Starting and Stopping Sybase Control Center in Windows

There are several ways to start and stop Sybase Control Center or the SCC agent. You can start manually, which is useful for testing and troubleshooting, or set the service to start automatically and to restart in case of failure.

This topic applies to both Sybase Control Center (the server) and the Sybase Control Center agent that runs on each product server managed by SCC.

If you run Sybase Control Center or the SCC agent manually, you must issue a command every time you start or shut down. If you run as a service (which is recommended), you can configure Windows to automatically start and restart Sybase Control Center or the SCC agent. These are the options:

- Use the **scc.bat** command to start Sybase Control Center or the SCC agent manually. The command gives you access to the Sybase Control Center console, which you can use to shut down and to display information about services, ports, system properties, and

## Get Started

environment variables. You can also use **scc.bat** to change the logging level for troubleshooting purposes. Using **scc.bat** prevents you from taking advantage of the automatic start and restart features available to services.

- Use the Services list under the Windows Control Panel to start, stop, and configure the Sybase Control Center service.
- Use the **net start** and **net stop** commands. This is another way to run Sybase Control Center or the SCC agent as a service.

---

**Note:** To start or stop Sybase Control Center as a service, you must have selected **Yes** in the installer to install Sybase Control Center as a service.

---

The installer attempts to start Sybase Control Center or the SCC agent as a service and configures the service to restart automatically. Before starting, check the Windows Services list for a Sybase Control Center service.

Here are the steps for each option:

- **Start Sybase Control Center or the SCC agent:**
  - a) (Skip this step for the SCC agent.) If you are starting Sybase Control Center for the first time in Windows Vista, Windows 2008, or Windows 7, set the **Run as Administrator** option on the command prompt so that Sybase Control Center can register its ODBC driver. (This is necessary even if you are logged in as an administrator.)

b) Enter:

```
%SYBASE%\SCC-3_2\bin\scc.bat
```

- **Stop Sybase Control Center or the SCC agent:**

a) Enter:

```
%SYBASE%\SCC-3_2\bin\scc.bat --stop
```

---

**Note:** You can also enter **shutdown** at the `scc-console>` prompt.

---

- **Start or stop from the Windows Control Panel; configure automatic start and restart:**
  - a) Open the Windows Control Panel.
  - b) Select **Administrative Tools > Services**.
  - c) Locate Sybase Control Center 3.2. If the service is running, the status column displays “Started.”
  - d) To start or stop the service, right-click **Sybase Control Center 3.2** and choose **Start** or **Stop**.
  - e) To configure automatic starting, double-click the service.
  - f) To set the service to automatically start when the machine starts, change the **Startup type** to Automatic.

- g) To restart the service in case of failure, choose the **Recovery** tab and change the First, Second, and Subsequent failures to Restart Service.
- h) Click **Apply** to save the modifications and close the dialog.
- **Start or stop the Sybase Control Center service (controlling either Sybase Control Center or the SCC agent) from the Windows command line:**

- a) To start the service, enter:

```
net start "sybase control center 3.2"

The Sybase Control Center 3.2 service is starting.....
The Sybase Control Center 3.2 service was started
successfully.
```

- b) To stop the service, enter:

```
net stop "sybase control center 3.2"

The Sybase Control Center 3.2 service is stopping.....
The Sybase Control Center 3.2 service was stopped
successfully.
```

### See also

- *Registering the ODBC Driver in Windows* on page 51
- *Starting and Stopping Sybase Control Center in UNIX* on page 53
- *Configuring Memory Usage* on page 56
- *scc Command* on page 59

## Starting and Stopping Sybase Control Center in UNIX

You can start Sybase Control Center or the SCC agent manually, which is useful for testing and troubleshooting, or you can set up a service to start automatically and to restart in case of failure.

This topic applies to both Sybase Control Center (the server) and the Sybase Control Center agent that runs on each product server managed by SCC.

If you start Sybase Control Center or the SCC agent on a managed server manually, you must issue a command every time you want to start or stop it. If you run Sybase Control Center or the SCC agent as a service (which is recommended), you can configure the service to start and restart automatically. These are the options:

- Use the **scc.sh** script to start Sybase Control Center or the SCC agent manually. You can do this in two ways:
  - Run **scc.sh** in the foreground to get access to the Sybase Control Center console, which you can use to shut down and to display information about services, ports, system properties, and environment variables.
  - Run **scc.sh** in the background to suppress the console.

## Get Started

You can use **scc.sh** to run Sybase Control Center at a nondefault logging level for troubleshooting. When you start manually with **scc.sh**, you cannot take advantage of the automatic start and restart features available to services.

- Use the **sccd** script to configure a service that starts Sybase Control Center or the SCC agent automatically.

Here are the steps for each option:

- **Before you start Sybase Control Center or the SCC agent for the first time, set environment variables.** Do this only once.
  - a) Change to the Sybase directory (the parent of the Sybase Control Center installation directory).
  - b) Execute one of the following to set environment variables.

Bourne shell:

```
. SYBASE.sh
```

C shell:

```
source SYBASE.csh
```

- **Run Sybase Control Center or the SCC agent in the foreground.**

Running in the foreground is a method of manually starting; you must issue commands to stop and restart Sybase Control Center or the SCC agent when you use this method.

- a) To start Sybase Control Center or the SCC agent and drop into the console when the start-up sequence is finished, enter:

```
.$SYBASE/SCC-3_2/bin/scc.sh
```

- **Run Sybase Control Center or the SCC agent in the background.**

You can use **nohup**, **&**, and **>** to run Sybase Control Center or the SCC agent in the background, redirect output and system error to a file, and suppress the SCC console. Sybase recommends that you do this from the Sybase Control Center `bin` directory. Running in the background is a method of manually starting; you must issue commands to stop and restart Sybase Control Center or the SCC agent when you use this method.

- a) Execute a command similar to the sample below that matches your shell. Both sample commands direct output to the file `scc-console.out`. If the output file already exists, you might need to use additional shell operators to append to or truncate the file.

For Bourne shell (sh) or Bash:

```
cd <SCC-install-dir>/bin; nohup ./scc.sh 2>&1 > scc-console.out &
```

For C shell:

```
cd <SCC-install-dir>/bin; nohup ./scc.sh >& scc-console.out &
```

- **Shut down Sybase Control Center or the SCC agent.**

- a) To shut down from the `scc-console>` prompt, enter:

```
shutdown
```

---

**Warning!** Do not enter **shutdown** at a UNIX prompt; it shuts down the operating system.

---

To shut down from the UNIX command line, enter:

```
$$SYBASE/SCC-3_2/bin/scc.sh --stop
```

- **Configure Sybase Control Center or the SCC agent to run as a service.**

A UNIX service is a daemon process that starts automatically after the machine is started and runs in the background. UNIX installations of Sybase Control Center include a shell script, **sccd**, which you can use to configure the Sybase Control Center service. (Some UNIX platforms supply tools that make service configuration easier; Linux **chkconfig** is an example.)

---

**Note:** Sybase recommends that if you are not familiar with the process of setting up services in UNIX, you delegate this task to a system administrator or consult the system administration documentation for your UNIX platform.

---

a) Copy `$$SYBASE/SCC-3_2/bin/sccd` into this directory:

- AIX (SCC agent only): `/etc/rc.d/init.d`
- HP-UX (SCC agent only): `/sbin/init.d`
- All other platforms: `/etc/init.d`

b) Open `sccd` and edit the line that sets the SYBASE variable. Set it to the location of your Sybase installation (that is, the parent of `SCC-3_2`, the Sybase Control Center installation directory).

c) In Linux, execute these commands to configure the service to run in run levels 2, 3, 4, and 5:

```
/usr/sbin/chkconfig --add sccd
/usr/sbin/chkconfig --level 2345 sccd
```

You can test the `sccd` script with `/usr/sbin/service sccd status`. (The **service** command accepts these options: `start | stop | status | restart`.)

d) On non-Linux platforms, locate this directory:

- AIX (SCC agent only): `/etc/rc.d/rc<X>.d`
- HP-UX (SCC agent only): `/sbin/rc<X>.d`
- Solaris: `/etc/rc<X>.d`

Where `<X>` is the run level (for example, 3). Make two soft links in the directory for your platform and set the links to point to:

- AIX (SCC agent only): `/etc/rc.d/init.d/sccd: S90sccd` and `/etc/rc.d/init.d/sccd: K10sccd`
- HP-UX (SCC agent only): `/sbin/init.d/sccd: S90sccd` and `/sbin/init.d/sccd: K10sccd`

## Get Started

- Solaris: `/etc/init.d/sccd: S90sccd` and `/etc/init.d/sccd: K10sccd`

The `S90sccd` link starts the service and the `K10sccd` link stops the service. The two-digit numbers in the links indicate the start and stop priorities of the service.

- e) Use the `S90sccd` and `K10sccd` links to test starting and stopping the service. The links are called automatically when the machine is started or shut down.

### See also

- *Registering the ODBC Driver in Windows* on page 51
- *Starting and Stopping Sybase Control Center in Windows* on page 51
- *Configuring Memory Usage* on page 56
- *scc Command* on page 59

## Configuring Memory Usage

(Optional) Determine whether you need to configure how much memory Sybase Control Center uses, and if so which configuration method to use.

It is not usually necessary to configure memory usage for Sybase Control Center. This table lists memory options you can set and circumstances under which you should consider changing them.

Modify this value	When	Guidelines
<p>Maximum memory</p> <ul style="list-style-type: none"><li>• <code>SCC_MEM_MAX</code> – if you are starting SCC from the command line or running it as a UNIX service</li><li>• <code>jvmopt=-Xmx</code> – if you are running SCC as a Windows service</li></ul>	<ul style="list-style-type: none"><li>• You need to prevent Sybase Control Center from using more than a given amount of memory</li><li>• An <code>OutOfMemory</code> error says Sybase Control Center is out of heap space</li><li>• A warning message about system memory appears during the start process</li><li>• The machine where Sybase Control Center is installed has less than 2GB of memory. (Starting SCC on a machine with less than 2GB of memory triggers the start-up warning message about system memory.)</li></ul>	<p>On machines with less than 2GB of memory, set maximum memory to 256MB or more.</p> <p>Default value: none. (On machines with 2GB or more of memory, maximum memory is set dynamically and is effectively limited only by the amount of system memory available.)</p>

Modify this value	When	Guidelines
Permanent memory <ul style="list-style-type: none"> <li>• <code>SCC_MEM_PERM</code> – if you are starting SCC from the command line or running it as a UNIX service</li> <li>• <code>jvmopt=-XX:MaxPermSize</code> – if you are running SCC as a Windows service</li> </ul>	An OutOfMemory error says Sybase Control Center is out of permanent generation space	Increase by 32MB increments. If you reach a value equal to twice the default and still see the OutOfMemory error, contact Sybase technical support.  Default value: 128MB

You can change memory options in two ways:

- For Sybase Control Center started from the command line – execute commands to set one or more environment variables before executing the **scc** command to start Sybase Control Center. When you use this method, your changes to the memory options last only as long as the current login session. This method is useful for testing new option values.
- For the Sybase Control Center service – modify a file used by the Sybase Control Center service. (Windows and UNIX services use different files.) When you use this method, your changes to the memory options persist—Sybase Control Center uses them every time it starts as a service.

### See also

- *Registering the ODBC Driver in Windows* on page 51
- *Starting and Stopping Sybase Control Center in Windows* on page 51
- *Starting and Stopping Sybase Control Center in UNIX* on page 53
- *scc Command* on page 59

### Changing a Memory Option on the Command Line

Before you start Sybase Control Center from the command line, you can issue a command to change the value of a memory option temporarily.

Changes made using this method last only as long as the current login session. This method is useful for testing new option values.

1. If Sybase Control Center is running, shut it down.
2. Set the environment variable using a command appropriate for your operating system. Specify a size in megabytes but do not indicate the units in the command.

Windows example:

```
> set SCC_MEM_MAX=512
```

UNIX example:

```
bash$ export SCC_MEM_MAX=512
```

3. Use the **scc** command to start Sybase Control Center.

### See also

- *Changing a Memory Option for an SCC Windows Service* on page 58
- *Changing a Memory Option for an SCC UNIX Service* on page 58
- *Starting and Stopping Sybase Control Center in Windows* on page 51
- *Starting and Stopping Sybase Control Center in UNIX* on page 53
- *scc Command* on page 59

### **Changing a Memory Option for an SCC Windows Service**

Add a **jvmopt** command to the `scc.properties` file to change a memory option (`-Xmx` or `-XX:MaxPermSize`) for a Sybase Control Center Windows service.

When you use this method to set memory options, your changes are permanent—Sybase Control Center uses them every time it starts as a service.

1. If Sybase Control Center is running, shut it down.
2. Open the SCC properties file:  

```
<SCC-install-directory>\SCC-3_2\bin\scc.properties
```
3. Add (or modify, if it already exists) a **jvmopt** line specifying the memory size in Java format. Use `m` for megabytes or `g` for gigabytes.

For example:

```
jvmopt=-Xmx512m
```

4. Save the file and start the Sybase Control Center Windows service.

### See also

- *Changing a Memory Option on the Command Line* on page 57
- *Changing a Memory Option for an SCC UNIX Service* on page 58
- *Starting and Stopping Sybase Control Center in Windows* on page 51

### **Changing a Memory Option for an SCC UNIX Service**

To change a memory setting for a Sybase Control Center UNIX service, add the appropriate environment variable (`SCC_MEM_MAX` or `SCC_MEM_PERM`) to the `sccd` script.

When you use this method to set memory options, your changes are permanent—Sybase Control Center uses them every time it starts as a service.

1. If Sybase Control Center is running, shut it down.
2. Open the `sccd` file: `/etc/init.d/sccd`



3. Add the environment variable at the top of the file (after the comments). Specify a size in megabytes but do not indicate the units in the command.

For example:

```
SCC_MEM_MAX=512
```

4. Save the file and start the Sybase Control Center UNIX service.

### See also

- *Changing a Memory Option on the Command Line* on page 57
- *Changing a Memory Option for an SCC Windows Service* on page 58
- *Starting and Stopping Sybase Control Center in UNIX* on page 53

## scc Command

Use **scc.bat** (Windows) or **scc.sh** (UNIX) to start and stop Sybase Control Center and to perform administrative tasks like configuring ports, enabling, and disabling services.

### Syntax

```
scc[.bat | .sh] [-a | --address RMI-service-address]
[-b | --bitwidth]
[--dbpassword]
[-disable | --disable service-names]
[-enable | --enable service-names]
[-h | --help]
[-I | --info [information-category]]
[-m | --message message-level]
[-password | --password password]
[-p | -port | -ports | --port | --ports {port-name=port-number |
service-name:property-name=port-number}]
[{-start | --start} | {-stop | --stop}]
[-status | --status]
[-user | --user login-name]
[-version | --version]
```

### Parameters

- **-a | --address *RMI-service-address*** – the address for the RMI service to use; must be an IP address on this machine or the name of this machine (which is the default).
- **-b | --bitwidth** – returns a string identifying the bit width (32 or 64) of the underlying platform; Sybase Control Center uses this option to determine which libraries to use for its internal database. If you use this option, the **scc** command does not start Sybase Control Center.
- **--dbpassword** – changes the password of the default dba account provided for the repository database. It prompts you for the new password, validates it, and starts the Sybase Control Center server. This option does not work if you start Sybase Control Center in the background—the server fails to start if there is no console.
- **-disable | --disable *service-names*** – disable the specified Sybase Control Center services. This option does not work while Sybase Control Center is running or as part of a command

that starts SCC. To use it, shut down SCC, execute `scc --disable`, then restart. Separate each service from the next with a comma.

- **-enable** | **--enable** *service-names* – enable the specified Sybase Control Center services. Separate each service from the next with a comma. When you use this option, **scc** does not start Sybase Control Center—use a separate command to start SCC.
- **-h** | **--help** – display help and usage information for the **scc** command. If you use this option, **scc** does not start Sybase Control Center.
- **-I** | **--info** [*information-category*] – display the specified categories of information about Sybase Control Center. Separate each category from the next with a comma. The information categories are:
  - **all** – returns all the information provided by the `sys`, `ports`, and `services` categories. Default option.
  - **sys** – returns general information about this instance of Sybase Control Center, including the version, the home (installation) directory, the host machine’s name and IP address, the RMI port number, the messaging level, and details about the platform and Java installation.
  - **ports** – lists all the ports on which the Sybase Control Center agent and its services listen, indicates whether each port is in use, and shows the service running on each port.
  - **services** – lists all the services known to the Sybase Control Center agent, indicates whether each service is enabled, and lists other services on which each service depends.
  - **sysprop** – lists all the Java system properties known the Java VM and their values.
  - **env** – lists the complete Java VM process environment.
- **-m** | **--message** *message-level* – set the amount of detail recorded in system logs; also known as the logging level. Valid values are OFF, FATAL, ERROR, WARN, INFO, DEBUG, and ALL. WARN is the default.
- **-password** | **--password** – specify the password of the user account Sybase Control Center will use to stop servers or query them for status. Use this option with **--user**. When you enter a command with **--user** but without **--password**, the console prompts you to enter a password.
- **-p** | **-port** | **-ports** | **--port** | **--ports** {*port-name=port-number* | *service-name:property-name=port-number*} – configure the specified service to run on the specified port. Changing ports is useful if you discover a port conflict between Sybase Control Center and other software on the same system. When you use this option, **scc** does not start Sybase Control Center—use a separate command to start SCC.

Valid port names, service names and property names are:

Short port name	Description	Service names	Property names	Default port number
db	Database port	ScsSADataserver Messaging Alert Scheduler	com.sybase.asa.server.port messaging.db.port alert.database.port org.quartz.data- Source.ASA.URL	3638
http	Web HTTP port	EmbeddedWebCon- tainer	http.port	8282
https	Web HTTPS (se- cure HTTP) port	EmbeddedWebCon- tainer	https.port	8283
jiniHttp	JINI HTTP server	Jini	httpPort	9092
jiniRmid	JINI Remote Meth- od Invocation dae- mon	Jini	rmidPort	9095
msg	Messaging port	Messaging	messaging.port	2000
rmi	RMI port	RMI	port	9999
tds	Tabular Data Stream™ port (used to communicate with other Sybase products)	Tds	tdsPort	9998

You can also execute `scc --info ports` to display service names and associated property names; they appear in the first two columns of the output.

- **-start | --start** – start the Sybase Control Center server. This is the default option—if you execute **scc** with no options, it starts SCC. This option cannot be combined in the same command with options that set ports or enable or disable services; use a separate **scc** command to start SCC.
- **-status | --status** – display a status message indicating whether the Sybase Control Center server is running.
- **-stop | --stop** – shut down the Sybase Control Center server if it is running.
- **-user | --user [login-name]** – specify the user account Sybase Control Center will use to stop managed servers or query them for status. Use this option with **--password**. If you do not enter a login name, the console prompts you to enter one.
- **-version | --version** – display the version of Sybase Control Center software running on this server. If you use this option, **scc** does not start Sybase Control Center.

## Examples

- **Set the RMI port** – each of these commands sets the RMI port to 9999 (the default). The first command illustrates the port name syntax; the second illustrates the service name:property name syntax.

```
scc --port rmi=9999  
scc --port RMI:port=9999
```

- **Set the RMI port and start SCC** – these commands set the RMI port to 9996, then start SCC. Two commands (separated by a semicolon here) are needed because **scc** does not start Sybase Control Center when it includes any of the port-setting options.

```
scc -p rmi=9996; scc
```

- **Set all database ports** – this command sets all four of the SQL Anywhere database ports (data server, messaging, database alert, and scheduler) to 3638. (SQL Anywhere is the Sybase Control Center internal repository.)

```
scc -port db=3638
```

- **Set the TDS port** – this command sets the TDS port to 9998 (the default):

```
scc --ports Tds:tdsPort=9998
```

- **Enable a service and start SCC** – these commands enable the TDS service, then start SCC. Two commands (separated by a semicolon here) are needed because **scc** does not start Sybase Control Center when it includes the **-enable** option.

```
scc -enable Tds; scc
```

## Permissions

**scc** permission defaults to all users. No permission is required to use it.

### See also

- *Registering the ODBC Driver in Windows* on page 51
- *Starting and Stopping Sybase Control Center in Windows* on page 51
- *Starting and Stopping Sybase Control Center in UNIX* on page 53
- *Configuring Memory Usage* on page 56
- *Configuring Ports* on page 77
- *Logging or Message Levels* on page 167

## Logging in to Sybase Control Center

---

Enter the Sybase Control Center Web console.

### Prerequisites

Install Adobe Flash Player in the browser you will use for SCC. See the *Sybase Control Center Installation Guide*.

## Task

Sybase Control Center typically authenticates users through the operating system or an LDAP directory service. Consult your SCC administrator if you are not sure which login account to use for SCC.

---

**Note:** When logging in to a newly installed Sybase Control Center for which secure authentication has not been configured, use the sccadmin account (with no password, by default). For more information, see the *Sybase Control Center Installation Guide*.

---

1. Connect to the Sybase Control Center server. In your Web browser, enter: `https://scc-hostname:8283/scc`.
2. Enter your user name and password, and click **Login**.

---

**Tip:** If you use a Windows account to log in to SCC, enter your user name in the format `username@domain`. Omit top-level domain extensions such as `.com` or `.net`—for example, enter `fred@sybase`, not `fred@sybase.com`.

---

## Logging out of Sybase Control Center

---

When you finish working in Sybase Control Center, end your login session.

From the main menu bar, select **Application > Logout**.

Alternatively, click **Logout** in the upper-right corner of the window.

---

**Note:** If an administrator has configured the automatic logout feature, Sybase Control Center logs you out if your session is idle (no typing or mouse movement) for longer than the timeout period, which is set by the administrator.

---

## Setting Up Security

---

Configure login authentication and map roles.

Read about security and follow these procedures before you configure Sybase Control Center product modules.

---

**Note:** These security topics are intended for use in a production environment. If you are evaluating or testing SCC, see the *Installation Guide* for instructions on getting started quickly.

---

1. *Security*

Sybase Control Center can authenticate user logins through an LDAP server, through the operating system, or both.

2. *Configuring Authentication for Windows*

Authentication through the Windows operating system is enabled by default, but it requires some configuration. First, set Sybase Control Center to create an account when a Windows user logs in to Sybase Control Center.

### 3. *Configuring a Pluggable Authentication Module (PAM) for UNIX*

Set up Sybase Control Center to support username and password login using accounts on the UNIX operating system. Optionally, have Sybase Control Center create an account when a UNIX user first logs in to Sybase Control Center.

### 4. *Configuring an LDAP Authentication Module*

Configure an LDAP authentication module for Sybase Control Center by editing the security properties file to point to the correct LDAP server.

### 5. *Mapping Sybase Control Center Roles to LDAP or OS Groups*

To grant Sybase Control Center privileges to users who are authenticated through LDAP or the operating system, associate roles used in Sybase Control Center with groups in LDAP or the operating system.

### 6. *Encrypting a Password*

Use the `passencrypt` utility to encrypt passwords and other values that must be kept secure while stored in text files.

### 7. *Configuring Ports*

(Optional) Use the `scc -port` command to assign Sybase Control Center services to new ports.

## **Security**

Sybase Control Center can authenticate user logins through an LDAP server, through the operating system, or both.

- Sybase Control Center can be configured to authenticate through any LDAP server that supports the `inetOrgPerson` (RFC 2798) schema.
- When Sybase Control Center authenticates through the operating system, it uses the operating system of the Sybase Control Center server machine (not the client).

Although you can create native user accounts in Sybase Control Center, Sybase does not recommend this approach to authentication. It is simpler and safer to configure Sybase Control Center to authenticate using existing LDAP, Windows, or UNIX login accounts.

Sybase strongly recommends that you use a common authentication provider for all Sybase products, including Sybase Control Center. A common authentication provider ensures that single sign-on works for users of Sybase Control Center and its managed servers.

Sybase Control Center requires each authenticated login account to have a predefined role. When a login is authenticated, roles for the login are retrieved by the security module and are mapped to Sybase Control Center predefined roles. Authorization is resolved through the mappings between the security module native roles and Sybase Control Center roles. You can enable mappings by creating a "sybase" group in your operating system or LDAP server and adding all Sybase Control Center users, or by modifying the Sybase Control Center `roles-`

map.xml file to configure the mapping of native roles to Sybase Control Center roles. The security module authenticates the logins and authorizes access to managed resources.

Sybase Control Center provides a set of predefined login modules for authentication. All login modules are defined in the `<install_location>/SCC-3_2/conf/csi.properties` file. The syntax is defined by the Sybase Common Security Infrastructure (CSI) framework. You can configure the different login modules to customize security strength. The login modules are:

- **Simple Login** – defines a user name, password, and a list of roles. The default user name is “sccadmin” with a blank password and a native role of “sccAdminRole”. You can create additional accounts by adding simple login modules to `csi.properties`. However, Sybase does not recommend the use of simple login modules for authentication in production environments.

---

**Note:** Add a password for the sccadmin account as soon as possible after you install Sybase Control Center. See the *Sybase Control Center Installation Guide* for instructions.

- **NT Proxy Login** – delegates authentication to the underlying Windows operating system. When you log in to Sybase Control Center through an NT Proxy Login module, enter your user name in the format `username@nt-domain-name`. For example, `user@sybase`. Windows authentication is enabled by default, but it requires some configuration.
- **UNIX Proxy Login** – delegates authentication to the underlying UNIX or Linux operating system using Pluggable Authentication Modules (PAM). When you log in to Sybase Control Center through a UNIX PAM, enter only your user name. UNIX authentication is enabled by default, but it requires some configuration.
- **LDAP Login** – delegates authentication to an LDAP server you specify. When you log in to Sybase Control Center through an LDAP server, enter only your user name. LDAP authentication is not enabled by default; you must configure the login module.

## Configuring Authentication for Windows

Authentication through the Windows operating system is enabled by default, but it requires some configuration. First, set Sybase Control Center to create an account when a Windows user logs in to Sybase Control Center.

This task is optional. However, if you choose not to create Sybase Control Center accounts automatically as described here, you must enter them manually. Sybase Control Center needs the accounts for purposes of setting authorization (user privileges).

1. Log in to Sybase Control Center using an account with administrative privileges. (The login account or its group must have sccAdminRole.)
2. Select **Application > Administration > Security**.
3. Check the box labeled **Automatically add SCC login records for authenticated logins**.
4. Check the box labeled **Automatically grant sccUserRole to newly created logins**.

5. Click **OK** to close the Security dialog.

**Next**

There are two next steps:

- If you opted not to automatically create Sybase Control Center login accounts, enter each account into Sybase Control Center manually.
- Whether you add accounts automatically or manually, you must grant privileges to any login accounts that require more than basic user access. You can grant privileges by assigning Sybase Control Center roles directly to the login accounts, or by assigning the login accounts to groups and mapping Sybase Control Center roles to the groups. The group approach is generally more efficient.

**See also**

- *Mapping Sybase Control Center Roles to LDAP or OS Groups* on page 76
- *Adding a Login Account to the System* on page 85

**Configuring a Pluggable Authentication Module (PAM) for UNIX**

Set up Sybase Control Center to support username and password login using accounts on the UNIX operating system. Optionally, have Sybase Control Center create an account when a UNIX user first logs in to Sybase Control Center.

1. Using a login account with root privileges, configure the pluggable authentication module for your platform:

Platform	Action
Solaris	Append the contents of the <SCC-install-dir>/utility/sunos/pam.conf file (provided with Sybase Control Center) to the /etc/pam.conf file on your Solaris platform.
Linux	Copy the <SCC-install-dir>/utility/linux/sybase-ua file (provided with Sybase Control Center) to the /etc/pam.d directory on your Linux platform.  <b>Note:</b> The sybase-ua file provided with Sybase Control Center is not compatible with the most recent SUSE Linux versions. For SUSE 11 and later, see the example at the end of this topic.

**Note:** In the table above, the portion of the path that indicates the operating system might differ slightly from what is shown.

2. (Skip if you configured a PAM before starting Sybase Control Center) Restart Sybase Control Center.
3. (Optional) If you want Sybase Control Center to create an account when a UNIX user logs in to Sybase Control Center, execute these steps. If you choose not to create Sybase



Control Center accounts automatically, you must enter them manually. Sybase Control Center needs the accounts for purposes of setting authorization (user privileges).

- a) Log in to Sybase Control Center using an account with administrative privileges (sccAdminRole).
- b) Select **Application > Administration > Security**.
- c) Check the box labeled **Automatically add SCC login records for authenticated logins**.
- d) Click **OK** to close the Security dialog.

### Example: PAM for SUSE Linux 11 and later

For SUSE 11 and later, do not use the `sybase-ua` file provided with Sybase Control Center. Instead, in your `/etc/pam.d` directory, create a `sybase-ua` file that contains:

```
# sybase-ua PAM Configuration (SUSE style)
auth      include      common-auth
account   include      common-account
password  include      common-password
session   include      common-session
```

### Next

There are two next steps:

- If you opted not to automatically create Sybase Control Center login accounts, enter each account into Sybase Control Center manually.
- Whether you add accounts automatically or manually, you must also grant privileges to the login accounts. You can grant privileges by assigning Sybase Control Center roles directly to the login accounts, or by assigning the login accounts to groups and mapping Sybase Control Center roles to the groups. The group approach is generally more efficient.

### See also

- *Mapping Sybase Control Center Roles to LDAP or OS Groups* on page 76
- *Adding a Login Account to the System* on page 85

## Configuring an LDAP Authentication Module

Configure an LDAP authentication module for Sybase Control Center by editing the security properties file to point to the correct LDAP server.

1. Open the `<SCC-install-dir>\conf\csi.properties` file.
2. Uncomment the LDAP module in the properties file by removing the `#` symbol at the beginning of each line (or, if necessary, add an LDAP module to the file). The sample module below specifies the LDAP server that will provide user authentication.

The sample module shows the properties used for an OpenDS LDAP server. See the example at the end for values that work for ActiveDirectory. Configuration properties you can use in the LDAP module are described in a subtopic.

## Get Started

Each line of the LDAP server module of the properties file must begin with "CSI.loginModule." followed by a module number. (The module number in this sample is 7.) The module number you assign must be unique in the properties file, and you must use the same module number in every line of the module.

```
CSI.loginModule.  
7.options.AuthenticationSearchBase=ou=users,dc=example,dc=com  
CSI.loginModule.7.options.BindDN=cn=Directory Manager  
CSI.loginModule.7.options.BindPassword=secret  
CSI.loginModule.7.options.DefaultSearchBase=dc=example,dc=com  
CSI.loginModule.7.options.ProviderURL=ldap://localhost:10389  
CSI.loginModule.  
7.options.RoleSearchBase=ou=groups,dc=example,dc=com  
CSI.loginModule.7.options.ServerType=openldap  
CSI.loginModule.7.options.moduleName=LDAP Login Module  
CSI.loginModule.7.controlFlag=sufficient  
CSI.loginModule.  
7.provider=com.sybase.ua.services.security.ldap.LDAPLoginModule
```

---

**Note:** Change the values of bolded lines only.

---

3. Save the file.
4. If your LDAP server's SSL certificate is signed by a nonstandard certificate authority (for example, if it is a self-signed certificate), use the **keytool** utility to configure your JVM or JDK to trust the certificate. Execute a command similar to this:

```
keytool -import -keystore <sybase-dir>/shared/JRE-6_0_6/bin/  
keytool/lib/security/cacerts -file  
<your cert file and path> -alias ldapcert -storepass changeit
```

### LDAP configuration values for ActiveDirectory

For an ActiveDirectory server, use these values for configuration properties in your LDAP login module:

```
ServerType: msad2K  
DefaultSearchBase: dc=<domainname>,dc=<tld> or o=<company  
name>,c=<country code>  
E.g. dc=sybase,dc=com or o=Sybase,c=us  
ProviderUrl: ldaps://<hostname>:<port>  
E.g.: ldaps://myserver:636  
AuthenticationFilter: (&(userPrincipalName={uid})  
(objectclass=user))  
BindDN: <User with read capability for all users>  
BindPassword: <Password for BindDN user>  
RoleFilter: (|(objectclass=groupofnames) (objectclass=group))  
controlFlag: sufficient
```

### Next

There are two additional steps:

- Set up roles and passwords for LDAP

- Map Sybase Control Center role to LDAP groups

### See also

- *Mapping Sybase Control Center Roles to LDAP or OS Groups* on page 76

### Setting Up Roles and Passwords

Set the initial user roles and passwords required for Sybase Control Center to authenticate through an LDAP server.

### Prerequisites

Configure an LDAP authentication module.

### Task

1. Open the `<SCC-install-dir>\conf\roles-map.xml` file and add an LDAP login module.

Insert an LDAP login module similar to this at the end of the security-modules portion of the file, just before `</security-modules>`:

```
<module name="LDAP Login Module">
  <role-mapping modRole="sybase"
    uafRole="uaAnonymous,uaPluginAdmin,sccUserRole" />
  <role-mapping modRole="administrators"
    uafRole="uaAnonymous,sccAdminRole" />
</module>
```

2. Ensure that the roles defined in the LDAP repository match the roles defined in `roles-map.xml`.
3. In the `<SCC-install-dir>\conf\csi.properties` file, set the `BindPassword` and `ProviderURL` properties with values used in your deployment.  
Sybase recommends that you encrypt sensitive values before saving them in `csi.properties`.

### Next

Map Sybase Control Center roles to LDAP groups.

### See also

- *LDAP Configuration Properties* on page 70
- *Encrypting a Password* on page 77

### **LDAP Configuration Properties**

Use these properties in your `csi.properties` file to control your LDAP service.

<b>Property</b>	<b>Default Value</b>	<b>Description</b>
ServerType	None	<p>Optional. The type of LDAP server you are connecting to:</p> <ul style="list-style-type: none"> <li>• <code>sunone5</code> -- SunOne 5.x OR iPlanet 5.x</li> <li>• <code>msad2k</code> -- Microsoft ActiveDirectory, Windows 2000</li> <li>• <code>nsds4</code> -- Netscape Directory Server 4.x</li> <li>• <code>openldap</code> -- OpenLDAP Directory Server 2.x</li> </ul> <p>The value you choose establishes default values for these other authentication properties:</p> <ul style="list-style-type: none"> <li>• <code>RoleFilter</code></li> <li>• <code>UserRoleMembership</code></li> <li>• <code>RoleMemberAttributes</code></li> <li>• <code>AuthenticationFilter</code></li> <li>• <code>DigestMD5Authentication</code></li> <li>• <code>UseUserAccountControl</code></li> </ul>
ProviderURL	<code>ldap://localhost:389</code>	<p>The URL used to connect to the LDAP server. Use the default value if the server is:</p> <ul style="list-style-type: none"> <li>• Located on the same machine as your product that is enabled with the common security infrastructure.</li> <li>• Configured to use the default port (389).</li> </ul> <p>Otherwise, use this syntax for setting the value:</p> <p><code>ldap://&lt;hostname&gt;:&lt;port&gt;</code></p>

Property	Default Value	Description
DefaultSearchBase	None	<p>The LDAP search base that is used if no other search base is specified for authentication, roles, attribution and self registration:</p> <ol style="list-style-type: none"> <li>1. <code>dc=&lt;domainname&gt;,dc=&lt;tld&gt;</code> For example, a machine in sybase.com domain would have a search base of <code>dc=sybase,dc=com</code>.</li> <li>2. <code>o=&lt;company name&gt;,c=&lt;country code&gt;</code> For example, this might be <code>o=Sybase,c=us</code> for a machine within the Sybase organization.</li> </ol>
SecurityProtocol	None	<p>The protocol to be used when connecting to the LDAP server.</p> <p>To use an encrypted protocol, use "ssl" instead "ldaps" in the url.</p> <hr/> <p><b>Note:</b> ActiveDirectory requires the SSL protocol when setting the value for the password attribute. This occurs when creating a user or updating the password of an existing user.</p> <hr/>
AuthenticationMethod	simple	<p>The authentication method to use for all authentication requests into LDAP. Legal values are generally the same as those of the <code>java.naming.security.authentication</code> JNDI property. Choose one of:</p> <ul style="list-style-type: none"> <li>• simple — For clear-text password authentication.</li> <li>• DIGEST-MD5 — For more secure hashed password authentication. This method requires that the server use plain text password storage and only works with JRE 1.4 or later.</li> </ul>

Property	Default Value	Description
AuthenticationFilter	<p>For most LDAP servers:  <code>(&amp;(uid={uid})  (object-  class=person))</code></p> <p>or</p> <p>For Active Directory  email lookups:  <code>(&amp;(userPrinci-  palName={uid})  (object-  class=user))  [ActiveDirec-  tory]</code></p> <p>For Active Directory  Windows username  lookups: <code>(&amp;(SAMAc-  count-  Name={uid})  (object-  class=user))</code></p>	<p>The filter to use when looking up the user.</p> <p>When performing a username based lookup, this filter is used to determine the LDAP entry that matches the supplied username.</p> <p>The string "{uid}" in the filter is replaced with the supplied username.</p>
AuthenticationScope	onelevel	<p>The authentication search scope. The supported values for this are:</p> <ul style="list-style-type: none"> <li>• onellevel</li> <li>• subtree</li> </ul> <p>If you do not specify a value or if you specify an invalid value, the default value is used.</p>
AuthenticationSearchBase	none	<p>The search base used to authenticate users. If this value is not specified, the LDAP DefaultSearch-Base is used.</p>

Property	Default Value	Description
BindDN	none	<p>The user DN to bind against when building the initial LDAP connection.</p> <p>In many cases, this user may need read permissions on all user records. If you do not set a value, anonymous binding is used. Anonymous binding works on most servers without additional configuration.</p> <p>However, the LDAP attributer may also use this DN to create the users in the LDAP server. When the self-registration feature is used, this user may also need the requisite permissions to create a user record. This behavior can occur if you do not set <code>useUserCredentialsToBind</code> to <code>true</code>. In this case, the LDAP attributer uses this DN to update the user attributes.</p>
BindPassword	none	<p>BindPassword is the password for BindDN, which is used to authenticate any user. BindDN and BindPassword are used to separate the LDAP connection into units.</p> <p>The <code>AuthenticationMethod</code> property determines the bind method used for this initial connection.</p> <p>If you use an encrypted the password using the CSI encryption utility, append <code>.e</code> to the property name. For example:</p> <pre>CSI.loginModule.7.options. BindPassword.e=1-AAAAEgQQOLL+LpX JO8fO9T4SrQYRC9lRT1w5ePfdczQTDs P8iACk9mDAbm3F3p5a1wXWKK8+NdJuk nc7w2nw5aGJlyG3xQ==</pre>
RoleSearchBase	none	<p>The search base used to retrieve lists of roles. If this value is not specified, the LDAP <code>DefaultSearchBase</code> is used.</p>

Property	Default Value	Description
RoleFilter	<p>For SunONE/iPlanet:            (&amp;(object-class=ldapsu-bentry) (objectclass=nsroledefinition))</p> <p>For Netscape Directory Server: (object-class=groupof-names) (object-class=groupofuniquenames))</p> <p>For ActiveDirectory:            (object-class=groupof-names) (object-class=group))</p>	<p>The role search filter. This filter should, when combined with the role search base and role scope, return a complete list of roles within the LDAP server. There are several default values depending on the chosen server type. If the server type is not chosen or this property is not initialized, no roles are available.</p>
RoleMemberAttributes	<p>For Netscape Directory Server: member,unique-member</p>	<p>The role's member attributes defines a comma-delimited list of attributes that roles may have that define a list of DN's of people who are in the role.</p> <p>These values are cross referenced with the active user to determine the user's role list. One example of the use of this property is when using LDAP groups as placeholders for roles. This property only has a default value when the Netscape server type is chosen.</p>
RoleNameAttribute	cn	<p>The attribute for retrieved roles that is the common name of the role. If this value is "dn" it is interpreted specially as the entire dn of the role as the role name.</p>
RoleScope	onelevel	<p>The role search scope. The supported values for this are:</p> <ul style="list-style-type: none"> <li>• onellevel</li> <li>• subtree</li> </ul> <p>If you do not specify a value or if you specify an invalid value, the default value is used.</p>



Property	Default Value	Description
UserRoleMembershipAttributes	For iPlanet/SunONE: nsRoleDN  For ActiveDirectory: memberOf  For all others: none	The user's role membership attributes property is used to define an attribute that a user has that contains the DN's of all of the roles as user is a member of.  These comma-delimited values are then cross-referenced with the roles retrieved in the role search base and search filter to come up with a list of user's roles.
UserFreeformRoleMembershipAttributes	None	The "freeform" role membership attribute list. Users who have attributes in this comma-delimited list are automatically granted access to roles whose names are equal to the attribute value. For example, if the value of this property is "department" and user's LDAP record has the following values for the department attribute, { "sales", "consulting" }, then the user will be granted roles whose names are "sales" and "consulting".
Referral	ignore	The behavior when a referral is encountered. The valid values are those dictated by LdapContext, for example, "follow", "ignore", "throw".
DigestMD5AuthenticationFormat	DN  For OpenLDAP: User-name	The DIGEST-MD5 bind authentication identity format.
UseUserAccountControlAttribute	For most LDAP servers: false  For ActiveDirectory: true	The UserAccountControl attribute to be used for detecting disabled user accounts, account expirations, password expirations and so on. ActiveDirectory also uses this attribute to store the above information.
controlFlag	optional	Indicates whether authentication with this login module is sufficient to allow the user to log in, or whether the user must also be authenticated with another login module. Rarely set to anything other than "sufficient" for any login module.  <b>Note:</b> controlFlag is a generic login module option rather than an LDAP configuration property.

**See also**

- *Setting Up Roles and Passwords* on page 69

## **Mapping Sybase Control Center Roles to LDAP or OS Groups**

To grant Sybase Control Center privileges to users who are authenticated through LDAP or the operating system, associate roles used in Sybase Control Center with groups in LDAP or the operating system.

You can configure Sybase Control Center to enable users to authenticate through their local operating system or through an LDAP server. To make this type of authentication work, Sybase Control Center roles must be mapped to groups that exist in the system providing authentication (LDAP or the operating system) or in the login module.

By default, Sybase Control Center assumes there is a “sybase” group in the authenticating system and maps the LDAP or OS “sybase” group to Sybase Control Center roles to provide basic privileges. The table lists additional default mappings of LDAP and OS groups to Sybase Control Center roles.

<b>Login module</b>	<b>OS group</b>	<b>Sybase Control Center roles</b>
UNIX Proxy	root	uaAnonymous, uaAgentAdmin, uaOSAdmin
	sybase	uaAnonymous, uaPluginAdmin, sccUserRole
	user	uaAnonymous, uaUser
	guest	uaAnonymous, uaGuest
NT Proxy	Administrators	uaAnonymous, uaAgentAdmin, uaOSAdmin
	sybase	uaAnonymous, uaPluginAdmin, sccUserRole
	Users	uaAnonymous, uaUser
	Guests	uaAnonymous, uaGuest
LDAP	sybase	uaAnonymous, uaPluginAdmin, sccUserRole

There are two ways to accomplish the mapping:

- (Recommended) Add a “sybase” group to the operating system or LDAP server Sybase Control Center is using to authenticate users, and add all users who need to access Sybase Control Center to the “sybase” group.
- Configure Sybase Control Center to use an existing group in LDAP or the operating system by editing the `roles-map.xml` file. This option is described here.

1. If Sybase Control Center is running, shut it down.

2. In a text editor, open:

```
<SCC-install-directory>/conf/roles-map.xml
```

3. Locate the appropriate login module (UNIX or NT (for Windows)).

4. Copy the line that maps the “sybase” group and paste it into the module just above the original sybase line.
5. Change “sybase” to the name of the group in your operating system to which Sybase Control Center users belong.

For example, if the group is SCCusers, the new line should look like this:

```
<role-mapping modRole="SCCusers"
  uafRole="uaAnonymous,uaPluginAdmin,sccUserRole" />
```

6. Save the file and exit.
7. Start Sybase Control Center.

### See also

- *Configuring an LDAP Authentication Module* on page 67

## Encrypting a Password

Use the **passencrypt** utility to encrypt passwords and other values that must be kept secure while stored in text files.

You can safely store an encrypted password in a properties file. Enter the password in clear text (unencrypted) when you execute **passencrypt** and when you use the password to log in.

**passencrypt**, which is located in the Sybase Control Center bin directory, uses the DES encryption algorithm.

1. Open a command window and change to the bin directory:

Windows: `cd <SCC-install-directory>\bin`

UNIX: `cd <SCC-install-directory>/bin`

2. To encrypt a password, enter **passencrypt**. Enter your new password at the resulting prompt.  
The **passencrypt** utility encrypts the password you enter and displays the password in encrypted form.
3. Copy the encrypted password.
4. Paste the encrypted password where needed.

### See also

- *Setting Up Roles and Passwords* on page 69

## Configuring Ports

(Optional) Use the **scc -port** command to assign Sybase Control Center services to new ports.

### Prerequisites

Check for port conflicts between Sybase Control Center and other software running on the same host.

**Task**

Sybase Control Center cannot function properly if other services use its ports. If you discover a conflict with any port listed in the right column below, you can either reconfigure the other service's port or reconfigure Sybase Control Center as described here.

Short port name	Description	Service names	Property names	Default port number
db	Database port	ScsSADataserver Messaging Alert Scheduler	com.sybase.asa.server.port messaging.db.port alert.database.port org.quartz.data-Source.ASA.URL	3638
http	Web HTTP port	EmbeddedWebContainer	http.port	8282
https	Web HTTPS (secure HTTP) port	EmbeddedWebContainer	https.port	8283
jiniHttp	JINI HTTP server	Jini	httpPort	9092
jiniRmid	JINI Remote Method Invocation daemon	Jini	rmidPort	9095
msg	Messaging port	Messaging	messaging.port	2000
rmi	RMI port	RMI	port	9999
tds	Tabular Data Stream™ port (used to communicate with other Sybase products)	Tds	tdsPort	9998

1. Shut down Sybase Control Center.
2. Execute **scc --info ports** to display a list of Sybase Control Center services, their properties, and their assigned ports.
3. To reassign a port, enter a command in one of these formats:  

```
scc --port port-name=port-number
```

```
scc --port service-name:property-name=port-number
```

Use the first, simpler format unless you want to configure the database services to use different ports. (By default, they all use the same port.)

4. Start Sybase Control Center.

5. Execute **scc --info ports** again to confirm that the port has been reassigned.

### Examples

Set all four database services (data server, messaging, database alert, and scheduler) to the same port, 3639. (The database is SQL Anywhere, used by the Sybase Control Center internal repository.)

```
scc --port db=3639
```

Set only the database messaging service to port 3639.

```
scc --port Messaging:messaging.db.port=3639
```

Set the HTTP port to 9292.

```
scc --port http=9292
```

Set the Jini RMI daemon to port 9696.

```
scc --port jiniRmid=9696
```

Set the main Sybase Control Center messaging service to port 2001.

```
scc --port msg=2001
```

Set the RMI port to 9991.

```
scc --port rmi=9991
```

Set the Tabular Data Stream port to 9997.

```
scc --port tds=9997
```

---

**Note:** **scc** commands that include a port-setting option (**-p** or **--port**, for example) do not start Sybase Control Center. To start SCC, execute a separate **scc** command.

---

### See also

- *scc Command* on page 59

## Configuring the E-mail Server

---

(Optional) Specify the e-mail server for Sybase Control Center to use to send e-mail alert notifications.

### Prerequisites

Launch Sybase Control Center and log in using an account with administrative privileges. (The login account or its group must have sccAdminRole.)

### Task

1. From the menu bar, select **Application > Administration**.
2. Select **General Settings**.
3. Click the **E-mail** tab.
4. Enter the name of the e-mail server through which Sybase Control Center will send alert notifications.
5. Change the default e-mail server port only in consultation with your e-mail administrator.
6. (Optional) Enter an e-mail address and click **Send** to dispatch a test message.  
If the test e-mail is received, you have properly configured the server for e-mail alert notifications.
7. Click **OK** (to apply the change and close the properties dialog) or **Apply** (to apply the change and leave the dialog open).

### Next

(Optional) Configure automatic logout.

### See also

- *Alerts* on page 145
- *Replication Data Collections* on page 99
- *Key Performance Indicators and Key Performance Areas for Replication* on page 100
- *Launching Sybase Control Center* on page 50
- *Logging in to Sybase Control Center* on page 62

---

## Configuring the Automatic Logout Timer

---

(Optional) Set Sybase Control Center to end login sessions when users are inactive for too long.

### Prerequisites

Launch Sybase Control Center and log in using an account with administrative privileges. (The login account or its group must have sccAdminRole.)

### Task

1. From the menu bar, select **Application > Administration**.
2. Select **General Settings**.
3. Click the **Auto-Logout** tab.
4. Enter the number of minutes after which an idle user will be automatically logged out.

Enter 0 or leave the box empty to disable automatic logout.

5. Click **OK** (to apply the change and close the properties dialog) or **Apply** (to apply the change and leave the dialog open).

**See also**

- *Launching Sybase Control Center* on page 50
- *Logging in to Sybase Control Center* on page 62

## User Authorization

---

The authorization mechanism in Sybase Control Center employs login accounts and task-based roles.

Access to Sybase Control Center is controlled by login accounts. You grant permissions to a login account by assigning predefined roles that control tasks the user can perform in Sybase Control Center, such as administration and monitoring of particular types of Sybase servers. The roles can be assigned directly to login accounts or to groups; a login account inherits the roles of any group to which it belongs. Component product modules assign some roles automatically.

Sybase Control Center classifies roles as follows:

- System roles – define how a user can interact with Sybase Control Center.
- Product roles – define how a user can interact with a particular managed resource in Sybase Control Center, for example the Replication Server named RepBoston01.

---

**Note:** The tools described here are for managing SCC-enabled login accounts; you cannot use them to manage accounts and groups that are native to your managed resource.

---

**See also**

- *Configuring a Login Account to Monitor Replication* on page 93
- *Authenticating a Login Account for a Managed Resource* on page 94

## Assigning a Role to a Login or a Group

---

Use the security configuration options to add one or more roles to a Sybase Control Center login account or to a group. Roles enable users to perform tasks such as monitoring servers or administering Sybase Control Center.

**Prerequisites**

You must have administrative privileges (sccAdminRole) to perform this task. To assign a monitoring role for a server, first register the server.

### Task

Assign the sccAdminRole to any login account that will perform administrative tasks in Sybase Control Center.

1. From the application menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Click **Logins** or **Groups**.
4. In the table, select the login account or group to which you want to assign a role.
5. Click the **Roles** tab.
6. In the **Available roles for resource** list, select the role, then click **Add**. For example, to grant administrative privileges, add the SCC Service:sccAdminRole. To grant monitoring privileges, add the MonitorRole for the desired server and server type.

---

**Note:** Sybase Control Center product modules assign certain roles automatically, so you might not need to add a MonitorRole.

---

If a role appears in the **Has following roles** list, this account or group has already been configured with that role.

7. Click **OK**.

### See also

- *Alerts* on page 145
- *Replication Data Collections* on page 99
- *Key Performance Indicators and Key Performance Areas for Replication* on page 100
- *Removing a Role from a Login or a Group* on page 82

## Removing a Role from a Login or a Group

Use the security configuration options to remove one or more roles from a Sybase Control Center login account or from a group.

### Prerequisites

You must have administrative privileges to perform this task.

### Task

1. From the menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Click **Logins** or **Groups**.
4. Select the login account or group from which you want to remove a role.
5. Click the **Roles** tab.
6. Select the role, then click **Remove**.



7. Click **OK**.

### See also

- *Assigning a Role to a Login or a Group* on page 81

## Adding a Group

Use the security configuration options to create a new group.

### Prerequisites

You must have administrative privileges (sccAdminRole) to perform this task.

### Task

Groups can make roles easier to manage. Rather than assigning roles to individual users, assign roles to groups and add users to the groups or remove them as needed.

1. From the main menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Select **Groups**.
4. Click **Create Group**.
5. Enter a group name and a description.
6. Click **Finish**.

### See also

- *Removing a Group* on page 83
- *Adding a Login Account to a Group* on page 84
- *Removing a Login Account from a Group* on page 84

## Removing a Group

Use the security configuration options to remove a group.

### Prerequisites

You must have administrative privileges (sccAdminRole) to perform this task.

### Task

1. From the main menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Select **Groups**.
4. Select the group to remove.

## Get Started

5. Click **Delete**.
6. Click **OK** to confirm the deletion.

### See also

- *Adding a Group* on page 83
- *Adding a Login Account to a Group* on page 84
- *Removing a Login Account from a Group* on page 84

## Adding a Login Account to a Group

Use the security configuration options to add one or more login accounts to a group.

### Prerequisites

You must have administrative privileges (sccAdminRole) to perform this task.

### Task

1. From the main menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Click **Groups**.
4. Select the group to which you want to assign an account.
5. Click the **Membership** tab.
6. Select the account, then click **Add**.
7. Click **OK**.

### See also

- *Adding a Group* on page 83
- *Removing a Group* on page 83
- *Removing a Login Account from a Group* on page 84

## Removing a Login Account from a Group

Use the security configuration options to remove one or more login accounts from a group.

### Prerequisites

You must have administrative privileges (sccAdminRole) to perform this task.

### Task

1. From the main menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties, expand the **Security** folder.

3. Select **Groups**.
4. Select the group from which to remove members.
5. Click the **Membership** tab.
6. Select the login, then click **Remove**.
7. Click **OK**.

### See also

- *Adding a Group* on page 83
- *Removing a Group* on page 83
- *Adding a Login Account to a Group* on page 84

## Adding a Login Account to the System

Use the security configuration options to create a native login account in Sybase Control Center.

### Prerequisites

- You must have administrative privileges (sccAdminRole) to perform this task.
- If you intend to use Windows, UNIX, or LDAP to authenticate users, configure the appropriate authentication module.

### Task

---

**Note:** Sybase does not recommend that you create a native login account for every Sybase Control Center user. It is more efficient to configure Sybase Control Center to authenticate users through their Windows, UNIX, or LDAP accounts.

---

1. From the main menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Select **Logins**.
4. Click **Create Login**.
5. Enter a login name and expiration for the new account. Expiration is optional.
6. Click **Next**.
7. Select **Specify new user information**.
8. Enter details about the user:
  - Title
  - First name\*
  - M.I. (middle initial)
  - Last name\*
  - Suffix

## Get Started

- E-mail address\*
- Phone
- Ext.
- Fax
- Mobile
- Supports text messaging (checkbox)

\*You must fill in the **First Name**, **Last Name**, and **E-mail Address** fields.

### 9. Click **Finish**.

---

**Note:** If you are using the predefined Simple Login module for authentication, the default login accounts, “sccadmin” and “sccuser,” come with blank passwords. To change or modify the passwords, configure the `csi.properties` file as described in the *Installation Guide*.

---

### **Next**

Grant privileges to the new login account. You can grant privileges by assigning Sybase Control Center roles directly to the login accounts, or by assigning the login accounts to groups and mapping Sybase Control Center roles to the groups. The group approach is generally more efficient.

## **Removing a Login Account from the System**

Use the security configuration options to delete a Sybase Control Center login account.

### **Prerequisites**

You must have administrative privileges (`sccAdminRole`) to perform this task.

### **Task**

1. From the main menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Select **Logins**.
4. Select the login to delete.
5. Click **Delete**.
6. Click **OK** to confirm the deletion.

## **Modifying a User Profile**

Use the security configuration options to suspend a login account, impose an expiration date, or modify the account’s user information.

### **Prerequisites**

You must have administrative privileges (`sccAdminRole`) to perform this task.

## Task

1. From the main menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Select **Logins**.
4. Select the login account to modify.
5. Click the **General** tab.
6. To suspend this account, click **Login disabled**.
7. To set the date on which this account will stop working, click the calendar icon next to the **Expiration** field and select a date.
8. Click **Apply**.
9. Click the **User Info** tab.
10. Edit the user information.  
When this user configures e-mail alert subscriptions, Sybase Control Center automatically populates the subscription dialog with the e-mail address you enter here.
11. Click **Apply**.

## Logins, Roles, and Groups

Sybase Control Center includes predefined login accounts and roles.

In Sybase Control Center, a login account identifies a user who can connect to the application. An account may have roles that specify the tasks the user is allowed to perform.

Sybase Control Center is designed to delegate user authentication to the operating system or to an LDAP directory service. Delegation requires some configuration, however, so Sybase Control Center comes with two predefined login accounts. Sybase recommends using the predefined accounts only for installing and setting up Sybase Control Center. These accounts are not intended for use in a production environment.

**Table 12. Predefined accounts**

Login name	Description
sccadmin	Can use all the administration features in Sybase Control Center
sccuser	Test account with no special privileges

A role is a predefined profile that can be assigned to a login account or a group. Roles control the access rights for login accounts. Sybase Control Center comes with predefined roles that are intended for use in production environments.

**Table 13. Predefined roles**

<b>Role</b>	<b>Description</b>
sccUserRole	Provides nonadministrative access to Sybase Control Center. Required for every user.
sccAdminRole	Provides administrative privileges for managing Sybase Control Center.
aseMonitorRole*	Provides privileges to monitor the Adaptive Server environment.
iqMonitorRole*	Provides privileges to monitor the Sybase IQ environment.
repMonitorRole	Provides privileges to monitor the replication environment.
repAdminRole	Provides administrative privileges for managing the replication environment.

\*These monitoring roles are assigned to users automatically by Sybase Control Center product modules; it is generally not necessary to assign them manually.

A group is made up of one or more login accounts; all the accounts in a group have the roles granted to the group. In Sybase Control Center you can create groups to suit your business requirements.

# Configure

Configure login accounts, statistics collection, and other replication monitoring options.

- 1. *Registering a Replication Server, Replication Agent, or Mirror Replication Agent***  
Register a resource (for example, a server that can be monitored) to make Sybase Control Center aware of it and its connection information.
- 2. *Importing Resources for Batch Registration***  
(Optional) Import and register multiple servers from an interfaces or sql.ini file.
- 3. *Creating a Perspective***  
Create a perspective in which you can add and manage resources.
- 4. *Adding a Resource to a Perspective***  
Add one or more resources to the current perspective.
- 5. *Configuring a Login Account to Monitor Replication***  
Use the security configuration options to add one or more roles to a Sybase Control Center login account or to a group. Roles enable users to perform tasks such as monitoring servers or administering Sybase Control Center.
- 6. *Authenticating a Login Account for a Managed Resource***  
Specify the login account Sybase Control Center will use when it connects to your server or agent to collect monitoring data or manage the resource.
- 7. *Setting Up the Latency Monitoring Process***  
Start the latency monitoring process for replication paths in the replication environment.
- 8. *Setting Up Statistics Collection***  
Use the Properties view of your managed resource to create a data collection job and add a schedule to the job.
- 9. *Setting Replication Parameters***  
Configure replication parameters to improve server performance. Sybase Control Center for Replication allows you to configure the parameters for Replication Server, Replication Agent, connection and logical connection, route, and Adaptive Server RepAgent thread.
- 10. *Creating an Alert***  
Use the Add Alert wizard to create an alert instance for your resource.
- 11. *Optional Configuration Steps***  
Perform additional configuration, including user authorization, alerts, data collection scheduling, backups, and setting purging options for the repository.

## See also

- *User Authorization* on page 45

## Configure

- *Logins, Roles, and Groups* on page 87
- *Setting Up Security* on page 63
- *Assigning a Role to a Login or a Group* on page 81

## Registering a Replication Server, Replication Agent, or Mirror Replication Agent

---

Register a resource (for example, a server that can be monitored) to make Sybase Control Center aware of it and its connection information.

1. In the Resource Explorer, select **Resources > Register**.
2. Specify:

**Table 14. New resource type details**

Field	Description
Resource Name	(Required) Name of the resource to register. Enter the actual name of the server, using uppercase and lowercase letters. If the name registered in Sybase Control Center does not exactly match the server name, some monitoring functions, including the topology view, do not work.
Resource Type	Select a resource type: <ul style="list-style-type: none"><li>• ASE Server, Replication Only (12.5.0.0) – monitor only the RepAgent threads for an Adaptive Server that is older than version 15.0.2.0. Choose this type for an Adaptive Server that is part of a replication environment.</li><li>• Replication Agent (15.5.0.0) – monitor Replication Agent.</li><li>• Replication Server (15.5.0.0) – monitor Replication Server.</li></ul>
Description	A brief description to help you identify the resource.

3. Click **Next**.
4. Specify the connection information for your resource:

**Table 15. New resource connection details**

Field	Description
Server Host Name/Host Name	Local host name
Port Number	Local host port number
RSSD Host Name	(Required) Name of the RSSD host
RSSD Port Number	(Required) RSSD host port number



---

**Note:** **RSSD Host Name** and **RSSD Port Number** are required only if you are registering a Replication Server.

---

5. Click **Next**.
6. (Optional) Click **Add this resource to the current perspective**. You must add a resource to a perspective (not necessarily the current perspective) before you can manage or monitor it.
7. (Optional) Click **Open the resource explorer to view this new resource**. (This option is not present when the Resource Explorer is open.)
8. Click **Finish**.

### See also

- *Resources* on page 153
- *Compatibility Matrix* on page 4
- *Common Display Options* on page 7
- *Unregistering a Resource* on page 154

## Importing Resources for Batch Registration

---

(Optional) Import and register multiple servers from an `interfaces` or `sql.ini` file.

### Prerequisites

Copy the `interfaces` or `sql.ini` file to a location on or accessible from the machine that hosts your Web browser.

### Task

An `interfaces` (UNIX) or `sql.ini` file (Windows) is a list of Sybase servers and their ports; it may contain other connection information as well. The file is created during the installation of a Sybase server:

- Windows: `%SYBASE%\ini\sql.ini`
- Unix: `$SYBASE/interfaces`

For more information on `interfaces` files, see the appendix on configuration files in *Configuration Guide Open Client and Open Server 15.0 for UNIX*.

For more information on `sql.ini` files, see the chapter on network communications using `sql.ini` in the Adaptive Server Enterprise 15.0 *Configuration Guide for Windows*.

---

**Note:** The Import Resources wizard imports servers in batches of a single type (Adaptive Server, Sybase IQ, or Replication Server, for example). If your `interfaces` or `sql.ini` file includes resources of more than one type, you must perform this procedure for each resource type.

---

## Configure

1. In the application menu, select **View > Open > Resource Explorer**.
2. In the Resource Explorer, select **Resources > Import**.  
The Import Resources wizard opens; **Interfaces file** is already selected.
3. Click **Next**.  
The Directory Service Connection page appears.
4. Click **Browse** and navigate to the interfaces file you want to import from.  
You cannot type in the **File name** field.
5. Click **Next**.
6. On the Import Resource Type page, select the type of server you want to import.
7. On the Resource Selection page, click to select the servers you want to import.  
Select only servers of the type you chose on the Import Resource Type page. If you import servers with incorrect types, Sybase Control Center will not be able to monitor or manage them properly.
8. Resources of your chosen type may require connection parameters in addition to those present in the file—RSSD host name and port for Replication Server, for example, or character set and language for Adaptive Server. Enter any required connection parameters.
9. Click **Next**.
10. (Optional) Click **Add these resources to the current perspective**. You must add a resource to a perspective (not necessarily the current perspective) before you can manage or monitor it.
11. Click **Next**.  
The Confirmation page displays a list of the resources you have selected.
12. Click **Finish** if you are ready to import, or click **Back** to return to the previous screens and change your selections.  
When you click **Finish**, Sybase Control Center imports and registers the resources and displays a summary page.
13. Click **Close** to finish the wizard.

The newly imported resources appear in the Resource Explorer. If you elected to add them to the current perspective, the resources also appear in the Perspective Resources view.

### See also

- *Resources* on page 153
- *Unregistering a Resource* on page 154

## Creating a Perspective

---

Create a perspective in which you can add and manage resources.

1. From the application menu bar, select **Perspective > Create**.
2. Enter a name for your perspective. The name can contain up to 255 characters.
3. Click **OK**.

## Adding a Resource to a Perspective

---

Add one or more resources to the current perspective.

Add servers or other resources to a perspective so you can monitor and manage them along with other resources in the same perspective.

1. From the Sybase Control Center toolbar, click the **Launch Resource Explorer** icon.
2. Select the resources to add to your perspective. Use **Shift-click** or **Control-click** to select multiple resources.
3. Perform one of these actions:
  - Select **Resources > Add Resources to Perspective**.
  - Drag and drop resources from the Resource Explorer onto the Perspective Resources view. You can select and drag multiple resources.

### See also

- *Removing a Resource from a Perspective* on page 155

## Configuring a Login Account to Monitor Replication

---

Use the security configuration options to add one or more roles to a Sybase Control Center login account or to a group. Roles enable users to perform tasks such as monitoring servers or administering Sybase Control Center.

### Prerequisites

You must have administrative privileges (sccAdminRole) to perform this task. To assign a monitoring role for a server, first register the server.

### Task

Assign the repMonitor and repAdminRole to any login account to perform monitoring and management tasks in Sybase Control Center.

## Configure

1. From the menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, expand the **Security** folder.
3. Click **Logins** or **Groups**.
4. Select the login account or group to which you want to assign a role.
5. Click the **Roles** tab.
6. From the **Available roles for resource** list, select the role, then click **Add**.

For example, to grant administrative privileges, add the SCC Service:sccAdminRole.

If a role appears in the **Has following roles** list, it means the account or group has already been configured with that role.

7. Click **OK**.

### See also

- *Authenticating a Login Account for a Managed Resource* on page 94
- *User Authorization* on page 81

## Roles or Permissions to Set Up Replication Monitoring Accounts

Sybase Control Center uses the user name and password account that you provide when you authenticate a server to retrieve monitoring information.

The user account you have specified must have these roles or permissions:

- Replication Server – a 'create object' or 'sa' permission.
- Replication Server System Database (RSSD) database – read privilege on all tables and create and execute privileges on stored procedures in the RSSD database. It is recommended to use the account created by **rs\_init** for the RSSD.
- Replication Agent or Mirror Replication Agent – an administrative account. There is only one administrative account in a Replication Agent.
- Adaptive Server for RepAgent threads – a system administrator role. Sybase Control Center uses the **dbcc monitor** command to retrieve statistics.

---

**Note:** 'sa' or 'dbo' permission are required for setting parameters and controlling data flow.

---

## Authenticating a Login Account for a Managed Resource

Specify the login account Sybase Control Center will use when it connects to your server or agent to collect monitoring data or manage the resource.

Perform this task for each resource registered with Sybase Control Center.

---

**Note:** You can also authenticate a server during administrative tasks like creating an alert or a collection job.

---

1. Connect a browser to Sybase Control Center and log in.
2. If the Perspective Resources view is not open, click the **Show/Hide Perspective Resources View** icon in the toolbar.
3. In the Perspective Resources view, select your resource and select **Resource > Authenticate** from the view menu.
4. Select **Use my current SCC login** or **Specify different credentials**.
5. If you chose **Specify different credentials**, enter the login and password for Sybase Control Center to use to connect to your resource.
6. If the selected server is a Replication Server, also enter the RSSD user name and password.
7. Click **OK** to save and exit the dialog.

**See also**

- *Configuring a Login Account to Monitor Replication* on page 93
- *User Authorization* on page 81

## Setting Up the Latency Monitoring Process

---

Start the latency monitoring process for replication paths in the replication environment.

**Prerequisites**

- Install and configure all the servers to be monitored. Verify that these servers have been registered and added to the Perspective Resources, and that you have the permission to perform this task.
- To use **rs\_ticket** in a replication environment to measure the latency of non-Sybase replicate databases, you must install JDBC drivers to enable Sybase Control Center for Replication. See "Installing the JDBC Drivers for Non-Sybase Replicate Databases" in the *Sybase Control Center Installation Guide*.

**Task**

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Paths**.
3. Select a path from the list.

---

**Note:** When selecting or highlighting a path, click outside the Path Name column. Clicking the path name opens the path dashboard.

---
4. Click **Quick Admin** to display the latency monitoring process administration view for the selected path.

---

**Note:** The selected path's primary and replicate Replication Server versions must be 15.1 or later, otherwise the **Quick Admin** option is disabled. For a non-Sybase primary database, the Replication Agent must also be version 15.1 or later.

---

All replicate databases to which the selected path replicates data are listed in the administration view. For Adaptive Server databases, all parameters are populated automatically. For non-Sybase databases, you need to provide the parameters manually in the administration view.

5. Specify the replicate database information, start and end dates, and the repeat interval time.
6. For non-Sybase databases, click **Test Connection** to verify that the connection information is valid.

---

**Note:** Repeat this step for all the listed replicate databases.

---

7. Click **Start**.

You can click the bar graph icon in the upper-right corner of the Latency window in the Replication Server Monitor's Paths view or in the Replication Path Dashboard to see the detailed latency history.

### See also

- *Setting Up Statistics Collection* on page 97
- *Stopping the Latency Monitoring Process* on page 188
- *Displaying Latency* on page 188
- *Latency Chart Details* on page 189
- *Replication Latency* on page 187
- *Data on Dashboards or Charts Is Missing* on page 191

## Latency Monitoring Process

Latency monitoring means executing the **rs\_ticket** command at the primary database, retrieving the latency data from the replicate database, and storing the results in the Sybase Control Center repository.

**rs\_ticket** gathers time information at various points in the replication path as it flows from the primary database to the replicate database. You can then use this latency information to identify bottlenecks in the replication path. Latency information helps ensure that data is flowing efficiently between the primary and replicate databases.

The latency monitoring process collects data on a specified schedule for each replicate Replication Server and for the primary Replication Server for the path you configured. The primary collection executes the **rs\_ticket** command in the primary database. Each replicate collection performs a collection in all its paths. When a path collection occurs, the results of the **rs\_ticket** command are retrieved from the replicate database, stored in the repository, and displayed in the latency history chart in the Replication Server Monitor's Paths view or in the Replication Path Dashboard for server performance monitoring.

Each collection repeats until the end date or until you manually stop the latency monitoring process. Once the process is stopped, all collections are deleted from the scheduler.

### See also

- *Displaying Replication Path Status* on page 187
- *Displaying Latency* on page 188
- *Stopping the Latency Monitoring Process* on page 188

## Setting Up Statistics Collection

---

Use the Properties view of your managed resource to create a data collection job and add a schedule to the job.

For best performance, Sybase recommends these guidelines for scheduling data collection jobs:

- Schedule only one collection job for each collection.
- Set the collection interval to 60 seconds/one minute or more. (The default is 5 minutes.)

Data collections for a managed resource do not run until the resource is authenticated.

1. In the Perspective Resources view, select a resource and select **Resource > Properties**.
2. Select **Collection Jobs**.
3. Click **Create Job**.
4. If this resource has not yet been authenticated, you see the Authentication page. Enter a user name and password that Sybase Control Center can use to log in to the resource. Click **Authenticate** to allow Sybase Control Center to verify your credentials. Because data collections can run only on an authenticated resource, you cannot proceed without authenticating.
5. On the Collection Information page, select the data collection that this job will run and click **Next**.
6. (Optional) If you do not want to create a schedule yet, unselect **Create a schedule for this job**.
7. Specify details for the new schedule:

**Table 16. New schedule details**

Field	Description
Name	A name for this schedule
Description	A description of this schedule
Start date	The day when the schedule will take effect

## Configure

Field	Description
Time	The time when the schedule will take effect

**Note:** Enter dates and times using your local time. Sybase Control Center converts your times for remote time zones if necessary.

### 8. Specify the duration of this schedule:

- **Run once**
- **Repeat until**

For **Repeat until**, specify these details:

Field	Description
Repeat interval	Time period (in seconds, minutes, hours, or days) between job executions
Repeat until	Date the job should stop running
Time	Time the job should stop running

- **Repeat indefinitely**

For **Repeat indefinitely**, specify these details:

Field	Description
Repeat interval	Time period (in seconds, minutes, hours, or days) between job executions

### 9. Click **Finish**.

#### See also

- *Setting Up the Latency Monitoring Process* on page 95
- *Setting Replication Parameters* on page 117
- *Job Scheduling* on page 140

## About Statistics

Understand availability and performance statistics in Sybase Control Center.

The statistics you work with in Sybase Control Center can be divided into two types:

- Availability statistics are concerned with present conditions; they help you determine whether a resource you are monitoring (a server or an agent, for example) is running and functioning properly.
- Performance statistics are concerned with behavior of the same resources over time. They describe the flow of data through your environment. You can use performance statistics to spot trends, identify problems like resource bottlenecks, and make plans.

Sybase Control Center includes predefined key performance indicators (KPIs) for each product module; these KPIs are grouped into collections. KPIs such as server status, which



serves as an availability statistic when it is fresh, have long-term value as historical performance statistics.

Availability statistics appear on the heat chart and on resource monitoring screens in each product module.

Performance statistics appear on the statistics chart and on resource monitoring screens in each product module.

Some KPIs are included in the default collection for each product module. To make other KPIs available to the heat chart, statistics chart, and resource monitoring views, you must set up collection jobs in the scheduler. See the data collections help topic for information on data collections and the KPIs contained in them.

Several configuration options affect the collection and display of data in Sybase Control Center:

- Collection repeat interval—The frequency of data collection. Set this on the collection job in the scheduler.
- Screen refresh interval—The period between screen refreshes. Refreshing the screen redraws it with the newest available data. Set the screen refresh interval in the product module. (May not be settable in all product modules.)
- Chart trend period—The period over which data is displayed in historical charts. Set the trend period in the product module. (May not be settable in all product modules.)

#### See also

- *Replication Data Collections* on page 99
- *Key Performance Indicators and Key Performance Areas for Replication* on page 100

## Replication Data Collections

Lists and describes predefined data collections you can use to create jobs for Replication.

**Table 17. Replication data collection**

Replication Objects	Replication Data Collection	Description
Replication Server	Monitoring Statistics (default collection*) <hr/> <b>Note:</b> This collection must be scheduled to enable alerts.	Collects the availability metrics displayed in the Replication Server Monitor and heat chart.

## Configure

Replication Objects	Replication Data Collection	Description
	Performance Counters	A diagnostic tool that collects historical performance metrics that you can later graph in the statistics chart.
ASE Server, Replication Only	RepAgent Statistics (default collection*) <hr/> <b>Note:</b> This collection must be manually started if the Adaptive Server is registered as an ASE Server type. "collection_ase_rat" is the name of the RepAgent Statistics collection in an ASE Server registered Adaptive Server.	Collects availability metrics for RepAgent thread.
Replication Agent	RA Monitoring Statistics (default collection*)	Collects availability metrics displayed in the Replication Agent Monitor and heat chart.
	Performance Counters	Collects historical performance metrics that you can later graph in the statistics chart.
*Default collections are automatically created upon authentication and are set to repeat indefinitely at a 60-second interval.		

### See also

- *About Statistics* on page 98
- *Alerts* on page 145
- *Creating an Alert* on page 121
- *Assigning a Role to a Login or a Group* on page 81
- *Configuring the E-mail Server* on page 79
- *Job Scheduling* on page 140

## Key Performance Indicators and Key Performance Areas for Replication

Lists and describes the key performance indicators (KPIs) and key performance areas (KPAs) that provide the statistics displayed on Replication screens and charts in Sybase Control Center.

Each Replication KPA includes a subset of the KPIs.

Table 18. Key performance indicators

KPI	Description
<b>Managed Object States</b>	
Primary State	Managed object primary state.
Secondary State	Managed object secondary state.
<b>Replication Server Performance Statistics</b>	
Insert commands	Insert command on active object.
Update commands total	Update command on active object.
Delete commands total	Delete command on active object.
Writetext commands total	Writetext command on active object.
Execute commands total	Execute command on active object.
AIO collect time total	Amount of time that the Asynchronous I/O Daemon spent in collecting async I/O requests in which Daemon is obliged to poll until notified of their completion.
AIO after poll total	Number of pending asynchronous I/O requests just after the Async I/O Daemon finishes polling for their completion.
AIO before poll total	Number of pending asynchronous I/O requests just before the Async I/O Daemon goes off to poll for their completion.
AIO poll time total	Amount of time that the Asynchronous I/O Daemon spent in polling I/O completions. This includes the time taken to notify AIO clients of their I/O requests completion.
AIO read retry total	The number of times an async read is made and the OpSys tells the client that it must try again.
AIO write retry total	The number of times an async write is made and the OpSys tells the client that it must try again.
Alarm milliseconds spent total	Number of milliseconds actually spent before the alarm was expired.
Alarm cancel total	Number of alarms cancelled.
Alarm examined total	Number of examined alarms to determine whether they are expired or not.
Alarm expired cancelled total	Number of alarms that were found canceled upon each 'handle expiration' execution.

## Configure

<b>KPI</b>	<b>Description</b>
Alarm expired total	Number of alarms that have expired upon each 'handle expiration' execution.
Alarm milliseconds expired interval total	Number of milliseconds until the next alarm expiration.
Alarm expired time total	Amount of time elapsed while handling expired alarms.
Alarm milliseconds requested total	Number of milliseconds originally requested for the alarm when it was set.
Alarm set total	Number of alarms set.
Thread start total	Total number of started threads.
Thread stop total	Number of threads stopped.
Begins total	Begin Tran statements sent to Replication Server System Database (RSSD).
Deletes total	Delete statements sent to RSSD.
Inserts total	Insert statements sent to RSSD.
Selects total	Select statements sent to RSSD.
Cache exceed total	Number of time System Table Services (STS) cached was exceeded.
Updates total	Update statements sent to RSSD.
<b>Replication Server</b>	
Replication Server State	The state of the Replication Server.
% Memory usage	The percent of the current memory used by the server.
Maximum Latency	The highest latency of any replication path in the server.
% Partition Usage	The percent full of all partitions in the Replication Server.
<b>Path</b>	
Path Status	The state of the replication path between a primary and a replicate database.
Path Latency	The time between when a transaction is committed at the primary database and when it is committed at the replicate database.

KPI	Description
Change in Path Activity	The number of commands sent to the replicate database by the Data Server Interface (DSI) thread since the last monitoring cycle.
Path Data Loss	Indicates possible data loss between the primary and replicate databases.
rs_ticket Count	The ticket's unique sequence number.
Primary Database Start Time	The time, in milliseconds, the <b>rs_ticket</b> was executed at the primary database.
Executor Thread Latency	The number of milliseconds from the start, to the time the ticket passes through the executor thread.
Distributor Thread Latency	The number of milliseconds from the primary Replication Server time, to the time the ticket passes through the distributor thread.
Replication Server Interface Latency	The number of milliseconds from the distributor (DIST) thread time, to the time the ticket passes through the Replication Server Interface (RSI) thread.
Data Server Interface Thread	The number of milliseconds from the RSI thread time, to the time the ticket passes through the DSI thread.
Path RDB Latency	The number of milliseconds from the DSI thread time, to the time the ticket arrived at the replicate database.
<b>Connection</b>	
Time closing an OB fadeout total	The amount of time spent closing a connection marked to be faded out.
Time waiting on OB fadeout total	The amount of time spent waiting for a connection marked to be faded out.
Commands read total	Commands read from an inbound queue by a DIST thread.
Resolved delete statements total	Delete commands encountered by a DIST thread and resolved by subscription resolution engine (SRE).
Unresolved statements total	DIST commands with no subscription resolution that a DIST thread discarded. This implies either there is no subscription or the 'where' clause associated with the subscription does not result in row qualification.

## Configure

KPI	Description
Resolved insert statements total	Insert commands that a DIST thread encountered, which SRE resolved.
Resolved update statements total	Update commands that a DIST thread encountered, which SRE resolved.
TD Begins total	Begin transaction commands that a DIST thread propagated.
TD Commits or Rollbacks total	Commit or Rollback commands that a DIST thread processed.
Transactions processed total	Transactions read by DIST thread from an inbound queue.
All large threads used total	This counter is incremented each time a Large Parallel Transaction must wait because there are no available parallel DSI threads.
All threads used total	This counter is incremented each time a Parallel Transaction must wait because there are no available parallel DSI threads.
Commands applied successfully total	Commands that a DSI successfully applied to the target database.
Time dispatching large groups total	Time spent by the Data Server Interface, scheduler thread (DSI/S) dispatching a large transaction group to a DSI/E. This includes the time spent finding a large group to dispatch.
Time dispatching regular groups total	Time that the DSI/S spent dispatching a regular transaction group to a DSI/E.
Time finding regular groups total	Time that the DSI/S spent finding a group to dispatch.
Time loading SQT cache total	Time that the DSI/S spent loading Stable Queue Transaction (SQT) cache.
Time executing special group total	Time that the DSI/S spent determining if a transaction is special, and executing it if it is.
DSI/E in sleep mode total	Number of DSI/E threads that the DSI/S put to sleep prior to loading SQT cache. These DSI/E threads have just completed their transaction.
Time putting DSI/E in sleep mode total	Time that the DSI/S spent putting free DSI/E threads to sleep.
Transaction groups read total	Transaction groups that the DSI read. If grouping is disabled, grouped and ungrouped transaction counts are the same.

KPI	Description
Ungrouped transactions read total	Ungrouped transactions that the DSI read. If grouping is disabled, grouped and ungrouped transaction counts are the same.
Transaction groups committed total	Transactions that a DSI thread successfully committed.
Transaction groups sent total	Transaction groups that the DSI thread sent to the target database. A transaction group can contain at most <b>dsi_max_xacts_in_group</b> transactions. This counter is incremented each time a 'begin' for a grouped transaction is executed.
Transaction groups success total	Transaction groups that a DSI thread successfully applied to a target database. This includes transactions that were successfully committed or rolled back according to their final disposition.
Transaction groups committed total	Transactions in groups sent by a DSI thread that committed successfully.
Transaction groups sent total	Transactions contained in transaction groups that a DSI thread sent.
Closed groups maximum bytes total	Transaction groups that a DSI thread closed due to the next transaction that caused the <b>dsi_xact_group_size</b> to exceed.
Closed groups next new origin total	Transaction groups that a DSI closed due to no open group from the origin of the next transaction. For example, there is a new origin in the next transaction, or the schedule forced a flush of the current group from the origin leaving no open group from that origin.
Closed groups partitioning total	Transaction groups that a DSI thread closed because of a Transaction Partitioning rule.
Closed groups maximum log transaction total	Transaction groups that a DSI thread closed due to the next transaction that caused the <b>dsi_max_xacts_in_group</b> to exceed.
Groups wait partitioning total	Transaction groups forced to wait for another group to complete (processed serially based on Transaction Partitioning rule).
True return of <b>rs_dsi_check_thread_lock</b> total	Number of <b>rs_dsi_check_thread_lock</b> invocations returning true. The function determined the calling thread holds locks required by other threads. A rollback and retry occurred.
Delete statements read total	<b>rs_delete</b> commands that a DSI executor (DSIEXEC) thread processed.

## Configure

KPI	Description
Batch size total	Size, in bytes, of commands batches, which a DSI submitted.
Batch time total	Time, in milliseconds, to process command batches, which a DSI submitted.
Bytes succeed total	Bytes that a DSI/E successfully applied to the target database.
Commands read total	Commands read from an outbound queue by a DSIEXEC thread.
Commands succeed total	Commands that a DSI/E successfully applied to the target database.
Function string mapping time total	Time, in milliseconds, to perform function string mapping on commands.
Input command count total	Number of input commands in command batches that a DSI submitted.
Output command count total	Number of output commands in command batches that a DSI submitted.
Result time total	Time, in milliseconds, to process the results of commands batches that a DSI submitted.
Sequencing check on command batches time total	Time, in milliseconds, to check the sequencing on command batches, which required some kind of synchronization such as <b>wait_for_commit</b> .
Sequencing check on commits time total	Time, in milliseconds, to check the sequencing on commits.
Transaction time total	Time, in milliseconds, for a DSI/E thread to process transactions. This includes function string mapping, sending and processing results. A transaction may span command batches.
Errors deadlock total	Times that a DSI thread failed to apply a transaction due to deadlocks in the target database (ASE Error 1205).
Errors out of lock total	Times that a DSI thread failed to apply a transaction due to no locks available in the target database (ASE Error 1204).
Writetext total	<b>rs_writetext</b> commands that a DSIEXEC thread processed.
Insert total	<b>rs_insert</b> commands that a DSIEXEC thread processed.
MemUsed group total	Memory that a DSI/S thread consumed for transaction groups.
Send RPC time total	Time, in milliseconds, spent in sending RPCs to the RDS.



KPI	Description
Send time total	Time, in milliseconds, spent in sending command buffers to the RDS.
System transaction read total	Internal system transactions that a DSIEXEC thread processed.
Transaction groups scheduled total	Transactions groups scheduled to a DSIEXEC thread.
Ungrouped transactions scheduled total	Transactions in transaction groups scheduled to a DSIEXEC thread.
Updates read total	<b>rs_update</b> commands that a DSIEXEC thread processed.
Bytes received total	Bytes that a RepAgent thread received. This size includes the TDS header size when in 'passthru' mode.
Mini abort total	<b>mini-abort</b> commands (in Adaptive Server, SAVEXACT records) that a RepAgent thread processed. <b>mini-abort</b> instructs Replication Server to rollback commands to a specific OQIQ value.
Commands received total	Commands that a RepAgent thread received.
Write wait time total	The amount of time the RepAgent spent waiting for the Stable Queue Manager (SQM) Writer thread to drain the number of outstanding write requests to get the number of outstanding bytes to be written under the threshold.
Yield time total	The amount of time the RepAgent spent yielding the processor while handling Log Transfer Language (LTL) commands each time the processor was yielded.
Execution time total	The amount of time, in milliseconds, RepAgent user thread is scheduled by Open Client/Server (OCS).
Receive time total	The amount of time, in milliseconds, spent receiving network packets or language commands.
Update rs_locator total	Updates to RSSD. <b>rs_locator</b> where type = 'e' executed by a RepAgent thread.
Replication Agent Thread State	The state of the Replication Agent thread in the Replication Server that is associated with the connection.
DSI State	The state of the DSI thread in the Replication Server that is associated with the connection.
DSI Activity	The number of commands that the DSI thread sent to the replicate database.

## Configure

<b>KPI</b>	<b>Description</b>
DSI Activity per Second	The number of commands that the DSI thread sent to the replicate database per second.
Transaction Ignored	The number of transactions that were ignored.
Transaction Skipped	The number of transactions that were skipped.
Transaction Succeeded	The number of transactions that were successfully committed to the replicate database.
Transaction Failed	The number of transactions that were failed.
Transaction Retried	The number of transactions that were retried.
DSI SQT Cache Percent Used	The percent of DSI SQT cache size used.
Transactions removed per second	The number of transactions removed from the DSI SQT cache per second.
SQT cache low boundry	The smallest size to which DSI SQT cache is configured before transactions start being removed from the cache.
Transactions read per second	The number of transactions that the DSI read per second.
Commands per Transaction	The number of commands per transaction.
Transactions per Group	The number of transactions per group.
Commands per Batch	The number of commands per batch.
<b>Logical Connection</b>	
Operation in Progress State	The state of the operation in progress.
<b>Route</b>	
Route State	The state of the route at both the origin and destination Replication Servers.
Route Activity	The number of bytes sent to the destination Replication Server.
Route Activity per Second	The number of bytes sent to the destination Replication Server per second.
Alarm time spent total	Number of milliseconds actually spent before an alarm expired.
Time spent cancelling alarms total	Amount of time elapsed while canceling an alarm.
Expired alarms to be cancelled total	Number of alarms that were found to have been expired while attempting to cancel them.

KPI	Description
Alarm required time total	Number of milliseconds originally requested for the alarm when it was set.
Alarm set total	Amount of time elapsed while setting an alarm.
Connection active time total	Amount of time elapsed while a thread makes a connection active.
Connection charset time total	Amount of time elapsed while checking a connection's character set.
Connection fadeout freetime total	Amount of time elapsed while this thread's free connections are marked for fadeout. Note that this thread is probably <i>*not*</i> the thread doing the work. Most likely it is the Alarm Handler doing the work.
Connection fadeout time total	Amount of time elapsed while this thread's assigned connections are marked for fadeout. Note that this thread is probably <i>*not*</i> the thread doing the work. Most likely it is the Alarm Handler doing the work.
Connection give-up total	Number of times the thread gave up a connection.
Connection give-up time total	Amount of time elapsed while a thread gives up a connection.
Connection idle time total	Amount of time elapsed while a thread makes a connection idle.
Connection open total	Number of times the thread made a connection request and received one that had to be opened.
Connection request total	Number of times the thread made a connection request and received one that was already open.
Connection sort order time total	Amount of time elapsed while checking a connection's sort order.
Connection time total	Amount of time elapsed while a thread obtains a connection.
Message queue get time total	Number of centiseconds spent getting a message from an internal message queue.
Message queue put time total	Number of centiseconds spent putting a message on an internal message queue.
Sleep time total	Amount of time elapsed after a thread puts itself to sleep.
Yield time total	Amount of time elapsed after a thread yields the CPU.

## Configure

KPI	Description
Blocks read total	Number of blocking ( <b>SQM_WAIT_C</b> ) reads that an RSI thread performed against SQM thread that manages a RSI queue.
Bytes sent total	Bytes that an RSI sender thread delivered.
Messages sent total	RSI messages that an RSI thread sent. These messages contain the distribute command.
Packets sent total	Packets that an RSI sender thread sent.
Send packet time total	Time, in milliseconds, spent in sending packets of data to the RRS.
Bytes received total	Bytes that an RSI user thread received. This size includes the TDS header size when in 'passthru' mode.
Command length total	Length of an RSI command.
Commands received total	Commands that an RSI user thread received. Includes RSI message, get truncation requests, etc.
Execution time total	The amount of time, in milliseconds, RSI User thread is scheduled by OCS.
Receive packet time total	The amount of time, in milliseconds, spent receiving network packets.
GetTrunc send time total	The amount of time, in milliseconds, spent responding to 'get truncation' requests.
SetTrunc send time total	The amount of time, in milliseconds, spent responding to 'set truncation' requests.
<b>Queue</b>	
Queue Writes	The number of commands written to the queue in the Replication Server.
Queue Writes per Second	The number of commands written to the queue in the Replication Server per second.
Queue Reads	The number of commands read from the queue in the Replication Server.
Queue Reads per Second	The number of commands read from the queue in the Replication Server per second.
Queue Bytes	The number of bytes written to the queue in the Replication Server.

KPI	Description
Queue Bytes per Second	The number of bytes written to the queue in the Replication Server per second.
Queue Size	The size of the queue in the Replication Server.
Queue SQT Cache Percent Used	The percent of SQT cache size used for inbound queue.
Duplicates Transaction during monitoring interval	The number of duplicate commands detected and ignored by the SQM.
Transactions removed per second	The number of transactions removed from the SQT cache per second.
SQT cache low boundry	The smallest size to which SQT cache would be configured before transactions start being removed from cache.
Commands processed by DIST per second	The number of commands that the distributor thread processed for an inbound queue per second.
Commands processed without rep def per second	The number of commands that did not have an associated replication definition, which the distributor thread processed for an inbound queue per second.
Percent of blocks that were full when written to the queue	The percentage of blocks that were full when written to the queue.
Percent of reads that came directly from the cache	The percentage of reads that came directly from the cache.
Blocks full write total	Number of full blocks that an SQM thread wrote. Individual blocks can be written due either to block full state or to sysadmin command <b>slow_queue</b> (only one message per block).
Blocks written total	Number of 16K blocks that an SQM thread wrote to a stable queue.
Bytes written total	Bytes that an SQM thread wrote to a stable queue.
Commands written total	Commands that an SQM thread wrote to a stable queue.
Command size total	Command size written to a stable queue.
Segments active total	Active segments of an SQM queue: the number of rows in <b>rs_segments</b> for the given queue where <b>used_flag = 1</b> .
Queue segments allocated total	Segments allocated to a queue during the current statistical period.

## Configure

KPI	Description
Queue segments deallocated total	Segments deallocated from a queue during the current statistical period.
Time new segments allocated total	The elapsed time, in milliseconds, to allocate a new segment. Timer starts when a segment is allocated. Timer stops when the next segment is allocated.
Updates to <b>rs_oqid</b> total	Updates to the RSSD. <b>rs_oqid</b> table by an SQM thread. Each new segment allocation may result in an update of <b>rs_oqid</b> value stored in <b>rs_oqid</b> for recovery purposes.
Write requests total	Message writes that an SQM client requested.
Write timer pop total	SQM writer thread initiated a write request due to timer expiration.
Blocks read total	Number of 16 blocks that an SQM Reader (SQMR) thread read from a stable queue.
Blocks read cached total	Number of 16K blocks that an SQMR thread read from a cache.
Commands read total	Commands that an SQMR thread read from a stable queue.
Time waiting for queue write total	The amount of time SQMR wait for a queue write.
Unread blocks total	The number of blocks within a partially read segment that are yet to be read.
Unread segments total	The number of segments yet to be read.
Read time total	The amount of time taken for SQMR to read a block.
Memory used total	SQT thread memory use. Each command structure allocated by an SQT thread is freed when its transaction context is removed. For this reason, if no transactions are active in SQT, SQT cache usage is zero.
Transactions added closed total	Transactions added to the Closed queue.
Transactions removed closed total	Transactions removed from the Closed queue.
Commands read total	Commands read from SQM. Commands include <b>XREC_BEGIN</b> , <b>XREC_COMMIT</b> , <b>XREC_CHECKPT</b> .
Commands in tran total	Commands in transactions completely scanned by an SQT thread.
Transactions added total	Transactions added to the Open queue.

<b>KPI</b>	<b>Description</b>
Transactions removed total	Transactions removed from the Open queue.
Transactions added Read Q total	Transactions added to the Read queue.
Transactions removed Read Queue total	Transactions removed from the Read queue.
Cache lower bound size total	The smallest size to which SQT cache can be configured before transactions start being removed from cache.
Closed transactions total	Current closed transaction count.
Open transactions total	Current open transaction count.
Read transactions total	Current read transaction count.
Truncation queue transaction total	Current truncation queue transaction count.
Transactions removed total	Transactions whose constituent messages have been removed from memory. Removal of transactions is most commonly caused by a single transaction exceeding the available cache.
Truncation queue transactions added total	Transactions added to the Truncation queue.
Truncation queue transactions removed total	Transactions removed from the Truncation queue
<b>Partition</b>	
Partition State	The state of the partition in the Replication Server.
Partition Usage	The percent of the partition in the Replication Server that is currently in use.
<b>RepAgent</b>	
Replication Agent State	The state of the Replication Agent.
<b>RepAgent VM</b>	
VM maximum memory	Maximum memory (in bytes) available to the Java Virtual Machine (VM).
VM total memory allocated	Total memory (in bytes) allocated to the Java VM at start-up.
VM free memory	Memory (in bytes) allocated but not used by the Java VM.
VM memory usage	Memory (in bytes) allocated and in use by the Java VM.

## Configure

KPI	Description
VM % max memory used	Percentage of the the maximum memory available to the Java VM, currently in use by the Java VM.
<b>RepAgent LTI Statistics</b>	
Number of LTL commands sent	Total number of LTL commands sent to Replication Server.
LTL Commands Sent per Second	LTL commands sent to Replication Server per second.
Avg LTL command size	Average size (in bytes) of each LTL command sent to Replication Server.
Avg LTL commands/sec	Average number of LTL commands sent per second to Replication Server.
Total bytes sent	Number of bytes sent to Replication Server.
Avg Bytes/second during transmission	Average bytes per second sent over connection to Replication Server.
Avg LTL buffer cache time	Average time (in milliseconds) it takes between placing the LTL commands into the LTL buffer to the time it is actually sent to the Replication Server.
Avg Rep Server turnaround time	Average time (in milliseconds) it takes Replication Server to acknowledge each LTL command buffer sent.
Avg data arrival time	Average time (in milliseconds) log transfer interface (LTI) waits between receiving change sets from Log Reader.
Avg time to create distributes	Average time (in milliseconds) LTI takes to convert a change-set into LTL.
Avg LTL buffer size	Average size (in bytes) of each LTL buffer sent to Replication Server
Avg LTM buffer utilization (%)	Average utilization (in percentage of LTL buffer size) of each LTL buffer sent to Replication Server.
Avg LTL commands/buffer	Average number of LTL commands per buffer sent to Replication Server.
LTI encoded column name cache size	Encoded column name cache size.
LTI input queue size	Number of change sets in the LTI input queue
LTI output queue size	Current number of LTL commands in the LTI output queue.



KPI	Description
<b>RepAgent Log Reader Statistics</b>	
Total operations scanned	Number of operations read from the database transaction log.
Operations Scanned per Second	Number of operations read from the database transaction log per second.
Total operations processed	Number of operations processed from the database transaction log.
Operations Processed per Second	Number of operations process from the database transaction log per second.
Total operations skipped	Number of operations read from the database transaction log and skipped for any reason.
Operations Skipped per Second	Number of operations read from the database transaction log and skipped for any reason per second.
Current operation queue size	Current size (in bytes) of the Log Reader input queue.
Current scan buffer size	Current size (in bytes) of the Log Reader scan buffer.
Total maintenance user operations filtered	Number of maintenance-user operations read from the database transaction log and skipped.
Total Maintenance User Operations Filtered per Second	Number of maintenance-user operations read from database transaction log and skipped per second.
<b>RepAgent LTM Statistics</b>	
Items held in Global LRU Cache	Number of object references in the internal Least Recently Used cache.
<b>Adaptive Server RepAgent Thread</b>	
ASE Replication Agent Thread Status	The status of the Adaptive Server RepAgent thread in the data server.
ASE Replication Agent Thread Log	The difference between the current marker and the end of the log.
ASE Replication Agent Thread Operations Scanned	The number of operations scanned from the Adaptive Server transaction log since the last monitoring cycle.
ASE Replication Agent Thread Commands Processed	The number of commands processed and sent to the Replication Server since the last monitoring cycle.

**Table 19. Key performance areas**

<b>KPA</b>	<b>Description</b>
KPA_RS_PERF_STATS	Replication Server common statistics.
KPA_RS_HEATCHART	Replication Server heat chart statistics.
kpa_path	Replication path statistics.
KPA_PATH_RS_TICKET	The latency times at various points in the path between the primary database and the replicate database.
kpa_connection	Replication Server connection statistics.
KPA_CONNECTION_PERF_STATS	Replication Server connection performance statistics.
kpa_logical_connection	Replication Server logical connection statistics.
kpa_route	Replication Server route statistics.
KPA_ROUTE_PERF_STATS	Replication Server route performance statistics.
kpa_queue	Replication Server queue statistics.
KPA_QUEUE_PERF_STATS	Replication Server queue performance statistics.
kpa_partition	Replication Server partition statistics.
Availability Statistics	Replication Agent availability statistics.
VM Statistics	Replication Agent performance statistics on JAVA VM component.
LTM component Statistics	Replication Agent performance statistics on log transfer manager (LTM) component.
LTI component Statistics	Replication Agent performance statistics on LTI component.
LR component Statistics	Replication Agent performance statistics on log reader (LR) component.
kpa_ase	Adaptive Server statistics
kpa_rat_ctrl_availability	Adaptive Server RepAgent thread controller availability statistics.
kpa_rat_availability	Adaptive Server RepAgent thread availability statistics.

**See also**

- *Historical Performance Monitoring* on page 138
- *Heat Chart* on page 137

- *Replication Latency* on page 187
- *Availability Monitoring* on page 172
- *About Statistics* on page 98
- *Alerts* on page 145
- *Creating an Alert* on page 121
- *Assigning a Role to a Login or a Group* on page 81
- *Configuring the E-mail Server* on page 79

## Setting Replication Parameters

---

Configure replication parameters to improve server performance. Sybase Control Center for Replication allows you to configure the parameters for Replication Server, Replication Agent, connection and logical connection, route, and Adaptive Server RepAgent thread.

### See also

- *Setting Up Statistics Collection* on page 97
- *Creating an Alert* on page 121

## Configuring Replication Server and Replication Agent Parameters

---

Configure Replication Server and Replication Agent parameters.

### Prerequisites

Add all the servers to be monitored to the Perspective Resources view, authenticate them, and verify that you have the permission to perform this task.

### Task

1. From the Perspective Resources view, select a server and click **Resource > Monitor**.
2. Click **Quick Admin**.
3. In the Configure tab, modify the current value of the server parameter in the Run Value column.

---

**Note:** Use the filter text box and check box options to search for the parameter you want to modify.

---

4. Click **Apply All**.
5. (Optional) Click **Reset All** to undo modifications that have not been applied.

---

**Note:** Not all of Replication Server and Replication Agent parameters can be configured. If a parameter cannot be configured, the text box in the administration view is greyed out.

---

## **Configuring Connection Parameters for Replication Server**

Configure connection parameters that affect database connections originating from the Replication Server.

### **Prerequisites**

Add all the servers to be monitored to the Perspective Resources view, authenticate them, and verify that you have the permission to perform this task.

### **Task**

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Connections**.
3. Select a connection and click **Quick Admin**.
4. In the Configure tab, modify the current value of the connection parameter in the Run Value column.

---

**Note:** Use the filter text box and check box options to search for the parameter you want to modify.

---

5. Click **Apply All**.
6. (Optional) Select **Recycle connection** before you click **Apply All** to allow Replication Server to suspend, then resume connection.

---

**Note:** This option allows the new parameters to be applied to the connection. If you click **Apply All** without selecting **Recycle connection**, the parameters are not applied to the connection until the connection is restarted.

---

7. (Optional) Click **Reset All** to undo modifications that have not been applied.

## **Configuring Logical Connection Parameters for Replication Server**

Configure Replication Server parameters that apply to logical connections for warm standby applications.

### **Prerequisites**

Add all the servers to be monitored to the Perspective Resources view, authenticate them, and verify that you have the permission to perform this task.

### **Task**

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Logical Connection**.

3. Select a logical connection and click **Quick Admin**.
4. In the Configure tab, modify the current value of the logical connection parameter in the Run Value column.

---

**Note:** Use the filter text box and check box options to search for the parameter you want to modify.

---

5. Click **Apply All**.
6. (Optional) Click **Reset All** to undo modifications that have not been applied.

## **Configuring Route Parameters for Replication Server**

Configure parameters that affect routes from the current Replication Server to other Replication Servers.

### **Prerequisites**

Add all the servers to be monitored to the Perspective Resources view, authenticate them, and verify that you have the permission to perform this task.

### **Task**

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Routes**.
3. Select a route and click **Quick Admin**.
4. In the Configure tab, modify the current value of the route parameter in the Run Value column.

---

**Note:** Use the filter text box and check box options to search for the parameter you want to modify.

---

5. Click **Apply All**.
6. (Optional) Select **Recycle route** before you click **Apply All** to allow Replication Server to suspend, then resume the route.

---

**Note:** This option allows the new parameters to be applied to the route. If you click **Apply All** without selecting **Recycle route**, the parameters are not applied to the route until the route is restarted.

---

7. (Optional) Click **Reset All** to undo modifications that have not been applied.

## Configuring Adaptive Server RepAgent Thread Parameters

Configure Adaptive Server RepAgent thread parameters that affect replication performance.

### **Prerequisites**

Add all the servers to be monitored to the Perspective Resources view, authenticate them, and verify that you have the permission to perform this task.

### **Task**

1. From the Perspective Resources view, select an Adaptive Server and click **Resource > Monitor**.
2. Select a RepAgent thread.
3. Click **Quick Admin**.
4. In the Configure tab, modify the current value of the RepAgent thread parameter in the Run Value column.

---

**Note:** Use the filter text box and check box options to search for the parameter that you want to modify.

---

5. Click **Apply All**.
6. (Optional) Click **Reset All** to undo modifications that have not been applied.

---

**Note:** Not all of Adaptive Server RepAgent thread parameters can be configured. If a parameter cannot be configured, the text box in the administration view is greyed out.

---

## Configuring Replication Server to Gather Zero Values for Counters

Set the Replication Server parameter to gather zero values for performance counters when you run a collection job.

### **Prerequisites**

Add all the servers to be monitored in the Perspective Resources, and verify that you have permission to perform this task.

### **Task**

If you want zero values to be gathered for performance counters, run this command in the Replication Server:

```
configure replication server set stats_show_zero_counters to "on"
```

## Creating an Alert

---

Use the Add Alert wizard to create an alert instance for your resource.

### Prerequisites

- You must have administrative privileges (sccAdminRole) to perform this task.
- Specify an e-mail server for Sybase Control Center to use for alerts. You cannot create e-mail subscriptions to alerts without an e-mail server.
- Schedule data collections. Alerts for each product module are based on one or more data collections. If the correct collection or collections are not scheduled to run, the alert system cannot function and no alerts are generated. See the data collections topic for your product module for information on which collections you need to schedule to enable alerts.
- (Optional) If you want this alert to trigger the execution of a shell script, copy the script to a location on or accessible from the machine that hosts your Sybase Control Center server. Set permissions to make the script executable.

---

**Warning!** Use caution in writing scripts. A poorly designed script can cause a blocking situation, creating a deadlock in your Sybase Control Center server.

---

### Task

1. In the Perspective Resources view, click the server or other resource and select **Resource > Properties** in the view's menu bar.
2. Select **Alerts** in the left pane and click **Add**.  
The Add Alert Wizard opens. If the selected resource supports child alerts, the wizard opens to the Resource page. If the resource does not support child alerts, the wizard opens to the Type page—in that case, skip to step 5.
3. On the Resource page of the wizard, select the object on which to set the alert. Expand the folder representing the server or agent to select lower-level child objects.
4. Click **Next**.
5. On the Type page, select the alert type and click **Next**.  
For this step and the next one, see the topic on key performance indicators for information on what this alert monitors and how it is triggered. (Each alert is based on a KPI.)
6. Based on the type of alert you selected, do one of the following:
  - For a state-based alert – select a severity level for each alert state.  

---

**Note:** You can associate only one severity level with each state.

---
  - For a threshold-based alert – review and if necessary adjust the range of values that defines each severity.

## Configure

7. Click **Next**.
8. (Optional) Enter the storm suppression period. Storm suppression blocks redundant alert notifications and script executions resulting from the same condition for the specified period of time. Enter this value in seconds, minutes, or hours and click **Next**.

9. (Optional) To configure this alert to trigger the execution of a script:

- a) **Alert Severity** specifies the severity level that triggers the script. Select **Critical**, **Warning**, or both.

Critical is typically more serious than Warning.

- b) Browse to the location of the script.

---

**Note:** In UNIX, make sure the script is executable. You cannot select a script unless it has execute permission.

---

- c) If the script requires parameter values, click **Select Parameters** to enter them in the **Execution Parameters** box.

You can include a number of predefined substitution parameters, which are replaced by values from the alert. The parameter values are passed on the command line to the script. See the example (below) and the substitution parameters topic (linked below) for more information.

---

**Note:** When you test a script, Sybase Control Center supplies values for the **%Severity %** and **%Source\_Application%** parameters. Any test values you supply for these parameters are discarded.

---

- d) (Optional) Click **Test** to perform a test execution of your script.

If your script takes parameters, the test may fail if parameter values are missing or incorrect.

- e) Click **Next**.

If the selected resource has sibling resources (databases or devices of the same type, for example) that support this alert type, you see the Duplicates page. If the selected resource has no identical siblings, you see the Subscription page.

10. (Optional) On the Duplicates page, select any resources that should use this alert definition as a template for their own alerts. Click the box at the top of the list to select all the resources listed. Then click **Next**.

This step saves time when you need to configure similar alerts for several resources of the same type.

11. (Optional) On the Subscription page, specify e-mail addresses if you want this alert to issue e-mail notifications when it fires.

The e-mail addresses default to the address in your user profile, but you can override the defaults.

For both critical and warning alerts:



**Table 20. Alert subscription details**

Option	Description
E-mail	To send an e-mail notification when this alert fires, click the <b>E-mail Message</b> box and enter the e-mail address of one user or list.
Escalation E-mail	To escalate this alert (by sending another e-mail notification if this alert has not been responded to after a specified period of time), click the <b>Escalation E-mail</b> box and enter the e-mail address of one user or list. You cannot enter an escalation address unless you enter an address for primary notification first.
Time Period	Specify how long to wait, following the initial alert notification, before Sybase Control Center sends an e-mail notification to the escalation address. (The same notification is sent again to the original notification address.) Select a time unit (hours, minutes, or seconds) and enter a number.

**12. Click Finish.**

If you are creating duplicate or child alerts, the **Cancel** button is activated; click it to interrupt the creation of further alerts. (The primary alert, at a minimum, is always created before the operation can be cancelled.) If you do not want to keep the duplicate or child alerts (if any) created before you cancelled the operation, drop them manually.

---

**Note:** Click **Cancel** to stop the creation of duplicate alerts.

---

**Examples: Alert-triggered scripts**

This sample script is a Windows `.bat` file. It outputs the parameter values you pass to it to a text file. Windows batch files support only nine arguments. (Arg0, the name of the script, is not counted.)

```
@echo off
@echo. >> stest.txt
@echo %date% %time% >> stest.txt
@echo arg0: %0 >> stest.txt
@echo arg1: %1 >> stest.txt
@echo arg2: %2 >> stest.txt
@echo arg3: %3 >> stest.txt
@echo arg4: %4 >> stest.txt
@echo arg5: %5 >> stest.txt
@echo arg6: %6 >> stest.txt
@echo arg7: %7 >> stest.txt
@echo arg8: %8 >> stest.txt
@echo arg9: %9 >> stest.txt
@echo. >> stest.txt
```

This is a sample execution parameter string for the script above:

```
Time:%Time%
Severity:%Severity%
```

## Configure

```
Resource:%Resource%
Server:%Top_resource%
KPI:%KPI%
State:%Current_state%
URL:%SCC_URL%
```

The script's output might look like this:

```
Tue 12/15/2009 14:54:45.58
arg0: C:\project\scmain\script-test.bat
arg1: Time:"Mon Dec 21 21:30:04 2009"
arg2: Severity:CRITICAL
arg3: Resource:"SCC Tester 1"
arg4: Server:"SCC Tester 1"
arg5: KPI:kpi_scc_mostate_primary
arg6: State:ERROR
arg7: HYPERLINK "http://ik-scc.sybase.com:8282/scc"URL:http://ik-
scc.sybase.com:8282/scc
arg8:
arg9:
```

This is a UNIX script. It also outputs the parameter values you pass to it to a text file.

```
#!/bin/sh
outfile=c:/testing/latest/scriptTest.out
echo> $outfile
echo `date` >> $outfile
count=1
while [ "$1" ]
do
  echo arg$count: $1 >> $outfile
  shift
  count=`expr $count + 1`
done
echo --- DONE --- >> $outfile
```

### See also

- *Setting Replication Parameters* on page 117
- *Optional Configuration Steps* on page 134
- *Alerts* on page 145
- *Replication Data Collections* on page 99
- *Key Performance Indicators and Key Performance Areas for Replication* on page 100
- *Testing an Alert-Triggered Script* on page 148

## Replication Alerts

Lists and describes alerts you can use to create alert instances for Replication.

Alerts are based on the same key performance indicators (KPIs) that are collected for the performance and availability monitor displays, and for the Statistics Chart.

Replication Objects	Alerts	Description	Alert Type
Replication Server	State Change	The alert to send when a Replication Server state changes.	State
	Memory Usage	The alert to send when a Replication Server memory usage is above the configured threshold.	Threshold
	Partition Usage	The alert to send when a Replication Server partition's usage is above the configured threshold.	Threshold
Paths	Path State Change	The alert to send when a replication path's state changes.	State
	Change in Path Activity	The alert to send when the numbers of operations sent on a replication path is above the configured threshold.	Threshold
Connections	Connection State Change	The alert to send when a Replication Server connection for the primary database changes state.	State
	DSI Activity	The alert to send when the numbers of operations sent on a Replication Server DSI connection is above the configured threshold.	Threshold
	DSI Activity per Second	The alert to send when the numbers of operations sent on a Replication Server DSI connection per second is above the configured threshold.	Threshold
Logical Connections	Logical Connection State Change	The alert to send when a Replication Server logical connection changes state.	State
Routes	Route State Change	The alert to send when a Replication Server route's state changes.	State
	Route Activity	The alert to send when the change in number of bytes sent through a Replication Server route is above the configured threshold.	Threshold

## Configure

Replication Objects	Alerts	Description	Alert Type
	Route Activity per Second	The alert to send when the number of bytes sent through a Replication Server route per second is above the configured threshold.	Threshold
Queues	Number of Commands Written	The alert to send when the number of commands written to a Replication Server queue is above the configured threshold.	Threshold
	Number of Commands Written per Second	The alert to send when the number of commands written to a Replication Server queue per second is above the configured threshold.	Threshold
	Number of Commands Read	The alert to send when the number of commands read from a Replication Server queue is above the configured threshold.	Threshold
	Number of Commands Read per Second	The alert to send when the number of commands read from a Replication Server queue per second is above the configured threshold.	Threshold
	Size of Commands Written	The alert to send when the number of commands bytes written to a Replication Server queue is above the configured threshold.	Threshold
	Size of Commands Written per Second	The alert to send when the number of bytes written to a Replication Server queue is above the configured threshold.	Threshold
	Queue Size	The alert to send when the size of a Replication Server queue is above the configured threshold.	Threshold
Partitions	Partition Usage	The alert to send when a Replication Server partition's usage is above the configured threshold.	Threshold

Replication Objects	Alerts	Description	Alert Type
Replication Agent and Mirror Replication Agent	State Change	The alert to send when a Replication Agent state changes.	State
	Memory Usage	The alert to send when a Replication Agent memory usage is above the configured threshold.	Threshold
	LTI Input Queue Size	The alert to send when the number of change sets in a Replication Agent Log Transfer Interface (LTI) input queue is above the configured threshold.	Threshold
	LTI Output Queue Size	The alert to send when the number of change sets in a Replication Agent LTI output queue is above the configured threshold.	Threshold
	Number of LTL Commands Sent	The alert to send when the number of Replication Agent Log Transfer Language (LTL) commands sent to Replication Server is above the configured threshold.	Threshold
	Number of LTL Commands Sent per Second	The alert to send when the number of Replication Agent LTL commands sent to Replication Server per second is above the configured threshold.	Threshold
	Number of Operations Scanned	The alert to send when the number of operations scanned by a Replication Agent Log Reader is above the configured threshold.	Threshold
	Number of Operations Scanned per Second	The alert to send when the number of operations scanned by a Replication Agent Log Reader per second is above the configured threshold.	Threshold
	Number of Operations Processed	The alert to send when the number of operations processed by a Replication Agent Log Reader is above the configured threshold.	Threshold

Configure

Replication Objects	Alerts	Description	Alert Type
	Number of Operations Processed per Second	The alert to send when the number of operations processed by a Replication Agent Log Reader per second is above the configured threshold.	Threshold
	Number of Operations Skipped	The alert to send when the number of operations skipped by a Replication Agent Log Reader is above the configured threshold.	Threshold
	Number of Operations Skipped per Second	The alert to send when the number of operations skipped by a Replication Agent Log Reader per second is above the configured threshold.	Threshold
	Number of Maintenance-User Operations Skipped	The alert to send when the number of maintenance-user operations skipped by a Replication Agent Log Reader is above the configured threshold.	Threshold
	Number of Maintenance-User Operations Skipped per Second	The alert to send when the number of maintenance-user operations skipped by a Replication Agent Log Reader per second is above the configured threshold.	Threshold
	Log Reader Queue Size	The alert to send when the size (in bytes) of a Replication Agent Log Reader input queue is above the configured threshold.	Threshold
	Log Reader Scan Buffer Size	The alert to send when the size (in bytes) of a Replication Agent Log Reader scan buffer is above the configured threshold.	Threshold
Adaptive Server Enterprise	State Change	The alert to send when an Adaptive Server state changes.	State
Adaptive Server RepAgent Thread	RepAgent Thread State Change	The alert to send when an Adaptive Server RepAgent Thread changes state.	State

Replication Objects	Alerts	Description	Alert Type
	Transaction Log Size	The alert to send when the size of an Adaptive Server RepAgent Thread's transaction log is above the configured threshold.	Threshold
	Number of Log Operations Scanned per Second	The alert to send when the number of log operations scanned per second by an Adaptive Server RepAgent Thread is above the configured threshold	Threshold
	Number of Log Operations Processed per Second	The alert to send when the number of log operations processed per second by an Adaptive Server RepAgent Thread is above the configured threshold.	Threshold

**See also**

- *Alert Types, Severities, and States for Replication* on page 129
- *Substitution Parameters for Scripts* on page 132
- *Alert-Triggered Scripts* on page 132

**Alert Types, Severities, and States for Replication**

Learn about the properties that define and control alerts.

An alert's type determines what causes it to fire.

**Table 21. Alert types**

Type	Description
State	A state alert fires when the metric on which it is based changes to a particular state. The possible states are running, pending, stopped, warning, error, and unknown.
Threshold	A threshold alert fires when the metric on which it is based passes a preset level.

Alert severities control when an alert is issued. You can configure the states or threshold values for each alert.

**Table 22. Alert severities**

Severity	Description
Normal	No alert is issued.

## Configure

Severity	Description
Warning	A problem has given cause for concern. An alert is issued; you can subscribe to alerts that fire at the Warning level.
Critical	A serious problem exists. An alert is issued; you can subscribe to alerts that fire at the Critical level.

States are used on the dashboards, heat chart, and topology icon decorators.

**Table 23. Replication States**

Replication Object	State	Description
Replication Server	Running	Replication Server is in Active or Quiesce state.
	Warning	Replication Server is in Suspect state.
	Stopped	Replication Server is in Rebuilding, Hibernating, Recovering, and Standalone state.
	Error	Replication Server is in Down state.
	Unknown	The state of the Replication Server cannot be determined.
Replication Server Connection	Running	Replication Server connection is in Active or Hidden state.
	Stopped	Replication Server connection is in Suspended state.
	Unknown	The state of the Replication Server connection cannot be determined.
Replication Server Logical Connection	Running	Replication Server logical connection is in Active state.
	Stopped	Replication Server logical connection is in Suspended state.
	Unknown	The state of the Replication Server logical connection cannot be determined.
Replication Server Route	Running	Replication Server route is in Active state.
	Stopped	Replication Server route is in Suspended state.



Replication Object	State	Description
	Unknown	The state of the Replication Server route cannot be determined.
Replication Path	Running	Replication path is in Active state.
	Stopped	Replication path is in Suspended state.
	Unknown	The state of the Replication path cannot be determined.
Replication Agent	Running	Replication Agent is in Replicating state.
	Stopped	Replication Agent is in Admin state.
	Error	Replication Agent is in Down state.
	Unknown	The state of the Replication Agent cannot be determined.
Adaptive Server Replication Agent Thread	Running	Adaptive Server Replication Agent thread is in Active state.
	Stopped	Adaptive Server Replication Agent thread is in Suspended state.
	Error	Adaptive Server Replication Agent thread is in Down state.
Replication-Only Adaptive Server	Running	Replication-only Adaptive Server is in Active state.
	Error	Replication-only Adaptive Server is in Down state.
	Unknown	The state of the Replication-only Adaptive Server cannot be determined.

**See also**

- *Replication Alerts* on page 124
- *Substitution Parameters for Scripts* on page 132
- *Alert-Triggered Scripts* on page 132

## **Alert-Triggered Scripts**

You can write a shell script and configure an alert to execute the script.

Use scripts to help manage and respond to alerts. A script might trigger a visual alarm in a control center or send an e-mail message about the alert to a list of addresses (a way of supplementing the alert subscription feature, which accepts a single address).

When you configure an alert to execute a script, you:

- Specify the states or thresholds that set off the alert
- Specify the severity level that triggers execution of the script
- Supply an execution parameter string to be passed to the script

Scripts are executed under the login account used to start Sybase Control Center. Make sure that account has permissions that allow it to perform the actions contained in all scripts.

When a script executes, Sybase Control Center logs the start time, end time, and status and exit codes to the alert services log at <SCC-installation-dir>\SCC-3\_2\services\Alert\log>alert-server.log.

---

**Warning!** Use caution in writing scripts. A poorly designed script can cause a blocking situation, creating a deadlock in your Sybase Control Center server.

---

### **See also**

- *Replication Alerts* on page 124
- *Alert Types, Severities, and States for Replication* on page 129
- *Substitution Parameters for Scripts* on page 132
- *Testing an Alert-Triggered Script* on page 148
- *Alerts* on page 145

## **Substitution Parameters for Scripts**

In the execution parameter string you supply to be passed to your shell script, you can include substitution parameters that are replaced at execution time with values from the alert that triggers the script.

Substitution parameters are available for both state-based and threshold-based alerts.

**Table 24. Substitution Parameters for State-Based Alerts**

<b>Parameter</b>	<b>Description</b>
%Alert%	A three-part name supplied by the alert system. The parts are the name of this alert, the name of the resource, and the name of the key performance indicator (KPI) on which this alert is based.

Parameter	Description
%Current_state%	The current state of the resource on which this alert is configured.
%KPI%	The name of the KPI on which this alert is based.
%Resource%	The name of the resource with which this alert is associated.
%SCC_URL%	A link to Sybase Control Center, where more information about the alert may be available.
%Severity%	The severity of this alert: critical or warning.
%Source_application%	The SCC product module that generated this alert.
%Time%	The date and time at which the alert fired, in this format: Tue Sep 15 10:10:51 2009
%Server%	The name of the alerted resource's top-level parent resource—usually the server. This is valuable when the alerted resource is a component of a larger system (a database in a server, for example). If the alerted resource has no parent, %Server% and %Resource% have the same value.

**Table 25. Substitution Parameters for Threshold-Based Alerts**

Parameter	Description
%Alert%	A three-part name supplied by the alert system. The parts are the name of this alert, the name of the resource, and the name of the key performance indicator (KPI) on which this alert is based.
%Datapoint%	The current value, on the alerted resource, of the KPI on which this alert is based.
%KPI%	The name of the KPI on which this alert is based.
%Resource%	The name of the resource with which this alert is associated.
%SCC_URL%	A link to Sybase Control Center, where more information about the alert may be available.
%Severity%	The severity of this alert: critical or warning. (Critical is more serious.)
%Source_application%	The SCC product module that generated this alert.
%Threshold%	The threshold value at which this alert fires.

## Configure

Parameter	Description
%Time%	The date and time at which the alert fired, in this format: Tue Sep 15 10:10:51 2009
%Server%	The name of the alerted resource's top-level parent resource. This is valuable when the alerted resource is a component of a larger system (a database in a server, for example). If the alerted resource has no parent, %Server% and %Resource% have the same value.

### See also

- *Replication Alerts* on page 124
- *Alert Types, Severities, and States for Replication* on page 129
- *Alert-Triggered Scripts* on page 132
- *Testing an Alert-Triggered Script* on page 148
- *Modifying an Alert* on page 147

## Optional Configuration Steps

---

Perform additional configuration, including user authorization, alerts, data collection scheduling, backups, and setting purging options for the repository.

**Table 26. Configuration areas**

Configuration area	Description	Topic
User authorization	Set up groups of users or assign roles. Make sure there are users with administrative privileges (sccAdminRole).	<i>User Authorization</i> on page 81
Authentication	Add authentication modules to allow Windows, UNIX, and LDAP users to log in to Sybase Control Center.	<i>Setting up Security</i> on page 63
Alerts	Modify alert thresholds and subscriptions and delete alerts.	<i>Alerts</i> on page 145
Data collection	Modify collection intervals and schedules, suspend and resume the schedule, and delete collection jobs.	<i>Job Scheduling</i> on page 140
Resources	Unregister resources, add them to perspectives, or remove them.	<i>Resources</i> on page 153

Configuration area	Description	Topic
Perspectives	Create, remove, and rename perspectives.	<i>Perspectives</i> on page 156
Repository	Set purging options and schedule backups of the repository database.	<i>Repository</i> on page 158

**See also**

- *Creating an Alert* on page 121

Configure

# Manage and Monitor

Manage and Monitor the servers and their components in the replication environment.

## Heat Chart

---

The heat chart displays status and availability statistics for managed resources in the current perspective.

The heat chart displays the state of resources in your perspective—whether the resources are running, suspended, or down. In addition, the heat chart lists the type of each resource and provides statistical data, including the start time of the last data collection.

In the Perspective Heat Chart view, you can filter the resources that you want to see and search and sort the results by column. You can also select a resource and pull down its context menu to see monitoring and administrative options that vary based on the resource type.

Heat chart data is collected directly from managed servers, tagged with the date and time when it was collected, and stored in the Sybase Control Center repository.

### See also

- *Historical Performance Monitoring* on page 138
- *Replication Latency* on page 187
- *Availability Monitoring* on page 172
- *Key Performance Indicators and Key Performance Areas for Replication* on page 100

## Displaying Resource Availability

Use the heat chart to view availability information on the servers in the current perspective.

1. From the application menu bar, select **View > Open > Heat Chart**.
2. (Optional) To display tools for filtering (narrowing the list of resources in the heat chart) or changing the columns, select **View > Filter** from the Perspective Heat Chart menu bar. The Filter and Column tools appear in the left pane.
3. (Optional) To use filtering, select **View > Filter** from the view's menu bar and enter a search term in the **Filter string** field.  
The search term can be any string that appears in the tabular portion of the heat chart, such as the name, or part of the name, of a server or a resource type (ASE Server, for example).
4. (Optional) Select a filtering setting:

- **Match case** – search for resources whose displayed data includes the search term, including uppercase and lowercase letters; or
  - **Exact match** – search for resources whose displayed data includes an item identical to the search term.
5. (Optional) Select a column from the **Filter on** list to restrict your search to that column.
  6. (Optional) Click **Columns** to customize your heat chart.
  7. (Optional) Unselect any column that should not appear in your heat chart.
  8. (Optional) Click the sorting arrow in the column headers to sort the column values in either ascending or descending order.
  9. (Optional) Click the resource's row and pull down the menu to the right of the resource name to view options for the selected resource.
  10. (Optional) To resize the Filter and Columns tools pane, move your mouse over the border between the tools pane and the resource table. When the mouse cursor changes to a resize icon, click and drag the border to the left or the right.
  11. (Optional) To hide the Filter and Columns tools, unselect **View > Filter**.

### See also

- *Graphing Performance Counters* on page 138
- *Configuring Repository Purging* on page 163

## Historical Performance Monitoring

---

Monitor performance data to determine whether your environment is working efficiently.

Obtain detailed information about the status of the resources in your environment. You can create performance graphs that illustrate resource performance over a specified period of time.

### See also

- *Heat Chart* on page 137
- *Replication Latency* on page 187
- *Availability Monitoring* on page 172
- *Key Performance Indicators and Key Performance Areas for Replication* on page 100

## Graphing Performance Counters

---

To show performance trends, generate a graph for any set of performance counters.

### Prerequisites

Verify that statistical data to be graphed has been collected. To verify data collection, go to the Collection Jobs page of the Resource Properties view and check the History tab for a



collection job. You can also look at the resource monitor: if data appears there, data is being collected.

## Task

---

**Tip:** Data collections start running when a resource is authenticated. A recently authenticated resource might not have accumulated enough data to make a useful graph.

---

1. In the Perspective Resources view, click a resource and select **Resource > Launch Statistics Chart** in the view menu bar.
2. Expand the folders in the Statistics tab and select the key performance indicator (KPI) you want to graph.
3. Click **Graph Statistic** or drag the KPI onto the Chart tab.  
The Chart tab displays the graphed data, while the KPI with its corresponding value and the date and time it was collected appear in the Data tab.
4. (Optional) Repeat to add KPIs to the graph.
5. (Optional) Use the slider at the bottom of the Chart tab to control the amount of time covered by the graph, ranging from a minute to a year.
6. (Optional) Use <<, <, >, and >> to move the displayed graph to an earlier or later time, depending on how the slider is set.

---

**Tip:** The statistics chart displays data covering a fixed period of time, and that period does not change automatically. If you are viewing the most recent statistics and want to keep the graph current, adjust the displayed time period as new statistics are collected.

---

7. (Optional) You can click the date/time labels that appear above the slider. Use these to change the start and end time and the chart time span.
8. (Optional) Click **Clear Graph** to remove all the graphed statistics and start anew.

---

**Note:** You can graph a maximum of five statistics with no more than two distinct units of measure. By default, only 24 hours of statistics are available; change the repository purge options to save statistics for a longer period.

---

## See also

- *Configuring Repository Purging* on page 163
- *Displaying Resource Availability* on page 137

## Manage Sybase Control Center

---

Manage and monitor Sybase Control Center for Replication through performance statistics and component activity logs.

## **Administration Console**

Use the Administration Console to browse and manage the selected resources in a perspective.

### **Browsing and Managing Resources**

Create new resources or browse and manage existing resources.

#### **Prerequisites**

If you want to view or manage existing resources, register at least one resource and add it to a perspective.

#### **Task**

The Administration Console enables you to view and manage both servers and resources below the server level, such as processes, databases, and devices.

1. To launch the Administration Console, select (from the application menu) **View > Open > Administration Console**.
2. Expand the objects in the left pane to explore the hierarchy of resource types.
3. Select a high-level resource type (a logical server, for example) in the hierarchy.  
The Administration Console displays a list of resources of that type. You can use the Folder menu to create another server of the same type, or to refresh the view.
4. Select various objects in the hierarchy.  
Information about each selected object appears in the table in the right pane.
5. In either the right or the left pane, select an object.  
A dropdown arrow appears to the right of the name. If the selected object is in the right pane, the **Resource** menu becomes active.
6. Click the dropdown arrow to display a menu of actions you can perform on that object. If the selected object is in the right pane, use the **Resource** menu to display the same actions.

---

**Note:** Some managed objects have no actions.

---

## **Job Scheduling**

A schedule defines a data collection job and specifies how often the job executes in your system.

In Sybase Control Center, collection jobs provide the data that appears on monitoring screens and charts. A collection is a set of key performance indicators (KPIs). When the scheduler runs a collection job, it gathers the value of each KPI in the collection and tags the data with the date and time it was gathered. The data is stored in the repository and displayed. Each product module has predefined collections that you can schedule.

You can define schedules as one-time or repeating. You can modify the schedule for a job based on a number of attributes such as:

- Repeat interval
- Date
- Time

The job history displays the status of jobs executed each day.

### See also

- *Setting Up Statistics Collection* on page 97
- *Replication Data Collections* on page 99

### **Executing and Stopping a Data Collection Job**

Use the Properties view to execute or stop a data collection job.

Most of the time, data collection jobs should run on a schedule; you should rarely need to start or stop a job manually.

1. In the Perspective Resources view, select the resource associated with the job and select **Resource > Properties**.
2. Select **Collection Jobs**.
3. Select the job and:
  - To execute a job immediately, click **Execute**.
  - To stop a job, click **Stop**, then click **Yes** to confirm.

### See also

- *Deleting a Data Collection Job* on page 141
- *Resuming and Suspending a Data Collection Job* on page 142
- *Adding a New Schedule to a Job* on page 142
- *Modifying the Data Collection Interval for a Job* on page 143
- *Resuming and Suspending the Scheduler* on page 144
- *Viewing the Job Execution History* on page 145

### **Deleting a Data Collection Job**

Use the Properties view for a resource to delete one or more data collection jobs.

1. In the Perspective Resources view, select the resource associated with the job and select **Resource > Properties**.
2. Select **Collection Jobs**.
3. Select the job and click **Delete**.
4. Click **OK** to confirm the deletion.

**See also**

- *Executing and Stopping a Data Collection Job* on page 141
- *Resuming and Suspending a Data Collection Job* on page 142
- *Adding a New Schedule to a Job* on page 142
- *Modifying the Data Collection Interval for a Job* on page 143
- *Resuming and Suspending the Scheduler* on page 144
- *Viewing the Job Execution History* on page 145

**Resuming and Suspending a Data Collection Job**

Use the Properties view for a resource to resume or suspend a data collection job.

1. In the Perspective Resources view, select the resource associated with the job and select **Resource > Properties**.
2. Select **Collection Jobs**.
3. Select the job and:
  - To resume a job, click **Resume**.
  - To suspend a job, click **Suspend**, then click **Yes** to confirm the suspension.

**See also**

- *Executing and Stopping a Data Collection Job* on page 141
- *Deleting a Data Collection Job* on page 141
- *Adding a New Schedule to a Job* on page 142
- *Modifying the Data Collection Interval for a Job* on page 143
- *Resuming and Suspending the Scheduler* on page 144
- *Viewing the Job Execution History* on page 145

**Adding a New Schedule to a Job**

Use the Properties view for a resource to add more than one schedule to a job.

1. In the Perspective Resources view, select the resource associated with the job and select **Resource > Properties**.
2. Select **Collection Jobs**.
3. Select the job.
4. Click **Add Schedule**.
5. Specify details for the new schedule:

**Table 27. New schedule details**

Field	Description
Name	A name for this schedule

Field	Description
Description	A description of this schedule
Start date	The day when the schedule will take effect
Time	The time when the schedule will take effect

**Note:** Enter dates and times using your local time. Sybase Control Center converts your times for remote time zones if necessary.

6. Specify the duration of this schedule:

- **Run once**
- **Repeat until**

For **Repeat until**, specify these details:

Field	Description
Repeat interval	Time period (in seconds, minutes, hours, or days) between job executions
Repeat until	Date the job should stop running
Time	Time the job should stop running

- **Repeat indefinitely**

For **Repeat indefinitely**, specify these details:

Field	Description
Repeat interval	Time period (in seconds, minutes, hours, or days) between job executions

7. Click **Apply**.

**See also**

- *Executing and Stopping a Data Collection Job* on page 141
- *Deleting a Data Collection Job* on page 141
- *Resuming and Suspending a Data Collection Job* on page 142
- *Modifying the Data Collection Interval for a Job* on page 143
- *Resuming and Suspending the Scheduler* on page 144
- *Viewing the Job Execution History* on page 145

**Modifying the Data Collection Interval for a Job**

Use the Properties view for a managed resource to modify the data collection schedule.

1. In the Perspective Resources view, select a server (or other resource).
2. In the view's menu bar, select **Resource > Properties**.

3. Select **Collection Jobs**.
4. Expand a collection folder and select a job.
5. On the **Schedule** tab, modify the Repeat interval field.
6. Click **Apply**.

### See also

- *Executing and Stopping a Data Collection Job* on page 141
- *Deleting a Data Collection Job* on page 141
- *Resuming and Suspending a Data Collection Job* on page 142
- *Adding a New Schedule to a Job* on page 142
- *Resuming and Suspending the Scheduler* on page 144
- *Viewing the Job Execution History* on page 145

### Resuming and Suspending the Scheduler

Use the scheduler settings to resume or suspend all scheduled jobs.

### Prerequisites

You must have administrative privileges (sccAdminRole) to perform this task.

### Task

1. From the main menu bar, select **Application > Administration**.
2. In the Sybase Control Center Properties dialog, select **Scheduler**.
3. Do one of the following:
  - To resume the scheduler, click **Resume**.
  - To suspend the scheduler, click **Suspend**.
4. Click **OK**.

### See also

- *Executing and Stopping a Data Collection Job* on page 141
- *Deleting a Data Collection Job* on page 141
- *Resuming and Suspending a Data Collection Job* on page 142
- *Adding a New Schedule to a Job* on page 142
- *Modifying the Data Collection Interval for a Job* on page 143
- *Viewing the Job Execution History* on page 145

## **Viewing the Job Execution History**

Use the Properties view to display a data collection job's execution history.

1. In the Perspective Resources view, select the resource associated with the job and select **Resource > Properties**.
2. Select **Collection Jobs**.
3. Select a job.
4. Click the **History** tab.

### **See also**

- *Executing and Stopping a Data Collection Job* on page 141
- *Deleting a Data Collection Job* on page 141
- *Resuming and Suspending a Data Collection Job* on page 142
- *Adding a New Schedule to a Job* on page 142
- *Modifying the Data Collection Interval for a Job* on page 143
- *Resuming and Suspending the Scheduler* on page 144

## **Alerts**

You can configure Sybase Control Center to notify you when a resource requires attention.

You do this by setting up a predefined alert that is triggered when a performance counter enters a particular state or passes a threshold value that you set. When the alert goes off, it generates an alert notification.

An alert notification takes the form of a visual indicator in the Alert Monitor and, optionally, an e-mail message. The Alert Monitor displays information about the alert, including the resource name, alert severity, value, and date. You can resolve the alert or allow it to escalate.

Configure, monitor, and control alerts for managed resources by:

- Enabling and disabling alert subscriptions for resources
- Configuring shell scripts to run when alerts fire
- Setting alert state or threshold triggers
- Responding to an alert by resolving it, adding notes if desired
- Modifying or deleting alerts
- Viewing alert history

### **See also**

- *Replication Data Collections* on page 99
- *Key Performance Indicators and Key Performance Areas for Replication* on page 100
- *Creating an Alert* on page 121
- *Assigning a Role to a Login or a Group* on page 81

- *Configuring the E-mail Server* on page 79
- *Alert-Triggered Scripts* on page 132

### **Types, Severities, and States**

Learn about the properties that define and control alerts.

An alert's type determines what causes it to fire.

**Table 28. Alert types**

Type	Description
State	A state alert fires when the metric on which it is based changes to a particular state. The possible states are running, pending, stopped, warning, error, and unknown.
Threshold	A threshold alert fires when the metric on which it is based passes a specified level.

Alert severities control when an alert is issued. You can configure the states or threshold values for each alert.

**Table 29. Alert severities**

Severity	Description
Normal	No alert is issued.
Warning	A problem has given cause for concern. An alert is issued; you can choose whether to subscribe to alerts that fire at the Warning level.
Critical	A serious problem exists. An alert is issued; you can choose whether to subscribe to alerts that fire at the Critical level.

State-based alerts use these states:

- Running
- Pending
- Unknown
- Warning
- Stopped
- Error

The definitions of these states vary by component and sometimes by alert. See the component-specific topics for details.

### **See also**

- *Viewing Alerts* on page 147
- *Modifying an Alert* on page 147



- *Testing an Alert-Triggered Script* on page 148
- *Deleting an Alert* on page 149
- *Alert Subscriptions* on page 149
- *Alert Notifications* on page 152

### **Viewing Alerts**

Display alert notifications and alerts that have been configured for a given resource.

- To display generated alerts (notifications):
  - a) Select **View > Open > Alert Monitor** from the application menu bar.  
For a given alert, the Alert Monitor displays only the most recent unresolved notifications at each severity level. That is, if an alert fires five times at the warning level, only the notification of the fifth firing is listed—even if the previous four alerts remain unresolved.
  - b) To display information about a generated alert, select the alert in the Alert Monitor and click **Properties**.
- To display configured alerts:
  - a) In the Perspective Resources view, select a resource and select **Resource > Properties**.
  - b) Click **Alerts** to view configured alerts for the selected resource.  
(This is a different route to the information displayed in the second step, above.)

### **See also**

- *Types, Severities, and States* on page 146
- *Modifying an Alert* on page 147
- *Testing an Alert-Triggered Script* on page 148
- *Deleting an Alert* on page 149
- *Alert Subscriptions* on page 149
- *Alert Notifications* on page 152

### **Modifying an Alert**

Use the Properties view of your managed resource to modify an alert.

1. In the Perspective Resources view, select a resource and select **Resource > Properties**.
2. Select **Alerts**.
3. Select the alert to modify.
4. On the Thresholds tab, modify the threshold values. Click **OK** to save your changes.
5. On the Script tab, click **Modify** to change the alert severity at which script execution is triggered, the path to the script, the execution parameters, or the test values. Click **Finish** to save your changes.

6. On the Subscriptions tab, select a subscription and click **Modify** to change its e-mail address or escalation address. Click **Finish** to save your changes.
7. On the Storm Suppression tab, pull down the menu to change the units and enter a value for the storm suppression period.
8. Click **OK** (to apply the changes and close the properties dialog) or **Apply** (to apply the changes and leave the dialog open).

### See also

- *Types, Severities, and States* on page 146
- *Viewing Alerts* on page 147
- *Testing an Alert-Triggered Script* on page 148
- *Deleting an Alert* on page 149
- *Alert Subscriptions* on page 149
- *Alert Notifications* on page 152

### **Testing an Alert-Triggered Script**

Execute a script to make sure it works properly.

### **Prerequisites**

Configure an alert with a script.

### **Task**

1. In the Perspective Resources view, select a resource and select **Resource > Properties**.
2. Select **Alerts**.
3. Select the alert to test.
4. On the Script tab, click **Modify**.
5. If the script requires parameter values, click **Select Parameters** to enter them in the **Execution Parameters** box.

You can include a number of predefined substitution parameters, which are replaced by values from the alert. The parameter values are passed on the command line to the script. For the test execution, use values that test all the parameters used by the script. See the substitution parameters topic (linked below) for more information.

---

**Note:** When you test a script, Sybase Control Center supplies values for the **%Severity%** and **%Source\_Application%** parameters. Any test values you supply for these parameters are discarded.

---

6. Click **Test** to perform a test execution of your script.

If your script takes parameters, the test may fail if parameter values are missing or incorrect.

**See also**

- *Types, Severities, and States* on page 146
- *Viewing Alerts* on page 147
- *Modifying an Alert* on page 147
- *Deleting an Alert* on page 149
- *Alert Subscriptions* on page 149
- *Alert Notifications* on page 152
- *Alert-Triggered Scripts* on page 132
- *Substitution Parameters for Scripts* on page 132
- *Creating an Alert* on page 121

**Deleting an Alert**

Use the Properties view of your resource to delete an alert.

1. In the Perspective Resources view, select a resource and select **Resource > Properties**.
2. Select **Alerts**.
3. Select an alert and click **Drop**.
4. Click **Yes** to confirm the deletion.

**See also**

- *Types, Severities, and States* on page 146
- *Viewing Alerts* on page 147
- *Modifying an Alert* on page 147
- *Testing an Alert-Triggered Script* on page 148
- *Alert Subscriptions* on page 149
- *Alert Notifications* on page 152

**Alert Subscriptions**

When an alert subscription is configured, the alert notifies the specified user or group of users by e-mail message when the alert fires.

You can configure an alert subscription to send e-mail notifications when the alert reaches a severity of warning, a severity of critical, or both.

You can also configure an alert subscription to escalate after a period of time that you specify. If the alert is not resolved within the escalation period, Sybase Control Center e-mails an escalation message to the user or group whose address you provide for escalations, as well as to the primary subscriber. The escalation message is identical to the primary notification message. Sybase recommends that if you configure alert subscriptions to escalate, you do so only for the most urgent alerts, those with a severity of critical.

### See also

- *Types, Severities, and States* on page 146
- *Viewing Alerts* on page 147
- *Modifying an Alert* on page 147
- *Testing an Alert-Triggered Script* on page 148
- *Deleting an Alert* on page 149
- *Alert Notifications* on page 152

### Adding or Modifying an Alert Subscription

Use the Properties view to subscribe to an alert or edit an alert subscription.

### Prerequisites

Specify the e-mail server to which Sybase Control Center will send e-mail alert notifications.

### Task

Each alert can support one subscription. To change addresses, modify the alert's existing subscription.

---

**Note:** E-mail notifications are sent from an address of the form SybaseControlCenter@yourdomain—for example, SybaseControlCenter@Bigcompany.com. Make sure your mail system does not block or filter that address.

---

1. In the Perspective Resources view, select a resource and select **Resource > Properties**.
2. Select **Alerts**.
3. Select an alert instance.
4. On the **Subscriptions** tab:
  - Click **Add** to create a subscription, or
  - Select a subscription and click **Modify** to edit an existing subscription
5. Follow the instructions in the Add Alert Subscription wizard.

For both critical and warning alerts:

**Table 30. Alert subscription details**

Option	Description
E-mail message	To send an e-mail notification when this alert fires, click the <b>E-mail message</b> box and enter the e-mail address of one user or list.

Option	Description
Escalation e-mail	To escalate this alert (by sending an e-mail notification to another address when this alert has not been responded to after a specified period of time), click the <b>Escalation e-mail</b> box and enter the e-mail address of one user or list.
Time period	Enter the amount of time to wait, following the initial alert notification, before Sybase Control Center sends an e-mail notification to the escalation address.

6. Click **Finish**.

**See also**

- *Unsubscribing from an Alert* on page 151
- *Enabling and Disabling Alert Subscription* on page 151

*Unsubscribing from an Alert*

Use the Properties view to unsubscribe from an alert.

1. In the Perspective Resources view, select a resource and select **Resource > Properties**.
2. Select **Alerts**.
3. Select an alert instance.
4. In the Subscriptions tab, select the alert subscription and click **Drop**.  
When you drop a regular subscription, any escalation subscription is also dropped. However, dropping an escalation does not affect the regular subscription.
5. Click **Yes** to confirm the deletion.

**See also**

- *Adding or Modifying an Alert Subscription* on page 150
- *Enabling and Disabling Alert Subscription* on page 151

*Enabling and Disabling Alert Subscription*

Use the Properties view to enable and disable alert subscription.

1. In the Perspective Resources view, select a resource and select **Resource > Properties**.
2. Select **Alerts**.
3. Select an alert instance.
4. In the **Subscriptions** tab, select an alert subscription and:
  - To enable subscription, click **Enable**.
  - To disable subscription, click **Disable**, then click **Yes** to confirm.

### See also

- *Adding or Modifying an Alert Subscription* on page 150
- *Unsubscribing from an Alert* on page 151

### Alert Notifications

An alert notification indicates that an alert has been generated.

Alert notifications are produced when alerts fire. An alert fires if the performance indicator on which it is based passes the threshold or state specified for the severity level of warning. If the performance indicator passes the threshold or state specified for the severity level of critical, the alert fires again and another notification is generated.

Detailed alert notifications appear in the Alert Monitor view. In addition, alerts appear as yellow ! symbols in the heat chart. You can set an alert to also send an e-mail message when it fires.

### See also

- *Types, Severities, and States* on page 146
- *Viewing Alerts* on page 147
- *Modifying an Alert* on page 147
- *Testing an Alert-Triggered Script* on page 148
- *Deleting an Alert* on page 149
- *Alert Subscriptions* on page 149

### Displaying Alert History and Resolutions

Use the Properties view to see historical information about resolved and unresolved alerts.

The History tab on the Alerts page of the Resource Properties view displays information about every time this alert has fired. Each row of the table represents a single notification generated by the selected alert.

The Resolutions tab displays information about alerts that have been resolved (closed) by a Sybase Control Center administrator.

The History and Resolutions tabs display the 100 most recent alerts or alerts for the last 24 hours, whichever is reached first.

1. In the Perspective Resources view, select a resource and select **Resource > Properties**.
2. Select **Alerts**.
3. Select the alert instance.
4. Click the **History** tab.
5. (Optional) Click the **Resolutions** tab.

### See also

- *Resolving Alerts* on page 153

### Resolving Alerts

After you address the cause of an alert, resolve it to remove it from the list of active alerts in the Alert Monitor.

#### **Prerequisites**

You must be logged in as a user with Sybase Control Center administrative privileges (sccAdminRole) to resolve alerts.

#### **Task**

1. In the Perspective Resources view, select a resource and select **Resource > Properties**.
2. In the left pane, select **Alerts**.
3. Select an alert instance in the top table.
4. Click **Resolve**.
5. Enter an explanation of how you resolved the alert.
6. Click **Submit**.

The state of the alert (shown in the State column) changes to Normal. Notifications on this alert disappear from the Alert Monitor.

---

**Note:** See the Resolutions tab for details on resolved alerts.

---

#### **See also**

- *Displaying Alert History and Resolutions* on page 152

### **Resources**

In Sybase Control Center, a resource is a unique Sybase product component or subcomponent. A server is the most common managed resource.

Sybase products comprise many components, including servers, agents, databases, devices, and processes. A managed resource is a product component or subcomponent that Sybase Control Center lets you monitor and administer. Two important tools for resource management are the Resource Explorer and the Perspective Resources view.

- The Resource Explorer lists resources that are registered with Sybase Control Center. The list may include resources that you have not yet added to a perspective. Registration enables Sybase Control Center to connect to the resource, log in, retrieve monitoring data, and issue commands. Resources are registered at the server or agent level, and registering a server or agent also makes Sybase Control Center aware of any subcomponents. You can register resources individually or register several at once by importing them in a batch.
- The Perspective Resources view lists registered resources that you have added to the current perspective. You must add a resource to a perspective to manage and monitor its availability and performance.

### See also

- *Compatibility Matrix* on page 4
- *Common Display Options* on page 7
- *Registering a Replication Server, Replication Agent, or Mirror Replication Agent* on page 90
- *Importing Resources for Batch Registration* on page 91

### Unregistering a Resource

Remove one or more servers or other resources from Sybase Control Center.

1. From the Sybase Control Center toolbar, click the **Launch Resource Explorer** icon.
2. In the Resource Explorer, select the resources you want to unregister. Use **Shift+click** or **Control+click** to select multiple resources.
3. Select **Resources > Unregister**.
4. Click **Yes** to confirm the removal.

### See also

- *Adding a Resource to a Perspective* on page 154
- *Removing a Resource from a Perspective* on page 155
- *Searching for Resources in the Resource Explorer* on page 155
- *Registering a Replication Server, Replication Agent, or Mirror Replication Agent* on page 90
- *Importing Resources for Batch Registration* on page 91

### Adding a Resource to a Perspective

Add one or more resources to the current perspective.

Add servers or other resources to a perspective so you can monitor and manage them along with other resources in the same perspective.

1. From the Sybase Control Center toolbar, click the **Launch Resource Explorer** icon.
2. Select the resources to add to your perspective. Use **Shift-click** or **Control-click** to select multiple resources.
3. Perform one of these actions:
  - Select **Resources > Add Resources to Perspective**.
  - Drag and drop resources from the Resource Explorer onto the Perspective Resources view. You can select and drag multiple resources.

### See also

- *Unregistering a Resource* on page 154
- *Removing a Resource from a Perspective* on page 155



- *Searching for Resources in the Resource Explorer* on page 155

### **Removing a Resource from a Perspective**

Remove one or more resources from the current perspective.

1. To open the Perspective Resources view, click the **Show/Hide the Resource Browser** icon in the perspective toolbar.
2. In the Perspective Resources view, select the resources to remove. Use **Shift-click** or **Control-click** to select multiple resources.
3. Select **Resource > Remove**.
4. Click **Yes** to confirm the removal.

### **See also**

- *Unregistering a Resource* on page 154
- *Adding a Resource to a Perspective* on page 154
- *Searching for Resources in the Resource Explorer* on page 155
- *Adding a Resource to a Perspective* on page 93

### **Searching for Resources in the Resource Explorer**

Search for all your managed resources or narrow your search for a particular resource.

1. Click the **Launch Resource Explorer** icon.
2. If the Filter pane is not visible in the Resource Explorer window, select **View > Filter** from the view's menu bar.
3. Enter your search term in the **Filter string** field.  
The search term can be any string that appears in the tabular portion of the Resource Explorer, such as the name, or part of the name, of a server or a resource type (ASE Server, for example).
4. (Optional) Select a filtering setting:
  - **Match case** – search for resources whose displayed data includes the search term, including uppercase and lowercase letters; or
  - **Exact match** – search for resources whose displayed data includes an item identical to the search term.
5. (Optional) Select a column from the **Filter on** list to restrict your search to that column.

### **See also**

- *Unregistering a Resource* on page 154
- *Adding a Resource to a Perspective* on page 154
- *Removing a Resource from a Perspective* on page 155

### **Perspectives**

A perspective is a named container for a set of one or more managed resources. You can customize perspectives to provide the information you need about your environment.

As the main workspaces in the Sybase Control Center window, perspectives let you organize managed resources. You might assign resources to perspectives based on where the resources are located (continents, states, or time zones, for example), what they are used for, which group owns them, or which administrator manages them. Perspectives appear as tabs in the main window.

Every perspective includes a Perspective Resources view, which lists the resources in that perspective and provides high-level status and descriptive information. Use the View menu to switch from detail view to icon view and back.

You can open additional views—the heat chart, statistics chart, or alert monitor, for example—as needed to manage the perspective’s resources. The views in a perspective display information only about resources in that perspective.

One resource can appear in many perspectives.

#### **Creating a Perspective**

Create a perspective in which you can add and manage resources.

1. From the application menu bar, select **Perspective > Create**.
2. Enter a name for your perspective. The name can contain up to 255 characters.
3. Click **OK**.

#### **See also**

- *Removing a Perspective* on page 156
- *Renaming a Perspective* on page 157

#### **Removing a Perspective**

Delete a perspective window.

1. Select the perspective tab you want to delete.
2. In the main menu bar, select **Perspective > Delete**.  
The selected perspective disappears. If there are other perspectives, Sybase Control Center displays one.

#### **See also**

- *Creating a Perspective* on page 156
- *Renaming a Perspective* on page 157

### **Renaming a Perspective**

Change the name of your perspective.

1. Select the perspective tab you want to rename.
2. From the main menu bar, select **Perspective > Rename..**
3. Enter the new name for your perspective.
4. Click **OK**.

#### **See also**

- *Creating a Perspective* on page 156
- *Removing a Perspective* on page 156

### **Views**

Use views to manage one or more resources within a perspective.

In Sybase Control Center, views are the windows you use to monitor and manage a perspective's resources. You can re-arrange, tile, cascade, minimize, maximize, and generally control the display of the views in your perspective.

Each perspective includes these views:

- Perspective Resources
- Administration Console
- Heat chart
- Alert monitor
- Component log viewer
- Views that exist for each managed resource. These vary by resource type, but typically include the statistics chart, the properties view, and a monitoring view.

### **Managing a View**

Open, close, minimize, maximize, or restore a view in the current perspective.

You can:

Task	Action
Open a view	Do one of the following: <ul style="list-style-type: none"> <li>• In the Perspective Resources view, click a resource, pull down its menu using the handle to the right of the resource name, and select the view to open.</li> <li>• In the application menu bar, select <b>View &gt; Open</b> and choose a view.</li> </ul>

Task	Action
Close a view	Select the view to close. In the application menu bar, select <b>View &gt; Close</b> . You can also click the <b>X</b> in the view's upper right corner.
Maximize a view	Click the box in the view's upper right corner. The view enlarges to fill the entire perspective window. Click the box again to return the view to its former size.
Minimize a view	Click the <b>_</b> in the view's upper right corner. The view shrinks to a small tab at the bottom of the perspective window.
Minimize all views	In the application menu bar, select <b>View &gt; Minimize All Views</b> .
Restore a view	Click the box on the minimized tab to maximize the view. Click the box again to return the view to its former (smaller) size so you can see other views at the same time.
Bring a view to the front	In the application menu bar, select <b>View &gt; Select</b> and choose the view you want from the submenu.

**See also**

- *Arranging View Layout in a Perspective* on page 158

**Arranging View Layout in a Perspective**

Use the view layout options to manage your perspective space.

Click one of these icons from the Sybase Control Center toolbar:

- **Cascade all open views**
- **Tile all open views vertically**
- **Tile all open views horizontally**

In a cascade, views overlap; in tiling arrangements, they do not.

Alternatively, you can arrange view layouts from the Sybase Control Center menu bar. From the menu bar, select **Perspective > Arrange** and select your view layout.

**See also**

- *Managing a View* on page 157

**Repository**

The Sybase Control Center embedded repository stores information related to managed resources, as well as user preference data, operational data, and statistics.

You can back up the repository database on demand, schedule automatic backups, restore the repository from backups, and configure repository purging options. Full and incremental

backups are available. A full backup copies the entire repository. An incremental backup copies the transaction log, capturing any changes since the last full or incremental backup.

By default, Sybase Control Center saves backups as follows:

- Each full backup is stored in its own subdirectory in <SCC-install-directory>/backup.
- Each incremental backup is stored in a file in <SCC-install-directory>/backup/incremental.

Sybase recommends that you periodically move backup files to a secondary storage location to prevent the installation directory from becoming too large.

### **Scheduling Backups of the Repository**

Configure full and incremental backups of the repository to occur automatically.

#### **Prerequisites**

Determine your backup strategy, including when to perform full backups and incremental backups. For example, you might schedule incremental backups every day and a full backup every Saturday.

You must have administrative privileges (sccAdminRole) to perform this task.

#### **Task**

A full backup copies the entire repository. An incremental backup copies the transaction log, capturing any changes since the last full or incremental backup.

1. From the main menu, select **Application > Administration**.
2. In the left pane, select **Repository**.
3. Click the **Full Backup** tab.
4. (Optional) To change the directory in which backups will be stored, click **Browse** and navigate to the desired directory.
5. Select **Schedule a Regular Backup**.
6. Specify the day you want scheduled backups to begin. Enter a **Start date** or click the calendar and select a date.
7. (Optional) Use the **Time** and **AM/PM** controls to specify the time at which backups occur.
8. Specify how often backups occur by setting the **Repeat interval** and selecting hours, days, or weeks.
9. (Optional) To purge the repository after each backup, select **Run a repository purge after the backup completes**.
10. If you include purging in the backup schedule, go to the **Size Management** tab and unselect **Automatically purge the repository periodically** to disable automatic purging.

11. Click **Apply** to save the schedule.
12. Click the **Incremental Backup** tab and repeat the steps above to schedule incremental backups to occur between full backups.

### Next

Set purging options on the Size Management tab.

### See also

- *Modifying the Backup Schedule* on page 160
- *Forcing an Immediate Backup* on page 161
- *Restoring the Repository from Backups* on page 161
- *Configuring Repository Purging* on page 163

### Modifying the Backup Schedule

Suspend or resume repository backups or change the backup schedule.

### Prerequisites

You must have administrative privileges (sccAdminRole) to perform this task.

### Task

1. From the main menu, select **Application > Administration**.
2. In the left pane, select **Repository**.
3. Choose the type of backup to modify:
  - Click the **Full Backup** tab, or
  - Click the **Incremental Backup** tab.
4. (Optional) To suspend or resume the backup schedule, select or unselect **Schedule a Regular Backup**.  
When you unselect (uncheck) this option, the scheduling area is grayed out and scheduled backups no longer occur. However, the schedule is preserved and you can reinstate it at any time.
5. To change the backup schedule, edit the **Start date**, **Time**, **Repeat interval**, or units. You can also select or unselect **Run a repository purge after the backup completes**.
6. Click **Apply** to save the schedule.

### See also

- *Scheduling Backups of the Repository* on page 159
- *Forcing an Immediate Backup* on page 161
- *Restoring the Repository from Backups* on page 161
- *Configuring Repository Purging* on page 163

## **Forcing an Immediate Backup**

Perform an unscheduled full or incremental backup of the repository.

### **Prerequisites**

You must have administrative privileges (sccAdminRole) to perform this task.

### **Task**

1. From the main menu, select **Application > Administration**.
2. In the left pane, select **Repository**.
3. Choose the type of backup to run:
  - Click the **Full Backup** tab, or
  - Click the **Incremental Backup** tab.
4. Click **Back up Now**.

Sybase Control Center saves the backup to the directory shown in the Location field.

### **See also**

- *Scheduling Backups of the Repository* on page 159
- *Modifying the Backup Schedule* on page 160
- *Restoring the Repository from Backups* on page 161
- *Configuring Repository Purging* on page 163

## **Restoring the Repository from Backups**

Load backup files into the repository database to revert undesirable changes or to recover from a catastrophic failure.

If you configured Sybase Control Center to store backups somewhere other than the default location, change the source directory in the copy commands in this procedure.

1. Shut down Sybase Control Center.
2. Copy the most recent full backup from <SCC-install-directory>/backup/<generated\_directory\_name> to <SCC-install-directory>/services/Repository. For example:

Windows:

```
copy C:\sybase\SCC-3_2\backup\repository.
270110161105\scc_repository.db
C:\sybase\SCC-3_2\services\Repository
```

UNIX:

```
cp <SCC-install-directory>/backup/repository.270110161105/  
scc_repository.db  
<SCC-install-directory>/services/Repository
```

3. If you have no incremental backups to load,
  - a) Also copy the log file from <SCC-install-directory>/backup/<generated\_directory\_name> to <SCC-install-directory>/services/Repository. For example:

Windows:

```
copy C:\sybase\SCC-3_2\backup\repository.  
270110161105\scc_repository.log  
C:\sybase\SCC-3_2\services\Repository
```

UNIX:

```
cp <SCC-install-directory>/backup/repository.270110161105/  
scc_repository.log  
<SCC-install-directory>/services/Repository
```

- b) Skip to step 5 on page 162.

4. Start the repository database using the -ad option, which directs it to load transaction logs (incremental backups) from the incremental directory. (The database loads full backups automatically.) For example:

Windows:

```
cd <SCC-install-directory>\services\Repository  
  
..\SccSaDataserer\sa\bin_<platform>\dbsrv11.exe  
scc_repository -ad <SCC-install-directory>\backup\incremental
```

UNIX:

```
cd <SCC-install-directory>/services/Repository  
  
../SccSaDataserer/sa/bin_<platform>/dbsrv11 scc_repository -ad  
<SCC-install-directory>/backup/incremental
```

The repository database loads the full backup and any subsequent incremental backups present in the incremental directory. Incremental backups are loaded in date order. After loading and saving, the database shuts down.

5. Start Sybase Control Center.

If you just loaded incremental backups, Sybase Control Center starts normally (that is, no further recovery occurs). If you copied a full backup to the Repository directory, the database recovers the repository from the full backup.

### Example: Loading incremental backups into the repository database

These commands start SQL Anywhere on a 32-bit Windows machine:

```
% cd C:\sybase\SCC-3_2\services\Repository  
  
% ..\SccSaDataserer\sa\bin_windows32\dbsrv11.exe  
scc_repository -ad C:\sybase\SCC-3_2\backup\incremental
```



These commands start SQL Anywhere on a 64-bit machine running AIX:

```
$ cd /opt/sybase/SCC-3_2/services/Repository
$ ../SccSaDatasever/sa/bin_aix64/dbsrv11 scc_repository -ad
/opt/sybase/SCC-3_2/backup/incremental
```

### See also

- *Scheduling Backups of the Repository* on page 159
- *Modifying the Backup Schedule* on page 160
- *Forcing an Immediate Backup* on page 161
- *Configuring Repository Purging* on page 163

### **Configuring Repository Purging**

Change repository purging options.

### **Prerequisites**

You must have administrative privileges (sccAdminRole) to perform this task.

### **Task**

As you decide how to purge your repository, consider that:

- Purging keeps the repository from absorbing too much disk space.
- By default, purging is enabled. It occurs once a day and purges data older than one day.
- Statistics and alert history can help you detect trends in server performance and user behavior. The Sybase Control Center statistics chart can graph performance data over a period of a year or more if the data is available. If you have enough disk space, consider saving data for a longer period of time or disabling the purging of statistics or alert history.
- Changing the purge frequency and other options might affect Sybase Control Center performance.

---

**Note:** If you configure purging as part of a scheduled backup of the repository, disable automatic purging on the Size Management tab.

---

1. From the main menu bar, select **Application > Administration**.
2. Select **Repository**.
3. Click the **Size Management** tab.
4. To turn automatic purging on or off, click **Automatically purge the repository periodically**.  
Turn this option off if purging is configured as part of your scheduled full or incremental backups.
5. Click purge options to turn them on or off:
  - **Purge statistics**

- **Purge alert history**
6. In **Purge data older than**, enter the number of days after which to purge repository data.
  7. Click **Apply**, then **OK**.

### See also

- *Scheduling Backups of the Repository* on page 159
- *Modifying the Backup Schedule* on page 160
- *Forcing an Immediate Backup* on page 161
- *Restoring the Repository from Backups* on page 161
- *Graphing Performance Counters* on page 138
- *Displaying Resource Availability* on page 137

## Logging

A log is a record of events related to a server or a client.

In Sybase Control Center, logging helps system administrators identify errors and other system events by recording messages about the events in log files. Sybase Control Center maintains these logs:

- The client log – captures messages about activities in the browser-based client components. These messages are generated by the component product modules to display information that is pertinent to the user but not critical enough to warrant a pop-up. Sybase also uses the client log to trace client browser operations.
- Server logs – capture messages about activities during the initialization sequence, such as starting services; auditing messages recording logins and logouts; errors such as missed scheduled events; and other events on the server. Server logs include:
  - Component logs, which record only events concerning individual product modules
  - The SCC agent log, which is a composite log that records events in all product modules and in the Sybase Control Center framework
- The repository log – captures information about inserts and updates that have occurred in the Sybase Control Center repository, a SQL Anywhere database. This log is in <SCC-installation-dir>\SCC-3\_2\services\Repository\log.
- The alert services log – captures information about execution of alert-triggered scripts, including the start time, end time, and status and exit codes. This log is in <SCC-installation-dir>\SCC-3\_2\services\Alert\log>alert-server.log.

### Viewing the Replication Component Log

Launch the Sybase Control Center Log Viewer to display replication activity log.

### **Prerequisites**

Verify that you are in a replication monitoring view.

**Task**

From any replication monitoring view, click the notebook icon in the left corner of the status bar. The status bar is at the bottom of a monitoring view.

**See also**

- *Viewing Sybase Control Center Server Logs* on page 165
- *Viewing the Sybase Control Center Client Log* on page 165
- *Changing the Logging Level* on page 166
- *Logging or Message Levels* on page 167
- *Changing Logging Configuration* on page 167

**Viewing Sybase Control Center Server Logs**

View event logs for the Sybase Control Center server.

Sybase Control Center logs events to several places:

- The console from which Sybase Control Center is launched.
- The Sybase Control Center agent log: <SCC-install-directory>/log/agent.log
- The repository log: <SCC-install-directory>/log/repository.log
- The component log for each installed Sybase Control Center product module. The path to the component log takes this form: <SCC-install-directory>/plugins/<component>/log/<component>.log

1. Display one of the log files using a log viewer or a method of your choice.
2. Look for entries of interest such as login attempts or the failure of a service to start.

On the console and in the Sybase Control Center agent log file, some components prepend the component name to log entries.

**See also**

- *Viewing the Replication Component Log* on page 164
- *Viewing the Sybase Control Center Client Log* on page 165
- *Changing the Logging Level* on page 166
- *Logging or Message Levels* on page 167
- *Changing Logging Configuration* on page 167

**Viewing the Sybase Control Center Client Log**

Display the event log for the current session of your Sybase Control Center browser client.

In the perspective tab window (the main window), do either of the following to display the client log:

- Enter **Ctrl+Alt+L**.

- Select **View > Open > Log Window**.

---

**Note:** The client log reader displays the 100 most recent log messages for the current login session.

---

### See also

- *Viewing the Replication Component Log* on page 164
- *Viewing Sybase Control Center Server Logs* on page 165
- *Changing the Logging Level* on page 166
- *Logging or Message Levels* on page 167
- *Changing Logging Configuration* on page 167

### **Changing the Logging Level**

Adjust the logging level that determines which events Sybase Control Center records in the server logs. This task requires you to restart Sybase Control Center.

If you are having a problem with Sybase Control Center, you might be able to discover the cause of the problem by changing the server logging level so that more events are recorded.

1. Shut down Sybase Control Center.
2. Restart Sybase Control Center using the -m option to change the logging level. In <SCC-installation-dir>/bin, enter:  

```
scc -m <logging-level>
```

The logging levels are OFF (logs nothing), FATAL (logs only the most severe events), ERROR, WARN, INFO, DEBUG, and ALL (logs everything).

3. Examine the server log for clues about what might be causing the problem.
4. When you have resolved the problem, set the logging level back to WARN, the default. Your log may become unmanageably large if you leave it at the DEBUG or ALL level.

### Example

These commands, which must be executed in the installation directory, start Sybase Control Center with the logging level set to debug:

```
Windows: bin\scc -m DEBUG  
UNIX: bin/scc -m DEBUG
```

### See also

- *Viewing the Replication Component Log* on page 164
- *Viewing Sybase Control Center Server Logs* on page 165
- *Viewing the Sybase Control Center Client Log* on page 165
- *Logging or Message Levels* on page 167
- *Changing Logging Configuration* on page 167
- *Starting and Stopping Sybase Control Center in Windows* on page 51

- *Starting and Stopping Sybase Control Center in UNIX* on page 53

### **Logging or Message Levels**

Describes values you can use to control the types of events that are logged by Sybase Control Center.

These are the logging levels, from highest to lowest. The higher the level, the more serious an event must be to be logged. Each level includes all the levels above it—for example, if you set the logging level to **WARN**, you log events for the **WARN**, **ERROR**, and **FATAL** levels.

OFF	Nothing is logged. This is the highest level.
FATAL	Logs only very severe error events that lead the server to abort. This is the highest level at which events are logged.
ERROR	Logs error events that might allow the server to continue running.
WARN	Logs potentially harmful situations. <b>WARN</b> is the default logging level during normal operation (that is, after system initialization).
INFO	Logs informational messages that track the progress of the server in a coarse-grained fashion. <b>INFO</b> is the default logging level during the system initialization process.
DEBUG	Logs a larger set of events that provides a finer-grained picture of how the server is operating. This level is recommended for troubleshooting.
ALL	Logs all loggable events. This is the lowest level.

### **See also**

- *Viewing the Replication Component Log* on page 164
- *Viewing Sybase Control Center Server Logs* on page 165
- *Viewing the Sybase Control Center Client Log* on page 165
- *Changing the Logging Level* on page 166
- *Changing Logging Configuration* on page 167
- *scc Command* on page 59

### **Changing Logging Configuration**

Edit the logging configuration file, `log4j.properties`, to modify Sybase Control Center logging.

You can change the names, locations, or maximum size of the log files as well as the number of log files backed up.

Options for the **scc** command let you change the overall Sybase Control Center log message level when you start SCC, but if you choose the **DEBUG** level, the large volume of log messages generated may be inconvenient. Editing the log properties file gives you finer control; you can set logging levels for each Sybase Control Center component separately.

Sybase recommends making such changes only if you are familiar with log4j and you are working with Sybase technical support; DEBUG-level log messages are not likely to be meaningful to you. (If you have not used log4j before, a good place to start is <http://logging.apache.org/log4j/1.2/manual.html>.)

1. Shut down Sybase Control Center.
2. Make a backup copy of the `log4j.properties` file located in `<SCC-installation-directory>/conf`.
3. Open the `log4j.properties` file for editing.
4. Change values in the file to suit your needs. For example:

To	Modify
Change the name or location of a log file	<ul style="list-style-type: none"> <li>• Agent log – <code>log4j.appender.agent.File</code></li> <li>• Repository log – <code>log4j.appender.repository.File</code></li> <li>• Collection statistics log – <code>log4j.appender.collection-stats.File</code></li> <li>• Alert server log – <code>log4j.appender.alert.File</code></li> <li>• Gateway log – <code>log4j.appender.gateway.File</code></li> </ul>
Change the maximum size that a log file can reach before Sybase Control Center creates a new file	<ul style="list-style-type: none"> <li>• Agent log – <code>log4j.appender.agent.MaxFileSize</code></li> <li>• Repository log – <code>log4j.appender.repository.MaxFileSize</code></li> <li>• Collection statistics log – <code>log4j.appender.collection-stats.MaxFileSize</code></li> <li>• Alert server log – <code>log4j.appender.alert.MaxFileSize</code></li> <li>• Gateway log – <code>log4j.appender.gateway.MaxFileSize</code></li> </ul>
Change the number of log files Sybase Control Center backs up before deleting the oldest file	<ul style="list-style-type: none"> <li>• Agent log – <code>log4j.appender.agent.MaxBackupIndex</code></li> <li>• Repository log – <code>log4j.appender.repository.MaxBackupIndex</code></li> <li>• Collection statistics log – <code>log4j.appender.collection-stats.MaxBackupIndex</code></li> <li>• Alert server log – <code>log4j.appender.alert.MaxBackupIndex</code></li> <li>• Gateway log – <code>log4j.appender.gateway.MaxBackupIndex</code></li> </ul>

5. Save and exit the file.
6. Start Sybase Control Center to make the logging changes take effect.

**See also**

- *Viewing the Replication Component Log* on page 164
- *Viewing Sybase Control Center Server Logs* on page 165
- *Viewing the Sybase Control Center Client Log* on page 165
- *Changing the Logging Level* on page 166
- *Logging or Message Levels* on page 167
- *Starting and Stopping Sybase Control Center in Windows* on page 51

- *Starting and Stopping Sybase Control Center in UNIX* on page 53

## **Sybase Control Center Console**

The console is a command-line interface for displaying details about the status of the Sybase Control Center server and its subsystems.

When you use the **scc** command to start Sybase Control Center, it displays start-up messages and then displays the console prompt.

---

**Note:** The console prompt does not appear if you start Sybase Control Center as a service, if you direct the output of **scc** to a file, or if you start Sybase Control Center in the background.

---

### **See also**

- *Launching Sybase Control Center* on page 50

### **Console Commands**

Use the Sybase Control Center console to get status information on Sybase Control Center and its ports, plug-ins, and services.

#### **help Command**

Display syntax information for one or more Sybase Control Center console commands.

### **Syntax**

```
help [command_name]
```

### **Parameters**

- **command\_name** – optional. status, info, or shutdown. If you omit *command\_name*, **help** returns information on all the console commands.

### **Examples**

- **Example 1** – returns information on the **status** command:

```
help status
```

### **Permissions**

**help** permission defaults to all users. No permission is required to use it.

### **See also**

- *info Command* on page 170
- *shutdown command* on page 171
- *status Command* on page 171

### info Command

Display information about specified parts of the Sybase Control Center server.

If you enter **info** with no parameters, it returns information for every parameter.

### Syntax

```
info [-a | --sys]
[-D | --sysprop [system-property]]
[-e | --env [environment-variable]]
[-h | --help]
[-m | --mem]
[-p | --ports]
[-s | --services]
```

### Parameters

- **-a | --sys** – optional. List all the services known to Sybase Control Center, indicate whether each service is enabled, and list other services on which each service depends.
- **-D | --sysprop [system-property]** – optional. Display information about the specified Java system property. Omit the system-property argument to return a list of all Java system properties and their values.
- **-e | --env [environment-variable]** – optional. List all the environment variables in the Sybase Control Center Java VM process environment. Omit the environment-variable argument to return a list of environment variables and their values.
- **-h | --help** – optional. Display information about the **info** command.
- **-m | --mem** – optional. Display information about the server's memory resources.
- **-p | --ports** – optional. List all the ports on which the Sybase Control Center agent and its services listen, indicate whether each port is in use, and show the service running on each port.
- **-s | --services** – optional. List all Sybase Control Center services, indicate whether each service is enabled, and list other services on which each service depends.

### Examples

- **Example 1** – displays information about ports on this Sybase Control Center server:

```
info -p
```

### Permissions

**info** permission defaults to all users. No permission is required to use it.

### **See also**

- *help Command* on page 169



- *shutdown command* on page 171
- *status Command* on page 171

### shutdown command

Stop the Sybase Control Center server if it is running.

### Syntax

```
shutdown
```

### Examples

- **Example 1** – shuts down Sybase Control Center:

```
shutdown
```

### Permissions

**shutdown** permission defaults to all users. No permission is required to use it.

### See also

- *help Command* on page 169
- *info Command* on page 170
- *status Command* on page 171

### status Command

Display the status of the SCC agent, plug-in, or service components of Sybase Control Center.

### Syntax

```
status [-a | --agent]
[-h | --help]
[-p | --plugin [plugin-name]]
[-s | --service [service-name]]
```

### Parameters

- **-a | --agent** – display the status of the Sybase Control Center agent component.
- **-h | --help** – display information about the **info** command.
- **-p | --plugin [plugin-name]** – display the status of the specified Sybase Control Center plug-in (for example, ASEMap, the Adaptive Server management module). Omit the plugin-name argument to return a list of plug-ins.
- **-s | --service [service-name]** – display the status of the specified Sybase Control Center service (for example, the Alert service or the Messaging service). Omit the service-name argument to return a list of services.

### Examples

- **Example 1** – displays status information on the Repository service:

```
status --service Repository
```

### Permissions

**status** permission defaults to all users. No permission is required to use it.

### **See also**

- *help Command* on page 169
- *info Command* on page 170
- *shutdown command* on page 171

## Manage and Monitor the Replication Environment

Monitor the availability of the servers in the replication environment, control the flow of data and configure replication parameters to improve server performance.

### Availability Monitoring

The statistics allow you to monitor the availability of each server and the state of the components, such as connections and routes, in a replication environment.

The status of a server is determined by its availability, whether it is up or down, and the state of the components within the server. The status of the server is a roll-up of the status of all the components within it.

Availability monitoring provides you with the information to determine not only the availability of the servers but also their effectiveness in the replication environment. There are a number of availability monitoring statistics that are gathered for replication. The process of gathering these statistics is turned on by default with the default interval time.

### **See also**

- *Historical Performance Monitoring* on page 138
- *Heat Chart* on page 137
- *Replication Latency* on page 187
- *Key Performance Indicators and Key Performance Areas for Replication* on page 100

## **Replication Topology**

Replication topology is a graphical representation of how the servers in a replication environment are connected to each other. A topology or network diagram illustrates how data moves in a replication environment.

It provides a visual map of the availability of the replication environment. The lines on a topology diagram represent the servers, connections, and routes from the source to the target data server.

### **See also**

- *Replication Latency* on page 187
- *Replication Monitors* on page 175

## **Replication Tracing**

Replication tracing provides the information you need to determine the source, target, and the path of the data flow anywhere in the replication environment.

Replication tracing supports large, complex, and geographically dispersed networks and these component types:

- **Sources** – these are servers, databases, tables, stored procedures, and all components to which Replication Agents provide access.
- **Targets** – these are servers, databases, tables, and stored procedures.
- **Replication Paths** – these are connections, routes, and intermediate Replication Servers.

### *Displaying Replication Tracing from Target to Source*

Select a database server and show the data flow path.

### **Prerequisites**

Add all the servers to be monitored to the Perspective Resources view, and verify that you have the permission to perform this task.

### **Task**

1. From the Perspective Resources view, select a Replication Server and click **Resource > View Replication Topology** .
2. Right-click a target database server and select **Trace Replication Sources**.  
The traced servers, connections, and routes are highlighted in the topology view. The list of servers that participate in the trace are displayed in the Replication Tracing tab.

---

**Note:** There can be more than one source, depending on the replication environment.

---

3. (Optional) To remove the replication tracing, right-click a server and select **Clear Replication Tracing**.

### See also

- *Displaying Replication Tracing from Source to Target* on page 174
- *Displaying Replication Tracing for a Replication Server* on page 174

### *Displaying Replication Tracing from Source to Target*

Select a database server and show the data flow path, which includes the final target destination.

### Prerequisites

Add all the servers to be monitored to the Perspective Resources view, and verify that you have the permission to perform this task.

### Task

1. From the Perspective Resources view, select a Replication Server and click **Resource > View Replication Topology**.
2. Right-click a source database server and select **Trace Replication Targets**.  
The traced servers, connections, and routes are highlighted in the topology view. The list of servers that participate in the trace are displayed in the Replication Tracing tab.

---

**Note:** There can be more than one target, depending on the replication environment.

---

3. (Optional) To remove the replication tracing, right-click a server and select **Clear Replication Tracing**.

### See also

- *Displaying Replication Tracing from Target to Source* on page 173
- *Displaying Replication Tracing for a Replication Server* on page 174

### *Displaying Replication Tracing for a Replication Server*

Select a Replication Server and display all the data flow paths through the replication environment, including other Replication Servers, Replication Agents, and database servers.

### Prerequisites

Add all the servers to be monitored to the Perspective Resources view, authenticate these servers, and verify that you have the permission to perform this task.

### Task

1. From the Perspective Resources view, select a Replication Server and click **Resource > View Replication Topology**.
2. Right-click a Replication Server and select **Trace Replication Server**.

3. (Optional) To change the layout type and orientation of the topology, use the **View Controls** tab on the left. You can also use the additional options that control the way the topology appears.
4. (Optional) To view the list of nodes and edges included in the current topology, select the **Details** tab on the left.

To retain any changes you have made to the default layout settings of the replication topology, close Sybase Control Center without closing the Replication Topology view.

### See also

- *Displaying Replication Tracing from Target to Source* on page 173
- *Displaying Replication Tracing from Source to Target* on page 174

### Replication Monitors

Replication monitors display the availability and critical performance statistics of a particular component in the replication environment.

The replication monitors provide the status of Replication Servers, Replication Agents, and replication paths. Each monitor also provides a Quick Admin view to allow you to control the flow of data and configure replication parameters, a list of replication paths, and a status bar for each view.

The Replication Server Monitor includes these views:

- **Overview** – displays high-level information, such as the server name, version, and its status. It also displays the memory usage graph, and a bar chart for partitions and the Top 10 queues by size.
- **Paths** – displays a table of Replication Server paths, including its state, activity, latency, and latency monitoring status information. It also displays the latency history chart of a Replication Server.
- **Connections** – displays the information for Replication Server connections, which include the name, Replication Agent (RA) status, and Data Server Interface (DSI) status. It also shows these graphs for the selected connection:
  - DSI activity and Stable Queue Transaction (SQT) cache
  - Transactions removed from SQT
  - Transaction activity
  - Transaction success rate
  - Group and batch size
- **Logical Connections** – displays the Replication Server logical connection information in a warm-standby environment.
- **Routes** – displays the Replication Server route information, which includes the name, route status, and the route's activity graph.
- **Queues** – displays Replication Server queues information, which includes the name and type. It also shows these graphs for the selected queue :

## Manage and Monitor

- Queue reads and writes
- Queue bytes and cache
- SQT cache (only for inbound queues)
- Backlog
- Duplicates detected
- Transactions Removed from SQT (only for inbound queues)
- Distributor activity (only for inbound queues)

The Replication Agent Monitor includes this view:

- **Overview** – displays high-level information, which includes the status, name, version number of the server, primary connection, primary host, Replication Server connection, and the information on when it was last started. It displays a list of paths, which you can click to open a path dashboard. It also displays these graphs:
  - Java Virtual Machine (JVM) memory usage
  - LTI activity and queue sizes
  - Log Reader activity, queue sizes, and scan buffer

The Adaptive Server Replication Agent Thread Monitor has this view:

- **Overview** – displays high-level information, such as the name, status, and controlling Replication Server. It also displays the log and activity details in a graph format.

The Replication Path Dashboard has this view:

- **Overview** – displays a detailed information of a particular path, which includes its name, status, data loss detection result, and these graphs:
  - Adaptive Server RepAgent thread commands sent per second
  - Inbound queue activity for the primary database
  - Outbound queue activity for the replicate database
  - Database Server Interface (DSI) commands sent per second
  - Latency
  - Latency history

### See also

- *Replication Latency* on page 187
- *Replication Topology* on page 173

### Data Flow Control

Controlling data flow comprises one part of troubleshooting in your replication environment.

The other part is tuning servers and components. You use either or both of the methods based on the problems in the environment.

**See also**

- *Replication Environment* on page 3
- *Replication Servers* on page 177
- *Replication Agents* on page 184
- *Replication Paths* on page 187
- *Compatibility Matrix* on page 4
- *Quiescing or Resuming Replication Server* on page 181
- *Suspending or Resuming a Connection's Replication Agent* on page 182
- *Suspending or Resuming a Connection* on page 183
- *Suspending or Resuming a Route* on page 183
- *Starting or Stopping an Adaptive Server RepAgent Thread* on page 186

**Replication Servers**

Replication Server maintains replicated data in multiple databases while ensuring the integrity and consistency of the data.

Replication Server provides clients using databases in the replication system with local data access, thereby reducing load on the network and centralized computer systems.

**See also**

- *Replication Environment* on page 3
- *Data Flow Control* on page 176
- *Replication Agents* on page 184
- *Replication Paths* on page 187
- *Compatibility Matrix* on page 4

***Displaying Replication Server Status***

View the most recent Replication Server statistics. Sybase Control Center automatically updates the page when new status and statistical values are collected.

**Prerequisites**

Register and add all the servers to be monitored to the Perspective Resources view, authenticate them, and verify that you have permission to perform this task.

**Task**

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor** .  
The Replication Server monitor view appears, with the Overview as the default display.
2. (Optional) To maximize or minimize a window within the monitor view, click the maximize or restore window icon in its right corner.

---

**Note:** You can also view the server status through the status badges on the server icons in the Perspective Resources, Perspective Heat Chart, Resource Explorer, and Replication Topology views.

---

### See also

- *Displaying Logical Connection Status* on page 178
- *Hiding Connection Thread Status* on page 180
- *Displaying Queue Status* on page 180
- *Displaying Route Status* on page 181
- *Logical Connection View Details* on page 179

### *Displaying Logical Connection Status*

View the information of all logical connections of a Replication Server in a warm standby replication environment.

### Prerequisites

Verify that the replication environment has been configured, and all servers have been registered and authenticated, and that the monitoring collection has been running.

### Task

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Logical Connections**.  
A list of all logical connection names along with their state information, active and standby connection names, their respective state information, and the inbound queue information for each logical connection appears in a table.
3. (Optional) Click the active or standby connection in the list to go to the Connections view, and see the status information of the physical connections that are associated with the logical connections.
4. (Optional) Click the inbound queue under its corresponding column to go to the Queues view.

### See also

- *Displaying Replication Server Status* on page 177
- *Hiding Connection Thread Status* on page 180
- *Displaying Queue Status* on page 180
- *Displaying Route Status* on page 181
- *Logical Connection View Details* on page 179



*Logical Connection View Details*

The columns on the **Logical Connection** view show different information about the logical connections of a Replication Server.

Column	Description
Name	The DBID (database ID) for the current logical connection.
State	The state of the current logical connection. The possible values are: <ul style="list-style-type: none"> <li>• Active</li> <li>• Switching Active Connection</li> <li>• Creating Standby Connection</li> </ul>
Active Connection	The DBID, the data server, and the database name for the current active database.
Active State	The state of the active connection's RepAgent thread. The possible values are: <ul style="list-style-type: none"> <li>• Active</li> <li>• Suspended</li> </ul>
Standby Connection	The DBID, the data server, and the database name for the current standby database.
Standby State	Shows the Data Server Interface (DSI) state of the standby connection. The possible values are: <ul style="list-style-type: none"> <li>• Active</li> <li>• Suspended</li> </ul>
Inbound Queue	The name of the inbound queue for a logical connection.

**See also**

- *Displaying Replication Server Status* on page 177
- *Displaying Logical Connection Status* on page 178
- *Hiding Connection Thread Status* on page 180
- *Displaying Queue Status* on page 180
- *Displaying Route Status* on page 181

### *Hiding Connection Thread Status*

Hide the connection status of a Replication Agent or Data Server Interface (DSI) thread.

#### **Prerequisites**

Verify that the replication environment has been configured and that all servers have been registered, authenticated, and replicating data correctly.

#### **Task**

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Connections**.
3. Select a Replication Server connection.
4. Click **Quick Admin**.
5. In the Hide Connection Status section of the **Control** tab, click either **Hide RepAgent Status** or **Hide DSI Status** to override the connection's current configuration.
6. Click **Apply**.

#### **See also**

- *Displaying Replication Server Status* on page 177
- *Displaying Logical Connection Status* on page 178
- *Displaying Queue Status* on page 180
- *Displaying Route Status* on page 181
- *Logical Connection View Details* on page 179

### *Displaying Queue Status*

View the status information of Replication Server queues in a replication environment.

#### **Prerequisites**

Verify that the replication environment has been configured, all servers have been registered and authenticated, and that monitoring collection has been running.

#### **Task**

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Queues**.
3. Select a queue from the table to view its corresponding activity graphs.

4. (Optional) To maximize or minimize a window within the monitor view, click the maximize or restore window icon in its right corner.

### See also

- *Displaying Replication Server Status* on page 177
- *Displaying Logical Connection Status* on page 178
- *Hiding Connection Thread Status* on page 180
- *Displaying Route Status* on page 181
- *Logical Connection View Details* on page 179

### *Displaying Route Status*

View the status information of Replication Server routes in a replication environment.

### Prerequisites

Verify that the replication environment has been configured, all servers have been registered and authenticated, and that monitoring collection has been running.

### Task

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Routes**.  
You can see a route's status in the Replication Server Routes table.
3. Select a route from the table to view its corresponding activity graph.
4. (Optional) To maximize or minimize a window within the monitor view, click the maximize or restore window icon in its right corner.

### See also

- *Displaying Replication Server Status* on page 177
- *Displaying Logical Connection Status* on page 178
- *Hiding Connection Thread Status* on page 180
- *Displaying Queue Status* on page 180
- *Logical Connection View Details* on page 179

### *Quiescing or Resuming Replication Server*

Shut down data flow from all sources and quiesce the current Replication Server or resume data flow from the up-stream replication path. You may need to quiesce all Replication Servers in your environment to recover databases, alter routes, and troubleshoot the system.

### Prerequisites

Register and add all the servers to be monitored to the Perspective Resources view, verify that the default collection is running, and that you have permission to perform this task.

### Task

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Quick Admin**.
3. In the Control tab, click **Quiesce** or **Resume All**.

### See also

- *Suspending or Resuming a Connection's Replication Agent* on page 182
- *Suspending or Resuming a Connection* on page 183
- *Suspending or Resuming a Route* on page 183
- *Starting or Stopping an Adaptive Server RepAgent Thread* on page 186
- *Data Flow Control* on page 176

### *Suspending or Resuming a Connection's Replication Agent*

Suspend or resume a connection's Replication Agent that is associated with a Replication Server.

### Prerequisites

Register and add all the servers to be monitored to the Perspective Resources view, verify that the default collection is running, and that you have permission to perform this task.

### Task

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Connections**.
3. Select a connection.
4. Click **Quick Admin**.
5. In the Replication Agent section of the Control tab, click **Suspend** or **Resume**.

### See also

- *Quiescing or Resuming Replication Server* on page 181
- *Suspending or Resuming a Connection* on page 183
- *Suspending or Resuming a Route* on page 183
- *Starting or Stopping an Adaptive Server RepAgent Thread* on page 186
- *Data Flow Control* on page 176

### *Suspending or Resuming a Connection*

Suspend or resume a Replication Server connection.

#### **Prerequisites**

Register and add all the servers to be monitored to the Perspective Resources view, verify that the default collection is running, and that you have permission to perform this task.

#### **Task**

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Connections**.
3. Select a connection.
4. Click **Quick Admin**.
5. In the Data Server Interface section of the Control tab, click **Suspend** or **Resume**.
6. (Optional) Click **Suspended Immediately**.
7. (Optional) Select one of these options when resuming a connection:
  - Skip the first transaction. This option is available only for versions of Replication Server 15.0 or earlier.
  - Resume after skipping transactions. Provide the number of transactions to skip. This option is available only for versions of Replication Server 15.1 and later.
  - Execute system transaction.

#### **See also**

- *Quiescing or Resuming Replication Server* on page 181
- *Suspending or Resuming a Connection's Replication Agent* on page 182
- *Suspending or Resuming a Route* on page 183
- *Starting or Stopping an Adaptive Server RepAgent Thread* on page 186
- *Data Flow Control* on page 176

### *Suspending or Resuming a Route*

Suspend or resume a route associated to a Replication Server.

#### **Prerequisites**

Register and add all the servers to be monitored to the Perspective Resources view, verify that the default collection is running, and that you have permission to perform this task.

### Task

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Routes**.
3. Select a route.
4. Click **Quick Admin**.
5. In the Control tab, click **Suspend** or **Resume**.
6. (Optional) Click **Skip transaction with large message** when resuming a route.

---

**Note:** This option applies only to direct routes where the site version at the replicate site is 12.1 or earlier.

---

### See also

- *Quiescing or Resuming Replication Server* on page 181
- *Suspending or Resuming a Connection's Replication Agent* on page 182
- *Suspending or Resuming a Connection* on page 183
- *Starting or Stopping an Adaptive Server RepAgent Thread* on page 186
- *Data Flow Control* on page 176

### Replication Agents

Replication Agents enable the movement and sharing of data where and when it is needed - into data warehouses, data marts, OLTP applications and mobile workforce.

Replication Agents allows heterogeneous data servers to act as primary data servers in a replication system based on Sybase replication technology.

### See also

- *Replication Environment* on page 3
- *Data Flow Control* on page 176
- *Replication Servers* on page 177
- *Replication Paths* on page 187
- *Compatibility Matrix* on page 4

### *Displaying Replication Agent Status*

Review high-level server availability by viewing the Replication Agent or Mirror Replication Agent status.

### Prerequisites

Register and add all the servers to be monitored to the Perspective Resources view, authenticate them, and verify that you have permission to perform this task.

## Task

1. From the Perspective Resources view, select a Replication Agent and click **Resource > Monitor**.

The monitor view appears displaying high-level information, which includes the status of the selected Replication Agent.

2. (Optional) To maximize or minimize a window within the monitor view, click the maximize or restore window icon in its right corner.

## See also

- *Displaying RepAgent Thread Status in Adaptive Server* on page 185
- *Suspending or Resuming a Replication Agent or Mirror Replication Agent* on page 186
- *Starting or Stopping an Adaptive Server RepAgent Thread* on page 186

### *Displaying RepAgent Thread Status in Adaptive Server*

View the RepAgent thread status in an Adaptive Server, either single instance or shared disk cluster, for replication.

## Prerequisites

Register and add all the servers to be monitored to the Perspective Resources view, authenticate them, and verify that you have permission to perform this task.

## Task

1. From the Perspective Resources view, select an Adaptive Server and click **Resource > Monitor**.

The Replication Agent Thread Monitor appears. You can view the status of an Adaptive Server RepAgent thread in the displayed table with its name and the controlling Replication Server information.

2. (Optional) To maximize or minimize a window within the monitor view, click the maximize or restore window icon in its right corner.

## See also

- *Displaying Replication Agent Status* on page 184
- *Suspending or Resuming a Replication Agent or Mirror Replication Agent* on page 186
- *Starting or Stopping an Adaptive Server RepAgent Thread* on page 186

### *Suspending or Resuming a Replication Agent or Mirror Replication Agent*

Suspend or resume a Replication Agent or a Mirror Replication Agent in a replication environment.

#### **Prerequisites**

Register and add all the servers to be monitored to the Perspective Resources view, verify that the default collection is running, and that you have permission to perform this task.

#### **Task**

1. From the Perspective Resources view, select a Replication Agent or a Mirror Replication Agent and click **Resource > Monitor**.
2. Click **Quick Admin**.
3. In the Control tab, click **Suspend** or **Resume**.

#### **See also**

- *Displaying Replication Agent Status* on page 184
- *Displaying RepAgent Thread Status in Adaptive Server* on page 185
- *Starting or Stopping an Adaptive Server RepAgent Thread* on page 186

### *Starting or Stopping an Adaptive Server RepAgent Thread*

Start or stop a RepAgent thread of an Adaptive Server.

1. From the Perspective Resources view, select an Adaptive Server and click **Resource > Monitor**.
2. Select a RepAgent thread (ASE Server, Replication Only) or click **Replication Agent** in the left pane, then select a RepAgent thread (ASE Server).
3. Click **Quick Admin**.
4. In the Control tab, click **Start** or **Stop**.
5. (Optional) Click **Stop immediately** before clicking **Stop**.

#### **See also**

- *Quiescing or Resuming Replication Server* on page 181
- *Suspending or Resuming a Connection's Replication Agent* on page 182
- *Suspending or Resuming a Connection* on page 183
- *Suspending or Resuming a Route* on page 183
- *Data Flow Control* on page 176
- *Displaying Replication Agent Status* on page 184
- *Displaying RepAgent Thread Status in Adaptive Server* on page 185
- *Suspending or Resuming a Replication Agent or Mirror Replication Agent* on page 186



### Replication Paths

A replication path is the set of all servers and internal components that transactions travel through when moving from the primary to the replicate database.

#### **See also**

- *Replication Environment* on page 3
- *Data Flow Control* on page 176
- *Replication Servers* on page 177
- *Replication Agents* on page 184
- *Compatibility Matrix* on page 4

#### *Displaying Replication Path Status*

View the status of the servers, connections, routes, and queues that make up a replication path.

#### **Prerequisites**

Register and add all the servers to be monitored to the Perspective Resources view, authenticate them, and verify that you have permission to perform this task.

#### **Task**

1. From the Perspective Resources view, select a Replication Server or a Replication Agent and click **Resource > Monitor**.
2. Click a replication path.  
The Replication Path Dashboard for the selected replication path appears.
3. (Optional) To maximize or minimize a window within the monitor view, click the maximize or restore window icon in its right corner.

If new statistics are collected while the replication path dashboard is displayed, Sybase Control Center automatically updates the information on the current page.

#### **See also**

- *Displaying Latency* on page 188
- *Latency Monitoring Process* on page 96

### **Replication Latency**

Replication latency is the amount of time it takes for a transaction that occurs in the primary database to be applied to the replicate database.

The time includes Replication Agent processing, Replication Server processing, and network usage. Replication latency appears on the path dashboard.

### See also

- *Historical Performance Monitoring* on page 138
- *Heat Chart* on page 137
- *Availability Monitoring* on page 172
- *Key Performance Indicators and Key Performance Areas for Replication* on page 100
- *Setting Up the Latency Monitoring Process* on page 95
- *Replication Topology* on page 173
- *Replication Monitors* on page 175

### Displaying Latency

View latency information to determine the amount of time it takes for a transaction to be applied from the primary database to the replicate database.

### Prerequisites

Add all the servers to be monitored in the Perspective Resources view. Verify that you have permission to perform this task and that the latency monitoring process has already been started.

### Task

1. From the Perspective Resources view, select a server and click **Resource > Monitor**.
2. Click **Paths**.
3. Select or click a path from the path list.  
When you select a path, its latency information appears below the path list. When you click a selected path, its dashboard opens, displaying the latency history graph.
4. (Optional) Click the bar graph icon in the top right corner of the Latency window to toggle between the overall latency and the latency monitoring history of the path.

### See also

- *Setting Up the Latency Monitoring Process* on page 95
- *Stopping the Latency Monitoring Process* on page 188
- *Latency Chart Details* on page 189
- *Displaying Replication Path Status* on page 187
- *Latency Monitoring Process* on page 96

### Stopping the Latency Monitoring Process

Stop the latency monitoring process.

### Prerequisites

Verify that all servers to be monitored have been registered, authenticated, and added to the Perspective Resources, that latency monitoring process is running, and that you have the permission to perform this task.

**Task**

1. From the Perspective Resources view, select a Replication Server and click **Resource > Monitor**.
2. Click **Paths**.
3. Select a path where the "Monitoring" value is true.
4. Click **Quick Admin** to display the latency monitoring process administration view for the selected path.
5. Click **Stop**.

**See also**

- *Setting Up the Latency Monitoring Process* on page 95
- *Displaying Latency* on page 188
- *Latency Chart Details* on page 189
- *Latency Monitoring Process* on page 96

**Latency Chart Details**

Learn about the threads that represent the latency chart in the path dashboard.

**Table 31. Latency threads**

Latency thread	Description
Replication Executor Thread (EXEC)	The number of seconds from the start, to time the ticket passes through the EXEC thread.
Distribution (DIST) Thread	The number of seconds from the primary Replication Server time to the time the ticket passes through the DIST thread. For each primary database managed by a Replication Server, there is a DIST, which in turn uses Stable Queue Transaction (SQT) to read from the inbound queue, and Stable Queue Manager (SQM) threads to write transactions to the outbound queue.
Replication Server Interface (RSI) Thread	The number of seconds from the DIST thread time to the time the ticket passes through the RSI thread. RSI threads send messages from one Replication Server to another. There is one RSI thread for each destination Replication Server.

Latency thread	Description
Data Server Interface (DSI) Thread	The number of seconds from the RSI thread time to the time the ticket passes through the DSI thread. The DSI thread translates the transaction modifications into remote procedure calls (RPC) or the language as specified by the function strings in the function-string class assigned to the destination database. Replication Server starts the DSI threads to submit transactions to a replicate database to which it has a connection.
Replicate Database	The number of seconds from the DSI thread time to the time the ticket arrived at the replicate database.
Total Latency	The number of seconds between the time at origin and destination for the transaction committed.

**See also**

- *Setting Up the Latency Monitoring Process* on page 95
- *Stopping the Latency Monitoring Process* on page 188
- *Displaying Latency* on page 188

# Troubleshoot Sybase Control Center for Replication

Troubleshoot problems that occur in Sybase Control Center for Replication.

## Collection Job for Adaptive Server Fails

---

Problem: A collection job for Adaptive Server may fail when the **number of open databases** is too low.

Solution: Modify the value of **number of open databases** by using either the Server Configuration screen of the Adaptive Server monitor, or these steps:

1. Log in to the Adaptive Server.  
`isql -S<server_name> -U<sa user name> -P<sa password>`
2. Run this command to display the current configuration value:  
`sp_configure 'number of open databases'`
3. Run this command to change the current configuration value:  
`sp_configure 'number of open databases', <number>`  
Add 10 to the current configuration value and substitute this number for *<number>*.

## Data on Dashboards or Charts Is Missing

---

Problem: There is no data displayed on the dashboards or on the charts.

Solution: Create collection jobs for Replication Server statistics collections.

### See also

- *Setting Up the Latency Monitoring Process* on page 95

## No Data Is Returned for Performance Counters Collection Job

---

Problem: No data is returned for the Performance Counters collection job after completing its execution.

Solution: Let the job execution complete for three cycles. The Replication Server Performance Counters collection job returns data in the Statistics Chart only after it completes execution of approximately three cycles.

## **Same Data Is Displayed for Two or More Adaptive Server Collection Job Executions**

---

**Problem:** If the interval time of the Adaptive Server RepAgent thread collection job is set to less than 60 seconds, Sybase Control Center still works but you may get the same data for two or more continuous executions of the job.

**Solution:** Do not set the interval time for the Adaptive Server RepAgent thread collection job to less than 60 seconds. This is because the collection data are updated only once during 60 seconds for better performance.

## **Servers Are Missing in the Topology View**

---

**Problem:** There are servers missing when you display the topology view.

**Solution:** Verify that all the servers have been added to the current perspective because the topology view can only display servers from current perspective.

## **Servers, Routes, or Connections Display an Unknown Status**

---

**Problem:** "Unknown" status is displayed for servers, routes, or connections.

**Solution:** Verify that a collection job is scheduled and running to display the correct status in the Replication Topology view.

## **Some Connector Lines Do Not Display a Status Icon**

---

**Problem:** Some connector lines do not display a status icon.

**Solution:** Not all connector lines are associated with a managed object. Those associated with a managed object are the only ones that display a status icon. Currently, status icons are displayed only on Replication connections and routes.

## Topology Display Is Incorrect When Two Replication Servers With the Same Name Are Registered

---

**Problem:** When you register two Replication Servers with the same name in a given replication environment, the replication topology view is displayed incorrectly.

**Solution:** Do not use the same name for two replication resources. The servers in a replication environment must have unique names.

## Topology View Displays Blank Canvas

---

**Problem:** The Replication Topology view displays blank canvas.

**Solution:** From the Replication Topology view, click Reset to restore the default layout. This problem is usually due to a layout that is actually displayed off-screen.

## Topology View Takes a Long Time to Display

---

**Problem:** The Replication Topology view takes a long time to display.

**Solution:** The Replication Topology view requires data from each server to be displayed. For large environments, this may take 10 to 15 seconds.

## Unable to Retrieve Topology Relationship Data or Server Objects

---

**Problem:** An error message "Unable to retrieve topology relationship data" or "Unable to retrieve topology server objects" is displayed.

**Solution:** These errors are displayed for a number of reasons. Perform these:

- Verify that you have the repMonitorRole for each server in the topology assigned to your login.
- Verify that each server in the topology has been authenticated.
- The server relationship data cannot be retrieved from the Replication Management plug-in or one or more servers cannot be retrieved from the Sybase Control Center.

Check the plug-in and the Unified Agent Framework (UAF) agent log files for errors:

### **For Windows**

- %SYBASE%\SCC-3\_1\plugins\RMAP\log\rmap.log
- %SYBASE%\SCC-3\_1\log\agent.log

### **For UNIX**

- `$(SYBASE)/SCC-3_1/plugins/RMAP/log/rmap.log`
- `$(SYBASE)/SCC-3_1/log/agent.log`

## Problems with Basic Sybase Control Center Functionality

Troubleshoot problems that involve basic features like starting and stopping, authentication, alerts, and scheduling.

### Cannot Log In

Problem: Cannot log in to Sybase Control Center Web console.

Solution: Make sure that Sybase Control Center has been configured:

- To allow logins through the operating system
- To grant appropriate roles to your login account

Ask the Sybase Control Center administrator to help you check.

#### **See also**

- *User Authorization* on page 81
- *Setting Up Security* on page 63

### Sybase Control Center Fails to Start

Problem: The Sybase Control Center server does not start.

Solution: There might be a port conflict with another server. To check for port conflicts:

1. Execute this command:

```
scc --info ports
```

The command lists all the ports on which Sybase Control Center and its services listen, indicates whether each port is in use, and shows the service running on each port. If Sybase Control Center is not running, any port shown to be in use represents a conflict.

2. If you discover a conflict, use **scc --port** to change the port used by the Sybase Control Center service.

#### **See also**

- *Configuring Ports* on page 77

### Browser Refresh (F5) Causes Logout

Problem: Pressing the **F5** key to refresh your browser logs you out of Sybase Control Center.

Solution: Do not use **F5** when you are logged in to Sybase Control Center. Browser refresh does not refresh data inside Sybase Control Center, but refreshes the loaded application or



pages in the browser—in this case, the Adobe Flash on which Sybase Control Center is built. Consequently, pressing **F5** logs you out of any servers you are currently logged in to, including Sybase Control Center.

### **Alerts Are Not Generated**

**Problem:** Alerts are not being generated in Sybase Control Center.

**Solution:** Schedule a job to run the data collection that supports your alerts. See the data collections topic for your Sybase Control Center product module for information on which collections must be scheduled.

#### **See also**

- *Setting Up Statistics Collection* on page 97

### **Performance Statistics Do Not Cover Enough Time**

**Problem:** I want to graph performance counters over a long period of time but the statistics chart displays only very recent data.

**Solution:** Ask your Sybase Control Center administrator to change the repository purging options to keep statistical data available for as long as you need it. By default, statistics are purged frequently to conserve disk space.

#### **See also**

- *Configuring Repository Purging* on page 163
- *Graphing Performance Counters* on page 138

### **Resetting the Online Help**

**Problem:** Sybase Control Center online help is corrupted or cannot be found (404 error).

**Solution:** Clear online help files to force SCC to build new ones.

1. Shut down Sybase Control Center.
2. Remove this directory:

```
<SCC-installation-directory>\SCC-3_2\services  
\EmbeddedWebContainer\container\Jetty-6.1.22\work  
\Jetty_0_0_0_0_8282_help.war__help__.smpe97
```

---

**Tip:** In Windows, you might see a deletion error. Regardless of what the errors says, it might be caused by the length of the path. If deletion fails, rename the Jetty\_0\_0\_0\_0\_8282\_help.war\_\_help\_\_.smpe97 folder to something very short, such as J. Then delete the renamed folder.

---

3. Remove these files:

```
<SCC-installation-directory>\SCC-3_2\services  
\EmbeddedWebContainer\container\Jetty-6.1.22\contexts  
\_help.xml
```

## Troubleshoot Sybase Control Center for Replication

```
<SCC-installation-directory>\SCC-3_2\services
\SybaseControlCenter\help\com.sybase.infocenter.scc.zip
<SCC-installation-directory>\SCC-3_2\services
\SybaseControlCenter\help\help.war
<SCC-installation-directory>\SCC-3_2\services
\SybaseControlCenter\help\help_info.xml
```

4. Start SCC. After the server comes up it rebuilds the help, which takes a few minutes.
5. To display the help, go to `https://<your-SCC-host>:8283/help/index.jsp`.

---

**Note:** If you try to display the help too soon after restarting, you get a file not found error. Wait a minute or two and try again.

---

### Data Collections Fail to Complete

Problem: A collection frequently times out or generates errors citing the REJECT\_DUPLICATE\_RESOURCE\_AND\_COLLECTION policy, but no problems with the monitored resources are evident.

The errors appear in the log and on the collection history screen.

Solution: Try to determine why the collection is taking so long. For example, are network delays slowing down traffic between Sybase Control Center and the monitored server?

In the case of network delays and other resource-related problems, the interval between collections might be shorter than the time needed to finish the collection. To fix this problem, increase the time between collections.

#### **See also**

- *Modifying the Data Collection Interval for a Job* on page 143

### Memory Warnings at Startup

Problem: When Sybase Control Center starts, you see warnings about system memory or heap memory allocation.

Solution: Increase the maximum memory setting (*SCC\_MEM\_MAX* or `jvmopt=-Xmx`).

#### **See also**

- *Configuring Memory Usage* on page 56

### OutOfMemory Errors

Problem: Sybase Control Center generates OutOfMemory errors.

Solution:

- If the `OutOfMemory` error says that Sybase Control Center is out of heap space, increase the maximum memory setting (`SCC_MEM_MAX` or `jvmopt=-Xmx`).
- If the `OutOfMemory` error says that Sybase Control Center is out of permanent generation space, increase the permanent memory setting (`SCC_MEM_PERM` or `jvmopt=-XX:MaxPermSize`).
- Repeated `OutOfMemory` errors may indicate a memory leak. `OutOfMemory` errors generate heap dumps:
  - When Sybase Control Center runs as a service in Windows:  
`C:\windows\system32`
  - When Sybase Control Center runs as a service in UNIX:  
`<SCC-install-directory>/SCC-3_2/bin`Send the heap dump files to Sybase technical support for analysis.

### See also

- *Configuring Memory Usage* on page 56



# Glossary: Sybase Control Center for Replication

Definitions of Sybase Control Center terms related to Replication.

**alert** – a mechanism for notifying administrators when a managed resource experiences a status change, or when a performance metric passes a user-specified threshold.

**alert instance** – a copy of an alert type that has been configured to generate a particular kind of alert for a specific managed resource.

**alert notification** – an indication that an alert has fired. Alert notifications appear in the Alert Monitor view. If e-mail notification is enabled, alert notifications are also delivered to the specified e-mail address.

**alert target** – the destination for an alert notification and source of an alert response.

**alert type** – (1) A template that defines the resource type and the key performance indicator (KPI) associated with an alert instance. (2) The basis on which an alert fires: state or threshold. Some alerts are triggered by the state of their key performance indicator (for example, running or stopped), while other alerts are triggered when their KPI's numerical value passes a specified threshold.

**alert storm** – the result of issuing many redundant alerts associated with a common or root occurrence. See also alert storm suppression.

**alert storm suppression** – a Sybase Control Center feature that can be configured to prevent alert storms by suppressing repeat alert notifications for a specified period of time.

**availability** – indicates whether a resource is accessible and responsive.

**collection** – a named, predefined set of key performance indicators for which values are collected from monitored servers at the same time. Collections supply the performance and availability data shown on Sybase Control Center screens and charts. Use the scheduler to view a list of collections and to control which collections run, how often they run, and the length of time for which they run.

**component** – A server object in a replication environment. Examples of components are connections, routes, and Replication Agent threads.

**connection** – A connection from a Replication Server to a database.

**database** – A set of related data tables and other objects that are organized and presented to serve a specific purpose.

**data server** – A server that provides the functionality necessary to maintain the physical representation of a replicated table in a database. An example of a data server is Sybase Adaptive Server.

**Data Server Interface (DSI)** – Replication Server threads corresponding to a connection between a Replication Server and replicate database. DSI threads submit transactions from the DSI outbound queue to a replicate database. They consist of a scheduler thread and one or more executor threads. The scheduler thread groups the transactions by commit order and dispatches them to the executor threads. The executor threads map functions to function strings and execute the transactions in the replicate database. DSI threads use an Open Client connection to a database. See also connection.

**edge** – A topology object representing a relationship between two nodes, displayed in the form of a line that connects the topology node icons. Edges are usually defined with a direction.

**Enterprise Connect Data Access (ECDA)** – An Open-Server-based software gateway that supports DB-Library and CT-Library application program interfaces and Open Database Connectivity (ODBC) protocols. It serves as a fundamental building block for database middleware applications that provides access to non-Sybase databases.

**environment** – A set of servers that interact to perform replication. It can be a subset of the replication domain identified by the ID server.

**event** – an activity in the system, such as a user logging in, a service starting or stopping, or a condition changing. Use the alerts feature to detect and notify you about system events.

**heat chart** – a graphical view of resource availability and selected performance and status metrics for all the registered resources in the current perspective.

**ID Server** – A Replication Server in a replication system. It assigns unique ID numbers to every Replication Server and database in the system and maintains the version information for the system.

**job** – a task performed by the scheduler in Sybase Control Center.

**key performance indicator (KPI)** – a single metric used to evaluate the status or performance of a monitored resource. A KPI value can be a state (such as running, error, or stopped) or a numerical value. KPIs are grouped into collections (and also, for some product modules, into key performance areas, or KPAs). KPI values are collected by scheduled collection jobs and appear on monitoring screens and in the statistics and heat charts. Examples of KPIs are Server Availability and Number of Blocked Processes.

**latency** – The measure of the time it takes to distribute a data modification operation from a primary database to a replicate database. The time includes Replication Agent processing, possibly ECDA processing—if the replicate database is non-Sybase—Replication Server processing, and network overhead.

**Mirror Activator** – Provides an integrated, zero-loss disaster recovery solution when used in conjunction with a storage replication system. Replication Server, Mirror Replication Agent, and Enterprise Connect Data Access (ECDA) are the components of Mirror Activator.

**Mirror Replication Agent** – A component of a Mirror Activator disaster recovery system that reads the mirror transaction log of the primary database and sends transaction data as LTL commands for replicated tables and replicated stored procedures to the primary Replication Server, which converts the LTL commands into SQL and applies the SQL to the replicate database.

**node** – A topology object representing a server or other entity type, displayed visually in the form of an icon.

**partition** – A raw disk partition or operating system file that a Replication Server uses for stable queue storage. See also stable queue.

**perspective** – a named tab in Sybase Control Center that displays information related to a collection of managed resources (such as servers) and a set of views associated with those resources. The views in a perspective are chosen by users of the perspective. You can create as many perspectives as you need, and customize them to monitor and manage your resources. Perspectives allow you to group resources in ways that make sense in your environment—for example by location, department, or project.

**RepAgent thread** – The Replication Agent for a primary Adaptive Server. It reads the transaction log and sends the transaction data as LTL commands for replicated tables and replicated stored procedures to the primary Replication server, which converts the LTL commands into SQL and applies the SQL to the replicate database.

**replication** – A process by which the changes to the data in one database—including creation, updating, and deletion of records—are also applied to the corresponding records in another database.

**Replication Agent** – Reads the transaction log of a primary, non-Sybase database, and sends transaction data as LTL commands for replicated tables and replicated stored procedures to the primary Replication Server, which converts the LTL commands into SQL and applies the SQL to the replicate database.

**replication path** – The set of all servers and internal components, such as threads and queues, that transactions travel through when moving from the primary to the replicate database.

**repository** – a database in Sybase Control Center that stores information related to managed resources, along with user preference data, operational data, and performance statistics.

**resource** – a unique Sybase product component (such as a server) or a subcomponent.

**route** – A one-way message stream from a source Replication Server to a destination Replication Server. Routes carry data modification commands (including those for RSSDs) and replicated functions or stored procedures between Replication Servers.

**SCC-enabled login account** – a user account that has been granted privileges in Sybase Control Center by mapping appropriate Sybase Control Center roles. (Roles are typically mapped to a group to which the account belongs rather than to the account itself.) The user account and group can be native to Sybase Control Center or created in the operating system or

## Glossary: Sybase Control Center for Replication

the LDAP directory service to which Sybase Control Center authentication is delegated. You must use an SCC-enabled account to log in to Sybase Control Center.

**SCC agent** – a Sybase Control Center agent that runs on a managed server and enables Sybase Control Center to manage it. The SCC agent is installed automatically as part of the Sybase server.

**schedule** – the definition of a task (such as the collection of a set of statistics) and the time interval at which Sybase Control Center executes the task.

**stable queue manager (SQM)** – A thread within Replication Server that manages the stable queues. Replication Server uses one SQM thread for each stable queue, whether inbound or outbound.

**stable queue** – A store-and-forward queue where Replication Server stores messages destined for a route or database connection. Replication Server builds stable queues using its disk partitions.

**topology** – A graphical representation of how the servers in a replication environment are connected to each other. It is a network diagram that provides a visual map of the availability of the replication environment.

**view** – a window in a perspective that displays information about one or more managed resources. Some views also let you interact with managed resources or with Sybase Control Center itself. For example, the Perspective Resources view lists all the resources managed by the current perspective. Other views allow you to configure alerts, view the topology of a replication environment, and graph performance statistics.



# Index

- Xmx maximum memory option 27, 58
- XX:MaxPermSize permanent memory option 27, 58

## A

- accessibility 12
- Adaptive Server collection job
  - same data collected for Replication, troubleshooting 192
- Adaptive Server shared disk cluster
  - RepAgent thread status 185
- Administration Console
  - display options 7
  - using 140
- Administration Console in SCC
  - column filtering 9
- Adobe Flex 12
- alert instances 199
- alert notifications 199
- alert storm 199
- alert storm suppression 199
- alert subscriptions
  - disable 151
  - enable 151
- alert targets 199
- alert type 199
- alert-triggered scripts
  - example 123
- alerts 199
  - about 145
  - configured, deleting 149
  - configured, modifying 147
  - configured, viewing 147
  - configuring duplicate alerts 122
  - configuring e-mail server 44, 79
  - configuring escalations 122
  - configuring storm suppression 122
  - configuring subscriptions 122
  - configuring to execute scripts 122
  - creating 121
  - displaying history 152
  - displaying resolutions 152
  - effects of repository purging on history 163
  - escalations 149

- log 132
- modifying subscriptions 150
- monitoring 147
- not being generated 195
- notifications, about 152
- notifications, viewing 147
- Replication 124
- resolving 153
- scripts executed by 132
- setting triggering states and thresholds 121
- subscribing to 150
- subscriptions 149
- substitution parameters for scripts 132
- testing 148
- triggering scripts, about 132
- types, states, and severities 146
- unsubscribing from 151
- alerts, Replication
  - types, states, and severities 129
- ALL logging level 167
- aseMonitorRole 48, 87
- authenticating
  - SCC 18, 94
- authentication
  - about 29, 64
  - configuring for LDAP 32, 67
  - configuring for UNIX 31, 66
  - configuring for Windows 30, 65
- authorization 45, 81
- availability 199
- availability, Replication
  - monitoring 172

## B

- background, running SCC or SCC agent in 22, 53
- backups
  - about 158
  - changing the schedule 160
  - forcing 161
  - restoring from 161
  - scheduling 159
  - suspending and resuming 160
- badges, status 6

## Index

### C

- charts, Replication
  - missing data, troubleshooting 191
- client log, viewing 165
- collection job
  - for Adaptive Server in Replication, troubleshooting 191, 192
  - Replication Performance Counters, troubleshooting 191
- collections 199
- column filtering in SCC 9
- columns
  - sorting by 7
- compatibility, Replication
  - server version 4
- component log
  - replication 164
- components 199
- configuration
  - optional 134
- configuration parameters, Replication
  - configuring 117
  - setting up 117
- configuring
  - logical connection parameters 118
  - RepAgent thread parameters 120
  - replication parameters 117
  - Replication Server parameter 120
- connection
  - configuring parameters 118
  - resuming 183
  - suspending 183
- connections 199
- connections, Replication
  - unknown status, troubleshooting 192
- connector lines
  - do not display a status icon for Replication, troubleshooting 192
- console
  - about 169
  - commands 169
- conventions, style and syntax 10

### D

- dashboards, Replication
  - missing data, troubleshooting 191
- data collection jobs
  - adding 97

- adding schedules 142
  - creating 97
  - deleting 141
  - displaying history 145
  - executing 141
  - resuming 142
  - stopping 141
  - suspending 142
- data collection schedules
  - adding 97
  - modifying 143
- data collections
  - replication 99
  - troubleshooting timeouts 196
- data server 199
- data server interface 200
- databases, Replication 199
- DEBUG logging level 167
- defined 199–202
- display options in Sybase Control Center 7
- displaying
  - queue status 180
  - replication log 164
  - replication topology view, troubleshooting 193
  - route status 181
- displaying status
  - replication path 187
- displaying, Replication
  - latency 188
  - Replication Agent status 19, 184
  - server status 19, 177
  - topology 174
- drivers
  - ODBC, registering 14, 51
- DSI
  - hiding connection status 180

### E

- e-mail server, configuring for alerts 44, 79
- edges 200
- Enterprise Connect Data Access 200
- environment 200
- environment variables
  - SCC\_MEM\_MAX 25–27, 56–58
  - SCC\_MEM\_PERM 25–27, 56–58
- ERROR logging level 167
- errors
  - OutOfMemory 196

REJECT\_DUPLICATE\_RESOURCE\_AND  
 \_COLLECTION policy 196  
 timeouts for data collections 196  
 evaluation  
   quick start instructions 13  
 events 200  
 expiration dates for login accounts 86

## F

F11 (browser full screen mode toggle) 9  
 F5 (browser refresh)  
   logging out of Sybase Control Center 194  
 FATAL logging level 167  
 Flash Player 15  
 foreground, running SCC or SCC agent in 22, 53  
 full backups 159  
 full screen mode 9

## G

getting started after installing 15  
 glossaries  
   Replication terms 199  
 graphing statistics 138  
 grid format, using 7  
 groups 48, 87  
   adding login accounts 47, 84  
   assigning monitoring and administration roles  
     46, 81  
   assigning Replication roles 17, 93  
   creating 47, 83  
   in LDAP, mapping to SCC roles 41, 76  
   in OS, mapping to SCC roles 41, 76  
   remove login 84  
   removing 83  
   removing roles 82

## H

heartbeat process  
   monitoring 96  
 heat chart 137, 200  
   customizing columns 18, 137  
   display options 7  
   displaying 18, 137  
   filtering resources displayed 18, 137  
   icons 6  
   launch icon 6

help command (console) 169  
 hiding  
   RepAgent connection status 180  
 historical performance monitoring 138  
 history displays for alerts 152

## I

icons  
   for server status 6  
   in SCC toolbar 6  
   minimize/maximize sections of a view 9  
 ID Server 200  
 incremental backups 159  
 info command (console) 170  
 INFO logging level 167  
 interfaces files, importing resources from 91  
 iqMonitorRole 48, 87

## J

Java system properties  
   displaying information about 170  
 jobs 200  
   modifying collection intervals 143  
   resuming 144  
   suspending 144  
 jvmopt memory options for Windows services 25,  
   27, 56, 58

## K

key performance areas  
   Replication 100  
 key performance indicators 200  
   Replication 100, 124  
 keyboard shortcuts for Adobe Flex 12  
 KPIs 200

## L

latency 200  
   chart details 189  
   displaying 188  
   monitoring 96  
   replication 187  
   stop monitoring 188  
   viewing 188

## Index

- latency monitoring
  - setting up 95
  - stopping 188
- LDAP
  - configuration properties 35, 70
  - configuring authentication 32, 67
  - configuring to authenticate SCC logins 29, 64
  - setting up roles 34, 69
- log4j.properties file 167
- logging in to Sybase Control Center 28, 62
  - troubleshooting 194
- logging in to Sybase Control Center - first user 15
- logging levels 167
- logging out of Sybase Control Center 63
  - unintentionally, using F5 browser refresh 194
- logical connection
  - configuring parameters 118
  - details 179
  - displaying 178
  - viewing 178
- login accounts
  - assigning monitoring and administration roles 46, 81
  - assigning Replication roles 17, 93
  - authenticating 18, 94
  - creating automatically (UNIX) 31, 66
  - creating automatically (Windows) 30, 65
  - expiration date, imposing 86
  - granting privileges with roles and groups 41, 76
  - modifying 86
  - native SCC, adding 85
  - predefined 48, 87
  - removing 86
  - removing roles 82
  - suspending 86
- login accounts, default
  - about 15
- login modules 29, 64
- login session timeout 63
  - setting 45, 80
- logs
  - agent log, viewing 165
  - alert services 132
  - alert services log, about 164
  - changing the logging level 166
  - client log, about 164
  - client log, viewing 165
  - component logs, about 164

- configuring 167
- repository log, about 164
- repository log, viewing 165
- SCC agent log, about 164
- script execution log, about 164
- server logs, about 164
- server logs, viewing 165

## M

- managed resources 153
- managing
  - replication environment 172
- memory
  - configuring 25, 56
  - displaying information about 170
  - warnings at startup 196
- memory leak 196
- message levels 167
- minimize/maximize icon 9
- Mirror Activator 200
- Mirror Replication Agent 201
- monitoring
  - heartbeat process 96
  - latency 96
  - performance 138
  - replication environment 172
- monitoring, Replication 1
  - roles or permissions to set up 94
  - server availability 172
  - server status 172
- monitors
  - connections 175
  - logical connections 175
  - overview 175
  - paths 175
  - queues 175
  - RepAgent thread 175
  - Replication Agent 175
  - Replication Server 175
  - route 175

## N

- new features
  - Sybase Control Center for Replication 1
- nodes 201

**O**

- ODBC drivers
  - registering 14, 51
- online help
  - resetting 195
- operating system
  - configuring to authenticate SCC logins 29, 64
- OutOfMemory errors 196

**P**

- parameters
  - configuring logical connection 118
  - routes, configuring 119
- parameters for scripts 132
- parameters, Replication
  - configuring 117
  - connection 118
- partitions 201
- passencrypt utility 42, 77
- passwords
  - encrypting 42, 77
  - for repository database dba account, changing 59
- path
  - replication 187
- performance counters, Replication
  - no data, troubleshooting 191
- permissions
  - Replication, configuring monitoring accounts 94
- Perspective Heat Chart view 137
- Perspective Resources view
  - about 153, 156
  - display options 7
  - icons 6
  - show/hide icon 6
- perspectives 201
  - about 156
  - adding resources 93, 154
  - creating 93, 156
  - removing 156
  - removing a resource 155
  - renaming 157
- pluggable authentication modules for UNIX
  - authentication 31, 66
- port conflicts 194
- ports
  - changing 59

- configuring 42, 77
  - default 59
  - displaying information about 170
- postinstallation tasks 15
- production environment, setting up SCC in 20

**Q**

- queues
  - displaying status 180
- quick start instructions 13
- quiescing
  - Replication Server 181

**R**

- registration
  - about 153
- REJECT\_DUPLICATE\_RESOURCE\_AND\_COLLECTION policy errors 196
- repAdminRole 48, 87
- RepAgent
  - hiding connection status 180
- RepAgent connection status
  - hiding 180
- RepAgent thread
  - configuring parameters 120
  - status in Adaptive Server shared disk cluster 185
- RepAgent thread, Replication
  - displaying status 185
  - starting 186
  - stopping 186
- RepAgent threads 201
- replication 201
  - data collections 99
  - heartbeat 187
  - latency 187
  - rs\_ticket 187
  - servers 3
  - topology 173
  - tracing 173
- Replication Agent
  - about 184
  - configuring parameters 117
  - resuming 182, 186
  - suspending 182, 186
- Replication Agents 201

## Index

- Replication Agents, Replication
    - displaying status 19, 184
  - replication environment
    - managing 172
    - monitoring 172
  - replication parameters
    - configuring 117
    - setting up 117
  - replication path 187, 201
    - displaying status 187
  - Replication Server
    - configuring parameters 117
    - displaying status 19, 177
    - quiescing 181
    - register, troubleshooting 193
    - resuming 181
    - viewing status 19, 177
  - Replication Servers
    - about 177
  - replication sources
    - displaying 173
    - tracing 173
    - viewing 173
  - replication targets
    - displaying 174
    - tracing 174
    - viewing 174
  - replication topology 173
    - displaying 174
    - viewing 174
  - repMonitorRole 48, 87
  - repository 158, 201
    - backing up 161
    - changing backup schedule 160
    - changing database dba password 59
    - configuring purging 163
    - restoring from backup 161
    - scheduling backups 159
  - resource explorer
    - launch icon 6
  - Resource Explorer
    - about 153
    - display options 7
    - searching in 155
  - resources 201
    - about 153
    - adding to a perspective 93, 154
    - authenticating 18, 94
    - browsing and managing 140
    - displaying availability 18, 137
    - importing in batch 91
    - modifying data collection schedules 143
    - registering with Sybase Control Center 16, 90
    - removing from a perspective 155
    - searching for 155
    - unregistering 154
  - restarts, configuring in UNIX 22, 53
  - restarts, configuring in Windows 21, 51
  - resuming
    - connection 183
    - Replication Server 181
    - route 183
  - roles
    - assigning to users and groups 46, 81
    - mapping SCC roles to LDAP or OS groups 41, 76
    - predefined 48, 87
    - product level 45, 81
    - removing 82
    - Replication, configuring monitoring accounts 94
    - system level 45, 81
  - roles, Replication
    - assigning to users and groups 17, 93
  - route
    - resuming 183
    - suspending 183
  - routes
    - configuring parameters 119
    - displaying status 181
    - viewing status 181
  - routes, Replication 201
    - unknown status, troubleshooting 192
  - RSSD user name, using to authenticate 18, 94
- ## S
- SCC agent 202
    - starting in UNIX 22, 53
    - starting in UNIX as a service 22, 53
    - starting in Windows 21, 51
    - starting in Windows as a service 21, 51
    - stopping in UNIX 22, 53
    - stopping in Windows 21, 51
  - scc command 59
    - using to launch Sybase Control Center 14, 50
  - SCC\_MEM\_MAX 25–27, 56–58, 196
  - SCC\_MEM\_PERM 25–27, 56–58
  - SCC-enabled login account 201

- scc.bat 14, 21, 51
- scc.sh 22, 53
- sccadmin account
  - about 15
- sccAdminRole 48, 87
- sccd shell script 22, 53
- sccuser account
  - about 15
- sccUserRole 48, 87
- scheduler
  - resuming 144
  - suspending 144
- schedules 140, 202
  - adding to a job 142
  - creating for a data collection job 97
- screens
  - maximizing 9
  - maximizing and minimizing sections of a view 9
- scripts
  - example 123
  - substitution parameters 132
  - triggered by alerts 132
- security 29, 64
  - configuring 28, 63
- security providers
  - configuring 29, 64
- server logs, viewing 165
- server status, Replication
  - monitoring availability 172
- server version, Replication
  - compatibility 4
- servers
  - authenticating 18, 94
  - displaying availability 18, 137
  - importing in batch 91
  - modifying data collection schedules 143
  - registering with Sybase Control Center 16, 90
  - replication environment 3
  - searching for 155
  - unregistering 154
- servers, Replication
  - missing in topology view, troubleshooting 192
  - unknown status, troubleshooting 192
- services
  - enabling and disabling 59
  - listing 170
- services, UNIX
  - configuring SCC memory options for 27, 58
  - running SCC or SCC agent as 22, 53
- services, Windows
  - configuring SCC memory options for 27, 58
  - running SCC or SCC agent as 21, 51
- setting up
  - latency monitoring 95
  - replication parameters 117
- severities for alerts 146
- severities for alerts, Replication 129
- shutdown command (console) 171
- sorting by column 7
- sql.ini files, importing resources from 91
- stable queue manager 202
- stable queues 202
- start up, automatic, configuring in UNIX 22, 53
- start up, automatic, configuring in Windows 21, 51
- starting Sybase Control Center 14, 50
- states, Replication 129
- statistics
  - about 98
  - availability 98
  - performance 98
- statistics chart
  - displaying data for a longer period 195
  - effects of repository purging on 163
  - graphing performance counters 138
  - troubleshooting 195
- stats\_show\_zero\_counters, Replication 120
- status command (console) 171
- status icons and badges for resources 6
- storm suppression for alerts 122
- substitution parameters for scripts 132
- suspending
  - connection 183
  - route 183
- Sybase Control Center
  - accessibility 12
  - connecting a browser to 15
  - console commands 169
  - display options 7
  - failure to start 194
  - log files 165
  - logging in 28, 62
  - logging out 63
  - logging out unintentionally with F5 194
  - starting 14, 50
  - starting in UNIX 22, 53

## Index

- starting in UNIX as a service 22, 53
- starting in Windows 21, 51
- starting in Windows as a service 21, 51
- stopping in UNIX 22, 53
- stopping in Windows 21, 51
- Sybase Control Center for Replication
  - enhancements 1
  - new features 1
- Sybase Control Center, Replication
  - About 1
  - managing 139
  - monitoring 139
- system properties
  - displaying information about 170
- system-wide features
  - configuring 28, 63

## T

- terms
  - Replication 199
- text conventions 10
- timeout
  - errors on data collections 196
  - setting for login sessions 45, 80
- toolbar icons 6
- topology 202
  - displaying 174
  - replication 173
  - server 173
  - viewing 174
- topology data
  - unable to retrieve for Replication 193
- topology view, Replication
  - blank canvas, troubleshooting 193
  - incorrect display, troubleshooting 193
- tracing
  - replication path 173
  - replication source 173
  - replication target 173
- troubleshooting
  - controlling data flow 176
  - Replication 191
- types of alerts 146
- types of alerts, Replication 129

## U

- UNIX
  - configuring authentication 31, 66

- running SCC or SCC agent in the background
  - 22, 53
- running SCC or SCC agent in the foreground
  - 22, 53
- starting, stopping SCC or SCC agent 22, 53
- user accounts
  - native SCC, adding 85
  - native SCC, not using 29, 64
- user information
  - modifying 86
- user interface, about 5

## V

- view layouts
  - cascade 158
  - horizontal tiling 158
  - vertical tiling 158
- View menu 9
- viewing
  - logical connection status 178
  - queue status 180
  - replication log 164
  - route status 181
- viewing, Replication
  - latency 188
  - Replication Agent status 19, 184
  - server status 19, 177
  - topology 174
- views 202
  - about 157
  - bringing to front of perspective 157
  - closing 157
  - icons for managing 6
  - maximizing 157
  - maximizing and minimizing sections 9
  - minimizing 157
  - opening 157
  - restoring 157

## W

- WARN logging level 167
- Windows
  - configuring authentication 30, 65
  - starting, stopping Sybase Control Center or SCC agent 21, 51