



Installation Guide

Replication Server[®] 15.7

UNIX

DOCUMENT ID: DC32237-01-1570-01

LAST REVISED: November 2011

Copyright © 2011 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

To order additional documents, U.S. and Canadian customers should call Customer Fulfillment at (800) 685-8225, fax (617) 229-9845.

Customers in other countries with a U.S. license agreement may contact Customer Fulfillment via the above fax number. All other international customers should contact their Sybase subsidiary or local distributor. Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase trademarks can be viewed at the Sybase trademarks page at <http://www.sybase.com/detail?id=1011207>. Sybase and the marks listed are trademarks of Sybase, Inc. ® indicates registration in the United States of America.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP AG in Germany and in several other countries all over the world.

Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

All other company and product names mentioned may be trademarks of the respective companies with which they are associated.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568.

Contents

Conventions	1
Installation Task Overview	5
Installation Task Flows	5
Replication Server Components	7
Planning Your Installation	9
Replication Server Release Bulletin	9
Mixed-Version Support	9
Obtaining a License	10
SySAM License Server	11
IPv6 Configuration	12
SySAM Licensing Checkout	12
Product Editions and License Types	12
Sub-capacity Licensing	15
System Requirements	17
System Requirements for Replication Server on UNIX	17
Installation Directory Structure	20
Replication Server Installation in a Unique Directory on UNIX Platforms	21
Installation Directory Contents and Layout	21
Installation Setup Options	22
Installation Mode	23
Performing Administrative Tasks	23
Creating the Sybase User Account	24
Installing Replication Server	25
Mounting the Installation Media	25
Installing Replication Server with the GUI Wizard	26
Installing Replication Server Data Assurance Option	29
Installing Replication Server in Console Mode	29
Installing Replication Server Using a Response File	30

Creating a Response File	30
Installing in GUI Mode Using a Response File	30
Installing in Silent Mode	31
Troubleshoot Installation Problems	32
Command Line Options	32
Postinstallation Tasks	33
Log Files	33
Adaptive Server for the RSSD	33
Sample Replication Server Configuration	34
Server Entries in the Interfaces File	35
Environment Variables on UNIX	35
Runserver File	37
Uninstalling Replication Server	39
Uninstalling with the GUI Wizard	39
Uninstalling in Console Mode	40
Uninstalling in Silent Mode	40
Installation and Uninstallation of Replication Manager	41
Installing Replication Manager	41
Installing Replication Manager with GUI Wizard	42
Installing Replication Manager in Console Mode	43
Installing with a Response File	44
Uninstalling Replication Manager	46
Uninstalling with the GUI Wizard	46
Uninstalling in Console Mode	47
Obtaining Help and Additional Information	49
Technical Support	49
Downloading Sybase EBFs and Maintenance Reports	49
Sybase Product and Component Certifications	50
Creating a MySybase Profile	50
Accessibility Features	50
Index	53

Conventions

These style and syntax conventions are used in Sybase® documentation.

Style conventions

Key	Definition
<code>monospaced(fixed-width)</code>	<ul style="list-style-type: none"> • SQL and program code • Commands to be entered exactly as shown • File names • Directory names
<i>italic monospaced</i>	In SQL or program code snippets, placeholders for user-specified values (see example below).
<i>italic</i>	<ul style="list-style-type: none"> • File and variable names • Cross-references to other topics or documents • In text, placeholders for user-specified values (see example below) • Glossary terms in text
bold san serif	<ul style="list-style-type: none"> • Command, function, stored procedure, utility, class, and method names • Glossary entries (in the Glossary) • Menu option paths • In numbered task or procedure steps, user-interface (UI) elements that you click, such as buttons, check boxes, icons, and so on

If necessary, an explanation for a placeholder (system- or setup-specific values) follows in text. For example:

Run:

```
installation directory\start.bat
```

where *installation directory* is where the application is installed.

Syntax conventions

Key	Definition
{ }	Curly braces indicate that you must choose at least one of the enclosed options. Do not type the braces when you enter the command.
[]	Brackets mean that choosing one or more of the enclosed options is optional. Do not type the brackets when you enter the command.
()	Parentheses are to be typed as part of the command.
	The vertical bar means you can select only one of the options shown.
,	The comma means you can choose as many of the options shown as you like, separating your choices with commas that you type as part of the command.
...	An ellipsis (three dots) means you may repeat the last unit as many times as you need. Do not include ellipses in the command.

Case-sensitivity

- All command syntax and command examples are shown in lowercase. However, replication command names are not case-sensitive. For example, **RA_CONFIG**, **Ra_Config**, and **ra_config** are equivalent.
- Names of configuration parameters are case-sensitive. For example, **Scan_Sleep_Max** is not the same as **scan_sleep_max**, and the former would be interpreted as an invalid parameter name.
- Database object names are not case-sensitive in replication commands. However, to use a mixed-case object name in a replication command (to match a mixed-case object name in the primary database), delimit the object name with quote characters. For example: **pdb_get_tables "TableName"**
- Identifiers and character data may be case-sensitive, depending on the sort order that is in effect.
 - If you are using a case-sensitive sort order, such as “binary,” you must enter identifiers and character data with the correct combination of uppercase and lowercase letters.
 - If you are using a sort order that is not case-sensitive, such as “nocase,” you can enter identifiers and character data with any combination of uppercase or lowercase letters.

Terminology

Replication Agent™ is a generic term used to describe the Replication Agents for Adaptive Server® Enterprise, Oracle, IBM DB2 UDB, and Microsoft SQL Server. The specific names are:

- RepAgent – Replication Agent thread for Adaptive Server Enterprise
- Replication Agent for Oracle

- Replication Agent for Microsoft SQL Server
- Replication Agent for UDB – for IBM DB2 on Linux, Unix, and Windows

Conventions

Installation Task Overview

To successfully install and configure Replication Server®, use the Replication Server Configuration Guide along with the Installation Guide.

The *Replication Server Installation Guide for UNIX* explains how to unload the Replication Server software from the distribution media to your hard disk.

The *Replication Server Configuration Guide for UNIX* explains how to:

- Gather the information you need to prepare your system for your configuration
- Configure Replication Servers and add databases to your replication system
- Upgrade existing Replication Server System Databases (RSSDs)
- Downgrade existing RSSDs and then reinstall an earlier version of the software
- Enable password encryption for a Replication Server or RepAgent
- Start and stop Replication Server or RepAgent

See *Replication Server Configuration Guide for UNIX > Preparation for Installing and Configuring Replication Server* for an installation worksheet and a database setup worksheet to help you plan your replication system.

Installation Task Flows

Task flows define a complete path for planning, installing, and uninstalling.

Choose the path that best describes your scenario.

Note: Print this topic and use it as a checklist.

Installing the product for the first time

1. Plan your installation and review system requirements. See *Planning Your Installation* on page 9 and *System Requirements* on page 17.
2. Install Replication Server. See *Installing Replication Server* on page 25.
3. Perform postinstallation. See *Postinstallation Tasks* on page 33.

Uninstalling Replication Server

Uninstall Replication Server. See *Uninstalling Replication Server* on page 39.

Installing and Uninstalling Replication Manager

1. Install Replication Manager. See *Installing Replication Manager* on page 41.
2. Uninstall Replication Manager. See *Uninstalling Replication Manager* on page 46.

Replication Server Components

Replication Server software includes several components, as well as a variety of support files.

Replication Server includes:

- Replication Server
- Replication Server support files (for example, scripts and configuration files)
- SQL Anywhere® for Embedded Replication Server System Database (ERSSD)

Note: Embedded Replication Server System Database (ERSSD) requires Sybase SQL Anywhere. It is not supported for 64-bit Linux on POWER.

- RepAgent for ERSSD
- Replication Monitoring Services (RMS)

Planning Your Installation

Before you install or upgrade, prepare your environment.

- Identify the components and options to install or upgrade.
- Obtain a license.

Note: If you are using served licenses, you must install the SySAM license server version 2.1 or later.

- Make sure your system meets all requirements for your installation scenario and planned use.

Replication Server Release Bulletin

Obtain the updated information from the release bulletin.

The release bulletin contains last-minute information about installing and upgrading Replication Server software.

The latest release bulletins are available on the Sybase Product Documentation Web site at <http://www.sybase.com/support/manuals>.

Mixed-Version Support

In a mixed-version environment, Replication Server must be version 12.6 and later.

If a replication system domain has Replication Server 15.5 and later, the system version and route versions in the replication system domain must be version 12.6 and later. Replication Server 15.5 does not support mixed-version environments containing versions earlier than 12.6.

See *Replication Server Configuration Guide for your platform > Requirements for Upgrading to Version 15.5 and Later*.

Note: Upgrading from any version earlier than 12.6 requires an intermediate upgrade. See *Replication Server Configuration Guide for your platform > Upgrading or Downgrading Replication Server*.

Obtaining a License

Before installing your product, choose a SySAM license model, determine license server information, and obtain license files.

1. Choose a SySAM license model.

License Model	Description
Unserviced license model	Licenses are obtained directly from the license file. If you are using an unserved license, save the license file to the machine on which you install the product.
Served license model	A license server manages the allocation of licenses among multiple machines.

2. For the served license model, decide whether to use an existing or new license server.

The license server and your product installation need not share the same machine, operating system, or architecture.

3. If you chose the served license model:

- To install on a machine that is running a SySAM 1.0 license server, follow migration instructions in the *SySAM Users Guide* to migrate to the newer SySAM version.

Note: There can be only one instance of a SySAM license server running on a given machine. To set up a SySAM 2 license server on a machine that is already running a SySAM 1.0 license server, you must migrate the old license server to SySAM 2. A migrated license server can serve licenses for both SySAM 1.0 and SySAM 2-enabled products.

4. Get your host IDs.

When you generate licenses at the Sybase Product Download Center (SPDC), you must specify the host ID of the machine where the licenses will be deployed.

- For unserved licenses – the host ID of the machine where the product will run. If you are running a product with per-CPU or per-chip licensing that supports SySAM sub-capacity and want to run the product in a virtualized environment, see “SySAM Sub-capacity Licensing” in the *SySAM Users Guide*.
- For served licenses – the host ID of the machine where the license server will run.

5. Before installing your product, get license files from SPDC at using SPDC access information you receive from Sybase or your Sybase reseller.

Log in to SPDC by using the information in your SPDC welcome e-mail message.

Note: If you purchased your Sybase software from a Sybase reseller, you receive a Web key rather than an e-mail message.

If you plan to use sub-capacity licensing, see the *SySAM Users Guide* for information on how to configure using the **sysamcap** utility.

Use **sysadmin lmconfig** to configure and show license management-related information in Replication Server. See *Replication Server Reference Manual > Replication Server Commands > sysadmin lmconfig*.

SySAM License Server

Make sure that you have installed the required SySAM license server version. Replication Server 15.5 and later include FLEXnet Publisher license server manager, which is platform-specific.

- License server version
You must install the SySAM license server version 2.1 or later. To determine the current license server version, use the **sysam version** command.

Note: License server version 2.0 and earlier do not include this command.

Download the latest license server from the SySAM License Server and Utilities Install Web site at <http://www.sybase.com/sysam/server>.

- FLEXnet Publisher version

Table 1. FLEXnet Publisher Versions Supported on UNIX Platforms

Platforms	FLEXnet Publisher Version
HP-UX Itanium (64-bit)	11.6
IBM AIX (64-bit)	10.8.5
IBM p-Series (Linux on POWER) (64-bit)	11.5
Red Hat Enterprise Linux (RHEL) (32-bit and 64-bit)	11.5
SuSE Linux Enterprise Server (SLES) (32-bit and 64-bit)	11.5
Sun Solaris SPARC 8, 9, and 10 (64-bit)	11.5
Sun Solaris 10 x86-64 (64-bit)	11.5

If you use a SySAM license server, you must update the SySAM license server to at least version 2.1, which includes the FLEXnet Publisher version 11.6.1 license server components on all platforms, before installing Replication Server 15.7. To check the version of your license server, examine the license server log or execute:

```
cd $SYBASE/SYSAM-2_0/bin
./lmutil lmver lmgrd
```

IPv6 Configuration

Use the **sysam configure** command to choose the version of the license server based on your environment.

Replication Server includes IPv4 and IPv6 versions of the SySAM license server software. By default, the installer configures SySAM for IPv4 support.

The IPv4 version of the license server cannot be used properly if you have enabled IPv6 on the license server host. If this is the case, you can:

- Disable IPv6 TCP/IP protocol on the license server host.
- Use another Windows host that does not have IPv6 enabled.
- Use a UNIX host for the license server. You can use the IPv4 version of the license even if both IPv4 and IPv6 are enabled on UNIX.

If you are using the IPv6 version of the license server on a Windows host, you can access this license server only through the IPv6 protocol. Any host with an IPv4 only network stack cannot obtain licenses from this IPv6 license server. To resolve this issue:

- Use a UNIX host for the license server. License servers on UNIX can serve licenses to both IPv4 and IPv6 client hosts.
- Use two separate Windows machines. Set up two license servers on two different hosts in the network; one to serve the IPv4 network and the other one to serve the IPv6 network.

You can use the SySAM script to configure the appropriate version of the license server:

```
sysam configure [IPv6 | IPv4]
```

For example, to configure use of the IPv4/IPv6 dual stack binaries, use:

```
sysam configure IPv6
```

SySAM Licensing Checkout

If Replication Server was licensed using a per-processor license type in versions earlier than 15.7, the license quantity was determined at start-up.

Replication Server periodically checks the number of processors it can use and attempts to check out additional licenses for any increase. Replication Server shuts down after a 30-day grace period expires if additional licenses are not made available within this period.

See *SySAM Users Guide*.

Product Editions and License Types

As of version 15.5, Replication Server is released as two separate product editions— Enterprise Edition (EE) and Real-Time Loading Edition (RTLE) — that comprise different base and optional features, and which require separate licenses.

Replication Server 15.7 is released as the Enterprise Edition.

Table 2. Enterprise Edition Features and Licenses

Feature Type	Features	Description	License
Base	Replication Server	Replication Server features, excluding Advanced Services Option, ExpressConnect for Oracle, and real-time loading.	REP_SERVER
Optional	Advanced Services Option	Replication Server performance enhancements. These enhancements include: <ul style="list-style-type: none"> • High Volume Adaptive Replication (HVAR) • Enhanced Data Server Interface (DSI) efficiency • Enhanced RepAgent executor thread efficiency • Enhanced distributor thread read efficiency • Enhanced memory allocation • Increasing queue block size • Multi-Path Replication™ 	REP_HVAR_ASE
	ExpressConnect for Oracle	Provides Replication Server with the capability to connect directly to Oracle. See the Replication Server Options 15.6 product documentation.	REP_EC_ORA
	Data Assurance Option	Data validation tool.	See the <i>Replication Server Data Assurance Option Installation Guide</i> .

Table 3. Real-Time Loading Edition Features and Licenses

Feature Type	Features	Description	License
Base	Replication Server	Replication Server features, excluding Advanced Services Option, ExpressConnect for Oracle, and real-time loading.	REP_SERVER

Feature Type	Features	Description	License
	Real-Time Loading (RTL)	Allows replication to Sybase® IQ from Adaptive Server and Oracle. Note: You cannot use the Real-Time Loading Edition to replicate to Adaptive Server or Oracle.	REP_RTL_IQ
	Advanced Services Option	Replication Server performance enhancements. These enhancements include: <ul style="list-style-type: none"> • High Volume Adaptive Replication (HVAR) • Enhanced Data Server Interface (DSI) efficiency • Enhanced RepAgent executor thread efficiency • Enhanced distributor thread read efficiency • Enhanced memory allocation • Increasing queue block size 	REP_HVAR_ASE
	Replication Agent for Oracle.	Includes Replication Agent for Oracle to connect to Oracle as a primary data server.	RTLE includes a license for Replication Server Options.
Optional	None		

Sybase Control Center License

Sybase Control Center is licensed free when you have a paid license for a product managed by Sybase Control Center such as Replication Server and Replication Server Data Assurance Option. Evaluation licenses are also available.

You need not obtain a license. The installer offers these licensing options:

- Install licensed copy of Sybase Control Center Suite – choose this option if you have a paid license for a product managed by Sybase Control Center. It installs Sybase Control Center under a permanent (nonexpiring) license.
- Evaluate Sybase Control Center Suite – choose this option if you do not have a paid license for a product managed by Sybase Control Center, or if you do not want to install a permanent copy of Sybase Control Center. The evaluation license expires after 30 days.

See *Sybase Control Center 3.2.4 Installation Guide* for more details.

Replication Server and Sybase IQ InfoPrimer Integration Licenses

Special licensing requirements apply to the integration of Replication Server and Sybase IQ InfoPrimer.

Table 4. Replication Server and Sybase IQ InfoPrimer Integration Licenses

Product	Features	Description	License
Replication Server	Real-Time Loading (RTL)	Allows replication to Sybase IQ from Adaptive Server. Note: You cannot use the Real-Time Loading Edition to replicate to Adaptive Server or Oracle.	REP_RTL_IQ
Sybase IQ InfoPrimer 15.3	Sybase IQ InfoPrimer	Used for the extraction and loading of data from Adaptive Server and transformation of data in Sybase IQ.	SY_INFOPRIMER_SERVER

Sub-capacity Licensing

Sybase offers sub-capacity licensing, which lets you license Sybase products on a subset of the CPUs available on a physical machine.

Platform Support

Table 5. SySAM Virtualization Sub-capacity Compatibility

Vendor	Product	Platform Support	Virtualization Type
HP	nPar	HP IA 11.31	Physical partition
	vPar		Virtual partition
	Integrity Virtual Machines with Resource Manager		Virtual machine
	Secure Resource Partitions		OS containers
IBM	LPAR	AIX 6.1, AIX 7	Virtual partition

Vendor	Product	Platform Support	Virtualization Type
	dLPAR		Virtual partition
Sun	Dynamic System Domains	Solaris 10	Physical partition
	Solaris Containers/Zones with Solaris Resource Manager		OS partition
Intel, AMD	VMWare ESX Server Guest O/S: Windows, Linux, and Sun Solaris x64 VMWare ESX Server excludes VMWare Workstation and VMWare Server.	VMWare ESX 3.5, ESX 4.0 and ESX 4.1, Guest OS: Windows 2008 R2, Windows 7, Red Hat 5.6, SuSE 11, Sun Solaris x64	Virtual machine
	Xen, DomainU: Windows and Linux Xen excludes Sun Solaris x64.	Windows 2008 R2, Windows 7, Red Hat 5.6, and SuSe 11	Virtual machine

Enabling Sybase Sub-capacity Licensing

You must have a sub-capacity licensing agreement with Sybase before you can enable sub-capacity licensing. As with other Sybase licenses, you must generate a license key. For specific steps, see the *SySAM Quick Start Guide*.

Note: Keep your license server up to date.

Although the installation media include a copy of the most recent SySAM license server, Sybase recommends that you periodically check for license server updates on the SySAM Standalone License Servers Web site at <http://www.sybase.com/sysam/server>.

Requirements

When using SySAM sub-capacity licensing, set the SYBASE_SAM_CAPACITY environment variable before installing, or, you can copy in the license key after installation.

If you are using sub-capacity licensing, do one of:

- Set the SYBASE_SAM_CAPACITY environment variable before starting your installer. Follow the instructions provided in the *SySAM Users Guide > Configuring SySAM Sub-capacity*. However, start your installer instead of starting the sub-capacity-enabled Sybase product. The installer includes the **sysamcap** utility located in `sysam_utilities/bin`.
- Select **Continue installation without a license key** in the Sybase Software Asset Management License pane during installation. After installation, copy your license key to

installed_directory/SYSAM-2_0/licenses directory where *installed_directory* is where you have installed your components.

System Requirements

Check the system requirements and system patches for the server on which you will install Replication Server.

System Requirements for Replication Server on UNIX

Verify that you are running a supported operating system and that you have sufficient space available to set up and run the sample Replication Server on UNIX platforms.

Item	Requirement
RAM	A minimum of 512MB RAM.
Disk storage	<p>For a full installation, the total disk space required is approximately 2GB.</p> <p>Disk space required:</p> <ul style="list-style-type: none"> • 950MB for the Replication Server software, supporting files, and log files. • 350MB if you are installing Data Assurance (DA) Option. • An additional 20MB for each Replication Server disk partition. The disk partition may be on a different disk than your Sybase software. <p>One of:</p> <ul style="list-style-type: none"> • Disk space for your Adaptive Server Enterprise database, which serves as your Replication Server System Database (RSSD) if you are not using the Embedded RSSD (ERSSD). See your Adaptive Server Enterprise documentation for system requirements. • 80MB for your SQL Anywhere database, which serves as your ERSSD. The database directory, transaction log directory, and backup directory that make up the 80MB should each reside on different disks. <p>More disk space may be required, depending on your replication system application.</p>

Item	Requirement
<p>Operating system</p>	<p>One of:</p> <ul style="list-style-type: none"> • HP-UX Itanium 11.31 (64-bit) The installer requires the gzip utility. Ensure that the path to gzip is set in the \$PATH environment variable. • IBM AIX (64-bit): <ul style="list-style-type: none"> • AIX 6.1 • AIX 7.x <p>Before you install Replication Server, install the IBM XL C/C++ Runtime for AIX and the SMP Runtime Libraries required for your version of AIX. Obtain the libraries from your IBM AIX operating system installation media.</p> <p>These libraries are also available from the IBM AIX Web site:</p> <ul style="list-style-type: none"> • The IBM XL C/C++ Runtime for AIX is available on the Web site under “Latest updates for supported IBM C and C++ compilers.” • The SMP Runtime Libraries for AIX are available on the Web site under “IBM XL C/C++ Enterprise Edition for AIX, Runtime Environment and Utilities.” • Linux x86-64 (64-bit): <ul style="list-style-type: none"> • Red Hat Enterprise Linux 5.5 <ul style="list-style-type: none"> • kernel - 2.6.18-194.el5 SMP • glibc - 2.5-49 • Red Hat Enterprise Linux 6.0 <ul style="list-style-type: none"> • kernel - 2.6.32-71.el6.x86_64 SMP • glibc - 2.12-1.7.el6.x86_64 • glibc - 2.12-1.7.el6.i686 • SuSE Linux Enterprise Server SLES 10, Service Pack 2 <ul style="list-style-type: none"> • kernel - 2.6.16.60-0.21 SMP • glibc - 2.4-31.54 • SuSE Linux Enterprise Server SLES 11 <ul style="list-style-type: none"> • kernel - 2.6.27.19-5.1 • glibc - 2.9-13.2 • SuSE Linux Enterprise Server SLES 11, Service Pack 1 <ul style="list-style-type: none"> • kernel - 2.6.32.12-0.7 • glibc - 2.11.1-0.17.4 • Linux on IBM p-Series (Linux on POWER) (64-bit): <ul style="list-style-type: none"> • Red Hat Enterprise Linux 5.5 <ul style="list-style-type: none"> • kernel- 2.6.18-194.el5 SMP • glibc-2.5-49

Item	Requirement
	<ul style="list-style-type: none"> • Red Hat Enterprise Linux 6.0 <ul style="list-style-type: none"> • kernel- 2.6.32-71.el6.ppc64 SMP • glibc-2.12-1.7.el6.ppc64 • glibc-2.12-1.7.el6.ppc • SuSE Linux Enterprise Server SLES 10, Service Pack 2 <ul style="list-style-type: none"> • kernel-2.6.16.60-0.21-ppc64 SMP • glibc-2.4-31.54 • SuSE Linux Enterprise Server SLES 11, Service Pack 1 <ul style="list-style-type: none"> • kernel-2.6.32.12-0.7-ppc64 SMP • glibc-2.11.1-0.17.4 • Sun Solaris 10 SPARC (64-bit) • Sun Solaris 10 x64 (64-bit)
Supported protocols	TCP/IP

Operating System Patch Requirements

Make sure that the latest patches are installed on your operating system.

On Linux – Linux distributors that supply Linux Kernel version 2.4.x should provide all the libraries you require. If you are alerted to any outdated or missing libraries, download them from your Linux distributor’s Web site.

Contact your operating system provider for any patches recommended for your installation, or check the Replication Server release bulletin for your platform.

If your operating system requires patches, install them before you install Replication Server components.

Note: Do not use a patch that is earlier than the version suggested for your operating system. If a patch has been superseded by a newer patch, use the most recent one.

Determining Operating System Patch Level on UNIX Platforms

Determine the current installed patches and display the operating system version level on UNIX platforms.

- On HP-UX, enter:

```
/usr/sbin/swlist -l patch
```
- On IBM AIX, enter:

```
/usr/sbin/instfix -a
```
- On Sun Solaris, enter:

```
showrev -p
```

- On Linux, enter:

```
rpm -q -a
```

Installation Directory Structure

Provides an overview of the installation directory, subdirectory hierarchy, and the naming convention used for the installed components.

Most components of Replication Server are installed in their own subdirectories, with the executable program, installation and configuration tools, and display-related files needed by the component. The naming convention for subdirectories includes a component identifier, such as REP (for Replication Server) or OCS (for Open Client™ and Open Server™), and the software release version.

Replication Server 15.7 includes a new version of Replication Server and many of its supporting components. Other Sybase products may contain earlier versions of the same components. You can install Replication Server 15.7 into the same directory containing these existing products.

However, if you are using other Sybase products, installing Replication Server 15.7 may cause some environment variables to change. Reset the environment variables to make individual products work.

Note: You can install Replication Server 15.7 in the same directory as Adaptive Server Enterprise and Open Client and Open Server versions 15.5 or later.

Sybase recommends that you do not uninstall Replication Server 15.7 if it has been installed in the same directory as older Sybase products that are installed using InstallShield installer, otherwise, these products may not work correctly.

You can install Replication Server 15.7 on top of Replication Server 12.6 and later, in the same \$SYBASE directory. Doing so creates a duplicate entry in the `interfaces` file for `SAMPLE_RS`, which is the sample Replication Server. `rs_init` warns you about the duplicate entry and uses the first instance of `SAMPLE_RS` found in the `interfaces` file.

Constraints

Do not install Replication Server version 15.7 on top of these Sybase products:

- Replication Server version 12.5 or earlier
- Adaptive Server version 12.5.0.x or earlier
- Adaptive Server version 12.x (64-bit)
- Open Client and Open Server version 12.5.0 or earlier
- OpenSwitch™ version 12.5 or earlier
- DirectConnect™ version 12.5 or earlier

Doing so incapacitates older versions of these products, and may also adversely affect other Sybase products. If you perform one of these installations, you cannot reverse it with an

uninstallation, as uninstalling might remove required components of the older Sybase products updated by Replication Server version 15.7. For this reason, Sybase recommends that you back up your current directory before installing Replication Server version 15.7.

If you are installing Replication Server 15.7 in an existing Sybase installation directory that contains Adaptive Server version 15.0.x, you may be asked if you want to install older `locales` or `charset` files on top of newer files. To ensure that you have the latest version of these files, select “No to all.”

Shared components are installed in subdirectories that are separate from component subdirectories. For example, the Replication Server subdirectory is `$$SYBASE/REP-15_5`. However, Open Client is installed in `$$SYBASE/OCS-15_0`. The exception is `SQL Anywhere`, which is installed in `$$SYBASE/REP-15_5/ASA12`, because it is used only for Replication Server. As a result, the directory structure enables you to install into an existing `$$SYBASE` directory structure, as well as to install and use multiple versions of some components.

Tip: If your earlier installation includes custom applications or scripts that refer to `$$SYBASE` subdirectories, change them to reflect the new installation directory structure.

A diagnostic server (`REP-15_5/bin/repserver.diag`) is installed to capture and display information about internal processes. Do not delete this program as you may need to use it at the direction of Sybase Technical Support, to diagnose and resolve Replication Server problems.

Note: Your actual directory structure may differ from what is documented, depending on the components you install.

Replication Server Installation in a Unique Directory on UNIX Platforms

You can install Replication Server in a unique directory without affecting Sybase environment variables on UNIX platforms.

Note: When you install Replication Server in a unique installation directory, you must maintain two `interfaces` files: one for Replication Server components and one for your other Sybase applications.

See also

- *Environment Variables on UNIX* on page 35
- *Installing Replication Server with the GUI Wizard* on page 26

Installation Directory Contents and Layout

Check the list of Replication Server components that are installed in the Sybase installation directory on your machine.

Within `$$SYBASE`:

Planning Your Installation

- `charsets` – character sets and sort order.
- `collate` – Unicode.
- `config` – configuration files.
- `interfaces` – `interfaces` file for UNIX.
- `jre32` – files used by the installer on the 32-bit platform.
- `jre64` – files used by the installer on the 64-bit platform.
- `locales` – localization files for Open Client and Open Server, and other components used by Replication Server. Does not include Replication Server specific localization files.
- `log` – log files of the installation process.
- `OCS-15_0` – Open Client and Open Server directories and files, including `bin`, `config`, `devlib`, `include`, `lib`, `lib3p`, `sample`, `scripts`, `sybhelp`, and `xappdefaults`.
- `REP-15_5` – Replication Server 15.7 files, including `ASA12`, `bin`, `certificates`, `devlib` (32-bit platforms), `devlib64` (64-bit platforms), `doc`, `init`, `install`, `lib64` (64-bit platforms), `lib3p64` (64-bit platforms), `locales`, `REFIMP-01_0`, `samp_repserver`, `scripts`, `sample`, `sysam`, `ThirdPartyLegal`, and `upgrade`.
- `SCC-3_2` – Sybase Control Center (SCC) for Replication Server and Data Assurance, including `auth`, `bin`, `common`, `conf`, `ldap`, `log`, `plugins`, `rtlib`, `server`, `services`, `shared`, and `utility`.
- `Shared` – common components shared across products, including the Java Runtime Environment.
- `Sybase_Install_Registry` – used for storing Sybase product registry information to keep track of version of installed and uninstalled software. The `si_reg.xml` file gets installed in the `$SYBASE/Sybase_Install_Registry` directory.

Warning! Modifying or removing `si_reg.xml` prevents the installer from accurately managing installed component versions when you install or uninstall Sybase software subsequent to this installation.

- `sybuninstall` – files used by the uninstaller to uninstall Replication Server software.
- `SYSAM-2_0` – software license manager files including `bin`, `licenses`, `locales`, and `log`. Linux has an additional software license manager file called `META-INF`.
- `SYBASE.csh`, `SYBASE.sh`, `SYBASE.env` – files created by the installer that you use to reset environment variables.

Installation Setup Options

Decide the Replication Server installation option that is appropriate for your setup. Typical is the default option.

The Replication Server **setup** program provides these installation options:

- Typical (default) – installs the Replication Server components considered to be useful for most customers. In this type of installation, only the English language module and its supported character sets are installed. You see a list of components that will be installed and the total disk space required before the installation begins.
- Full – installs every Replication Server component including all the supported language modules from the installation media. You see a list of components that will be installed and the total disk space required before the installation begins.
- Custom – allows you to select the components to install. Recommended for advanced users.

Note: Certain components are automatically installed if they are required to run other selected components.

Installation Mode

Decide which installation mode you want to use. GUI mode is the default option.

You can install Replication Server using:

- Graphical user interface (GUI) – lets you install the components in an interactive user mode.
- Console – lets you install components in a command line environment.
- Response file – lets you record or create a response file. You can install Replication Server in two different ways using a response file:
 - Silent – save the installation settings in a response file and install the product without any interaction required on your part. This is convenient if you are performing identical installations on multiple machines.
 - Interactive installation using response file – install interactively, but with all the responses already filled in, so you can accept all the defaults and install Replication Server according to the responses in the response file. This can be convenient if several sites are installing Replication Server in a nongraphical user interface environment and must conform to a standard installation with minor changes.

Performing Administrative Tasks

Complete the administrative tasks before you begin the installation process.

1. Back up your current replication system.
2. Create the “sybase” user account and make sure it has read, write, and execute permissions.
3. Verify that the directory location for the Sybase installation has sufficient space.
4. Verify that your network software is configured.

Sybase software uses network software, even if Replication Server and Sybase client applications are installed on a machine that is not connected to a network.

5. If you are using an RSSD, verify that Adaptive Server Enterprise is up and running.

Creating the Sybase User Account

Create a Sybase user account to ensure that Sybase product files and directories are created with consistent ownership and privileges.

One user (typically the Sybase system administrator, who has read, write, and execute privileges) should perform all installation, configuration, and upgrade tasks.

1. To create a Sybase system administrator account, choose an existing account, or create a new account and assign a user ID, group ID, and password for it.

This account is sometimes called the “sybase” user account. See your operating system documentation for instructions on creating a new user account.

If you have installed other Sybase software, the “sybase” user should already exist.

2. Verify that you can log in to the machine using this account.

Installing Replication Server

Install Replication Server using your chosen method.

Prerequisites

Complete installation planning tasks.

Task

1. Choose an installation method:
 - GUI wizard (recommended)
 - Console mode
 - Response file
2. Follow the instructions for your chosen method.
3. Perform postinstallation steps.

Mounting the Installation Media

If you are installing using the CD or DVD, mount the installation media.

The location of the **mount** command is site-specific and may differ from the instructions shown here. If you cannot mount the installation media in the appropriate drive using the path shown, check your operating system documentation or contact your system administrator.

- For HP-UX:

Log out, log in as root, and issue:

```
mount -F cdrfs -o ro device_name /mnt/cdrom
```

Then, log out as root and log in again as “sybase.”

- For IBM AIX:

Log in as “sybase” and issue:

```
mount -v 'cdrfs' -r device_name /mnt/cdrom
```

- For Sun Solaris:

The operating system automatically mounts the CD or DVD. Log in as “sybase.” If CD- or DVD-reading errors occur, check your operating system kernel to make sure that the ISO 9660 option is turned on. If you have previously installed a Sybase CD or DVD on your system, the # sign interferes with the installation process. Before installing your current CD or DVD, either:

- Restart your system, or,

Installing Replication Server

- Eject the CD or DVD. Delete the *Volume Label* file in `/vol/dsk`, and reinsert the CD or DVD.
- For Linux and Linux on POWER:
Log in as “sybase” and issue:

```
# mount -t iso9660 /dev/cdrom /mnt/cdrom
```

See also

- *Installing Replication Server with the GUI Wizard* on page 26

Installing Replication Server with the GUI Wizard

The installer creates the target directory and installs the selected components into that directory.

Prerequisites

Verify that the drive on which you install the Replication Server has enough disk space for the components being installed, and at least 100MB of extra disk space for the installation program.

Task

1. Insert the Replication Server media in the appropriate drive, or download and extract the Replication Server installation image from the Sybase Product Download Center (SPDC).
2. If you downloaded the product from SPDC, go to the directory where you extracted the installation image and start the installer:

```
./setup.bin
```

If you are installing using CD or DVD, mount it and start the installer.

- On HP-UX:

```
cd /cdrom  
./setup.bin
```

- On IBM AIX:

```
cd /device_name  
./setup.bin
```

- On Sun Solaris:

```
cd /cdrom/Volume Label  
./setup.bin
```

- On Linux and Linux on POWER:

```
cd /mnt/cdrom  
./setup.bin
```

where:

- *cdrom* and */mnt/cdrom* is the directory (mount-point) you specified when mounting the CD or DVD drive.
- *device_name* is the name of the CD or DVD device drive.
- *setup.bin* is the executable file name to install Replication Server.

If there is not enough disk space in the temporary disk space directory, set the environment variable `IATEMPDIR` to *tmp_dir* before running the installer again, where *tmp_dir* is where the installation program writes the temporary installation files. When specifying the *tmp_dir*, include the full path.

3. In the Introduction window, click **Next**.
4. Specify where to install Replication Server:

Option	Description
Click Choose .	To select an installation directory. A window appears, and from that window browse for and select the directory.
Enter a new directory path.	To create a new directory.
Click Restore Default Folder .	To restore to the default directory if you do not want to use the directory that you have entered.

- If the directory you chose does not exist, click **Yes** to create it.
- If it does exist, and already contains a Replication Server installation, you are warned that you will overwrite the older version. Click **Next**.

5. Select the type of installation:

Option	Description
Typical	Installs the default components. This is recommended for most users.
Full	Installs every Replication Server component, including all the supported language modules.
Custom	Lets you select the components to install. Some components are automatically installed if they are required to run your selected components.

Click **Next**.

6. Select the geographic location, agree to the license agreement, then click **Next**.
7. On the Sybase Software Asset Management License Server window:

Option	Choose
<p>Specify license keys</p>	<p>Either:</p> <ul style="list-style-type: none"> • Click Browse to select the license file. • Use Shift+Click or Ctrl+Click to select multiple license files. The license pane displays the license information. • Copy and paste the license information directly in the license pane. <p>Click Next.</p> <p>If you specify a served license key, the installer prompts you to install a new SySAM license server. Select:</p> <ul style="list-style-type: none"> • Next – to install the new SySAM license server. Follow the installation prompts. • Previous – and select Use previously deployed license server if you have an existing SySAM license server on the same host.
<p>Use previously deployed license server</p>	<p>Enter the:</p> <ul style="list-style-type: none"> • Host name of the machine where the license server is running • Port number if the port number you are using is not the default <p>Click Next.</p>
<p>Continue installation without a license key</p>	<p>If you do not have licenses for any of the Replication Server components, select this option, then click Next to proceed.</p> <p>The installer allows you to install and use Replication Server components without a license for a grace period of 30 days. To continue using these components after the end of the grace period, obtain valid licenses from the SPDC, and install these licenses using the Replication Server License Installer.</p>

Use **sysadmin lmconfig** to configure and show license management-related information in Replication Server. See *Replication Server Reference Manual > Replication Server Commands > sysadmin lmconfig*.

8. Set SySAM e-mail configuration if necessary. Click **Next**.
9. The installation summary window displays the selections you have made. Review the information, and click **Install**.
10. On the Start Sample Replication Server window, select:

Option	Description
<p>Yes</p>	<p>To configure and start a sample Replication Server. The installer displays the configuration information for the sample Replication Server. Write this information down.</p>

Option	Description
No	To complete the installation. You can manually configure a full-featured Replication Server and start a sample Replication Server after installation.

Click **Next**.

11. When the installation finished, click **Done**.

Next

Verify that the installation is valid and successful.

- View the logs files in `$SYBASE/log` directory to check for errors. A valid installation does not contain the word “ERROR.”
- Check that the date of the `si_reg.xml` file in `$SYBASE/Sybase_Install_Registry` directory reflects the date of this installation.

See also

- *Postinstallation Tasks* on page 33
- *Runserver File* on page 37
- *Mounting the Installation Media* on page 25

Installing Replication Server Data Assurance Option

Replication Server Data Assurance (DA) Option is available as a separately licensed product for Replication Server. Obtain the **setup** program from where you have extracted the installation image.

See the *Replication Server Data Assurance Option Installation Guide* for details.

Installing Replication Server in Console Mode

Choose command line installation if you prefer a nonwindowing interface or for developing custom installation scripts.

Prerequisites

Launch the installer in console mode. If the installer launches automatically, click **Cancel** to cancel the GUI installation, then launch the **setup** program from a terminal or console.

Task

The steps for installing components in an interactive text mode are the same as those described in installing in GUI mode, except you use **setup -i console** to execute the installer from the command line, and you enter text to select installation options.

Installing Replication Server

1. At the command prompt, enter:

```
./setup.bin -i console
```

2. The flow of the installation is identical to a GUI installation, except output is written to a terminal window and responses are entered using the keyboard. Follow the remaining prompts to install Replication Server.

See also

- *Installing Replication Server with the GUI Wizard* on page 26

Installing Replication Server Using a Response File

Unattended or silent installations are typically used to update multiple systems across the enterprise.

To perform a silent, or “unattended” installation, run the installer and provide a response file that contains your preferred installation configuration.

Creating a Response File

Record installation responses into a response file, which is a text file you can edit to change any responses before using it in subsequent installations.

To create a response file when installing in GUI or console mode, specify the **-r** command line argument, which records your responses to the installation wizard’s prompts and creates a response file when the installation wizard exits.

To generate a response file during installation, enter:

```
./setup.bin -r responseFileName
```

where *responseFileName* is the file name you choose for the response file. When specifying the response file name, include its full path. For example:

```
/home/sybase/REP/ResponseFile.txt
```

Note: You must provide the full path name for the response file you create.

Installing in GUI Mode Using a Response File

Unattended or silent installations are typically used to update multiple systems across the enterprise.

Prerequisites

Create an installation response file.

An interactive installation using a response file lets you either accept the default values supplied by the response file or enter different values. This is useful when installing multiple instances of Replication Server that have similar but not identical settings.

Task

To run the GUI installation using the response file, enter:

```
./setup.bin -f responseFileName
```

where *responseFileName* is the file name containing the installation options you chose. When specifying the response file name, include its full path.

See also

- *Command Line Options* on page 32
- *Creating a Response File* on page 30
- *Installing Replication Server with the GUI Wizard* on page 26

Installing in Silent Mode

Unattended or silent installations are typically used to update multiple systems across the enterprise.

Prerequisites

Create an installation response file.

A silent or unattended installation does not involve user interaction; and all installation configuration information is taken from the response file. This is useful when you want multiple identical installations, or to fully automate installation.

Task

To install in silent mode, run:

```
./setup.bin -f responseFileName -i silent  
-DAGREE_TO_SYBASE_LICENSE=true
```

where:

- *responseFileName* – is the absolute path of the file name containing the installation options you chose.
- **-D** – specifies that you agree with the Sybase License Agreement text.

Except for the absence of the GUI screens, all actions of the installer are the same, and the result of an installation in silent mode is exactly the same as one performed in GUI mode with the same responses.

Note: You must agree to the Sybase License Agreement when installing in silent mode. You can either:

- Include the option `-DAGREE_TO_SYBASE_LICENSE=true` in the command line argument, or,
 - Edit the response file to include the property `AGREE_TO_SYBASE_LICENSE=true`.
-

See also

- *Command Line Options* on page 32
- *Creating a Response File* on page 30
- *Installing Replication Server with the GUI Wizard* on page 26

Troubleshoot Installation Problems

Set the installer to debug mode to troubleshoot problems encountered during installation.

Set the environment variable LAX_DEBUG to true before running the installer. The installer then generates additional detailed installation information that is useful for debugging installer issues.

Tip: If you encounter errors during installation, check the installation log file to see a record of the installation process. The log file is located in \$SYBASE/log.

If this is the first time you have installed a Sybase product on this machine, the installer creates a Sybase installation directory that contains the support files for all Sybase products.

Command Line Options

Options for installing or uninstalling Replication Server in console mode.

Option	Purpose
-i swing	Uses GUI mode.
-i console	Uses the console interface mode, where messages during installation appear on the Java console and the wizard is run in console mode.
-i silent	Installs or uninstalls the product in silent mode, where the installation or uninstal- lation is performed with no user interaction.
-D	Passes custom variables and properties. For example, to override the default in- stallation directory when you run the installer, enter: <code>install_launcher_name</code> <code>-DUSER_INSTALL_DIR=/sybase</code>
-r	Generates a response file and a reference.
-f	References response files.
-l	Sets the installer's locales.
-\?	Displays the installer help.

Postinstallation Tasks

After installing Replication Server, perform the postinstallation tasks necessary for your site.

See the *Replication Server Configuration Guide for UNIX*.

Log Files

Check the information about the configuration of Replication Server that is stored in the log files.

- Replication Server installer error log file:
`$SYBASE/log`
- Sample Replication Server error logs:
`$SYBASE/REP-15_5/SAMPLE_RS.log`
- Sample Replication Server SQL Anywhere error logs:
`$SYBASE/REP-15_5/samp_repserver/errorlog/`
- **rs_init** log file:
`$SYBASE/REP-15_5/init/logs/logmddd.xxx`
For example: `$SYBASE/REP-15_5/init/logs/log1106.001`
- Replication Server log file:
`$SYBASE/REP-15_5/install/rs_name.log`
For example: `$SYBASE/REP-15_5/install/REP_redtail.log`

Adaptive Server for the RSSD

Start the RSSD stored on Adaptive Server.

To use the RSSD stored on Adaptive Server Enterprise, install the Adaptive Server Enterprise database, if you have not done so already. See the *Adaptive Server Enterprise Installation Guide* for your platform.

After successful installation, start Adaptive Server Enterprise. See the *Adaptive Server Enterprise Configuration Guide* for your platform.

Note: If you are upgrading Adaptive Server Enterprise and you have replicated databases, see the *Adaptive Server Enterprise Installation Guide* for your platform.

Sample Replication Server Configuration

If you have not configured the sample Replication Server during installation, you can use the resource file created by the installer to configure and start the sample Replication Server.

During installation, the installer prompts you to configure and start a sample Replication Server. Regardless of your choice, the installer creates a resource file, `$SYBASE/REP-15_5/samp_repserver/SAMPLE_RS.res`, for the sample Replication Server and updates the `interfaces` file. Use this resource file to configure and start the sample Replication Server after installation. The sample Replication Server resource file creates an ERSSD.

At the command prompt, enter:

```
cd $SYBASE/REP-15_5/samp_repserver
./rs_init-SAMPLE_RS.sh
```

The `rs_init` utility in this script displays commands as it executes them, and writes this output to its log.

If you encounter errors during configuration and start-up of the sample Replication Server, read the log file `$SYBASE/REP-15_5/init/logs/logmdd.xxx`, where:

- *mm* – is the month.
- *dd* – is the day.
- *xxx* – is the number of that instance of the log on that day.

All files and logs associated with the sample Replication Server are in `$SYBASE/REP-15_5/samp_repserver`.

Table 6. Sample Replication Server Configuration Information

Sample Replication Server Item	Definition
Name	<i>SAMPLE_RS</i>
Port	11752
User name	<i>sa</i>
Password	None
ERSSD server name	<i>SAMPLE_RS_ERSSD</i>
ERSSD server port	11751
ERSSD user name	<i>SAMPLE_RS_RSSD_prim</i>
ERSSD password	<i>SAMPLE_RS_RSSD_prim_ps</i>

See *Replication Server Configuration Guide for UNIX > Configure Replication Server and Add Databases Using rs_init*.

Server Entries in the Interfaces File

Modify network connection information using the **dsedit** utility.

If either the primary or the replicate Adaptive Server is not on the Replication Server machine, you must change the default host name “localhost” in the Replication Server `interfaces` file to the actual server name. Use **dsedit** to update the `interfaces` file.

dsedit creates and modifies network connection information in the `interfaces` file. The utility is located in `$SYBASE/$SYBASE_OCS/bin`.

Tip: If your system does not have X-Windows, use **dscp** to configure server entries in the `interfaces` file. The utility is located in `$SYBASE/$SYBASE_OCS/bin`.

See *Adaptive Server Enterprise Utility Guide > Using dscp*.

Source `SYBASE.csh` or `SYBASE.sh` to set the required environment variables before executing **dsedit**.

See *Adaptive Server Enterprise Utility Guide > Using dsedit*.

Environment Variables on UNIX

The Replication Server installer automatically sets the required system environment variables, such as `PATH`, as well as additional environment variables used by your newly installed Sybase software.

The environment variables are in these files:

- `$SYBASE/SYBASE.sh`
- `$SYBASE/SYBASE.csh`
- `$SYBASE/SYBASE.env`

After exiting the Replication Server installer, you may need to reset the environment variables, for example, if someone other than the Sybase administrator must use the software.

To set these environment variables, you can either:

- Source `SYBASE.sh` (Bourne, Korn, or BASH shell) or `SYBASE.csh` (C shell) to change the component’s environment variables immediately for your current session, before invoking any component, or,
- Update the environment variables in the shell files to permanently change the component’s environment variables.

Table 7. Environment Variables for UNIX and Linux

Environment Variable	Description
<ul style="list-style-type: none"> • For HP-UX Itanium: \$LD_LIBRARY_PATH \$SHLIB_PATH • For Linux, Linux on POWER (IBM pSeries): \$LD_LIBRARY_PATH • For Sun Solaris: \$LD_LIBRARY_PATH \$LD_LIBRARY_PATH_64 • For IBM AIX: \$LIBPATH 	Subdirectory path to the Open Client and Open Server runtime shared library
\$PATH	Includes directories that are needed to execute Replication Server (such as Replication Server executables and OCS libraries)
\$SYBASE	Home directory where you install all Sybase products
For HP-UX Itanium, Sun Solaris, and Linux: <ul style="list-style-type: none"> • \$SYBASE_JRE6_32 	Subdirectory path to where the Java Runtime Environment (JRE) resides
\$SYBASE_JRE6	Subdirectory path to where the Java Runtime Environment (JRE) resides
For HP-UX Itanium, IBM AIX, Sun Solaris, and Linux on POWER (IBM pSeries): <ul style="list-style-type: none"> • \$SYBASE_JRE6_64 	Subdirectory path to where the Java Runtime Environment (JRE) resides
\$SCC_JAVA_HOME	Subdirectory path to Sybase Control Center framework and Replication Monitoring Services
\$SYBASE_OCS	Subdirectory path to Open Client files
\$SYBASE_REP	Subdirectory path to Replication Server

Runserver File

The runserver file is an executable script that contains the complete command line required to start a Replication Server. When you install a new Replication Server to your replication system, **rs_init** creates a runserver file in the Sybase installation directory.

The runserver file name is constructed based on the name of the server. For example, for a Replication Server named ROME_RS, the runserver file is named RUN_ROME_RS.

Uninstalling Replication Server

Uninstall the product.

Prerequisites

- Log in to your machine using an account with administrator privileges.
- Shut down all Sybase applications and processes.

Note: The uninstaller removes only those files that were loaded from the installation media. Some Sybase files, such as log and configuration files, are left intact for administrative purposes. `jre` and other installed directories are also not removed by the uninstaller. You must manually remove these directories.

Task

1. Choose an uninstallation method:
 - GUI wizard (recommended)
 - Console mode
 - Silent mode
2. Follow the instructions for your chosen method.

Uninstalling with the GUI Wizard

Uninstall Replication Server in GUI mode.

1. Enter:

```
$SYBASE/sybuninstall/RepServer_Suite/uninstall
```

2. Click **Next**.

3. Select one of:

- **Complete Uninstall** – completely remove all features and components of Replication Server. Files and folders created after the installation are unaffected.
- **Uninstall Specific Features** – uninstall specific features of Replication Server.

Click **Next**.

4. The uninstallation summary window displays the selections you have made. Review the information, and click **Next**.

Uninstalling Replication Server

Note: If you installed SySAM during installation, this window shows the SySAM license utility. Sybase recommends that you do not uninstall the SySAM license utility if you are using a SySAM license server.

The Uninstall Complete window lists the items that cannot be removed.

5. Click **Done**.

Uninstalling in Console Mode

Uninstall Replication Server in console mode.

1. At the command prompt, navigate to the installation directory and enter:

```
$SYBASE/sybuninstall/RepServer_Suite/uninstall -i console
```

The **uninstall** program starts.

2. The flow of the **uninstall** program is identical to a regular GUI uninstallation, except output is written to a terminal window and responses are entered using the keyboard. Follow the remaining prompts to uninstall Replication Server.

Note: You may be prompted to decide whether to remove shared files. Sybase recommends that you do not remove shared files.

See also

- *Command Line Options* on page 32
- *Uninstalling with the GUI Wizard* on page 39

Uninstalling in Silent Mode

Uninstall Replication Server in silent mode.

At the command prompt, navigate to the installation directory and enter:

```
$SYBASE/sybuninstall/RepServer_Suite/uninstall -i silent
```

The **uninstall** program starts.

Note: You may be prompted to decide whether to remove files that are created outside the installer. Sybase recommends that you do not remove these files.

See also

- *Command Line Options* on page 32
- *Uninstalling with the GUI Wizard* on page 39

Installation and Uninstallation of Replication Manager

There are several different methods available for setting up and uninstalling Replication Manager; however, Sybase recommends that you use GUI mode.

Replication Manager is a utility for creating, managing, and monitoring replication environments, and is available as a plug-in to Sybase Central™, Java Edition. Replication Manager communicates directly with Replication Server and Adaptive Server Enterprise servers.

Depending on the scale and complexity of your replication environment, you can set up either a two-tier or a three-tier solution. In a two-tier management solution, Replication Manager connects directly to the servers without communicating through the management layer.

In a three-tier management solution, Replication Manager monitors large and complex replication environments with the help of Replication Monitoring Services (RMS). Replication Manager connects to the servers through RMS.

Replication Manager:

- Uses a graphical user interface.
- Allows you to manage, monitor, and troubleshoot replication system components, such as connections, routes, replication definitions, subscriptions, and so forth.
- Runs on Microsoft Windows operating systems as well as all UNIX operating systems that Replication Server supports.
- Runs within the same Sybase Central framework as the Adaptive Server plug-in.
- Manages a warm standby environment.
- Supports multisite availability (MSA).
- Supports an ERSSD.
- Provides for logging and tracing of server commands.
- Provides two-tier and three-tier management solutions by supporting RMS.

See *Replication Server Administration Guide Volume 1 > Manage Replication Environment with Sybase Central*.

Installing Replication Manager

Select a method by which to install Replication Manager.

1. Choose an installation method:

- GUI wizard

Installation and Uninstallation of Replication Manager

- Console mode
 - Response file
2. Follow the instructions for your chosen method.
 3. Perform postinstallation steps.

Installing Replication Manager with GUI Wizard

The installer creates the target directory and installs the selected components into that directory.

1. Launch the installer.
 - On IBM AIX (64-bit):
`/ibmaix64/RMP_Suite/setupaix.bin`
 - On HP-UX (64-bit):
`/hpia64/RMP_Suite/setuphpia64.bin`
 - Linux on POWER (IBM pSeries) (64-bit):
`/ibmplinux64/RMP_Suite/setuplinuxppc64.bin`
 - On Linux x86-64 (64-bit):
`/linuxamd64/RMP_Suite/setuplinux64.bin`
 - On Sun Solaris 10 SPARC (64-bit):
`/sunsparc64/RMP_Suite/setupSolarisSparc.bin`
 - On Sun Solaris 10 x64 (64-bit):
`/sunx64/RMP_Suite/setupSolarisx86.bin`
2. In the Introduction window, click **Next**.
3. Select the geographic location, agree to the license agreement, then click **Next**.
4. Indicate where to install Replication Manager:

Option	Description
Click Choose .	To select an installation directory. A window appears, and from that window browse for and select the directory.
Enter a new directory path.	To create a new directory.
Click Restore Default Folder .	To restore to the default directory if you do not want to use the directory that you have entered.

- If the directory you chose does not exist, click **Yes** to create it.
- If it does exist, and already contains a Replication Manager installation, you are warned that you will overwrite the older version. Click **Next**.

5. The installation summary window displays the selections you have made. Review the information, and click **Install**.
6. When the installation finished, click **Done**.

Next

Verify that the installation is valid and successful.

- View the `InstallAndRegister.log` file and logs in `$$SYBASE/log` to check for errors. A valid installation does not contain the word “error.”
- Ensure that the date of the `si_reg.xml` file in `$$SYBASE/Sybase_Install_Registry` reflects the date of the current installation.
- Ensure that you can access Replication Manager from Sybase Central.
See [Replication Server Administration Guide Volume 1 > Manage Replication Environment with Sybase Central](#).

Note: Before you use Replication Manager, make sure that the Replication Manager is registered with Sybase Central. See “Preparing to manage a replication environment” in the Replication Manager plug-in online help.

Installing Replication Manager in Console Mode

Choose command line installation if you prefer a nonwindowing interface or for developing custom installation scripts.

Prerequisites

Launch the installer in console mode. If the installer launches automatically, click **Cancel** to cancel the GUI installation, then launch the **setup** program from a terminal or console.

Task

The steps for installing components in an interactive text mode are the same as those described in installing in GUI mode, except you use **setup -i console** to execute the installer from the command line, and you enter text to select installation options.

1. At the command prompt, enter:

- On IBM AIX (64-bit):

```
/ibmaix64/RMP_Suite/setupaix.bin -i console
```
- On HP-UX (64-bit):

```
/hpia64/RMP_Suite/setuphpia64.bin -i console
```
- On Linux on POWER (64-bit):

```
/ibmplinux64/RMP_Suite/setuplinuxppc64.bin -i console
```
- On Linux x86-64 (64-bit):

Installation and Uninstallation of Replication Manager

```
/linuxamd64/RMP_Suite/setuplinux64.bin -i console
```

- On Sun Solaris 10 SPARC (64-bit):

```
/sunsparc64/RMP_Suite/setupSolarisSparc.bin -i console
```

- On Sun Solaris 10 x64 (64-bit):

```
/sunx64/RMP_Suite/setupSolarisx86.bin -i console
```

2. The flow of the installation is identical to a GUI installation, except output is written to a terminal window and responses are entered using the keyboard. Follow the remaining prompts to install Replication Manager.

See also

- *Command Line Options* on page 32
- *Installing Replication Manager with GUI Wizard* on page 42

Installing with a Response File

Unattended or silent installations are typically used to update multiple systems across the enterprise.

To perform a silent, or “unattended” installation, run the installer and provide a response file that contains your preferred installation configuration.

Creating a Response File

Record installation responses into a response file, which is a text file you can edit to change any responses before using it in subsequent installations.

To create a response file when installing in GUI or console mode, specify the **-r** command line argument, which records your responses to the installation wizard’s prompts and creates a response file when the installation wizard exits.

To generate a response file during installation, enter:

- On IBM AIX (64-bit):

```
/ibmaix64/RMP_Suite/setupaix.bin -r responseFileName
```

- On HP-UX (64-bit):

```
/hpia64/RMP_Suite/setuphpia64.bin -r responseFileName
```

- On Linux on POWER (64-bit):

```
/ibmplatix64/RMP_Suite/setuplinuxppc64.bin -r  
responseFileName
```

- On Linux x86-64 (64-bit):

```
/linuxamd64/RMP_Suite/setuplinux64.bin -r responseFileName
```

- On Sun Solaris 10 SPARC (64-bit):

```
/sunsparc64/RMP_Suite/setupSolarisSparc.bin -r  
responseFileName
```

- On Sun Solaris 10 x86/x64 (64-bit):


```
/sunx64/RMP_Suite/setupSolarisx86.bin -r responseFileName
```

where *responseFileName* is the file name you choose for the response file. When specifying the response file name, include its full path. For example:

```
/home/sybase/RMP/ResponseFile.txt
```

Installing in Silent Mode

Unattended or silent installations are typically used to update multiple systems across the enterprise.

Prerequisites

Create an installation response file.

A silent or unattended installation requires no user interaction, and all installation configuration information is taken from the response file. This is useful when you want multiple identical installations, or to fully automate installation.

Task

To install in silent mode, run:

- On IBM AIX (64-bit):

```
/ibmaix64/RMP_Suite/setupaix.bin -f responseFileName  
-i silent -DAGREE_TO_SYBASE_LICENSE=true
```

- On HP-UX (64-bit):

```
/hpia64/RMP_Suite/setuphpia64.bin -f responseFileName  
-i silent -DAGREE_TO_SYBASE_LICENSE=true
```

- On Linux on POWER (64-bit):

```
/ibmplinux64/RMP_Suite/setuplinuxppc64.bin -f  
responseFileName -i silent -DAGREE_TO_SYBASE_LICENSE=true
```

- On Linux x86-64 (64-bit):

```
/linuxamd64/RMP_Suite/setuplinux64.bin -f responseFileName  
-i silent -DAGREE_TO_SYBASE_LICENSE=true
```

- On Sun Solaris 10 SPARC (64-bit):

```
/sunsparc64/RMP_Suite/setupSolarisSparc.bin -f  
responseFileName -i silent -DAGREE_TO_SYBASE_LICENSE=true
```

- On Sun Solaris 10 x64 (64-bit):

```
/sunx64/RMP_Suite/setupSolarisx86.bin -f responseFileName  
-i silent -DAGREE_TO_SYBASE_LICENSE=true
```

where:

- *responseFileName* is the absolute path of the file name containing the installation options you chose.
- The **-D** option specifies that you agree with the Sybase License Agreement text.

Note: You must agree to the Sybase License Agreement when installing in silent mode. You can either:

- Include the option `-DAGREE_TO_SYBASE_LICENSE=true` in the command line argument, or,
 - Edit the response file to include the property `AGREE_TO_SYBASE_LICENSE=true`.
-

Except for the absence of the GUI screens, all actions of the installer are the same, and the result of an installation in silent mode is exactly the same as one performed in GUI mode with the same responses.

See also

- *Command Line Options* on page 32
- *Creating a Response File* on page 44

Uninstalling Replication Manager

Uninstall the product.

Prerequisites

- Log in to your machine using an account with administrator privileges.
- Shut down all Sybase applications and processes.

Note: The uninstaller removes only those files that were loaded from the installation media in the uninstallation process. Some Sybase files, such as log and configuration files, are left intact for administrative purposes.

Task

1. Choose an uninstallation method:
 - GUI wizard (recommended)
 - Console mode
2. Follow the instructions for your chosen method.

Uninstalling with the GUI Wizard

Uninstall Replication Manager in GUI mode.

1. Enter:

```
$SYBASE/sybuninstall/ReplicationManager/uninstall
```

2. In the Introduction window, click **Next**.

3. The uninstallation summary window shows where you have installed Replication Manager. Click **Next**.
4. When the Uninstall Complete window appears, click **Done**.

Note: You may be prompted to decide whether to remove files that are created outside the installer. Sybase recommends that you do not remove these files.

5. If you are uninstalling the Replication Manager plug-in from Sybase Central, Java Edition, and you have previously installed both the Replication Manager plug-in and the Adaptive Server plug-in to Sybase Central, Java Edition, unregister the Replication Manager plug-in inside Sybase Central.

See the Replication Manager plug-in online help.

Uninstalling in Console Mode

Uninstall Replication Manager in console mode.

1. At the command prompt, navigate to the installation directory and enter:

```
$SYBASE/sybuninstall/ReplicationManager/uninstall -i  
console
```

The **uninstall** program starts.

2. The flow of the **uninstall** program is identical to a regular GUI uninstallation, except output is written to a terminal window and responses are entered using the keyboard. Follow the remaining prompts to uninstall Replication Manager.

Note: You may be prompted to decide whether to remove files that are created outside the installer. Sybase recommends that you do not remove these files.

3. If you are uninstalling the Replication Manager plug-in from Sybase Central, Java Edition, and you have previously installed both the Replication Manager plug-in and the Adaptive Server plug-in to Sybase Central, Java Edition, unregister the Replication Manager plug-in inside Sybase Central.

See the Replication Manager plug-in online help.

See also

- *Command Line Options* on page 32
- *Uninstalling with the GUI Wizard* on page 46

Obtaining Help and Additional Information

Use the Sybase Getting Started CD, Product Documentation site, and online help to learn more about this product release.

- The Getting Started CD (or download) – contains release bulletins and installation guides in PDF format, and may contain other documents or updated information.
- Product Documentation at <http://sybooks.sybase.com/> – is an online version of Sybase documentation that you can access using a standard Web browser. You can browse documents online, or download them as PDFs. In addition to product documentation, the Web site also has links to EBFs/Maintenance, Technical Documents, Case Management, Solved Cases, Community Forums/Newsgroups, and other resources.
- Online help in the product, if available.

To read or print PDF documents, you need Adobe Acrobat Reader, which is available as a free download from the *Adobe* Web site.

Note: A more recent release bulletin, with critical product or document information added after the product release, may be available from the Product Documentation Web site.

Technical Support

Get support for Sybase products.

If your organization has purchased a support contract for this product, then one or more of your colleagues is designated as an authorized support contact. If you have any questions, or if you need assistance during the installation process, ask a designated person to contact Sybase Technical Support or the Sybase subsidiary in your area.

Downloading Sybase EBFs and Maintenance Reports

Get EBFs and maintenance reports from the Sybase Web site.

1. Point your Web browser to <http://www.sybase.com/support>.
2. From the menu bar or the slide-out menu, under **Support**, choose **EBFs/Maintenance**.
3. If prompted, enter your MySybase user name and password.
4. (Optional) Select a filter from the **Display** drop-down list, select a time frame, and click **Go**.
5. Select a product.

Padlock icons indicate that you do not have download authorization for certain EBF/Maintenance releases because you are not registered as an authorized support contact. If

Obtaining Help and Additional Information

you have not registered, but have valid information provided by your Sybase representative or through your support contract, click **My Account** to add the “Technical Support Contact” role to your MySybase profile.

6. Click the **Info** icon to display the EBF/Maintenance report, or click the product description to download the software.

Sybase Product and Component Certifications

Certification reports verify Sybase product performance on a particular platform.

To find the latest information about certifications:

- For partner product certifications, go to http://www.sybase.com/detail_list?id=9784
- For platform certifications, go to <http://certification.sybase.com/ucr/search.do>

Creating a MySybase Profile

MySybase is a free service that allows you to create a personalized view of Sybase Web pages.

1. Go to <http://www.sybase.com/mysybase>.
2. Click **Register Now**.

Accessibility Features

Accessibility ensures access to electronic information for all users, including those with disabilities.

Documentation for Sybase products is available in an HTML version that is designed for accessibility.

Vision impaired users can navigate through the online document with an adaptive technology such as a screen reader, or view it with a screen enlarger.

Sybase HTML documentation has been tested for compliance with accessibility requirements of Section 508 of the U.S Rehabilitation Act. Documents that comply with Section 508 generally also meet non-U.S. accessibility guidelines, such as the World Wide Web Consortium (W3C) guidelines for Web sites.

Note: You may need to configure your accessibility tool for optimal use. Some screen readers pronounce text based on its case; for example, they pronounce ALL UPPERCASE TEXT as initials, and MixedCase Text as words. You might find it helpful to configure your tool to announce syntax conventions. Consult the documentation for your tool.

For information about how Sybase supports accessibility, see the Sybase Accessibility site: <http://www.sybase.com/products/accessibility>. The site includes links to information about Section 508 and W3C standards.

You may find additional information about accessibility features in the product documentation.

Index

A

- accounts, creating sybase user 24
- Adaptive Server
 - for the Replication Server System Database 33
 - upgrading 33
- administration tasks 23

C

- charsets subdirectory 21
- checking for a valid installation
 - in Replication Manager 42
 - in Replication Server 26
- collate subdirectory 21
- command line installation
 - Replication Manager 44
 - Replication Server 30
- commands
 - source 35
- components of Replication Server 7
- config subdirectory 21
- console mode
 - installing Replication Manager 43
 - installing Replication Server 29
 - response file, installing Replication Server with 30
 - troubleshooting 32
 - uninstalling Replication Manager 47
 - uninstalling Replication Server 40
- conventions
 - style 1
 - syntax 1
- creating
 - response files for Replication Manager 44
 - response files for Replication Server 30
 - sybase user accounts 24
- custom installation 22, 26

D

- D flag and setup
 - Replication Manager 45
 - Replication Server 31

- default directory 26
- definitions
 - runserver 37
- diagnosing software problems 20
- directories
 - default 26, 42
 - installation, structure of 20
 - Sybase_Install_Registry 26
- disk storage requirements 17
- dscp utility 35
- dsedit utility 35

E

- Embedded Replication Server System Database (ERSSD) 7, 17
- environment variables
 - \$LD_LIBRARY_PATH 35
 - \$LD_LIBRARY_PATH_64 35
 - \$LIBPATH 35
 - \$PATH 35
 - \$SCC_JAVA_HOME 35
 - \$SHLIB_PATH 35
 - \$SYBASE 35
 - \$SYBASE_JRE6 35
 - \$SYBASE_JRE6_32 35
 - \$SYBASE_JRE6_64 35
 - \$SYBASE_OCS 35
 - \$SYBASE_REP 35
 - required for dsedit 35
 - setting 35
 - SYBASE_SAM_CAPACITY 16
 - table of 35
- errors
 - while starting installer 26
- existing installation directories 42

F

- files
 - installation log, Replication Manager 42
 - installation log, Replication Server 26, 32
 - log.txt 21, 32
 - runserver 37
 - si_reg.xml 26, 42

Index

- SYBASE.csh 21, 35
- SYBASE.env 21, 35
- SYBASE.sh 21, 35
- full installation 22, 26

G

- graphical user interface (GUI) installation 23
- GUI mode
 - installing Replication Manager 42
 - installing Replication Server 26
 - uninstalling Replication Manager 46
 - uninstalling Replication Server 39
- gzip utility, for HP 17

I

- installation
 - GUI mode 26
 - log file, Replication Server 32
 - methods, Replication Manager 41
 - overview 5
 - plan 9
 - Replication Server CD or DVD, mounting 25
 - troubleshooting during silent or console mode 32
 - typical software components 26
- installation directories
 - contents 21
 - existing 42
 - new 42
- installer
 - custom installation 22, 26
 - errors in starting 26
 - full 22
 - full installation 26
 - standard installation, typical 22
 - typical installation 26
- installing
 - Adaptive Server for the Replication Server System Database 33
 - Replication Manager 41
 - Replication Manager, using -D flag 45
 - Replication Server Data Assurance (DA) Option 29
 - Replication Server, using -D flag 31
- interactive mode
 - response file, installing Replication Server with 23

- interfaces subdirectory 21

J

- jre subdirectory 21

L

- \$LD_LIBRARY_PATH 35
- \$LD_LIBRARY_PATH_64 35
- \$LIBPATH 35
- libraries
 - SMP runtime 17
- license agreement 42
- licenses
 - check number of processors 12
 - license model 10
 - obtaining 10
 - sub-capacity 15, 16
 - Sybase Control Center 14
 - Sybase IQ InfoPrimer integration 15
 - types of 12, 15
- log files, reviewing after installation 33
- log.txt file 21, 32

M

- methods of installation
 - Replication Manager 41
 - Replication Server 25
- mixed-version requirements 9
- modifying
 - remove si_reg.xml file 21
- mount commands by platform 25
- mounting the Replication Server installation media 25

N

- new installation directories 42

O

- obtaining licenses 10
- OCS-15_0 subdirectory 21
- operating system
 - patch requirements 19
 - requirements 17

- overview
 - installation 5
 - SySAM licensing 10
 - SySAM sub-capacity licensing 10
- P**
- \$PATH 35
- planning replication system 5
- platform
 - mount commands 25
- postinstallation tasks
 - Replication Manager 42
 - Replication Server 33
- preinstallation tasks 9
- product editions, types of 12
- programs
 - repsrvr.diag 20
- R**
- release bulletin 9
- REP-15_5 subdirectory 21
- Replication Manager
 - in command line mode 43, 44
 - in console mode 43
 - in GUI mode 42
 - in silent mode 45
 - overview 41
 - uninstalling, prerequisites 46
 - with response files 44
- Replication Monitoring Services (RMS) 41
- Replication Server
 - components 7
 - details 7
 - in console mode 23, 29
 - in GUI mode 23, 26
 - in silent mode 23, 31
 - installing in command line mode 23, 30
 - installing in silent mode, unattended 30
 - licenses 10
 - uninstalling, prerequisites 39
 - with response files 23
- Replication Server Configuration Guide for UNIX
 - 5
- repsrvr.diag program 20
- requirements
 - disk storage 17
 - operating system 17

- operating system patches 19
- response files
 - installing command line mode 23
 - installing with, Replication Server 23
 - Replication Manager, creating for 44
 - Replication Server, creating for 30
- reviewing log files after installing 33
- rs_init utility 34
- runtime libraries 17
- S**
- SCC-3_2 subdirectory 21
- setting environment variables 35
- shared subdirectory 21
- \$SHLIB_PATH 35
- si_reg.xml file 21
- silent mode
 - uninstalling Replication Server 40
- silent mode installations
 - Replication Manager 45
 - Replication Server 23, 31
 - response file, installing Replication Manager with 45
 - response file, installing Replication Server with 31
 - troubleshooting 32
- software, diagnosing problems 20
- source command 35
- standard installation 22, 26
- starting
 - the sample Replication Server 34
- subdirectories
 - charsets 21
 - config 21
 - interfaces 21
 - jre 21
 - OCS-15_0 21
 - REP-15_5 21
 - SCC-3_2 21
 - Shared 21
 - Sybase_Install_Registry 21
 - sybuninstall 21
 - SYSAM-2_0 21
- supported protocols 17
- Sybase Control Center (SCC) 21
- \$SYBASE environment variable 35
- Sybase installation directories
 - contents 21
- Sybase IQ InfoPrimer 15

Index

- sybase user 23
 - creating accounts 24
- Sybase_Install_Registry subdirectory 21
- \$SYBASE_JRE6_64 environment variable 35
- \$SYBASE_JRE6_32 environment variable 35
- \$SYBASE_JRE6 environment variable 35
- \$SYBASE_OCS environment variable 35
- \$SYBASE_REP environment variable 35
- SYBASE_SAM_CAPACITY 16
- \$SCC_JAVA_HOME environment variable 35
- SYBASE.csh file 21, 35
- SYBASE.env file 21, 35
- SYBASE.sh file 21, 35
- sybuninstall subdirectory 21
- SySAM
 - configure IPv6 12
 - FLEXnet Publisher 11
 - license checkout 12
 - license server version 11
 - sub-capacity licensing 11, 15
- SySAM license model 10
- SySAM license server 11
- SySAM sub-capacity 15
 - requirements 16
- SYSAM-2_0 subdirectory 21
- sysamcap utility 10
- system patches
 - listing currently installed 19
- system requirements 17

T

- tables
 - system requirements 17

- tasks, administration 23
- troubleshooting
 - during console or silent mode installation 32
- types of installations
 - custom 22, 26
 - full 22, 26
 - standard 26
 - typical 22, 26
- typical installation 22, 26

U

- uninstalling
 - in console mode, Replication Manager 47
 - in console mode, Replication Server 40
 - in GUI mode, Replication Manager 46
 - in GUI mode, Replication Server 39
 - in silent mode, Replication Server 40
- upgrading
 - Adaptive Server Enterprise 33
 - mixed-version environments 9
- utilities
 - dscp 35
 - dsedit 35
 - gzip 17
 - rs_init 34
 - sysamcap 10, 16

V

- version restrictions, when upgrading 9