

SYBASE®

Installation Guide

Replication Server®

15.5

[Windows]

DOCUMENT ID: DC32236-01-1550-01

LAST REVISED: March 2010

Copyright © 2010 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

To order additional documents, U.S. and Canadian customers should call Customer Fulfillment at (800) 685-8225, fax (617) 229-9845.

Customers in other countries with a U.S. license agreement may contact Customer Fulfillment via the above fax number. All other international customers should contact their Sybase subsidiary or local distributor. Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase trademarks can be viewed at the Sybase trademarks page at <http://www.sybase.com/detail?id=1011207>. Sybase and the marks listed are trademarks of Sybase, Inc. ® indicates registration in the United States of America.

Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

All other company and product names mentioned may be trademarks of the respective companies with which they are associated.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568.

Contents

About This Book	v	
CHAPTER 1	Before You Begin	1
	Introduction	1
	Replication Server components	1
	Installation task overview	2
	Preinstallation tasks	2
	Reading the release bulletin	2
	Planning your replication system.....	2
	Obtaining a license.....	3
	Reviewing system requirements	6
	Understanding the installation directory structure	8
	Determining the installation type	11
	Determining the installation mode	11
	Using dsedit utility to update sql.ini file.....	12
	Performing administrative tasks	12
CHAPTER 2	Installing Replication Server	13
	Installing Replication Server.....	13
	Installing Replication Server in GUI mode.....	13
	Installing Replication Server in console mode.....	17
	Installing Replication Server using a response file.....	17
	Checking for a valid installation.....	19
	Troubleshooting installation problems.....	19
	Command line options	20
CHAPTER 3	Postinstallation Tasks	21
	Review the log files	21
	Start Adaptive Server for the RSSD.....	22
	Configure and start the sample Replication Server.....	22
	Set environment variables.....	23
	Start Replication Server	24
	Create a .bat file for Replication Server start-up	24

	Start Replication Server automatically	25
CHAPTER 4	Uninstalling Replication Server.....	27
	Uninstallation procedures.....	27
CHAPTER 5	Installing and Uninstalling Replication Manager	31
	Overview	31
	Installing Replication Manager	32
	Installing Replication Manager in GUI mode	32
	Installing Replication Manager in console mode	34
	Installing using a response file	34
	Checking for a valid installation.....	36
	Uninstalling Replication Manager.....	37
Index		39

About This Book

Audience

This book is for system administrators and other qualified installers who are familiar with their system's environment, networks, disk resources, and media devices.

How to use this book

Before you install Replication Server®, read Chapter 1, “Preparing to Install and Configure Replication Server” in the *Replication Server Configuration Guide for Windows* to help you plan your installation. However, the step is unnecessary if you plan to install a sample Replication Server.

This guide contains these chapters:

- Chapter 1, “Before You Begin,” describes Replication Server pre-installation information and tasks.
- Chapter 2, “Installing Replication Server,” describes how to install Replication Server.
- Chapter 3, “Postinstallation Tasks,” provides information about the tasks you must perform after installing Replication Server.
- Chapter 4, “Uninstalling Replication Server,” describes how to uninstall Replication Server.
- Chapter 5, “Installing and Uninstalling Replication Manager,” describes how to install and uninstall the Replication Manager.

Related documents

The Sybase® Replication Server documentation set consists of:

- The release bulletin for your platform – contains last-minute information that was too late to be included in the books.

A more recent version of the release bulletin may be available on the World Wide Web. To check for critical product or document information that was added after the release of the product CD, use the Sybase Product Manuals at <http://www.sybase.com/support/manuals/>.

- *Installation Guide* for your platform (this book) – describes installation procedures for all Replication Server and related products.

-
- *Configuration Guide* for your platform – describes configuration procedures for all Replication Server and related products.
 - *Getting Started with Replication Server* – provides step-by-step instructions for installing and setting up a simple replication system.
 - *ASE-to-ASE Replication Quick Start Guide* – provides information for Adaptive Server® users who want to set up a Replication Server to replicate data from one Adaptive Server database to another.
 - *New Features Guide* – describes the new features in Replication Server.
 - *Administration Guide* – contains an introduction to replication systems. This manual includes information and guidelines for creating and managing a replication system, setting up security, recovering from system failures, and improving performance.
 - *Design Guide* – contains information about designing a replication system and integrating heterogeneous data servers into a replication system.
 - *Heterogeneous Replication Guide* and the Replication Server Options documentation set – describes how to use Replication Server to replicate data between databases supplied by different vendors.
 - *Reference Manual* – contains the syntax and detailed descriptions of Replication Server commands in the Replication Command Language (RCL); Replication Server system functions; Sybase Adaptive Server commands, system procedures, and stored procedures used with Replication Server; Replication Server executable programs; and Replication Server system tables.
 - *System Tables Diagram* – illustrates system tables and their entity relationships in a poster format. Available only in print version.
 - *Troubleshooting Guide* – contains information to aid in diagnosing and correcting problems in the replication system.
 - Replication Manager plug-in help, which contains information about using Sybase Central™ to manage Replication Server.
 - *Sybase Software Asset Management Users Guide* – this manual introduces you to Sybase asset management concepts and provides instructions for establishing and managing your license files.
 - *FLEXnet Licensing End User Guide* – this Macrovision manual explains FLEXnet Licensing for administrators and end users and describes how to use the tools which are part of the standard FLEXnet Licensing distribution kit from Sybase.

Other sources of information

Use the Sybase Getting Started CD and the Sybase Product Manuals Web site to learn more about your product:

- The Getting Started CD is included with your software and contains release bulletins, installation guides in PDF format, and other documents or updated information. To read or print documents on the Getting Started CD, you need Adobe Acrobat Reader, which you can download at no charge from the Adobe Web site using a link provided on the CD.

You can also access the documents available on the Getting Started CD from the Sybase Product Manuals Web site.

- The Sybase Product Manuals Web site, which can be accessed using a standard Web browser, includes the Replication Server documents that are not included in the Getting Started CD. In addition to product manuals, you will find links to EBFs/Maintenance, Technical Documents, Case Management, Solved Cases, newsgroups, and the Sybase Developer Network.

To access the Sybase Product Manuals Web site, go to Product Manuals at <http://www.sybase.com/support/manuals/>.

Sybase certifications on the Web

Technical documentation at the Sybase Web site is updated frequently.

❖ Finding the latest information on product certifications

- 1 Point your Web browser to Technical Documents at <http://www.sybase.com/support/techdocs/>.
- 2 Click Partner Certification Report.
- 3 In the Partner Certification Report filter select a product, platform, and timeframe and then click Go.
- 4 Click a Partner Certification Report title to display the report.

❖ Finding the latest information on component certifications

- 1 Point your Web browser to Availability and Certification Reports at <http://certification.sybase.com/>.
- 2 Either select the product family and product under Search by Base Product; or select the platform and product under Search by Platform.
- 3 Select Search to display the availability and certification report for the selection.

❖ **Creating a personalized view of the Sybase Web site (including support pages)**

Set up a MySybase profile. MySybase is a free service that allows you to create a personalized view of Sybase Web pages.

- 1 Point your Web browser to Technical Documents at <http://www.sybase.com/support/techdocs/>.
- 2 Click MySybase and create a MySybase profile.

Sybase EBFs and software maintenance

❖ **Finding the latest information on EBFs and software maintenance**

- 1 Point your Web browser to the Sybase Support Page at <http://www.sybase.com/support>.
- 2 Select EBFs/Maintenance. If prompted, enter your MySybase user name and password.
- 3 Select a product.
- 4 Specify a time frame and click Go. A list of EBF/Maintenance releases is displayed.

Padlock icons indicate that you do not have download authorization for certain EBF/Maintenance releases because you are not registered as a Technical Support Contact. If you have not registered, but have valid information provided by your Sybase representative or through your support contract, click Edit Roles to add the “Technical Support Contact” role to your MySybase profile.

- 5 Click the Info icon to display the EBF/Maintenance report, or click the product description to download the software.

Conventions

This section describes the stylistic and syntactic conventions used in this book.

Style conventions Syntax statements (displaying the syntax and options for a command) are printed as follows:

```
alter user user
set password new_passwd
[verify password old_passwd]
```

Examples that show the use of Replication Server commands are printed as follows:

```
alter user louise
set password hFE5t
verify password hFE5t
```


Command names, command option names, program names, program flags, keywords, configuration parameters, functions, and stored procedures are printed as follows:

- Use `alter user` to change the password for a login name.
- Variables, parameters to functions and stored procedures, and user-supplied words are in italics in syntax and in paragraph text, as follows:
The `set password` *new_passwd* clause specifies a new password.
- Names of database objects, such as databases, tables, columns, and datatypes, are in italics in paragraph text, as follows:
The `base_price` column in the `Items` table is a money datatype.
- Names of replication objects, such as function-string classes, error classes, replication definitions, and subscriptions, are in italics.

Syntax conventions Syntax formatting conventions are summarized in Table 1. Examples combining these elements follow.

Table 1: Syntax formatting conventions

Key	Definition
<i>variable</i>	Variables (words standing for values that you fill in) are in italics.
{ }	Curly braces mean you must choose at least one of the enclosed options. Do not include braces in the command.
[]	Brackets mean you may choose or omit enclosed options. Do not include brackets in the command.
	Vertical bars mean you may choose no more than one option (enclosed in braces or brackets).
,	Commas mean you may choose as many options as you need (enclosed in braces or brackets). Separate your choices with commas, to be typed as part of the command. Commas may also be required in other syntax contexts.
()	Parentheses are to be typed as part of the command.
...	An ellipsis (three dots) means you may repeat the last unit as many times as you need. Do not include ellipses in the command.

Obligatory choices

- Curly braces and vertical bars – choose only one option.
`{red | yellow | blue}`
- Curly braces and commas – choose one or more options. If you choose more than one, separate your choices with commas.

```
{cash, check, credit}
```

Optional choices

- One item in square brackets – choose it or omit it.

```
[anchovies]
```

- Square brackets and vertical bars – choose none or only one.

```
[beans | rice | sweet_potatoes]
```

- Square brackets and commas – choose none, one, or more options. If you choose more than one, separate your choices with commas.

```
[extra_cheese, avocados, sour_cream]
```

Repeating elements An ellipsis (...) means that you may repeat the last unit as many times as you need. For the alter function replication definition command, for example, you can list one or more parameters and their datatypes for either the add clause or the add searchable parameters clause:

```
alter function replication definition function_rep_def
{deliver as 'proc_name' |
  add @parameter datatype[, @parameter
  datatype]... |
  add searchable parameters @parameter
  [, @parameter]... |
  send standby {all | replication definition}
  parameters}
```

Accessibility features

This document is available in an HTML version that is specialized for accessibility. You can navigate the HTML with an adaptive technology such as a screen reader, or view it with a screen enlarger.

Replication Server HTML documentation has been tested for compliance with U.S. government Section 508 Accessibility requirements. Documents that comply with Section 508 generally also meet non-U.S. accessibility guidelines, such as the World Wide Web Consortium (W3C) guidelines for Web sites.

Note You might need to configure your accessibility tool for optimal use. Some screen readers pronounce text based on its case; for example, they pronounce ALL UPPERCASE TEXT as initials, and MixedCase Text as words. You might find it helpful to configure your tool to announce syntax conventions. Consult the documentation for your tool.

For information about how Sybase supports accessibility, see Sybase Accessibility at <http://www.sybase.com/accessibility>. The Sybase Accessibility site includes links to information on Section 508 and W3C standards.

If you need help

Each Sybase installation that has purchased a support contract has one or more designated people who are authorized to contact Sybase Technical Support. If you cannot resolve a problem using the manuals or online help, please have the designated person contact Sybase Technical Support or the Sybase subsidiary in your area.



Before You Begin

This chapter provides information about system and licensing requirements for installing Replication Server. It also discusses other preinstallation tasks you must complete before you install Replication Server.

Topic	Page
Introduction	1
Preinstallation tasks	2

Introduction

This section describes the components of Replication Server and provides an overview of the tasks involved in installing and setting up Replication Server.

Replication Server components

Replication Server consists of:

- Replication Server
- Replication Server support files (for example, scripts and configuration files)
- SQL Anywhere® for Embedded Replication Server System Database (ERSSD)
- RepAgent for ERSSD
- Replication Monitoring Services (RMS)

Installation task overview

The *Replication Server Installation Guide for Windows* explains how to unload the Replication Server software from the distribution media to your hard disk.

The *Replication Server Configuration Guide for Windows* explains how to:

- Gather the information you need to prepare your system for the installation
- Install Replication Servers and add databases to your replication system
- Upgrade existing Replication Server System Databases (RSSDs)
- Downgrade existing RSSDs and then reinstall an earlier version of the software
- Enable password encryption for a Replication Server or RepAgent
- Start and stop Replication Server or RepAgent

Preinstallation tasks

Before you install Replication Server, follow the steps outlined in this section.

Reading the release bulletin

The release bulletin contains last-minute information about installing and upgrading Replication Server software.

The latest release bulletins are available at the Product Manuals Web page at <http://www.sybase.com/support/manuals>.

Planning your replication system

The *Replication Server Configuration Guide for Windows* provides the necessary information, including an installation worksheet and a database setup worksheet to help you plan your replication system. Become familiar with Chapter 1, “Preparing to Install and Configure Replication Server” and the requirements of your replication system before continuing with the installation.

Upgrading and mixed-version requirements

If a replication system domain has Replication Server 15.5 and later, then the system version and route versions in the replication system domain must be version 12.6 and later. With Replication Server 15.5, mixed-version environments containing versions earlier than 12.6 are not supported.

You can upgrade directly to Replication Server 15.5 from versions 12.6, 15.0, 15.0.1, and 15.2 and subsequent ESDs.

If the Replication Server version, the site version, and the route version are earlier than 12.6, you must upgrade Replication Server to version 12.6 or later, set site version to 12.6 or later, and upgrade routes to 12.6 or later, before you can install Replication Server 15.5.

You must upgrade the Adaptive Server containing the RSSD to version 15.0 or later, before you can install Replication Server 15.5.

Note Upgrading from any earlier version requires an intermediate upgrade. See Chapter 3, “Upgrading or Downgrading Replication Server” in the *Replication Server Configuration Guide* for your platform.

Obtaining a license

Replication Server works for a 30-day grace period without a license. You can use the Sybase Software Asset Management (SySAM) system that comes with Replication Server to register your Replication Server product.

Before you begin the installation, get your license files from the Sybase Product Download Center (SPDC) at <https://sybase.subscribenet.com>, to which you are automatically enrolled in when you purchase a Sybase product. Log in to SPDC by using the information in your SPDC welcome e-mail.

Note If you have purchased your Sybase software from a Sybase reseller, you will receive a Web key rather than an e-mail message.

For information about SySAM 2, see the *Sybase Software Asset Management Users Guide*.

Product edition license

Replication Server 15.5 is released as two product editions that contain different base and optional features that require separate licenses:

- Enterprise Edition
- Real-time Loading Edition

Table 1-1 describes the base and optional features in each edition and lists the license names for each feature.

Note You cannot use the “Replication Server – Real-Time Loading Edition” to replicate to Adaptive Server.

Table 1-1: Replication Server product edition features and licenses

Edition	Feature type	Features	Description	License
Enterprise	Base	Replication Server		REP_SERVER
	Optional	Advanced Services Option	Replication Server performance enhancements.	REP_HVAR_ASE
		ExpressConnect for Oracle	Provides Replication Server with the capability to connect directly to Oracle. See the Replication Server Options 15.5 documentation.	REP_EC_ORA
Real-Time Loading Edition	Base	Replication Server		REP_SERVER
		Real-time Loading (RTL).	Allows replication to Sybase® IQ.	REP_RTL_IQ
		Advanced Services Option	Replication Server performance enhancements.	REP_HVAR_ASE
	Optional	None		

Installing SySAM

Before you install Replication Server, you must plan the type of SySAM license configuration you want to use. Depending on your configuration choice, you may also need to perform additional preinstallation tasks before installing Replication Server.

SySAM allows you to acquire a license using a local file or you can acquire a license from a network license server. For more information about SySAM licensing concepts and choosing a license model, see the *Sybase Software Asset Management Users Guide*.

Note There can only be one instance of a SySAM license server running on a machine. To set up a SySAM 2 license server on a machine that is already running SySAM 1, migrate the SySAM 1 license to SySAM 2. A migrated license server can serve licenses for products that are licensed under both SySAM 1 and SySAM 2.

For instructions on migrating a license server, see the *Sybase Software Asset Management Users Guide*.

Replication Server 15.5 is linked with FLEXnet Publisher version 11.6.1 for Windows 32-bit and 11.5 for Windows 64-bit. If you use a SySAM license server, you must update the license server to at least this version of FLEXnet Publisher before installing Replication Server 15.5. To check the version of your license server, examine the license server log or executing the following command:

```
cd %SYBASE%\SYSAM-2_0\bin
lmutil lmver lmgrd
```

Configuring SySAM for IPv6

Replication Server includes IPv4 and IPv6 versions of the SySAM license server software. You can choose the version of the license server based on your environment using the `sysam configure` command. By default, the installer configures SySAM for IPv4 support.

The IPv4 version of the license server cannot be used properly if you have enabled IPv6 on the license server host. If this is the case you can:

- Disable IPv6 TCP/IP protocol on the license server host.
- Use another Windows host that does not have IPv6 enabled.
- Use a UNIX host for the license server. You can use the IPv4 version of the license even if both IPv4 and IPv6 are enabled on UNIX.

If you are using the IPv6 version of the license server on a Windows host, then this license server can be accessed only through IPv6 protocol. Any host with an IPv4 only network stack will not be able to obtain licenses from this IPv6 license server. To resolve this issue:

- Use a UNIX host for the license server. License servers on UNIX are able to serve licenses to both IPv4 and IPv6 client hosts.
- If you need to use a Windows host for the license server and have both IPv4 and IPv6 clients to the license server, setup two license servers one serving the IPv4 network and the other serving the IPv6 network.

You can use the SysSAM script to configure the appropriate version of the license server:

```
sysam configure [IPv6|IPv4]
```

For example, this command configures use of the IPv4/IPv6 dual stack binaries:

```
sysam configure IPv6
```

Reviewing system requirements

Replication Server requires a computer with the system configuration described in Table 1-2.

Table 1-2: System requirements for Windows

Item	Requirement
CPU	A Pentium processor.
RAM	A minimum of 512MB RAM.
Disk storage	<p>A minimum of 580MB of available hard disk space:</p> <ul style="list-style-type: none"> • 450MB for the Replication Server software, supporting files, and log files. • 20MB for each Replication Server disk partition. The disk partition may be on a different disk than your Sybase software. • 30MB for temporary usage during installation. <p>One of the following:</p> <ul style="list-style-type: none"> • Disk space for your Adaptive Server® Enterprise database, which serves as your Replication Server System Database (RSSD) if you are not using the Embedded RSSD (ERSSD). See your Adaptive Server Enterprise documentation for system requirements. • 80MB for your SQL Anywhere database, which serves as your ERSSD. The database directory, transaction log directory, and backup directory that make up the 80MB should each reside on different disks. <p>More disk space may be required, depending on your replication system application.</p>

Item	Requirement
Operating system	<p>One of the following:</p> <ul style="list-style-type: none"> • Windows XP Professional, Service Pack 2 or later • Windows 2003, Service Pack 2 or later • Windows Vista Enterprise, Service Pack 1 • Windows Vista Business, Service Pack 1 • Windows Server 2008 R2 • Windows 7 <p>You must install the relevant Microsoft Visual Studio 2005 patch for your x86 or x64 Windows platform before you start Replication Server. See Microsoft Visual C++ 2005 Service Pack 1 Redistributable Package ATL Security Update at http://www.microsoft.com/downloads/details.aspx?familyid=766a6af7-ec73-40ff-b072-9112bab119c2&displaylang=en.</p>
Additional hardware	A minimum of 32-bit network card for better performance.
Supported protocols	TCP/IP, IPX/SPX, Microsoft Named Pipes.

Review operating system patch requirements

On Windows If your operating system requires a service pack, install it before you install Replication Server. Contact your operating system representative for a complete list of service packs, or check the latest Replication Server release bulletin for your platform. First, you must determine which service pack operating system level and build number are installed on the system.

Note Do not use a service pack that is earlier than the version suggested for your operating system. If a service pack has been superseded by a newer service pack, use the newer service pack.

❖ Determining service pack operating system level and build number

- 1 Select Start | Programs | Accessories | Windows Explorer.
- 2 Select the Help menu, and click About Windows.
- 3 Find the Service Pack number on the Version line.

In the following example, *xxxx* is the build number and *n* is the service pack number:

```
Version 5.0 (Build xxxx: Service Pack n)
```

Understanding the installation directory structure

Most components of Replication Server are installed in their own subdirectories, with the executable program, installation and configuration tools, and display-related files needed by the component. The naming convention for subdirectories includes a component identifier, such as REP (for Replication Server) or OCS (for Open Client™ and Open Server™), and the software release version, such as 15_5.

Replication Server 15.5 includes a new version of Replication Server and many of its supporting components. Other Sybase products may contain earlier versions of the same components. Installing Replication Server 15.5 into the same directory containing these existing products, will not impact the products.

However, if you are using other Sybase products, installing Replication Server 15.5 may cause some environment variables to change. You will have to reset the environment variables in order to make the individual products work.

Note Replication Server 15.5 can be installed in the same directory as Adaptive Server Enterprise and Open Client and Open Server versions 12.5.1 or later.

However, if you have installed Replication Server 15.5 and other Sybase products versions earlier than 15.5 in the same directory, Sybase recommends that you do not uninstall any of these products from this common directory. Otherwise, these products can no longer be used after uninstallation.

You can install Replication Server 15.5 on top of Replication Server 12.6 and later, in the same `%SYBASE%` directory. Installing 15.5 on top of Replication Server 12.6 and later versions will create a duplicate entry in the `sql.ini` file for `SAMPLE_RS`, which is the sample Replication Server. `rs_init` will warn you about the duplicate entry and will use the first instance of `SAMPLE_RS` found in the `sql.ini` file.

Constraints

Do not install Replication Server version 15.5 on top of these Sybase products:

- Replication Server version 12.5 or earlier
- Adaptive Server version 12.5.0.x or earlier
- Adaptive Server version 12.x (64-bit)
- Open Client and Open Server version 12.5.0 or earlier
- OpenSwitch™ version 12.5 or earlier
- DirectConnect™ version 12.5 or earlier

Doing so incapacitates older versions of these products, and can also adversely affect other Sybase products. If you perform one of these installations, you cannot reverse it with an uninstallation, as uninstalling might remove required components of the older Sybase products updated by Replication Server version 15.5. For this reason, Sybase recommends that you back up your current directory before installing Replication Server version 15.5.

Note If you are installing Replication Server 15.5 in an existing Sybase installation directory that contains Adaptive Server version 15.0.x, you may be asked if you wish to install older locales or charset files on top of newer files. To ensure that you have the latest version of these files select “No to all.”

Shared components are installed in subdirectories that are separate from component subdirectories. For example, the Replication Server subdirectory is `%SYBASE%\REP-15_5`. However, Open Client is installed in `%SYBASE%\OCS-15_0`. The exception is SQL Anywhere (SA), which is installed in `%SYBASE%\REP-15_5\ASA11`, because it is used only for Replication Server. As a result, the directory structure enables you to install into an existing `%SYBASE%` directory structure, as well as to install and use multiple versions of some components.

Note If your earlier installation includes custom applications or scripts that refer to `%SYBASE%` subdirectories, change them to reflect the new installation directory structure.

A diagnostic server `REP-15_5\bin\drepsrvr.exe` is installed to capture and display information about internal processes. Do not delete this program as you may need to use it at the direction of Sybase Technical Support, to diagnose and resolve Replication Server problems.

Note The directory structure listed in this section is a partial directory structure. Your actual directory structure may differ, depending on the components you choose to install.

Reviewing the Sybase installation directory contents

The section lists the contents of the Sybase installation directory in alphabetical order.

Installation directory after installing Replication Server

The following items are installed on your machine.

Within %SYBASE%:

- *charsets* – character sets and sort order.
- *collate* – Unicode.
- *ini* – initialization files, including *objectid.dat*, *mnemonic.dat*, *sql.ini*, and *trusted.txt*.
- *jre32* – files used by the installer on the 32-bit platform.
- *jre64* – files used by the installer on the 64-bit platform.
- *locales* – localization files for Open Client and Open Server, and other components used by Replication Server. Does not include Replication Server specific localization files.
- *log* – log files of the installation process.
- *OCS-15_0* – Open Client and Open Server directories and files, including *bin*, *dll*, *include*, *ini*, *lib*, *lib3p*, *sample*, and *scripts*.
- *REP-15_5* – Replication Server 15.5 files, including *ASA11*, *bin*, *certificates*, *devlib* (32-bit platforms), *devlib64* (64-bit platforms), *doc*, *init*, *install*, *lib* (32-bit platforms), *lib64* (64-bit platforms), *lib3p* (32-bit platforms), *lib3p64* (64-bit platforms), *locales*, *REFIMP-01_0*, *samp_repsrver*, *scripts*, *sysam*, *ThirdPartyLegal*, and *upgrade*.
- *Shared* – common components shared across products, including the Java runtime environment and files and directories for Unified Agent Framework 2.5.
- *Sybase_Install_Registry* – used for storing Sybase product registry information to keep track of version of installed and uninstalled software. The *si_reg.xml* file gets installed in the %SYBASE%\Sybase_Install_Registry directory.

Warning! Do not modify or remove *si_reg.xml*. Modifying or removing this file prevents the installer from accurately managing installed component versions when you install or uninstall Sybase software subsequent to this installation.

- *sybuninstall* – files used by the uninstaller to uninstall Replication Server software.

- *SYSAM-2_0* – software license manager files, including *bin*, licenses, and *log*.
- *UAF-2_5* – the Unified Agent Framework files for the Replication Monitoring Services (RMS), including *bin*, *common*, *conf*, *ldap*, *log*, *plugins*, *server*, *services*, *thirdparty*, and *utility*.
- *SYBASE.bat*, *SYBASE.env* – files created by the installer that you use to reset environment variables.

Determining the installation type

The Replication Server setup program provides these installation options:

- Typical (default) – installs the Replication Server components considered to be useful for most customers. In this type of installation, only the U.S. English language module and its supported character sets are installed. The components that will be installed and the total disk space required display prior to installation.
- Full – installs every Replication Server component including all the supported language modules from the installation media. The components that will be installed and the total disk space required display prior to installation.
- Custom – allows you to select the components to install. Recommended for advanced users.

Note Certain components are automatically installed if they are required to run other selected components.

Determining the installation mode

You can install Replication Server using:

- Graphical user interface (GUI) – lets you install the components in an interactive user mode.
- Console – lets you install components in a command line environment.
- Response file – lets you record or create a response file. You can install Replication Server in two different ways using a response file:

- Silent – lets you save the installation settings in a response file and install the product without any interaction required on your part. This is convenient if you are performing identical installations on multiple machines.
- Interactive installation using response file – lets you install interactively but with all the responses already filled in, so that you can accept all the defaults and install Replication Server according to the responses in the response file. This can be convenient if several sites are installing Replication Server in a nongraphical user interface environment and must conform to a standard installation with minor changes.

Using *dsedit* utility to update *sql.ini* file

The Replication Server installation also includes a utility called *dsedit*.

Use *dsedit* utility to update *sql.ini* file

The *dsedit* utility creates and modifies network connection information in the *sql.ini* file. The utility is located in `%SYBASE%\%SYBASE_OCS%\bin`.

Execute *SYBASE.bat* to set the required environment variables before executing *dsedit*.

See “Set environment variables” on page 23 for more information.

For more information about *dsedit*, see the *Adaptive Server Enterprise Utility Guide*.

Performing administrative tasks

This section describes administrative tasks that you must complete before you begin the installation process.

- 1 Back up your current replication system.
- 2 Log in using an account with Windows administrator privileges.
- 3 Close any open applications or utilities, including currently installed Sybase components, to free disk space and system resources.
- 4 Verify that the installation directory does not have a space in the directory name.

Topic	Page
Installing Replication Server	13
Checking for a valid installation	19
Troubleshooting installation problems	19
Command line options	20

Installing Replication Server

You can install Replication Server using either GUI mode, console mode, or silent mode. However, Sybase recommends that you use GUI mode. See “Installing Replication Server in GUI mode.”

Installing Replication Server in GUI mode

Follow the procedure to install Replication Server components in GUI mode.

❖ Installing in GUI mode

- 1 Verify that the drive on which you install the Replication Server has enough disk space for the components being installed, and at least 100MB of extra disk space for the installation program.
- 2 Launch the setup program.

The installer starts automatically.

Note If the installer does not start automatically, double-click *setup.exe* or select Start | Run, and enter the following, where *x*: is your CD drive:

```
x:\setup.exe
```

Installer does not have enough space to run Set the environment variable TMP to *directory_name* before running it again, where *directory_name* is the name of the temporary directory to which the installation program writes the temporary installation files. When specifying the *directory_name*, include its full path.

- 3 In the Introduction window, click Next.
- 4 Indicate where to install Replication Server:
 - To select an installation directory, click Choose. A window appears, and from that window browse for and select the directory.
 - To create a new directory, enter a new directory path.
 - To restore to the default directory if you do not want to use the directory that you have entered, click Restore Default Folder.

One of these occurs:

- If the installation directory you chose does not exist, this message appears:

The directory <*directory_name*> does not exist. Do you want to create it?

Click Yes.

- If the installation directory you selected exists, and contains a prior installation, this message appears:

Warning: You have chosen to install into an existing directory.

If you proceed with this installation, any older versions of the products you choose to install that are detected in this directory will be replaced.

Click Next.

- 5 Select the type of installation:
 - Typical – installs the default components. This is recommended for most users.
 - Full – installs every Replication Server component, including all the supported language modules.
 - Custom – selects the components to install. Some components are automatically installed if they are required to run your selected components.

Click Next.

6 Read the License and Copyright Agreement:

- 1 Select the geographic location from where you are installing to display the agreement for your region.
- 2 Select “I agree to the terms of the Sybase license for the install location specified.” You must agree to the license and copyright agreement before you can continue with the installation.
- 3 Click Next.

7 On the Sybase Software Asset Management License Server window, select one of:

- Specify License Keys – click Browse to select the license file. To select multiple license files, use Shift+Click or Ctrl+Click. The license pane displays the license information.

Alternatively, copy and paste the license information directly in the license pane. Click Next.

If you specify a served license key, the installer prompts you to install a new SySAM license server. Click one of:

- Next – to install the new SySAM license server and follow the installation prompts.
- Previous – and select the “Use previously deployed license server” option if you have an existing SySAM license server on the same host.
- Use Previously Deployed License Server – if you have a previously deployed license server, enter the host name of the machine where the license server is running, and the port number if the port number you are using is not default. Click Next.
- Continue installation without a license key – if you do not have licenses for any of the Replication Server components, you can select this option, and click Next to proceed. The installer allows you to install and use the Replication Server components without a license for a grace period of 30 days. To continue using these components after the end of the grace period, obtain valid licenses from the SPDC, and install these licenses using the Replication Server License Installer.

For more information on SySAM licensing, see the *Sybase Software Asset Management Users Guide*.

- 8 Configuring your server for e-mail notification enables designated users receive information about license management events requiring attention.

Provide the following information:

- SMTP server host name
- SMTP server port number
- E-mail Return Address
- Recipient e-mail addresses
- Message severity that triggers e-mail messages

Click Next.

- 9 The installation summary window displays the selections you have made. Review the information, and click Install.

- 10 On the Start Sample Replication Server window, select:

- Yes – to configure and start a sample Replication Server. The installer displays the configuration information for the sample Replication Server. Write this information down.
- No – to complete the installation and configure a fully-featured Replication Server manually.

If you select No, you can configure and start a sample Replication Server after installation. See “Start Replication Server” on page 24 for more information.

Click Next.

- 11 If you chose to configure and start a sample Replication Server, the installer will proceed with the process to configure and start the sample Replication Server.

Click Next when done.

- 12 If Replication Server is installed successfully, a final window appears, indicating a successful installation. Click Done to exit the installer.

After the successful installation:

- Verify the installation. See “Checking for a valid installation” on page 19.
- Perform the postinstallation tasks. See Chapter 3, “Postinstallation Tasks.”

Installing Replication Server in console mode

To run the installation program without the GUI, launch the installer in console mode. If the installer launches automatically, click Cancel to cancel the GUI installation, then launch the setup program from a terminal or console.

❖ Installing in console mode

The steps for installing components in an interactive text mode are the same as those described in “Installing Replication Server in GUI mode” on page 13, except that you execute the installer from the command line using the `setup -i` console command, and you enter text to select installation options.

- 1 At the command prompt, enter:

```
x:\setupConsole.exe -i console
```

where *x* is the location of the installer.

- 2 The flow of the installation is identical to a GUI installation, except that the display is written to a terminal window and responses are entered using the keyboard. Follow the remaining prompts to install Replication Server.

Installing Replication Server using a response file

To perform a silent, or "unattended" installation, run the installer and provide a response file that contains your preferred installation configuration.

Creating a response file

To create a response file when installing in GUI or console mode, specify the `-r` command line argument. The `-r` argument records your responses to the installation wizard's prompts and creates a response file when the installation wizard exits. The response file is a text file that you can edit to change any responses prior to using it in any subsequent installations.

To generate a response file during installation, on the command line:

```
x:\setupConsole.exe -r responseFileName
```

where *responseFileName* is the file name you choose for the response file and *x* is the location of the installer. When specifying the response file, include its full path. For example:

```
C:\Sybase\REP\ResponseFile.txt
```

Note You must provide the full path name for the response file you create.

Interactive installation using a response file

An interactive installation using a response file lets you either accept the default values supplied by the response file or enter a different value. This is useful when installing multiple instances of Replication Server that have similar but not identical settings.

To run the GUI installation using the response file, enter:

```
x:\setupConsole.exe -f responseFileName
```

where *responseFileName* is the file name containing the installation options you chose and *x* is the location of the installer. When specifying the response file name, include its full path.

Installing in silent mode

A silent or unattended installation does not involve user interaction; and all installation configuration information is taken from the response file. This is useful when you want multiple identical installations or a fully automated.

To install in silent mode, run:

```
x:\setupConsole.exe -f responseFileName -i silent  
-DAGREE_TO_SYBASE_LICENSE=true
```

Where:

- *x* – is the location of the installer.
- *responseFileName* – is the absolute path of the file containing the installation options you chose.

- `-D` option– specifies that you agree with the Sybase License Agreement text.

Warning! When running in silent installation mode, Sybase recommends that you use *setupConsole.exe*. The normal *setup.exe* runs the installation program in the background, and gives the impression that the installation has terminated immediately. This results in additional installation attempts. Multiple installations at the same time can corrupt the Windows Registry and lead to an operating system restart failure.

Except for the absence of the GUI screens, all actions of the installer are the same, and the result of an installation in silent mode is exactly the same as one done in GUI mode with the same responses.

Note You must agree to the Sybase License Agreement when installing in silent mode. You can either:

- Include the option `-DAGREE_TO_SYBASE_LICENSE=true` in the command line argument.
 - Edit the response file to include the property
`AGREE_TO_SYBASE_LICENSE=true`
-

Checking for a valid installation

- 1 View the log files in `%SYBASE%\log` directory to check for errors. A valid installation does not contain the word “error.”
- 2 Check that the date of the *si_reg.xml* file reflects the date of this current installation.

Troubleshooting installation problems

For troubleshooting during installation:

Press the Ctrl key while starting the installer and until a console window appears. The installer will generate additional detailed installation information that is useful for debugging installer issues.

Note If you encountered errors during installation using any installation mode, check the installation log file to see a record of the installation process. The log file is located in `%SYBASE%\log` directory.

If this is the first time you have installed a Sybase product on this machine, the installer creates a Sybase installation directory. This directory contains the support files for all Sybase products.

Command line options

Table 2-1 lists the command line options that you can use when running an installer or uninstaller.

Table 2-1: Command line options

Option	Purpose
-i swing	Uses the GUI mode.
-i console	Uses the console interface mode, where messages during installation are displayed on the Java console and the wizard is run in console mode.
-i silent	Installs or uninstalls the product in silent mode, where the installation or uninstallation is performed with no user interaction and the installation is “silent.”
-D	Passes custom variables and properties. For example, if you want to override the default installation directory when you run the installer, enter: <pre><install_launcher_name> -DUSER_INSTALL_DIR=E:\Sybase</pre>
-r	Generates a response file and a reference.
-f	References response files.
-l	Sets the installer’s locales.
-\?	Displays the installer help.

This chapter describes the postinstallation tasks that you need to perform after installing the Replication Server software.

For more information, see the *Replication Server Configuration Guide for Windows*.

Topic	Page
Review the log files	21
Start Adaptive Server for the RSSD	22
Configure and start the sample Replication Server	22
Set environment variables	23
Start Replication Server	24

Review the log files

Information about the configuration of Replication Server is stored in the following log files:

- Replication Server installer error log file:
`%SYBASE%\log`
- Sample Replication Server error logs:
`%SYBASE%\REP-15_5\SAMPLE_RS.log`
- Sample Replication Server SQL Anywhere error logs:
`%SYBASE%\REP-15_5\samp_repserver\errorlog`
- rs_init log file:
`%SYBASE%\REP-15_5\init\logs\logmdd.xxx`
For example: `%SYBASE%\REP-15_5\init\logs\log1106.001`
- Replication Server log file:
`%SYBASE%\REP-15_5\install\rs_name.log`

For example: `%SYBASE%\REP-15_5\install\REP_redtail.log`

Start Adaptive Server for the RSSD

To use the RSSD stored on Adaptive Server Enterprise, install the Adaptive Server Enterprise database, if you have not done so already. For installation instructions, see the *Adaptive Server Enterprise Installation Guide* for your platform.

After successful installation, start Adaptive Server Enterprise. For more information, see the *Adaptive Server Enterprise Configuration Guide* for your platform.

Note If you are upgrading to a later version of Adaptive Server Enterprise and you have replicated databases, see the *Adaptive Server Enterprise Installation Guide* for your platform.

Configure and start the sample Replication Server

During installation, the installer prompts you if you want to configure and start a sample Replication Server. Regardless of your choice, the installer creates a resource file, `%SYBASE%\REP-15_5\samp_repserver\SAMPLE_RS.res`, for the sample Replication Server and updates the `sql.ini` file. If you selected No, you can still configure and start the sample Replication Server after installation using this resource file.

To create and start the sample Replication Server after installation, at the command prompt, enter:

```
cd %SYBASE%\REP-15_5\samp_repserver
rs_init-SAMPLE_RS.bat
```

A setup window displays the status of configuration and the `rs_init` utility in this script displays commands in the DOS window as it executes them, then writes this output to its log.

If you encounter errors during configuration and start-up of the sample Replication Server, you can read this log file, `%SYBASE%\REP-15_5\init\logs\logmdd.xxx`, where:

- `mm` – is the month.
- `dd` – is the day.
- `xxx` – is the number of that instance of the log on that day.

The sample Replication Server is configured using the `SAMPLE_RS.res` resource file. All files and logs associated with the sample Replication Server are in the directory `%SYBASE%\REP-15_5\samp_repserver`.

Table 3-1 contains the sample Replication Server configuration information. Keep this information in a safe place for later reference.

Table 3-1: Sample Replication Server configuration information

Sample Replication Server item	Definition
Name	<code>SAMPLE_RS</code>
Port	11752
User name	<code>sa</code>
Password	None
ERSSD server name	<code>SAMPLE_RS_ERSSD</code>
ERSSD server port	11751
ERSSD user name	<code>SAMPLE_RS_RSSD_prim</code>
ERSSD password	<code>SAMPLE_RS_RSSD_prim_ps</code>

For more information about `rs_init`, see Chapter 2, “Configuring Replication Server and Adding Databases with `rs_init`,” in the *Replication Server Configuration Guide for Windows*.

Set environment variables

Replication Server installer automatically sets the required system environment variables, such as `PATH`, as well as additional environment variables used by your newly installed Sybase software. Replication Server installer installs two files that contain these environment variables:

- `%SYBASE%\SYBASE.bat`
- `%SYBASE%\SYBASE.env`

After exiting Replication Server installer, you can reset the environment variables using these files, if needed.

Table 3-2 describes the environment variables.

Table 3-2: Environment variables for Windows

Environment variable	Description
%LM_LICENSE_FILE%	Specifies the subdirectory path to the <i>license.dat</i> file, which SySAM needs to run the license manager.
%PATH%	Specifies the directory path to Replication Server files.
%SYBASE%	Specifies the home directory where you install all Sybase products.
%SYBASE_JRE6%	Specifies the subdirectory path to the Java Runtime Environment (JRE) resides.
%SYBASE_JRE6_32%	Specifies the subdirectory path to the Java Runtime Environment (JRE) resides.
%SYBASE_OCS%	Specifies the subdirectory path to Open Client files.
%SYBASE_REP%	Specifies the subdirectory path to Replication Server.
%SYBASE_UA%	Specifies the subdirectory path to the Unified Agent Framework and Replication Monitoring Services.

Start Replication Server

This section explains how you can start Replication Server by executing a batch file.

Create a *.bat* file for Replication Server start-up

To create a *.bat* file for Replication Server, insert the contents of the *x:\InstallDirectory\SYBASE.bat* file at the beginning of the *x:\InstallDirectory\REP-15_5\install\RUN_servername.bat* file, where:

- *x* is the drive name.
- *InstallDirectory* is the name of the installation directory.
- *servername* is the name of your Replication Server.

When you execute the *.bat* files, you set all environment variables for Replication Server to use the unique Replication Server product directory.

Start Replication Server automatically

To start Replication Server automatically when you restart the system:

- 1 Go to *C:\Documents and Settings\adminuser\Start Menu\Programs\Startup*.
- 2 Add a new shortcut for *x:\InstallDirectory\REP-15_5\install\RUN_servername.bat*, where:
 - *x* is the drive name.
 - *InstallDirectory* is the name of the installation directory.
 - *servername* is the name of your Replication Server.

Replication Server now starts automatically after you restart the system.

Uninstalling Replication Server

Topic	Page
Uninstallation procedures	27

Before uninstalling:

- Log on to your machine using an account with administrator privileges.
- Shut down all Sybase applications and processes.
- Determine the mode of uninstallation—GUI or silent mode. Sybase recommends that you use the GUI mode to uninstall.

Note The uninstaller removes only those files that were loaded from the installation media. Some Sybase files, such as log and configuration files, are left intact for administrative purposes. *jre* and other installed directories are also not removed by the uninstaller. You must remove these directories manually.

Uninstallation procedures

You can invoke the uninstall procedure using either GUI or console methods. Sybase recommends that you use the GUI method.

❖ Uninstalling in GUI mode

1 To uninstall, choose one of the following methods:

- Select Start | Settings | Control Panel | Add or Remove Programs.
- From the command line, enter:

```
%SYBASE%\sybuninstall\RepServer_Suite\uninstall.exe
```

- Click Start | Run and enter:

`%SYBASE%\sybuninstall\RepServer_Suite\uninstall.exe`

- Open Windows Explorer, navigate to `%SYBASE%\sybuninstall\RepServer_Suite`, and double-click `uninstall.exe`.
- 2 Click Next.
 - 3 Select one of:
 - Complete Uninstall – completely remove all features and components of Replication Server. The files and folders created after the installation are not affected.
 - Uninstall Specific Features – uninstall specific features of Replication Server.
Click Next.
 - 4 The uninstallation summary window displays the selections you have made. Review the information, and click Next.

Note If you have installed SySAM during installation, this window shows SySAM license utility. Sybase recommends that you do not uninstall the SySAM license utility if you are using SySAM license server.

The Uninstall Complete window lists the items that cannot be removed.

- 5 Click Done to exit from the installer.

❖ Uninstalling in console mode

- 1 At the command prompt, navigate to the installation directory and enter:

```
%SYBASE%\sybuninstall\RepServer_Suite\uninstall.exe -i console
```

The uninstall program starts.

- 2 The flow of the uninstall program is identical to a regular GUI uninstall, except that the display is written to a terminal window and responses are entered using the keyboard. Follow the remaining prompts to uninstall Replication Server.

For a complete list of command line options, see “Command line options” on page 20.

Note You may be prompted to decide whether to remove shared files. Sybase recommends that you do not remove shared files.

❖ **Uninstalling in silent mode**

- At the command prompt, navigate to the installation directory and enter:

```
%SYBASE%\sybuninstall\RepServer_Suite\uninstall.exe -i silent
```

The uninstall program starts.

For a complete list of command line options, see “Command line options” on page 20.

Note You may be prompted to decide whether to remove shared files. Sybase recommends that you do not remove shared files.

Installing and Uninstalling Replication Manager

Topic	Page
Overview	31
Installing Replication Manager	32
Checking for a valid installation	36
Uninstalling Replication Manager	37

Overview

Replication Manager is a utility for creating, managing, and monitoring replication environments, and is available as a plug-in to Sybase Central, Java Edition. Replication Manager communicates directly with Replication Server and Adaptive Server Enterprise servers.

Depending upon the scale and complexity of your replication environment, you can set up either a two-tier or a three-tier solution for your environment. In a two-tier management solution, Replication Manager connects directly to the servers in the environment without communicating through the management layer.

In a three-tier management solution, Replication Manager monitors large and complex replication environments with the help of Replication Monitoring Services (RMS). Replication Manager connects to the servers in the environment through RMS.

Replication Manager:

- Uses a graphical user interface.
- Allows you to manage, monitor, and troubleshoot replication system components, such as connections, routes, replication definitions, subscriptions, and so forth.

- Runs on Microsoft Windows operating systems as well as all UNIX operating systems that Replication Server supports.
- Runs within the same Sybase Central framework as Adaptive Server Enterprise plug-in to Sybase Central, Java Edition.
- Manages a warm standby environment.
- Supports multisite availability (MSA).
- Supports embedded Replication Server System Database (RSSD).
- Provides for logging and tracing of server commands.
- Provides two-tier and three-tier management solutions by supporting RMS.

See Chapter 3, “Managing Replication Server with Sybase Central” in the *Replication Server Administration Guide Volume 1*.

Installing Replication Manager

You can install Replication Manager using either GUI mode, console mode, or silent mode. However, Sybase recommends that you use GUI mode.

Installing Replication Manager in GUI mode

Follow the procedures in this section to install the Replication Manager.

❖ Installing in GUI mode

1 Launch the installer.

- *On Windows (32-bit):*

```
\nt386\RMP_Suite\setupwin32.exe
```

The installer should start automatically. If it does not, select Start | Run, and enter the following, where *x*: is location of the installed image:

```
x:\nt386\RMP_Suite\setupwin32.exe
```

- *On Windows (64-bit):*

```
\winx64\RMP_Suite\setupwin64.exe
```

The installer should start automatically. If it does not, select Start | Run, and enter the following, where *x*: is location of the installed image:

```
x:\winx64\RMP_Suite\setupwin64.exe
```

- 2 In the Introduction window, click Next.
- 3 Read the License and Copyright Agreement:
 - 1 Select the geographic location from where you are installing to display the agreement for your region.
 - 2 Select “I agree to the terms of the Sybase license for the install location specified.” You must agree to the license and copyright agreement before you can continue with the installation.
 - 3 Click Next.
- 4 Indicate where to install Replication Manager:
 - To select an installation directory, click Choose. A window appears, and from that window browse for and select the directory.
 - To create a new directory, enter a new directory path.
 - To restore to the default directory if you do not want to use the directory that you have entered, click Restore Default Folder.

One of these occurs:

- If the installation directory you chose does not exist, this message appears:

```
The directory <directory name> does not exist. Do you want to create it?
```

Click Yes.

- If the installation directory you selected exists, and contains a prior installation, this message appears:

```
Warning: You have chosen to install into an existing directory.
```

```
If you proceed with this installation, any older versions of the products you choose to install that are detected in this directory will be replaced.
```

Click Next.

- 5 The installation summary window displays the selections you have made. Review the information, and click Install.

- 6 If Replication Manager is installed successfully, a final window appears, indicating a successful installation. Click Done to exit the installer.

Installing Replication Manager in console mode

To run the installation program without the GUI, launch the installer in console mode. If the installer launches automatically, click Cancel to cancel the GUI installation, then launch the setup program from a terminal or console.

❖ Installing in console mode

The steps for installing components in an interactive text mode are the same as those described in “Installing in GUI mode” on page 32, except that you execute the installer from the command line using the `setup -i console` command, and you enter text to select installation options.

- 1 At the command prompt, enter:

- On Windows (32-bit):

```
\nt386\RMP_Suite\setupconsole32.exe -i console
```

- On Windows (64-bit):

```
\winx64\RMP_Suite\setupconsole64.exe -i console
```

- 2 The flow of the installation is identical to a GUI installation, except that the display is written to a terminal window and responses are entered using the keyboard. Follow the remaining prompts to install Replication Manager.

For a complete list of command line options, see Table 2-1 on page 20.

Installing using a response file

To perform a silent, or “unattended” installation, run the installer and provide a response file that contains your preferred installation configuration.

Creating a response file

To create a response file when installing in GUI or console mode, specify the `-r` command line argument. The `-r` argument records your responses to the installation wizard's prompts and creates a response file when the installation wizard exits. The response file is a text file that you can edit to change any responses prior to using it in any subsequent installations.

To generate the response file during installation, run:

- On Windows (32-bit):

```
\nt386\RMP_Suite\setupconsole32.exe -r responseFileName
```

- On Windows (64-bit):

```
\winx64\RMP_Suite\setupconsole64.exe -r responseFileName
```

where *responseFileName* is the file name you choose for the response file. When specifying the response file, include its full path. For example:

```
C:\Sybase\RMP\ResponseFile.txt
```

Note You must provide the full path name for the response file you create.

Installing in silent mode

A silent or unattended installation requires no user interaction, and all installation configuration information is taken from the response file. This is useful when you want multiple identical installations or a fully automated installation process.

To install in silent mode, run:

- On Windows (32-bit):

```
\nt386\RMP_Suite\setupconsole32.exe -f responseFileName -i silent  
-DAGREE_TO_SYBASE_LICENSE=true
```

- On Windows (64-bit):

```
\winx64\RMP_Suite\setupconsole64.exe -f responseFileName -i silent  
-DAGREE_TO_SYBASE_LICENSE=true
```

Where:

- *responseFileName* is the absolute path of the file name containing the installation options you chose.

- The -D option specifies that you agree with the Sybase License Agreement text.

Note You must agree to the Sybase License Agreement when installing in silent mode. You can either:

- Include the option `-DAGREE_TO_SYBASE_LICENSE=true` in the command line argument.
- Edit the response file to include the property
`AGREE_TO_SYBASE_LICENSE=true`

Except for the absence of the GUI screens, all actions of the installer are the same, and the result of an installation in silent mode is exactly the same as one done in GUI mode with the same responses.

Warning! Sybase recommends that you use the `setupconsole32.exe` or `setupconsole64.exe` executable, which runs in the foreground when you are running a silent installation. The normal `setupwin32.exe` or `setupwin64.exe` executable runs in the background, giving you the impression that the installation has terminated, and results in additional installation attempts using the silent installation. Multiple installations at the same time may corrupt the Windows Registry and lead to a failure to restart the operating system.

Checking for a valid installation

Check the following to make sure that your Replication Manager installation is valid and successful:

- View the `%SYBASE%\RMP-15_5\InstallallAndRegister.log` and also view all logs in `%SYBASE%\log` to check for errors. A valid installation does not contain the word “error.”
- Ensure that the date of the `si_reg.xml` file reflects the date of the current installation.
- Ensure that you can access Replication Manager from Sybase Central.

For information about using Sybase Central, the Replication Manager, and the Replication Manager plug-in online help, see Chapter 3, “Managing Replication Server with Sybase Central” in the *Replication Server Administration Guide Volume 1*.

Note Before you use the Replication Manager, make sure that the Replication Manager is registered with Sybase Central. See the “Preparing to manage a replication environment” section in the Replication Manager plug-in online help for information.

Uninstalling Replication Manager

Before uninstalling:

- Log on to your machine using an account with administrator privileges.
- Shut down all Sybase applications and processes.
- Determine the mode of uninstallation—GUI or silent mode. Sybase recommends that you use the GUI mode to uninstall.

Note The uninstaller removes only those files that were loaded from the installation media in the uninstallation process. Some Sybase files, such as log and configuration files, are left intact for administrative purposes.

❖ Uninstalling in GUI mode

1 To uninstall in GUI mode, choose one of the following methods:

- Select Start | Settings | Control Panel | Add or Remove Programs.
- From the command line, enter:

```
%SYBASE%\sybuninstall\ReplicationManager\uninstall.exe
```

- Click Start | Run and enter:

```
%SYBASE%\sybuninstall\ReplicationManager\uninstall.exe
```

- Open Windows Explorer, navigate to *%SYBASE%\sybuninstall\ReplicationManager*, and double-click *uninstall.exe*.

2 In the Introduction window, click Next.

- 3 The uninstallation summary window displays the location where you have installed Replication Manager. Click Next.
- 4 The Uninstall Complete window appears. Click Done to exit from the installer.

Note You may be prompted to decide whether to remove files that are created outside the installer. Sybase recommends that you do not remove these files.

- 5 If you are uninstalling the Replication Manager plug-in from Sybase Central, Java Edition, and you have previously installed both the Replication Manager plug-in and the Adaptive Server plug-in to Sybase Central, Java Edition, unregister the Replication Manager plug-in inside Sybase Central.

See the Replication Manager plug-in online help for more information.

❖ Uninstalling in console mode

- 1 At the command prompt, navigate to the installation directory and enter:

```
%SYBASE%\sybuninstall\ReplicationManager\uninstall.exe -i console
```

The uninstall program starts.

- 2 The flow of the uninstall program is identical to a regular GUI uninstall, except that the display is written to a terminal window and responses are entered using the keyboard. Follow the remaining prompts to uninstall Replication Manager.

For a complete list of command line options, see “Command line options” on page 20.

Note You may be prompted to decide whether to remove files that are created outside the installer. Sybase recommends that you do not remove these files.

- 3 If you are uninstalling the Replication Manager plug-in from Sybase Central, Java Edition, and you have previously installed both the Replication Manager plug-in and the Adaptive Server plug-in to Sybase Central, Java Edition, unregister the Replication Manager plug-in inside Sybase Central.

See the Replication Manager plug-in online help for more information.

Index

A

- Adaptive Server
 - for the Replication Server System Database 22
 - upgrading 22
- administration tasks 12

C

- charsets* subdirectory 10
- checking for a valid installation
 - in Replication Manager 36
 - in Replication Server 19
- collate* subdirectory 10
- command line installation
 - of Replication Manager 34
 - Replication Server 17
- complete installation 11
- components of Replication Server 1
- console mode
 - installing Replication Manager 34
 - installing Replication Server 17
 - response file, installing Replication Server with 18
 - troubleshooting 19
 - uninstallation in. *See* uninstalling
- conventions
 - document style viii
 - examples viii
 - syntax statements ix
- CPU requirements 6
- creating
 - a *.bat* file for Replication Server start-up 24
 - response files for Replication Manager 17
- custom installation 11, 14

D

- D flag and setup
 - Replication Server 19
- default directory 14, 33
- details
 - Replication Server Configuration Guide for Windows NT* 2
 - Replication Server Installation Guide for Windows NT* 2
- diagnosing software problems 9
- directories
 - default 14, 33
 - installation, structure of 8
- disk storage requirements 6
- drepsrvr.exe** program 9
- dsedit** utility 12

E

- Embedded Replication Server System Database (ERSSD) 1, 6
- environment variables
 - %LM_LICENSE_FILE%* 24
 - %PATH%* 24
 - required for **dsedit** 12
 - setting 23
 - %SYBASE%* 24
 - %SYBASE_JRE%* 24
 - %SYBASE_JRE6_32%* 24
 - %SYBASE_OCS%* 24
 - %SYBASE_REP%* 24
 - %SYBASE_UA%* 24
- errors
 - while starting installer 13
- examples
 - style conventions viii
- existing installation directories 14, 33

F

files

- installation log 20
 - log.txt* 10, 20
 - SYBASE.bat* 11, 23
 - SYBASE.env* 11
- full installation 11, 14

G

- graphical user interface (GUI) installation 11
- GUI mode
- installing Replication Manager 32
 - installing Replication Server 13
 - uninstallation in. *See* uninstalling

H

- hardware requirements 7

I

- ini* subdirectory 10
- installation
- custom installation 14
 - GUI mode 13
 - methods, Replication Manager. *See* installing Replication Manager
 - overview 2
 - starting 13
 - troubleshooting during silent or console mode 19
 - typical software components 14
- installation directories
- contents 9
 - existing 14, 33
 - new 14, 33
- installation log file 20
- installer
- complete installation 11
 - custom installation 11
 - errors in starting 13
 - standard installation 11, 14
- installing

- Adaptive Server for the Replication Server System Database 22
- Replication Manager. *See* installing in Replication Manager
- Replication Server. *See* installing in Replication Server
- response file 17
- SySAM 4
- installing Replication Manager 32
- in command line mode 34
 - in console mode 34
 - in GUI mode 32
 - with response files 35
- installing Replication Server
- in command line mode 17
 - in console mode 11, 17
 - in GUI mode 11
 - in silent mode 12
 - using **-D** flag 19
 - with response files 12
- interactive mode
- response file, installing Replication Server with 12

J

- jre* subdirectory 10

L

- license agreement 15, 33
- licenses 3
- product edition 4
- %LM_LICENSE_FILE%* 24
- log files, reviewing after installation 21
- log.txt* file 10, 20

M

- methods of installation
- Replication Manager. *See* installing in Replication Manager
- Microsoft Visual Studio 7
- Modifying or removing *si_reg.xml* file 10

N

new installation directories 14, 33

O

OCS-15_0 subdirectory 10
 operating system
 determining service pack levels for 7
 requirements 7
 service pack requirements for 7
 overview
 installation 2
 SySAM licensing 3

P

%PATH% 24
 planning replication system 2
 postinstallation tasks
 Replication Manager 36
 Replication Server 21
 preinstallation tasks 2
 product edition licenses
 Enterprise Edition 4
 Real-time Loading Edition 4
 programs
 drepsrvr.exe 9

R

RAM requirements 6
 release bulletin 2
REP-15_5 subdirectory 10
 Replication Manager
 installing. *See* installing Replication Manager
 Replication Server
 components 1
 details 1
 installing. *See* installing Replication Server
 licenses 3
 upgrading and mixed-version requirements 3
Replication Server Configuration Guide for Windows NT 2

Replication Server Installation Guide for Windows NT
 2

requirements
 CPU 6
 disk storage 6
 hardware 7
 operating system 7
 operating system service packs 7
 RAM 6
 system 6
 response file installation mode 17
 response files
 installing Replication Manager with 35
 installing Replication Server with 11
 installing with, Replication Server. *See* installing in
 Replication Server 11
 Replication Manager, creating for 17
 reviewing log files after installing 21
RMS plug-in subdirectory 11

S

service pack levels 7
 setting environment variables 23
Shared subdirectory 10
 silent mode
 uninstallation in. *See* uninstalling
 silent mode installations
 for Replication Manager 35
 Replication Server 12, 18
 troubleshooting 19
 software, diagnosing problems 9
 standard installation 11, 14
 installer 14
 starting
 installation 13
 Replication Server 24
 Replication Server automatically 25
 the sample Replication Server 22
 subdirectories
 charsets 10
 ini 10
 jre 10
 OCS-15_0 10
 REP-15_5 10

Index

- RMS plug-in* 11
- Shared* 10
- Sybase_Install_Registry* 10
- sybuninstall* 10
- SYSAM-2_0* 11
- UAF-2_5* 11
- supported protocols 7
- %SYBASE%* environment variable 24
- Sybase installation directories
 - contents 9
- Sybase Software Asset Management System. See SySAM
- SYBASE.bat* file 11, 23
- SYBASE.env* file 11
- Sybase_Install_Registry* subdirectory 10
- %SYBASE_JRE%* environment variable 24
- %SYBASE_JRE6_32%* environment variable 24
- %SYBASE_OCS%* environment variable 24
- %SYBASE_REP%* environment variable 24
- %SYBASE_UA%* environment variable 24
- sybuninstall* subdirectory 10
- syntax statements, conventions ix
- SySAM
 - description 3
 - install 4
 - licensing instruction overview 3
- SYSAM-2_0* subdirectory 11
- system requirements 6

T

- tables
 - system requirements 6
- tasks, administration 12
- troubleshooting
 - during console or silent mode installation 19
- types of installations
 - complete installation 11
 - custom 11, 14
 - full 11, 14
 - full installation 14
 - standard installation 11, 14
 - typical 11, 14
- typical installation 11, 14
 - software components for a 14

U

- UAF-2_5* subdirectory 11
- uninstalling
 - in console mode, Replication Manager 38
 - in console mode, Replication Server 27, 28
 - in GUI mode, Replication Manager 37
 - in GUI mode, Replication Server 27
 - in silent mode, Replication Server 29
- upgrading
 - Adaptive Server Enterprise 22
 - Replication Server 3
- utilities
 - dsedit** 12

V

- valid installation check
 - Replication Manager 36
 - Replication Server 19