# SYBASE\*

Client-Library™/C Programmers Guide

Open Client™

15.0

#### DOCUMENT ID: DC35570-01-1500-02

#### LAST REVISED: December 2008

Copyright © 2008 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

To order additional documents, U.S. and Canadian customers should call Customer Fulfillment at (800) 685-8225, fax (617) 229-9845.

Customers in other countries with a U.S. license agreement may contact Customer Fulfillment via the above fax number. All other international customers should contact their Sybase subsidiary or local distributor. Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase trademarks can be viewed at the Sybase trademarks page at http://www.sybase.com/detail?id=1011207. Sybase and the marks listed are trademarks of Sybase, Inc. ® indicates registration in the United States of America.

Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

All other company and product names used herein may be trademarks or registered trademarks of their respective companies.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568.

# **Contents**

About This Book.		ix
CHAPTER 1	Getting Started with	
	Client-Library	
	Client-Library overview	1
	Types of Client-Library applications	2
	Adaptive Server client applications	
	Open Server client or gateway applications	
	Summary of changes for version 15.0	
	A simple sample program	5
	Building programs	6
	Steps in the example	6
	Source listing	7
	Step 1: Set up the Client-Library programming environment	19
	Header files	19
	Allocating a context structure	19
	Setting CS-Library context properties	19
	Initializing Client-Library	20
	Setting Client-Library context properties	
	External configuration	
	Step 2: Define error handling	
	Step 3: Connect to a server	
	Allocating a connection structure	
	Setting connection structure properties	
	Logging in to a server	
	Step 4: Send commands to the server	
	Allocating a command structure	
	Setting command structure properties	
	Executing a command	
	Step 5: Process the results of the command	
	Step 6: Finish	
	Deallocating command structures	
	Closing and deallocating connections	
	Exiting Client-Library	

	Deallocating a context structure	29
CHAPTER 2	Understanding Structures, Constants, and Conventions	31
	Hidden structures	
	CS CONTEXT	
	CS_CONNECTION	
	CS_COMMAND	
	Control structure hierarchy	
	Connection and command rules	
	CS LOGINFO	
	CS_DS_OBJECT	
	CS_BLKDESC	
	CS_LOCALE	
	Exposed structures	
	CS_BROWSEDESC	
	CS_CLIENTMSG	
	CS_DATAFMT	
	CS DATEREC	
	CS IODESC	_
	CS_SERVERMSG	
	SQLCA, SQLCODE, and SQLSTATE	
	SQLDA	
	Constants	
	Type constants	
	Format constants	
	Other symbolic constants	
	Conventions	
	NULL and unused parameters	
	Input parameter strings	
	Output parameter strings	
	Pointers to basic structures	
	Item numbers	
	action, buffer, buflen, and outlen	
CHAPTER 3	Using Open Client and Server Datatypes	47
	Types and type constants	
	Where are datatypes declared?	
	Why use Open Client and Open Server datatypes?	48
	unichar datatype	
	unitext datatype	
	xml datatype	
	What are type constants?	
	Datatype summary	

**iv** Open Client

	Binary types	56
	Bit types	
	Character types	
	Datetime types	
	Numeric types	
	Money types	
	Text and image types	
	Null substitution values	
	Open Client user-defined datatypes	
CHAPTER 4	Handling Errors and Messages	65
OHAI IER 4	About messages	
	How to identify messages	
	Two methods for handling messages	
	Handling messages with callback routines	
	Defining a client-message callback	
	Defining a server-message callback	
	Installing callbacks  Handling messages inline	
	The CS_EXTRA_INF property The CS_DIAG_TIMEOUT_FAIL property	
	Sequencing long messages	
	Extended error data  Uses of extended error data	
	Server transaction states	74
CHAPTER 5	Choosing Command Types	75
	Command overview	
	Types of commands	
	Executing commands	
	Initiating a command	
	Defining parameters for a command	
	Processing results	
	Resending a command	
	Language commands	
	Building language commands	
	Results-handling for language commands	
	When to use language commands	
	When not to use language commands	
	RPC commands	
	Building RPC commands	
	RPC command results handling	82
	When to use RPC commands	84

	RPCs versus execute language commands	85
	Client-Library cursor commands	86
	Building Client-Library cursor commands	86
	When to use Client-Library cursors	86
	When not to use Client-Library cursors	87
	Dynamic SQL commands	87
	Building Dynamic SQL commands	87
	When to use dynamic SQL commands	88
	When not to use dynamic SQL	88
	Message commands	88
	When to use message commands	89
	When not to use message commands	89
	Package commands	90
	Send-data commands	90
	When to use send-data commands	90
	When not to use send-data commands	91
CHAPTER 6	Writing Results-Handling Code	0.2
CHAPIER		
	Types of resultsStructure of the basic loop	
	•	
	Processing regular row results	
	Processing cursor results  Processing scrollable cursor results	
	· · · · · · · · · · · · · · · · · · ·	
	Processing parameter results	
	Processing return status results	
	Processing compute results	
	Processing message results	
	Processing describe results	
	Processing format results	
	Values of result_type that indicate command status	
	Logical commands	
	ct_results final return code	108
CHAPTER 7	Using Client-Library Cursors	111
	Cursor overview	
	Language cursors versus Client-Library cursors	
	Language cursors	
	Client-Library cursors	
	When to use Client-Library cursors	
	Benefits of Client-Library cursors	
	Performance issues when using Client-Library cursors	
	Using Client-Library cursors	
	Step 1: Declare the cursor	

Vi Open Client

	Step 2: Set cursor rows	125
	Step 3: Open the cursor	
	Step 4: Process cursor rows	
	Step 5: Close the cursor	
	Step 6: Deallocate the cursor	
	Client-Library cursor properties	
	Chefit-Library cursor properties	131
CHAPTER 8	Using Dynamic SQL Commands	133
	Dynamic SQL overview	133
	Benefits of dynamic SQL	134
	Limitations of dynamic SQL	134
	Performance of dynamic SQL commands	134
	Adaptive Server restrictions and database requirements	135
	Alternatives to dynamic SQL	136
	Using the execute-immediate method	
	When to use the execute-immediate method	136
	Coding an execute-immediate command	137
	Using the prepare-and-execute method	137
	When to use prepare-and-execute method	
	Program structure for the prepare-and-execute method	138
	Step 1: Prepare the statement	140
	Step 2: Get a description of command inputs	140
	Step 3: Get a description of command outputs	142
	Step 4: Execute the prepared statement	143
	Step 5: Deallocate the prepared statement	144
	Dynamic SQL versus stored procedures	144
CHAPTER 9	Using Directory Services	1 17
CHAPTER 3	Directory service overview	
	How do applications use a directory service?	
	Searching the directory	
	Example code	
	Program structure	
	Step 1: Starting the search	
	Initialize data structures	
	Setting directory service properties	
	Installing the directory callback	
	Calling ct_ds_lookup	
	Example code to start a directory search	
	Step 2: Collecting search results in the directory callback	
	Defining the directory callback	
	Directory callback example	
	Step 3: Inspecting directory objects	

	Attribute data structures	159
	Example code to inspect a directory object	160
	Step 4: Cleaning up	172
APPENDIX A	Logical Sequence of Calls	175
	Client-Library state machines	
	Command-level sequence of calls	
	Commands state table	176
	Initiated-commands state table	176
	Result-types state table	
	Summary	
	Command states	
	Command-level routines	180
	Callable routines in each command state	181
	Initiated commands	193
	Initiated command routines	194
	Callable routines for initiated commands	195
	Result types	198
	Result type processing routines	
	Callable routines for each result type	
	Pending results	
Index		205

Viii Open Client

### About This Book

This book, the Open Client *Client-Library/C Programmers Guide*, contains information on how to write C applications using Open Client<sup>TM</sup> Client-Library<sup>TM</sup>.

#### **Audience**

How to use this book

The Open Client *Client-Library/C Programmers Guide* is written for application programmers familiar with the C programming language.

When writing a Client-Library application, use this book as a source of general information on how to construct Client-Library programs.

- Chapter 1, "Getting Started with Client-Library" explains how to structure a basic Client-Library program and includes a simple, complete Client-Library application.
- Chapter 2, "Understanding Structures, Constants, and Conventions" contains information about Client-Library structures, constants, and parameter conventions.
- Chapter 3, "Using Open Client and Server Datatypes" contains a summary of datatypes that can be used in a Client-Library application.
- Chapter 4, "Handling Errors and Messages" explains how to handle Client-Library and server errors in your application.
- Chapter 5, "Choosing Command Types" explains when and how to use the different command types in your application.
- Chapter 6, "Writing Results-Handling Code" explains Client-Library's results processing model.
- Chapter 7, "Using Client-Library Cursors" explains how to declare and manipulate Client-Library cursors.
- Chapter 8, "Using Dynamic SQL Commands" explains how to use dynamic SQL queries in your applications.
- Chapter 9, "Using Directory Services" contains information on how to use Client-Library directory services.
- Appendix A, "Logical Sequence of Calls" contains diagrams of the legal call sequences in Client-Library applications.

#### Related documents

- The Open Server and SDK New Features for Microsoft Windows, Linux, and UNIX, which describes new features available for Open Server and the Software Developer's Kit. This document is revised to include new features as they become available.
- The installation guide explains how to install Client-Library.
- The Open Client *Client-Library/C Reference Manual* contains reference information for Client-Library.
- The Open Client *Client-Library Migration Guide* contains information on how DB-Library™ applications can be converted to Client-Library applications. For DB-Library programmers, this book is also a useful comparison of the DB-Library and Client-Library interfaces.
- The Open Client and Open Server<sup>TM</sup> Common Libraries Reference Manual contains reference information for:
  - CS-Library
  - Bulk-Library
- The Open Client and Open Server Programmers Supplement for Microsoft Windows and Open Client and Open Server Programmers Supplement for UNIX contain platform-specific material for Open Client and Server developers. The documents includes information about:
  - Compiling and linking an application
  - The sample programs that are included with Open Client and Open Server products
  - Routines that have platform-specific behavior
- The Open Client and Open Server Configuration Guide for Microsoft Windows and Open Client and Open Server Configuration Guide for UNIX contain information needed by system administrators who configure the Open Client and Open Server installation environment. The documents include information about:
  - Platform-specific localization mechanisms
  - Configuring Sybase® drivers for network services
  - The interfaces file
- The Open Client and Open Server *International Developer's Guide* contains information needed by programmer's who develop international applications with Client-Library. This document includes:

- A description of the localization mechanism used by the Open Client and Open Server libraries
- Guidelines for developing international applications with the Open Client and Open Server libraries

Because application development can draw on a number of different parts of the Sybase system, you may encounter most of the Sybase documents at some time. The following manuals are particularly useful:

- The Sybase Adaptive Server Enterprise Reference Manual describes the Transact-SQL® (T-SQL) database language, which an application uses to create and manipulate Sybase Adaptive Server® Enterprise database objects.
- The Transact-SQL User's Guide serves as a textbook on Transact-SQL for new SQL programmers or programmers who are experienced with another Structured Query Language (SQL) dialect.
- The Open Client DB-Library Reference Manual describes DB-Library, a
  collection of routines for use in writing client applications. Because DBLibrary is an older interface, Sybase encourages customers to use ClientLibrary for new application development.
- The Open Server Server-Library/C Reference Manual contains reference information for Open Server Server-Library, a collection of routines for use in writing Open Server applications.

# Other sources of information

Use the Sybase Getting Started CD, the SyBooks CD, and the Sybase Product Manuals Web site to learn more about your product:

- The Getting Started CD contains release bulletins and installation guides in PDF format, and may also contain other documents or updated information not included on the SyBooks CD. It is included with your software. To read or print documents on the Getting Started CD, you need Adobe Acrobat Reader, which you can download at no charge from the Adobe Web site using a link provided on the CD.
- The SyBooks CD contains product manuals and is included with your software. The Eclipse-based SyBooks browser allows you to access the manuals in an easy-to-use, HTML-based format.

Some documentation may be provided in PDF format, which you can access through the PDF directory on the SyBooks CD. To read or print the PDF files, you need Adobe Acrobat Reader.

Refer to the *SyBooks Installation Guide* on the Getting Started CD, or the *README.txt* file on the SyBooks CD for instructions on installing and starting SyBooks.

 The Sybase Product Manuals Web site is an online version of the SyBooks CD that you can access using a standard Web browser. In addition to product manuals, you will find links to EBFs/Maintenance, Technical Documents, Case Management, Solved Cases, newsgroups, and the Sybase Developer Network.

To access the Sybase Product Manuals Web site, go to Product Manuals at http://www.sybase.com/support/manuals/.

# Sybase certifications on the Web

Technical documentation at the Sybase Web site is updated frequently.

#### **❖** Finding the latest information on product certifications

- 1 Point your Web browser to Technical Documents at http://www.sybase.com/support/techdocs/.
- 2 Click Certification Report.
- 3 In the Certification Report filter select a product, platform, and timeframe and then click Go.
- 4 Click a Certification Report title to display the report.

#### Finding the latest information on component certifications

- 1 Point your Web browser to Availability and Certification Reports at http://certification.sybase.com/.
- 2 Either select the product family and product under Search by Base Product; or select the platform and product under Search by Platform.
- 3 Select Search to display the availability and certification report for the selection.

#### Creating a personalized view of the Sybase Web site (including support pages)

Set up a MySybase profile. MySybase is a free service that allows you to create a personalized view of Sybase Web pages.

- 1 Point your Web browser to Technical Documents at http://www.sybase.com/support/techdocs/.
- 2 Click MySybase and create a MySybase profile.

XII Open Client

# Sybase EBFs and software maintenance

#### ❖ Finding the latest information on EBFs and software maintenance

- 1 Point your Web browser to the Sybase Support Page at http://www.sybase.com/support.
- 2 Select EBFs/Maintenance. If prompted, enter your MySybase user name and password.
- 3 Select a product.
- 4 Specify a time frame and click Go. A list of EBF/Maintenance releases is displayed.

Padlock icons indicate that you do not have download authorization for certain EBF/Maintenance releases because you are not registered as a Technical Support Contact. If you have not registered, but have valid information provided by your Sybase representative or through your support contract, click Edit Roles to add the "Technical Support Contact" role to your MySybase profile.

5 Click the Info icon to display the EBF/Maintenance report, or click the product description to download the software.

#### Conventions

Table 1: Syntax conventions

Key	Definition	
command	Command names, command option names, utility names, utility flags, and other keywords are in sans serif font.	
variable	Variables, or words that stand for values that you fill in, are in <i>italics</i> .	
{ }	Curly braces indicate that you choose at least one of the enclosed options. Do not include braces in your option.	
[ ]	Brackets mean choosing one or more of the enclosed items is optional. Do not include brackets in your option.	
( )	Parentheses are to be typed as part of the command.	
	The vertical bar means you can select only one of the options shown.	
,	The comma means you can choose as many of the options shown as you like, separating your choices with commas to be typed as part of the command.	

# Accessibility features

This document is available in an HTML version that is specialized for accessibility. You can navigate the HTML with an adaptive technology such as a screen reader, or view it with a screen enlarger.

Open Client and Open Server documentation has been tested for compliance with U.S. government Section 508 Accessibility requirements. Documents that comply with Section 508 generally also meet non-U.S. accessibility guidelines, such as the World Wide Web Consortium (W3C) guidelines for Web sites.

**Note** You might need to configure your accessibility tool for optimal use. Some screen readers pronounce text based on its case; for example, they pronounce ALL UPPERCASE TEXT as initials, and MixedCase Text as words. You might find it helpful to configure your tool to announce syntax conventions. Consult the documentation for your tool.

For information about how Sybase supports accessibility, see Sybase Accessibility at http://www.sybase.com/accessibility. The Sybase Accessibility site includes links to information on Section 508 and W3C standards.

If you need help

Each Sybase installation that has purchased a support contract has one or more designated people who are authorized to contact Sybase Technical Support. If you cannot resolve a problem using the manuals or online help, please have the designated person contact Sybase Technical Support or the Sybase subsidiary in your area.

**xiv** Open Client

# CHAPTER 1 Getting Started with Client-Library

This chapter includes the fundamental concepts required to develop Client-Library/C applications.

Topic	Page
Client-Library overview	1
Types of Client-Library applications	2
Summary of changes for version 15.0	4
A simple sample program	5
Step 1: Set up the Client-Library programming environment	19
Step 2: Define error handling	22
Step 3: Connect to a server	23
Step 4: Send commands to the server	25
Step 5: Process the results of the command	26
Step 6: Finish	28

## **Client-Library overview**

Client-Library is a collection of routines for sending commands to and retrieving results from Sybase servers.


For an overview of Sybase's client/server architecture and products, see Chapter 1, "Introducing Client-Library," in the Open Client *Client-Library/C Reference Manual*.

# Types of Client-Library applications

Client-Library applications vary mainly in the types of commands that they send. Once connected to a server, all client applications use the "send commands, process results" paradigm illustrated in Figure 1-1:

Server

Figure 1-1: The commands/results paradigm



#### **Adaptive Server client applications**

The following examples illustrate what kinds of tasks an Adaptive Server client application might carry out:

- SQL interpreter the client application prompts the user for queries, sends these queries to the server as language commands, retrieves the results from the Adaptive Server, and displays the results. The Sybase isql utility is such an application; it calls the following Client-Library routines:
  - ct\_command(CS\_LANG\_CMD) to define a language command and its text
  - ct send to send it to the server
  - ct results to read the results
  - ct\_res\_info and ct\_describe to find out column formats
  - ct bind and ct fetch to retrieve rows

See "Language commands" on page 78 for more information on this type of command. See also the example application shown in "A simple sample program" on page 5.

- Data-entry an application that always runs the same queries. The
  application uses Adaptive Server stored procedures to implement
  application logic for performing inserts, updates, and menu population.
  The client program invokes the stored procedures by sending RPC
  commands. Such an application calls:
  - ct\_command(CS\_RPC\_CMD) to define an RPC command
  - ct\_param or ct\_setparam to define parameter values with which to call the procedure
  - ct send to send the command to the server
  - ct\_results, ct\_bind, ct\_fetch, and so forth, to read the results

See "RPC commands" on page 80 for more information on this type of command.

- Interactive query-by-example an application that prompts for queries that can contain markers, indicated by a question mark (?), for values to be supplied at runtime. The application uses dynamic SQL commands to:
  - Prepare the statement, by sending a ct\_dynamic(CS\_PREPARE) command and handling the results
  - Query for parameter formats, by sending a ct\_dynamic(CS\_DESCRIBE\_INPUT) command and handling the results
  - After prompting for input values, execute the statement by sending a ct\_dynamic(CS\_EXECUTE) command and handling the results

See Chapter 8, "Using Dynamic SQL Commands" for more information on this type of command.

#### Open Server client or gateway applications

Open Server Server-Library is a collection of routines that allows you to create custom server applications. Server-Library routines are documented in the Open Server-Library/C Reference Manual.

The following examples illustrate the tasks that an Open Server client application might carry out:

- Client for custom Open Server application a client application sends RPC commands to invoke custom server routines that have been "registered" as callable server procedures in the Open Server application program. See the Open Server Server-Library/C Reference Manual for information on registered procedures. See "RPC commands" on page 80 for a description of how client applications send RPC commands.
- Notification client Open Server provides a feature called "registered procedure notification" that allows client applications to watch for invocations of selected registered procedures. For example, a client application that caches copies of important data might watch for a notification on a registered procedure that updates the data. The notification indicates when the cached copy must be refreshed. See the "Registered Procedures" topics page in the Open Client Client-Library/C Reference Manual for more information on this feature.
- Gateway application a server application acts as an intermediary between its own clients and other servers. The gateway accepts client commands, forwards them to a remote server, reads the results, and forwards the results to its own client. If the remote server is a Sybase server, the gateway makes Client-Library calls to communicate with the remote server.

# Summary of changes for version 15.0

This section contains information on changes to this manual in this version. The changes are:

- Sybase library name change: Naming conventions for Open Server and SDK libraries have changed, with the addition of *syb* to Sybase libraries. Names for non-Sybase libraries remain the same.
- BCP partitions: You can now copy ASE partitions with added support for BLKLIB and BCP programs.
- BCP computed columns: Two new Client-Library options have been added to support BCP computed columns.

CS\_OPT\_HIDE\_VCC instructs the Adaptive Server to hide Virtual Computed Columns (VCC), while CS\_OPT\_SHOW\_FI adds columns for each Functional Index (FI).

- Large identifiers: Limits on lengths of identifiers have been reduced. This
  is now 255 bytes for identifiers.
- Unilib® support: Unicode Infrastructure Library (Unilib), an independent library of Unicode-based routines, has been included to facilitate character-set conversion.
- ASE default packet size support: You can now configure packet size centrally on the server, with the default set to 8192 bytes.
- Clusters support: A cluster of servers can now perform load balancing for all client connections coming into the cluster.
- Scrollable cursors: You can now set the position of a cursor anywhere in the cursor result set.
- Table 1-1 lists the new datatypes introduced in this version:

Table 1-1: New Datatypes

Type category	Open Client and Open Server type constant	Description	Corresponding C datatype	Corresponding server datatype
XML type	CS_XML_TYPE	Variable-length character type	CS_XML	xml
Numeric types	CS_BIGINT_TYPE	8-byte integer type	CS_BIGINT	bigint
	CS_USMALLINT_TYPE	2-byte unsigned integer type	CS_USMALLINT	usmallint
	CS_UINT_TYPE	4-byte unsigned integer type	CS_UINT	uint
	CS_UBIGINT_TYPE	8-byte unsigned integer type	CS_UBIGINT	ubigint
Text and image types	CS_UNITEXT_TYPE	Variable-length character type	CS_UNITEXT	unitext

# A simple sample program

This section walks you through an sample program that connects to a server, sends a query, processes the results, then exits. Most Client-Library applications exhibit a program structure similar to this.

#### **Building programs**

The Open Client and Open Server *Programmer's Supplement* for Microsoft Windows and Open Client and Open Server *Programmer's Supplement* for UNIX describe how to build a Client-Library application on your platform and includes information about required compile/link options, library file names, and runtime requirements.

#### Steps in the example

The following steps show a simple Client-Library application:

- 1 Set up the Client-Library programming environment:
  - a Use cs ctx alloc to allocate a context structure.
  - b Use cs\_config to set any CS-Library properties for the context.
  - c Use ct\_init to initialize Client-Library.
  - d Use ct\_config to set Client-Library properties for the context.
- 2 Define error handling. Most applications use callback routines to handle errors:
  - Use cs\_config(CS\_MESSAGE\_CB) to install a CS-Library error callback.
  - b Use ct\_callback to install a client message callback.
  - c Use ct\_callback to install a server message callback.

**Warning!** Applications that do not define error handling do not receive notification of errors that occur in the program, on the network, or on the server. Code your applications to handle errors and server messages. Applications that do not perform error handling are difficult to debug and maintain.

- 3 Connect to a server:
  - a Use ct\_con\_alloc to allocate a connection structure.
  - b Use ct\_con\_props to set any properties in the connection structure
  - c Use ct\_connect to open a connection to a server.
  - d Use ct\_options to set any server options for this connection.

- 4 Send a language command to the server:
  - a Use ct\_cmd\_alloc to allocate a command structure.
  - b Use ct\_command to initiate a language command.
  - c Use ct\_send to send the command.
- 5 Process the results of the command:
  - a Use ct\_results to set up results for processing (called in a loop).
  - b Use ct\_res\_info to get information about a result set.
  - c Use ct\_describe to get information about a result item.
  - d Use ct\_bind to bind a result item to program data space.
  - e Use ct\_fetch to fetch result rows (called in a loop).

#### 6 Finish:

- a Use ct\_cmd\_drop to deallocate the command structure.
- b Use ct\_close to close the connection with the server.
- c Use ct\_exit to exit Client-Library.
- d Use cs\_ctx\_drop to deallocate the context structure.

#### **Source listing**

The following sample program, called *firstapp.c*, demonstrates the steps outlined in the previous section. Commentary for each step follows the example (beginning with "Step 1: Set up the Client-Library programming environment" on page 19).

The source code for this application is included with the Client-Library sample programs. See the Client-Library chapter in the Open Client and Open Server *Programmer's Supplement* for Microsoft Windows or Open Client and Open Server *Programmer's Supplement* for UNIX for information on making and running the sample programs.

```
/*
** Language Query Example Program.
*/
#include <stdio.h>
#include <stdlib.h>
```

```
#include <string.h>
#include <ctpublic.h>
#include "example.h"
#define MAXCOLUMNS
#define MAXSTRING
#define ERR CH stderr
#define OUT CH stdout
** Define a macro that exits if a function return code indicates
** failure.
#define EXIT ON FAIL(context, ret, str) \
  if (ret != CS_SUCCEED) \
    fprintf(ERR CH, "Fatal error: %s\n", str); \
    if (context != (CS CONTEXT *) NULL) \
      (CS VOID) ct exit(context, CS FORCE EXIT); \
      (CS VOID) cs ctx drop(context); \
    } \
    exit(-1); \
** Callback routines for library errors and server messages.
*/
CS RETCODE CS PUBLIC csmsg callback PROTOTYPE((
        CS CONTEXT *context,
        CS CLIENTMSG *clientmsq));
CS RETCODE CS PUBLIC clientmsg callback PROTOTYPE((
        CS CONTEXT
                     *context,
    CS CONNECTION *connection,
        CS CLIENTMSG *clientmsq));
CS_RETCODE CS_PUBLIC servermsg_callback PROTOTYPE((
        CS CONTEXT *context,
    CS CONNECTION *connection,
        CS CLIENTMSG *servermsg ));
** Main entry point for the program.
*/
main(int argc, char *argv[])
```

```
CS CONTEXT
                *context; /* Context structure
CS CONNECTION *connection; /* Connection structure. */
CS COMMAND
                *cmd:
                             /* Command structure.
/* Data format structures for column descriptions: */
CS DATAFMT columns [MAXCOLUMNS];
CS INT
              datalength[MAXCOLUMNS];
CS SMALLINT indicator [MAXCOLUMNS];
CS INT
                count;
              ret;
CS RETCODE
CS RETCODE
              results ret;
CS INT
               result type;
             name[MAXSTRING];
CS CHAR
CS CHAR
              city[MAXSTRING];
EX SCREEN INIT();
/*
** Step 1: Initialize the application.
* /
                For more commentary, see "Step 1: Set up the Client-Library programming
                environment" on page 19.
/*
** First allocate a context structure.
context = (CS CONTEXT *) NULL;
ret = cs ctx alloc(EX CTLIB VERSION, &context);
EXIT ON FAIL(context, ret, "cs ctx alloc failed");
** Initialize Client-Library.
* /
ret = ct init(context, EX CTLIB VERSION);
EXIT ON FAIL(context, ret, "ct init failed");
/*
** Step 2: Set up the error handling. Install callback handlers
** for: - CS-Library errors - Client-Library errors - Server
** messages
* /
```

For more commentary, see "Step 2: Define error handling" on page 22.

```
/*
** Install a callback function to handle CS-Library errors
ret = cs config(context, CS SET, CS MESSAGE CB,
                (CS VOID *) csmsq callback,
                CS UNUSED, NULL);
EXIT ON FAIL (context, ret,
            "cs config(CS MESSAGE CB) failed");
** Install a callback function to handle Client-Library errors
** The client message callback receives error or informational
** messages discovered by Client-Library.
* /
ret = ct callback(context, NULL, CS SET, CS CLIENTMSG CB,
                  (CS VOID *) clientmsq callback);
EXIT ON FAIL (context, ret,
            "ct callback for client messages failed");
** The server message callback receives server messages sent by
** the server. These are error or informational messages.
*/
ret = ct callback(context, NULL, CS SET, CS SERVERMSG CB,
                   (CS VOID *) servermsg callback);
EXIT ON FAIL (context, ret,
            "ct callback for server messages failed");
** Step 3: Connect to the server. We must: - Allocate a connection
** structure. - Set user name and password. - Create the
** connection.
* /
               For more commentary, see "Step 3: Connect to a server" on page 23.
** First, allocate a connection structure.
* /
ret = ct con alloc(context, &connection);
EXIT_ON_FAIL(context, ret, "ct_con_alloc() failed");
/*
** These two calls set the user credentials (username and
** password) for opening the connection.
* /
```

```
ret = ct con props (connection, CS SET, CS USERNAME,
           Ex username, CS NULLTERM, NULL);
EXIT ON FAIL (context, ret, "Could not set user name");
ret = ct con props (connection, CS SET, CS PASSWORD,
           Ex password, CS NULLTERM, NULL);
EXIT_ON_FAIL(context, ret, "Could not set password");
** Create the connection.
if (EX SERVER == NULL)
    ret = ct connect(connection, (CS CHAR *) NULL, 0);
else
   ret = ct connect(connection, (CS CHAR *) EX SERVER, strlen(EX SERVER));
EXIT_ON_FAIL(context, ret, "Could not connect!");
/*
** Step 4: Send a command to the server, as follows: - Allocate a
** CS COMMAND structure - Build a command to be sent with
** ct command. - Send the command with ct send.
*/
               For more commentary, see "Step 4: Send commands to the server" on page 25.
/*
** Allocate a command structure.
ret = ct cmd alloc(connection, &cmd);
EXIT ON FAIL(context, ret, "ct cmd alloc() failed");
/*
** Initiate a language command. This call associates a guery with
** the command structure.
* /
ret = ct command(cmd, CS LANG CMD,
         "select au lname, city from pubs2..authors \
         where state = 'CA'",
         CS NULLTERM, CS UNUSED);
EXIT ON FAIL(context, ret, "ct command() failed");
/*
** Send the command.
* /
ret = ct send(cmd);
EXIT ON FAIL(context, ret, "ct send() failed");
/*
```

```
** Step 5: Process the results of the command.
* /
               For more commentary, see "Step 5: Process the results of the command" on
               page 26.
while ((results ret = ct results(cmd, &result type))
       == CS SUCCEED)
{
    /*
    ** ct results sets result type to indicate when data is
    ** available and to indicate command status codes.
    * /
    switch ((int)result type)
    case CS ROW RESULT:
        ** This result type value indicates that the rows
        ** returned by the query have arrived. We bind and
        ** fetch the rows.
        ** We're expecting exactly two character columns:
        ** Column 1 is au lname, 2 is au city.
        **
        ** For each column, fill in the relevant fields in
        ** the column's data format structure, and bind
        ** the column.
        * /
        columns[0].datatype = CS CHAR TYPE;
        columns[0].format = CS FMT NULLTERM;
        columns[0].maxlength = MAXSTRING;
        columns[0].count = 1;
        columns[0].locale = NULL;
        ret = ct bind(cmd, 1, &columns[0],
                     name, &datalength[0],
                     &indicator[0]);
        EXIT ON FAIL (context, ret,
          "ct bind() for au lname failed");
        ** Same thing for the 'city' column.
        */
        columns[1].datatype = CS CHAR TYPE;
        columns[1].format = CS FMT NULLTERM;
        columns[1].maxlength = MAXSTRING;
        columns[1].count = 1;
```

```
columns[1].locale = NULL;
ret = ct bind(cmd, 2, &columns[1], city,
             &datalength[1],
             &indicator[1]);
EXIT ON FAIL (context, ret,
  "ct bind() for city failed");
** Now fetch and print the rows.
while(((ret = ct fetch(cmd, CS UNUSED, CS UNUSED,
                       CS UNUSED, &count))
        == CS SUCCEED)
      | | (ret == CS ROW FAIL))
    ** Check if we hit a recoverable error.
    * /
    if ( ret == CS ROW FAIL )
        fprintf(ERR_CH,
                "Error on row %ld.\n",
                (long) (count+1));
    ** We have a row, let's print it.
    fprintf(OUT CH, "%s: %s\n", name, city);
}
** We're finished processing rows, so check
** ct fetch's final return value to see if an
** error occurred. The final return code should be
** CS END DATA.
*/
if ( ret == CS END DATA )
    fprintf(OUT CH,
            "\nAll done processing rows.\n");
else /* Failure occurred. */
    EXIT ON FAIL (context, CS FAIL,
                "ct fetch failed");
```

}

```
}
        /*
        ** All done with this result set.
        */
        break;
  case CS CMD SUCCEED:
        ** We executed a command that never returns rows.
        fprintf(OUT_CH, "No rows returned.\n");
        break;
    case CS CMD FAIL:
        ** The server encountered an error while
        ** processing our command. These errors will be
        ** displayed by the server-message callback that
        ** we installed earlier.
        */
        break;
    case CS CMD DONE:
        /*
        ** The logical command has been completely
        ** processed.
        * /
        break;
    default:
        /*
        ** We got something unexpected.
        EXIT ON FAIL (context, CS FAIL,
           "ct_results returned unexpected result type");
        break;
    }
** We've finished processing results. Check the return value
** of ct_results() to see if everything went okay.
```

```
* /
switch( (int) results ret)
case CS END RESULTS:
        /*
        ** Everything went fine.
        * /
        break;
    case CS FAIL:
        ** Something terrible happened.
        * /
        EXIT ON FAIL (context, CS FAIL,
                     "ct results() returned CS FAIL.");
        break;
    default:
        /*
        ** We got an unexpected return value.
        EXIT ON FAIL (context, CS FAIL,
           "ct results returned unexpected return code");
        break;
}
** Step 6: Clean up and exit.
*/
               For more commentary, see "Step 6: Finish" on page 28.
/*
** Drop the command structure.
ret = ct cmd drop(cmd);
EXIT_ON_FAIL(context, ret, "ct_cmd drop failed");
/*
** Close the connection and drop its control structure.
ret = ct close(connection, CS UNUSED);
EXIT ON FAIL(context, ret, "ct close failed");
ret = ct con drop(connection);
EXIT ON FAIL(context, ret, "ct con drop failed");
```

```
/*
    ** ct exit tells Client-Library that we are done.
    ret = ct exit(context, CS UNUSED);
   EXIT ON FAIL(context, ret, "ct exit failed");
    ** Drop the context structure.
    * /
   ret = cs_ctx_drop(context);
   EXIT ON FAIL(context, ret, "cs ctx drop failed");
    /*
    ** Normal exit to the operating system.
    * /
   exit(0);
}
/*
** Handler for server messages. Client-Library will call this
** routine when it receives a message from the server.
CS RETCODE CS PUBLIC
servermsg callback(CS CONTEXT *cp, CS CONNECTION *chp, CS SERVERMSG *msgp)
    /*
    ** Print the message info.
    * /
    fprintf(ERR CH,
        "Server message:\n\t");
    fprintf(ERR CH,
        "number(%ld) severity(%ld) state(%ld) line(%ld)\n",
        (long) msqp->msqnumber, (long) msqp->severity,
        (long) msgp->state, (long) msgp->line);
    ** Print the server name if one was supplied.
    */
    if (msqp->svrnlen > 0)
        fprintf(ERR CH, "\tServer name: %s\n", msgp->svrname);
    /*
    ** Print the procedure name if one was supplied.
    if (msgp->proclen > 0)
        fprintf(ERR CH, "\tProcedure name: %s\n", msgp->proc);
```

```
/*
    ** Print the null terminated message.
    fprintf(ERR CH, "\t%s\n", msgp->text);
    ** Server message callbacks must return CS SUCCEED.
    return(CS SUCCEED);
/*
** Client-Library error handler. This function will be invoked
** when a Client-Library has detected an error. Before Client-
** Library routines return CS FAIL, this handler will be called
    with additional error information.
* /
CS RETCODE CS PUBLIC
clientmsq callback(CS CONTEXT *context, CS CONNECTION *conn, CS CLIENTMSG
*emsqp)
     /*
     ** Error number:
     ** Print the error's severity, number, origin, and
     ** layer. These four numbers uniquely identify the error.
     * /
     fprintf(ERR CH,
             "Client Library error:\n\t");
     fprintf(ERR CH,
        "severity(%ld) number(%ld) origin(%ld) layer(%ld)\n",
        (long) CS SEVERITY (emsgp->severity),
        (long) CS NUMBER (emsqp->msqnumber),
        (long) CS ORIGIN(emsgp->msgnumber),
        (long) CS LAYER(emsgp->msgnumber));
     /*
     ** Error text:
     ** Print the error text.
     * /
     fprintf(ERR CH, "\t%s\n", emsqp->msqstring);
     ** Operating system error information: Some errors, such as
     ** network errors, may have an operating system error associated
     ** with them. If there was an operating system error, this code
     ** prints the error message text.
```

```
*/
     if (emsqp->osstringlen > 0)
          fprintf(ERR CH,
                  "Operating system error number(%ld):\n",
                  (long) emsgp->osnumber);
          fprintf(ERR CH, "\t%s\n", emsqp->osstring);
     }
     ** If we return CS FAIL, Client-Library marks the connection as
     ** dead. This means that it cannot be used anymore. If we return
     ** CS SUCCEED, the connection remains alive if it was not already
     ** dead.
     * /
    return (CS SUCCEED);
/*
** CS-Library error handler. This function will be invoked
** when CS-Library has detected an error.
*/
CS RETCODE CS PUBLIC
csmsg callback(CS CONTEXT *context, CS CLIENTMSG *emsgp)
{
 ** Print the error number and message.
  */
  fprintf(ERR CH,
          "CS-Library error:\n");
  fprintf(ERR CH,
           "\tseverity(%ld) layer(%ld) origin(%ld) number(%ld)",
           (long) CS_SEVERITY(emsgp->msgnumber),
           (long) CS LAYER (emsgp->msgnumber),
           (long) CS ORIGIN(emsqp->msqnumber),
           (long) CS_NUMBER(emsgp->msgnumber));
  fprintf(ERR CH, "\t%s\n", emsgp->msgstring);
  ** Print any operating system error information.
  * /
  if(emsgp->osstringlen > 0)
   fprintf(ERR CH, "Operating System Error: %s\n",
      emsgp->osstring);
```

```
}
return (CS_SUCCEED);
}
```

# Step 1: Set up the Client-Library programming environment

A Client-Library programming environment is defined by:

- A CS\_CONTEXT structure, which defines a programming context
- A Client-Library version level, which is indicated by an application's call to ct init

#### Header files

All Client-Library/C applications require the header file *ctpublic.h*, which contains typedefs and declarations required by Client-Library routines.

#### Allocating a context structure

A Client-Library application calls the CS-Library routine cs\_ctx\_alloc to allocate a context structure. A Client-Library application must allocate a context structure before initializing Client-Library.

**Note** CS-Library routines start with the prefix "cs." Client-Library routines start with the prefix "ct". All Client-Library programs include at least two calls to CS-Library, because they must allocate and drop a context structure.

## **Setting CS-Library context properties**

After allocating a context structure, a Client-Library application can call cs\_config to set CS-Library properties for the context structure.

Context properties define aspects of an application's behavior at the context level. *firstapp.c* calls cs\_config to set the CS\_MESSAGE\_CB property. This property defines a CS-Library message callback routine. An application needs to set this property if it will be handling CS-Library errors using the callback method. For more information, see Chapter 4, "Handling Errors and Messages."

You may need to code your application to set other CS-Library context properties as well. Besides CS\_MESSAGE\_CB, applications most commonly set the following properties with cs\_config:

- CS\_LOC\_PROP describes localization information for the context. An
  application must set this property if a context requires localization
  information that differs from the localization information that is available
  in the operating system environment. For example, if an application that is
  running in a German environment requires a French context, it can call
  cs\_config to set the CS\_LOC\_PROP property.
- CS\_EXTERNAL\_CONFIG specifies whether ct\_init will read default application property settings from the OCS runtime configuration file. See "External configuration" on page 22 for more information.
- CS\_APP\_NAME specifies a name for the application. If external
  configuration is enabled (CS\_EXTERNAL\_CONFIG is CS\_TRUE), then
  the application name specifies a section of the configuration file from
  which to read settings. CS\_APP\_NAME is also inherited by allocated
  CS\_CONNECTION structures.

For more information about CS-Library properties, see cs\_config in the Open Client and Open Server *Common Libraries Reference Manual*.

#### **Initializing Client-Library**

To initialize Client-Library, an application calls ct\_init, which sets up internal control structures and defines the version of Client-Library behavior that the application requires. ct\_init must be the first Client-Library call in an application.

Most applications call ct\_init only once; however, it is not an error for an application to call ct\_init multiple times. Client-Library permits multiple ct\_init calls because some applications cannot guarantee which of several modules will execute first. These types of applications need to call ct\_init in each module.

ct\_init takes as its parameter a symbol describing the version of Client-Library behavior that the application expects.

If Client-Library cannot provide this behavior, ct\_init returns CS\_FAIL.

#### **Setting Client-Library context properties**

*firstapp.c* calls ct\_config to set the CS\_MAX\_CONNECT context property. This property specifies the maximum number of connections for a context.

Client-Library context properties serve one of two purposes:

- They define aspects of a context's behavior.
   CS\_MAX\_CONNECT is an example of this category.
- They define default properties for connections created from the context.

The CS\_NETIO property is an example of this category. If a context CS\_NETIO property is set to CS\_SYNC\_IO, to indicate synchronous connections, then any connection structure allocated within the context will be synchronous. ct\_con\_props can be called to change the value of CS\_NETIO for a specific connection after it has been allocated.

For a complete list of Client-Library context properties, see the "Properties" topics page in the Open Client *Client-Library/C Reference Manual*.

Applications that are not multithreaded can call ct\_config to change a context's properties at any time during the program's execution. Multithreaded applications must set context properties in single-threaded, start-up code or limit all access to a context and its child connections to a single thread. For more information on using Client-Library in multithreaded programs, see the "Multithreaded Programming" topics page in the Open Client *Client-Library/C Reference Manual*.

When an application calls ct\_config to change a context property, property values for existing connections do not change, but connections allocated after the ct\_config call will pick up the new property values.

#### **External configuration**

As an alternative to setting properties with hard-coded ct\_config calls, Client-Library allows external configuration of property values for applications that have been configured to use this feature. For more information, see the topics page "Using the Runtime Configuration File" in the Open Client *Client-Library/C Reference Manual*.

# Step 2: Define error handling

Errors can be handled inline or with callback functions. The sample program uses callback functions. See "Two methods for handling messages" on page 66 for information on the inline method.

ct\_callback installs Client-Library callback routines. which are application routines that Client-Library calls automatically when a triggering event of the appropriate type occurs.

There are several types of callbacks, but the sample program installs only two: a client message callback, to handle Client-Library error and informational messages, and a server message callback, to handle server error and informational messages.

The client message callback is called automatically whenever Client-Library generates an error or informational message. For example, if the application passes an invalid parameter value, or calls routines out of sequence, then Client-Library generates an error and calls the client message callback with a description of the error.

The server message callback is called whenever the server sends an informational or error message during results processing. For example, if the application sends a language command that contains a syntax error or refers to a nonexistent table, then the server sends a message that describes the error.

The sample program also calls cs\_config to install a CS-Library error handler. CS-Library calls the application's CS-Library error handler when an error occurs in a CS-Library call.

Other types of callbacks include:

 Completion callbacks, used by asynchronous connections to handle asynchronous operation completions

- Notification callbacks, used to handle registered procedure notifications received from an Open Server
- Signal callbacks, used by UNIX applications to handle non-Client-Library signals

See the ct\_callback reference page and the "Callbacks" topics page in the Open Client *Client-Library/C Reference Manual* for more information on these types of callbacks.

**Note** A CS-Library message callback is not installed in the same way as Client-Library message callbacks: An application installs a CS-Library message callback by calling cs\_config rather than ct\_callback. Once installed, both types of callbacks function similarly.

# Step 3: Connect to a server

Connecting to a server is a three-step process. An application:

- Allocates a connection structure
- Sets properties for the connection, if necessary
- Logs in to a server

## Allocating a connection structure

An application calls ct\_con\_alloc to allocate a connection structure.

#### Setting connection structure properties

An application calls ct\_con\_props to set, retrieve, or clear connection structure properties.

Connection properties define various aspects of a connection's behavior. For example:

 The CS\_USERNAME property defines the user name that a connection will use when logging in to a server.

- The CS\_APPNAME property specifies the application name that appears in the Adaptive Server *sysprocess* table after the connection is opened.
- The CS\_PACKETSIZE property defines the Tabular Data Stream<sup>TM</sup> (TDS) packet size, which determines the size of network packets that the application will send and receive over this connection. By default, Open Client Server (OCS) 15.0 allows the server to choose a packetsize between 512 and 65535 bytes. Servers supporting Server Specified Packetsize like ASE 15.0 may choose a packetsize freely. The packetsize may also be smaller or larger than the packetsize specified with CS\_PACKETSIZE.

When a connection structure is allocated, it picks up some default property values from its parent context. For example, if the CS\_APPNAME property is set at the context level, all connection structures allocated from that context inherit the application name. Other properties that do not exist at the context level, such as CS\_PACKETSIZE, default to standard Client-Library values.

For a complete list of connection properties, see the ct\_con\_props reference page in the Open Client *Client-Library/C Reference Manual*.

#### Required connection properties

At a minimum, an application must set the connection properties that specify the connection's user name (CS\_USERNAME) and allow the server to authenticate the user's identity. Servers can confirm a user's identity in two ways:

- By requiring a valid password
- By using network-based user authentication

If the server requires a password, then the application must set the CS\_PASSWORD property to the value of the user's server password.

For more information on properties that control application security, see the "Security Features" topics page in the Open Client *Client-Library/C Reference Manual*.

#### Logging in to a server

An application calls ct\_connect to connect to a server. In the process of establishing a connection, ct\_connect sets up communication with the network, logs in to the server, and communicates any connection-specific property information to the server.

For example, if the server supports network-based user authentication and the client application requests it, then Client-Library and the server query the network's security system to see if the user (whose name is specified by CS\_USERNAME) is logged in to the network. Applications must request network-based user authentication by setting the CS\_SEC\_NETWORKAUTH connection property.

# Step 4: Send commands to the server

In Client-Library, a *command* is a request for action sent from the client application to the server. Each command belongs to a command type and may have input data associated with it. Client-Library bundles this information into a symbolic format and sends it over the network to the server, where it is executed.

firstapp.c sends a language command to the server. This command instructs the server to parse and execute the query that was defined as ct\_command's text (third) parameter. For information on other command types, see Chapter 5, "Choosing Command Types."

An application defines and sends commands to a server by using a CS\_COMMAND structure. To define and send a command, the application:

- Allocates a CS\_COMMAND structure
- If necessary, sets properties for the command structure
- Initiates the command
- Defines any parameters required for the command
- · Sends the command

# Allocating a command structure

An application calls ct\_cmd\_alloc to allocate a command structure. Several command structures can be allocated from the same connection.

#### Setting command structure properties

An application calls ct\_cmd\_props to set, retrieve, or clear command structure properties.

Command-structure properties determine aspects of Client-Library behavior at the command-structure level. For example, the CS\_HIDDEN\_KEYS property determines whether or not Client-Library exposes any hidden keys that are returned as part of a result set.

*firstapp.c* sets no command-structure properties; instead, it uses the default command-level behavior. Command structures inherit default property values from their parent connection.

For a complete list of command-structure properties, see the ct\_cmd\_props reference page in the Open Client *Client-Library/C Reference Manual*.

#### **Executing a command**

An application calls ct\_command, ct\_cursor, or ct\_dynamic to initiate a command. ct\_send sends any type of command to the server.

*firstapp.c* calls ct\_command to initiate a language command. ct\_send sends the command text to the server, which parses, compiles, and executes it.

For more information on the other command types, see Chapter 5, "Choosing Command Types."

# Step 5: Process the results of the command

Applications call ct\_results repeatedly to handle the results returned by the server. Almost all Client-Library programs process results by executing a loop controlled by ct\_results return status. Inside the loop, a switch takes place on the current type of result. Different types of results require different types of processing.

The results-processing model used in the example is based on this pseudocode:

while ct\_results returns CS\_SUCCEED
switch on result\_type
case row results
for each column:
ct bind

```
end for

while ct_fetch is returning rows

process each row

end while

check ct_fetch's final return code

end case row results

case command done ....

case command failed ....

case other result type....

... raise an error ...

end switch

end while

check ct results' final return code
```

**Note** Sybase strongly recommends that you use this type of program structure, even in the case of a simple language command. In more complex programs, you cannot predict the number and type of result sets that an application will receive in response to a command. Code that calls ct\_results in a loop is also easier to maintain, enhance, or reuse, since the results-handling logic is centralized.

ct\_results sets up results for processing and sets the return parameter *result\_type* to indicate the type of result data that is available for processing.

If the select statement sent by *firstapp.c* executes successfully on the server, the sample program receives result types of CS\_ROW\_RESULT and CS\_CMD\_DONE, in that order. If the statement does not execute successfully on the server, the program receives a result type of CS\_CMD\_FAIL.

Because this program is so simple, most result types are not included as cases in the *result\_type* switch. However, the code does raise an error for unexpected values of *result\_type*. Code this check into your program's results loop—the error raised may help you trap coding bugs early in the development cycle.

For row results, typically the number of columns in the result set is determined and then used to control a loop in which result items are bound to program variables. An application can call ct\_res\_info to get the number of result columns and ct\_describe to get a description of each column. However, in *firstapp.c*, these calls are not necessary because the example was coded with knowledge of how many columns were selected and their format.

ct\_bind binds a result item to a program variable. Binding creates an association between a result item and a program data space.

ct\_fetch fetches result data. In the example, since binding has been specified and the count field in the CS\_DATAFMT structure for each column is set to 1, each ct\_fetch call copies one row of data into program data space. As each row is fetched, the sample program prints it.

ct\_fetch is called until there are no more rows, then the sample program checks ct\_fetch's final return code to find out whether the loop terminated normally or because of failure.

For information on the other result types that an application can receive, see Chapter 6, "Writing Results-Handling Code."

# Step 6: Finish

Before exiting, a Client-Library application must:

- 1 Deallocate all command structures for each connection.
- 2 Close and deallocate all open connections.
- 3 Exit Client-Library.
- 4 Deallocate all context structures.

As noted in "Exiting Client-Library" on page 29, step 2 can be included with step 3.

#### **Deallocating command structures**

An application calls ct\_cmd\_drop to deallocate a command structure. It is an error to deallocate a command structure that has pending results or an open cursor.

#### Closing and deallocating connections

An application calls ct\_close to close a connection and ct\_con\_drop to deallocate a closed connection. It is an error to deallocate a connection that has not been closed.

## **Exiting Client-Library**

An application calls ct\_exit to exit Client-Library for a specific context. ct\_exit closes and deallocates any open connections and cleans up internal Client-Library data space. ct\_exit must be the last Client-Library call for a context.

Because ct\_exit closes and deallocates all open connections, it is not strictly necessary for an application to close and deallocate connections by calling ct\_close and ct\_con\_drop; instead, the application can just call ct\_exit.

### **Deallocating a context structure**

The CS-Library routine cs\_ctx\_drop deallocates a context structure.

# CHAPTER 2 Understanding Structures, Constants, and Conventions

This chapter contains information about Client-Library structures, constants, and conventions.

Topic	Page
Hidden structures	31
Connection and command rules	33
CS_LOGINFO	34
CS_DS_OBJECT	34
CS_BLKDESC	35
CS_LOCALE	35
Exposed structures	35
Constants	39
Conventions	41

### **Hidden structures**

Hidden structures are structures whose internals are not documented. For example, a Client-Library application needs to call CS-Library or Client-Library routines to allocate, inspect, modify, and deallocate hidden structures. The application cannot access the structure contents directly. Hidden structures include:

- CS\_CONTEXT, which defines a Client-Library programming context.
- CS\_CONNECTION, which defines an individual client/server connection.
- CS\_COMMAND, which is used to send commands and process results

- CS\_LOGINFO, the server login information structure. This structure, which is associated with a CS\_CONNECTION, contains server login information such as user name and password.
- CS\_DS\_OBJECT, which contains information about a directory entry.
- CS\_BLKDESC, a control structure used by applications that call Bulk-Library routines. For information on Bulk-Library, see the Open Client and Open Server *Common Libraries Reference Manual*.
- CS\_LOCALE, which is used to store localization information.

#### **CS CONTEXT**

Before an application can initialize Client-Library, it must allocate a CS\_CONTEXT, or context, structure.

A CS\_CONTEXT structure stores configuration information that describes a particular *context*, or operating environment, for a set of server connections. CS\_CONTEXT is shared by CS-Library, Client-Library, and Server-Library. A CS\_CONTEXT structure is allocated and dropped using the CS-Library routines cs\_ctx\_alloc and cs\_ctx\_drop.

Although an application can use more than one context, a simple application typically requires only one.

**Note** An Open Client application that is running under CICS on an IBM host is restricted to one context per application.

Some context information is stored in the form of *properties*. Properties have values that an application can change to customize a context. Properties include CS\_MAX\_CONNECT, which defines the maximum number of connections allowed within the context, and CS\_NETIO, which determines whether or a context's connections default to synchronous or asynchronous behavior.

Connection and command structures also have properties. When a connection is allocated, it picks up default property values from its parent context. When a command structure is allocated, it picks up default property values from its parent connection.

For more information about properties, see the "Properties" topics page in the Open Client *Client-Library/C Reference Manual*.

### **CS\_CONNECTION**

A CS\_CONNECTION structure stores information about a particular client/server connection, including the user name and password for the connection, the packet size the connection will use, and whether the connection is synchronous or asynchronous.

As with a context, some connection information is stored in the form of properties. When a connection is created, it picks up some default property values from its parent context. Other properties (those that do not exist at the context level, such as CS\_PACKETSIZE), default to standard Client-Library values.

Multiple connections to one or more servers can exist simultaneously within a single context.

#### CS\_COMMAND

A CS\_COMMAND, or command, structure is used to send commands to a server and to process the results of those commands.

A command structure is associated with a specific parent connection. Multiple command structures can exist simultaneously for a single connection.

#### **Control structure hierarchy**

CS\_CONTEXT, CS\_CONNECTION, and CS\_COMMAND are the basic control structures to set up the Client-Library environment, connect to a server, send commands, and process results. All three of these structures are hidden.

## **Connection and command rules**

The following rules apply to connection and command structures:

 Within a connection, the results of a command must be completely processed before another command can be sent.

The exception to this rule is a ct\_cursor (CS\_CURSOR\_OPEN) command, which generates a cursor result set. After ct\_results returns CS\_CURSOR\_RESULT to indicate that cursor results are available:

- The command structure that sent the cursor open command can be used to send a cursor update or cursor delete command related to the newly opened cursor.
- Any other command structure within the connection can be used to send a command not related to the newly opened cursor.
- A separate command structure must be used for each Client-Library cursor. A Client-Library cursor is one that is declared through ct\_cursor.
   For more information on cursors, see Chapter 7, "Using Client-Library Cursors."

# **CS LOGINFO**

A CS\_LOGINFO, or login information, structure, is used internally to contain connection structure information, such as user name and password, that is used when logging in to a server.

Connection properties that reside in this structure are known as *login* properties.

The Client-Library routines ct\_getloginfo and ct\_setloginfo use a CS\_LOGINFO structure. An application can use these routines to copy login properties from an open connection to a new connection structure.

## CS DS OBJECT

A CS\_DS\_OBJECT, or directory object, structure, contains information about a directory entry. Client-Library and Server-Library use a directory to store the network address information required to create connections. Storage for the directory can be provided by the Sybase interfaces file or a network-based directory, such as the Windows Registry.

An application receives pointers to one or more CS\_DS\_OBJECT structures as the result of a directory search by the Client-Library routine ct\_ds\_lookup.

For more information on how an application can search a directory, see Chapter 9, "Using Directory Services."

# CS\_BLKDESC

Bulk-library routines use a CS\_BLKDESC, or bulk descriptor structure. The bulk descriptor is the control structure for bulk copy operations.

An application calls blk\_alloc to allocate a CS\_BLKDESC structure.

After completing a bulk copy operation, an application frees a CS\_BLKDESC by calling blk\_drop.

Bulk-Library routines are documented in the Open Client and Open Server *Common Libraries Reference Manual*.

# CS\_LOCALE

A CS\_LOCALE, or locale structure, can be used to specify localization information at the context, connection, command structure, or data element levels.

A CS\_LOCALE structure specifies:

- A language, character set, and collating sequence
- How to represent dates, times, numeric, and monetary values in character format

An application can call the CS-Library routines cs\_loc\_alloc, cs\_locale, and cs\_loc\_drop to allocate, set values for, and drop a CS\_LOCALE structure.

For more information, see the "International Support" topics page in the Open Client *Client-Library/C Reference Manual*.

# **Exposed structures**

Exposed structures are structures whose internals are documented. A Client-Library application must allocate any exposed structures it intends to use. Type definitions for the exposed structures are included in the header file *ctpublic.h.* In addition, Chapter 2, "Topics," in the Open Client *Client-Library/C Reference Manual* contains a topics page for each exposed structure.

Exposed structures include:

- CS\_BROWSEDESC the browse descriptor structure
- CS\_CLIENTMSG the Client-Library message structure
- CS\_DATAFMT the data format structure
- CS\_DATEREC the datetime descriptor structure
- CS\_IODESC the I/O descriptor structure
- CS\_SERVERMSG the server message structure
- SQLCA the SQL communications area structure
- SQLCODE the SQL code structure
- SQLSTATE the SQL state structure

#### CS\_BROWSEDESC

ct\_br\_column uses a CS\_BROWSEDESC structure to return information about a browse mode column. Browse mode columns are returned by a Transact-SQL select ... for browse statement.

For more information about browse mode, see the "Browse Mode" topics page in the Open Client *Client-Library/C Reference Manual*.

For a description of the fields in a CS\_BROWSEDESC structure, see the "CS\_BROWSEDESC Structure" topics page in the Open Client *Client-Library/C Reference Manual*.

### CS\_CLIENTMSG

Client-Library uses a CS\_CLIENTMSG structure to describe a Client-Library error or informational message.

For a discussion of Client-Library message handling, see Chapter 4, "Handling Errors and Messages."

For a description of the fields in a CS\_CLIENTMSG structure, see the "CS\_CLIENTMSG Structure" topics page in the Open Client *Client-Library/C Reference Manual*.

#### CS\_DATAFMT

Client-Library routines use the CS\_DATAFMT structure to describe data values and program variables.

Some routines require a CS\_DATAFMT structure as an input parameter. For example, ct\_bind requires a data format structure describing the destination variable for a bind, and ct\_param requires a data format structure describing the parameter being passed.

Other routines fill in CS\_DATAFMT fields with a description of output data, which an application can then access directly. For example, ct\_describe initializes a CS\_DATAFMT structure with a description of a result data item.

Client-Library routines that use the CS\_DATAFMT structure include ct\_bind, ct\_describe, and ct\_param. CS-Library routines that use CS\_DATAFMT include cs\_convert and cs\_set\_convert.

For a description of the fields in a CS\_DATAFMT structure, see the "CS\_DATAFMT Structure" topics page in the Open Client *Client-Library/C Reference Manual*.

When a CS\_DATAFMT structure is an input parameter to a routine, the routine ignores the contents of any fields in the structure that it does not use. For example, ct\_bind ignores the contents of the *name*, *namelen*, *status*, and *usertype* fields.

The reference page for each routine that uses CS\_DATAFMT contains a table listing the fields that are used and the values they can have.

#### CS\_DATEREC

The CS\_DATEREC structure is used with the CS-Library routine cs\_dt\_crack to interpret date and time data returned from the server. Date and time data is represented on the server by either the date, time, datetime or datetime4 datatype. Both of these are packed structures. cs\_dt\_crack unpacks the date and time components into the CS\_DATEREC fields.

For a description of the server datetime datatype and the equivalent Client-Library types, see "Datetime types" on page 58. For a description of the CS\_DATEREC structure, see the cs\_dt\_crack reference page in the Open Client and Open Server Common Libraries Reference Manual.

#### **CS\_IODESC**

Client-Library uses a CS\_IODESC structure to describe text or image data.

For a discussion of how the CS\_IODESC is used to process text and image values, see the "text and image Data Handling" topics page in the Open Client *Client-Library/C Reference Manual*.

For a description of the fields in a CS\_IODESC structure, see the "CS\_IODESC Structure" topics page in the Open Client *Client-Library/C Reference Manual*.

#### CS\_SERVERMSG

Client-Library uses a CS\_SERVERMSG structure to describe a server error or informational message.

For a discussion of Client-Library message handling, see Chapter 4, "Handling Errors and Messages."

For a description of the fields in a CS\_SERVERMSG structure, see the "CS\_SERVERMSG Structure" topics page in the Open Client *Client-Library/C Reference Manual*.

#### SQLCA, SQLCODE, and SQLSTATE

When an application is handling error and informational messages inline, the Client-Library routine ct\_diag can return message information in a SQLCA, SQLCODE, or SQLSTATE structure.

For a discussion of Client-Library message handling, see Chapter 4, "Handling Errors and Messages."

For a description of the SQLCA, SQLCODE, and SQLSTATE structures, see the "SQLCA Structure," "SQLCODE Structure," and "SQLSTATE Structure" topics pages in the Open Client *Client-Library/C Reference Manual*.

#### **SQLDA**

Applications can use a SQLDA structure with the Client-Library routine ct\_dynsqlda to pass parameters for server commands and handle the results from server commands.

For a description of the SQLDA structure and its use in applications, see the ct\_dynsqlda reference page in the Open Client *Client-Library/C Reference Manual*.

#### **Constants**

Client-Library makes use of a wide variety of constants, including type constants, format constants, and other symbolic constants.

Constants related to a routine (for example, symbolic constants used as return values) are listed on the reference page for the routine in the Open Client *Client-Library/C Reference Manual*.

## Type constants

Open Client and Open Server use type constants to describe the datatypes of program variables. For example, when calling ct\_bind to describe a bind variable of type CS\_DATETIME, an application sets the datatype field of the CS\_DATAFMT structure to CS\_DATETIME\_TYPE.

Client-Library routines that use type constants include ct\_bind, ct\_describe, and ct\_param. In addition, the CS-Library routine cs\_convert uses type constants.

The type constant for a datatype is the name of the datatype with "\_TYPE" appended. For example, the type constant for the datatype CS\_CHAR is CS\_CHAR\_TYPE.

With the exception of CS\_CHAR, all datatypes correspond to a single type constant.

CS\_CHAR corresponds to three: CS\_CHAR\_TYPE, CS\_BOUNDARY\_TYPE, and CS\_SENSITIVITY\_TYPE. This means that variables described as CS\_BOUNDARY\_TYPE or CS\_SENSITIVITY\_TYPE must be declared as CS\_CHAR.

Table 3-3 on page 54 lists Open Client type constants.

#### **Format constants**

Open Client and Open Server use format constants to describe how to format character and binary data. In particular, the format field of the CS\_DATAFMT structure is a bitmask of format constants indicating how to format character, text, and binary data.

Table 2-1 lists Open Client format constants:

Table 2-1: Format constants

Format constant	Valid types	Resulting format
CS_FMT_NULLTERM	Character and text	The data is null-terminated.
CS_FMT_PADBLANK	Character and text	The data is padded with blanks to the full length of the variable.
CS_FMT_PADNULL	Character, text, binary, and image	The data is padded with nulls to the full length of the variable.
CS_FMT_UNUSED	All	No formatting takes place.

## Other symbolic constants

Open Client makes use of a wide variety of other symbolic constants. Many Client-Library routines use symbolic constants as input and output parameter values.

Table 2-2 lists some of the symbolic constants used in Open Client:

Table 2-2: Other symbolic constants

Symbolic constant	Meaning
CS_FAIL	A return code indicating failure
CS_FALSE	A Boolean false value.
CS_MAX_NAME	The maximum column name length allowed by Adaptive Server.
CS_NULLTERM	CS_NULLTERM passed as a buffer's length indicates that the value contained in the buffer is null-terminated.
CS_SUCCEED	A return code indicating successful execution of a library call.
CS_TRUE	A Boolean true value.

**Note** The underlying values of symbolic constants may change from version to version. For this reason, Client-Library application programmers should always code using the symbolic constants themselves and not their underlying values.

## **Conventions**

This section contains information about Client-Library's parameter conventions.

Topics include NULL and unused parameters, string parameters, and the standard Client-Library parameters *action*, *buffer*, *buflen*, and *outlen*.

# **NULL** and unused parameters

This section contains information about NULL and unused parameters.

#### **Pointer parameters**

A pointer parameter can:

- Have a non-NULL value
- Have a value of NULL

#### Be unused

Pass NULL and unused pointer parameters as NULL.

If the parameter has a NULL value, the length variable associated with the parameter, if any, must be 0 or CS\_UNUSED.

If the parameter is unused, the length variable associated with the parameter, if any, must be CS\_UNUSED.

Client-Library uses current programming context information to determine whether to interpret the parameter as NULL or unused.

#### Non-pointer parameters

Pass non-pointer, unused parameters as CS\_UNUSED.

#### Input parameter strings

Most string parameters are associated with a parameter that indicates the length of the string.

When passing a null-terminated string, an application can pass the length parameter as CS\_NULLTERM.

When passing a string that is not null-terminated, an application must set the associated length parameter to the length, in bytes, of the string.

If a string parameter is NULL, the associated length parameter must be 0 or CS\_UNUSED.

#### **Output parameter strings**

An application indicates the length of a string buffer by setting an associated length parameter. If the length parameter indicates that the buffer is not large enough to hold a null-terminated output string, Client-Library routines return CS FAIL.

#### Pointers to basic structures

All Client-Library routines take a pointer to a CS\_CONTEXT structure, a CS\_CONNECTION structure, or a CS\_COMMAND structure as a parameter.

An application must allocate these structures (using cs\_ctx\_alloc, ct\_con\_alloc, or ct\_cmd\_alloc) before using them as parameters.

If an application passes an invalid control structure address to a Client-Library routine, the routine returns CS\_FAIL, and Client-Library does not call the application's client message callback routine. Client-Library requires the address of a valid control structure to retrieve the address of the application's callback routine.

#### Item numbers

Many Client-Library routines that process results or return information about results take an *item number* as a parameter. An item number identifies a result item in a result set, and can be a column number, a compute column number, a parameter number, or a return status number.

Item numbers start at 1 and never exceed the number of items in the current result set. An application can call ct\_res\_info with *type* as CS\_NUMDATA to obtain the number of items in the current result set.

When the result set contains columns, *item* is a column number. Columns are returned to an application in select-list order.

When the result set contains compute columns, *item* is the column number of a compute column. Compute columns are returned in the order in which they are listed in the compute clause.

When the result set contains parameters, *item* is a parameter number. Stored procedure return parameters are returned in the same order in which the parameters were originally listed in the stored procedure's create procedure statement. This is not necessarily the same order as specified in the Remote Procedure Call (RPC) command that invoked the stored procedure. In determining what number to pass as *item*, do not count nonreturn parameters. For example, if the second parameter in a stored procedure is the only return parameter, pass *item* as 1.

When the result set contains a return status, *item* is always 1, as there can be only a single status in a return status result set.

#### action, buffer, buflen, and outlen

Many Client-Library routines use some combination of the parameters *action*, *buffer*, *buflen*, and *outlen*.

 action – describes whether to set or retrieve information. For most routines, action can take the symbolic values CS\_GET, CS\_SET, and CS\_CLEAR.

If action is CS\_CLEAR, buffer must be NULL, and buflen must be CS\_UNUSED.

• buffer – typically a pointer to program data space.

If information is being set, *buffer* points to the value to use in setting the information.

If information is being retrieved, *buffer* points to the space in which the Client-Library routine places the requested information.

If information is being cleared, *buffer* must be NULL.

If the Client-Library routine returns CS\_FAIL, \*buffer remains unchanged.

• buflen – the length, in bytes, of the buffer data space.

If information is being set and the value in \*buffer is null-terminated, pass buflen as CS\_NULLTERM.

If \*buffer is a fixed-length value, a symbolic value, or a function, buflen must be CS\_UNUSED.

If buffer is NULL, buflen must be 0 or CS\_UNUSED.

• *outlen* – a pointer to an integer variable.

outlen must be NULL if information is being set.

When information is being retrieved, *outlen* is an optional parameter. If supplied, Client-Library sets the variable to the length, in bytes, of the requested information.

If the information is longer than *buflen* bytes, an application can use the value of \*outlen to determine how many bytes are needed to hold the information.

Table 2-3 summarizes the interaction between *action*, *buffer*, *buflen*, and *outlen*:

Table 2-3: Interaction between action, buffer, buflen, and outlen parameters

action	buffer	buflen	outlen	What happens
CS_CLEAR	NULL	CS_UNUSED	NULL	The Client-Library information is cleared by resetting it to its default value.

action	buffer	buflen	outlen	What happens
CS_SET	A pointer to a null- terminated character string	CS_NULLTERM or the length of the string, not including the null terminator	NULL	The Client-Library information is set to the value of the *buffer character string.
CS_SET	A pointer to a character string that is not null-terminated	The length of the string	NULL	The Client-Library information is set to the value of the *buffer character string.
CS_SET	A pointer to a variable-length, noncharacter value (for example, binary data)	The length of the data	NULL	The Client-Library information is set to the value of the *buffer data.
CS_SET	A pointer to a fixed- length or symbolic value	CS_UNUSED	NULL	The Client-Library information is set to the value of the integer or symbolic value.
CS_SET	NULL	0 or CS_UNUSED	NULL	The Client-Library information is set to NULL.
CS_GET	A pointer to space large enough for the return character string plus a null terminator	The length of *buffer	Supplied or NULL	The return value is copied to *buffer.  A null terminator is appended.  If supplied, *outlen is set to the length of the return value, including the null terminator.
CS_GET	A pointer to space that is not large enough for the return character string plus a null terminator	The length of *buffer	Supplied or NULL	No data is copied to *buffer.  If supplied, *outlen is set to the length of the return value, including the null terminator.  The routine returns CS_FAIL.
CS_GET	A pointer to space that is large enough for the return variable-length, noncharacter data	The length of *buffer	Supplied or NULL	The return value is copied to *buffer.  If supplied, *outlen is set to the length of the return value.
CS_GET	A pointer to space that is not large enough for the return variable- length, noncharacter data	The length of *buffer	Supplied or NULL	No data is copied to *buffer.  If supplied, *outlen is set to the length of the return value.  The routine returns CS_FAIL.

action	buffer	buflen	outlen	What happens
CS_GET	A pointer to space that is assumed to be large enough for a fixed- length or symbolic value	CS_UNUSED	Supplied or NULL	The return value is copied to *buffer.  If supplied, *outlen is set to the length of the return value.

# CHAPTER 3 Using Open Client and Server Datatypes

This chapter summarizes the datatypes that are shared by Open Client and Open Server.

Topic	Page
Types and type constants	47
Datatype summary	54
Null substitution values	61
Open Client user-defined datatypes	63

# Types and type constants

Client-Library supports a wide range of datatypes, which are shared with CS-Library and Server-Library. In most cases, they correspond directly to Adaptive Server datatypes.

## Where are datatypes declared?

The header file *cstypes.h* contains type definitions (typedefs) for all of the Open Client and Open Server datatypes. The *cstypes.h* file is included in Client-Library applications using *ctpublic.h*—there is no need to include it explicitly.

An application declaring program variables uses these type definitions in its declaration section. For example:

```
CS_CHAR buffer[40];
CS_INT result_type, count;
CS_MONEY profit;
```

#### Why use Open Client and Open Server datatypes?

There are two reasons why you should use Open Client and Open Server datatypes in your application rather than the native C datatypes: heterogeneous architecture, and portability of application code.

In a client/server application, data may be shared among machines with different architectures.

Open Client and Open Server datatypes provide a platform-independent representation for data that is transported between machines with different architectures. For example, if a client program is compiled and run on a machine that stores the bytes of integer values in a different order from the machine where the server is running, the bytes are swapped when CS\_INT values are transported over a connection. For this reason, always use the correct CS\_TYPEDEF to declare any variable that holds data to be sent to the server or read from the results of a server command.

Open Client and Open Server datatypes also permit application source code to be ported between platforms. For example, a CS\_INT is always mapped to a system datatype that matches a 4-byte integer. Always use the correct CS\_TYPEDEF to declare variables that are used in calls to Client-Library or CS-Library routines.

#### unichar datatype

unichar supports 2-byte characters, supporting multilingual client applications, and reducing the overhead associated with character-set conversions.

Designed the same as the Open Client and Open Server CS\_CHAR datatype, CS\_UNICHAR is a shared, C-programming datatype that can be used anywhere the CS\_CHAR datatype is used. The CS\_UNICHAR datatype stores character data in Unicode UCS Transformational Format 16-bit (UTF-16), which is 2-byte characters.

The Open Client and Open Server CS\_UNICHAR datatype corresponds to the Adaptive Server 12.5 UNICHAR fixed-width and UNIVARCHAR variable-width datatypes, which store 2-byte characters in the Adaptive Server database.

As a standalone, Open Client 12.5 applications can use this new functionality to convert other datatypes to and from CS\_UNICHAR at the client side, even if the server does not have the capability to process 2-byte characters.

#### **Datatypes and capabilities**

To send and receive 2-byte characters, the client specifies its preferred byte order during the login phase of the connection. Any necessary byte-swapping is performed on the server site.

Following are the Open Client ct\_capability() parameters:

- CS\_DATA\_UCHAR is a request sent to the server to determine whether the server supports 2-byte characters.
- CS\_DATA\_NOUCHAR is a parameter sent from the client to tell the server not to support unichar for this specific connection.

To access 2-byte character data, Open Client and Open Server implements:

- CS\_UNICHAR a datatype.
- CS\_UNICHAR\_TYPE a datatype constant to identify the data's datatype.

Setting the CS\_DATAFMT parameter's datatype to CS\_UNICHAR\_TYPE allows you to use existing API calls, such as ct\_bind, ct\_describe, ct\_param, and so on.

CS\_UNICHAR uses the format bitmask field of CS\_DATAFMT to describe the destination format.

For example, in the Client-Library sample program, *rpc.c*, the BuildRpcCommand() function contains the section of code that describes the datatype:

```
strcpy (datafmt.name, "@charparam");
datafmt.namelen = CS_NULLTERM;
datafmt.datatype = CS_CHAR_TYPE;
datafmt.maxlength = CS_MAX_CHAR;
datafmt.status = CS_RETURN;
datafmt.locale = NULL;
```

In this example, from the *uni\_rpc.c* sample program, the character type is defined as datafmt.datatype = CS\_CHAR\_TYPE. Use an ASCII text editor to edit the datafmt.datatype field to:

```
strcpy (datafmt.name, "@charparam");
datafmt.namelen = CS_NULLTERM;
datafmt.datatype = CS_UNICHAR_TYPE;
datafmt.maxlength = CS_MAX_CHAR;
```

```
datafmt.status = CS_RETURN;
datafmt.locale = NULL;
```

Samples are found in *%SYBASE*%\*%SYBASE\_OCS*%\*sample* for Windows, and in *\$SYBASE*/*\$SYBASE\_OCS*/*sample* for UNIX.

Since CS\_UNICHAR is a UTF-16 encoded Unicode character datatype that is stored in 2 bytes, the maximum length of CS\_UNICHAR string parameter sent to the server is restricted to one-half the length of CS\_CHAR, which is stored in 1-byte format.

Table 3-1 lists the CS\_DATAFMT bitmask fields.

Bitmask field	Description			
CS_FMT_NULLTERM	The data is 2-byte Unicode null-terminated (0x0000).			
CS_FMT_PADBLANK	The data is padded with 2-byte Unicode blanks to the full length of the destination variable (0x0020).			
CS_FMT_PADNULL	The data is padded with 2-byte Unicode nulls to the full length of the destination variable (0x0000).			
CS_FMT_UNUSED	No format information is provided.			

Table 3-1: CS\_DATAFMT structure

#### isql and bcp utilities

Both the isql and the bcp utilities automatically support unichar data if the server supports 2-byte character data. bcp now supports 4K, 8K and 16K page sizes.

If the client's default character set is UTF-8, isql displays 2-byte character data, and bcp saves 2-byte character data in the UTF-8 format. Otherwise, the data is displayed or saved, respectively, in 2-byte Unicode data in binary format.

Use isql -Jutf8 to set the client character set for isql. Use bcp -Jutf8 to set the client character set for the bcp utility.

#### Limitations

The server to which the Open Client and Open Server is connecting must support 2-byte Unicode datatypes, and use UTF-8 as the default character set.

If the server does not support 2-byte Unicode datatypes, the server returns an error message: "Type not found. Unichar/univarchar is not supported."

CS\_UNICHAR does not support the conversion from UTF-8 to UTF-16 byte format for CS\_BOUNDARY and CS\_SENSITIVITY. All other datatype formats are convertible.

CS\_UNICHAR does not provide C programming operations on UTF-16 encoded Unicode data such as Unicode character strings. For full support for Unicode character strings, you must use the Sybase product, Unilib. See the *Unilib Reference Manual* at http://sybooks.sybase.com. The reference manual is part of the Sybase Unicode Developers Kit 2.0.

#### unitext datatype

CS\_UNITEXT is an Open Client and Open Server C Programming datatype that corresponds directly to the server UNITEXT datatype. CS\_UNITEXT also exhibits identical syntax and semantics to CS\_TEXT. The difference is that CS\_UNITEXT encodes character data in the Unicode UTF-16 format.

#### **Datatypes and capabilities**

To send and receive 2-byte characters, the client specifies its preferred byte order during the login phase of the connection. Any necessary byte-swapping is performed on the server side.

The Open Client ct\_capability() parameters:

- CS\_DATA\_UNITEXT is a request sent to the server to determine whether the server supports 2-byte Unicode datatypes.
- CS\_DATA\_NOUNITEXT is a parameter sent from the client to tell the server not to send unitext for this specific connection.

To access 2-byte character data, Open Client and Open Server implements:

- CS\_UNITEXT a datatype.
- CS\_UNITEXT\_TYPE a datatype constant to identify the data's datatype.

Setting the CS\_DATAFMT parameter's datatype to CS\_UNITEXT\_TYPE allows you to use existing API calls, such as ct\_bind, ct\_describe, ct\_param, ct\_setparam, cs\_convert and so on.

Since CS\_UNITEXT is encoded as a UTF-16 Unicode datatype and stored in the 2-byte format, it can be used anywhere CS\_TEXT is used. The maximum length of the CS\_UNITEXT string parameter is half of the maximum length of CS\_TEXT.

Like CS\_TEXT, CS\_UNITEXT uses CS\_DATAFMT to describe the destination format. The symbols and meanings of the format field values are as follows:

Table 3-2: CS\_DATAFMT structure

Bitmask field	Description
CS_FMT_NULLTERM	The data is 2-byte Unicode null-terminated (0x0000).
CS_FMT_PADBLANK	The data is padded with 2-byte Unicode blanks to the full length of the destination variable (0x0020).
CS_FMT_PADNULL	The data is padded with 2-byte Unicode nulls to the full length of the destination variable (0x0000).
CS_FMT_UNUSED	No format information is provided.

#### isql and bcp utilities

In an Open Client application, UNITEXT is always activated, with no configuration parameter required. UNITEXT is part of the Open Client and Open Server libraries and the utilities (isql & bcp) that are shipped with them. isql displays and bcp saves the server's UNITEXT in binary format.

#### Limitations

The server to which the Open Client and Open Server is connecting must support 2-byte Unicode datatypes.

If the server does not support 2-byte Unicode datatypes, the server returns an error message. However, the client can convert other datatypes to or from CS UNITEXT.

CS\_UNITEXT does not provide C programming operations on UTF-16 encoded Unicode data such as Unicode character strings. For full support for Unicode character strings, you must use the Sybase product, Unilib. See the *Unilib Reference Manual* at http://sybooks.sybase.com. The reference manual is part of the Sybase Unicode Developers Kit 2.0.

#### xml datatype

CS\_XML is a variable-width Open Client and Open Server C Programming datatype. CS\_XML corresponds directly to CS\_TEXT and CS\_IMAGE datatypes. CS\_XML can be used anywhere CS\_TEXT and CS\_IMAGE are used to represent XML documents and contents.

#### **Datatypes and capabilities**

Following are the Open Client ct\_capability() parameters:

- CS\_DATA\_XML is a request sent to the server to determine whether the server supports XML.
- CS\_DATA\_NOXML is a parameter sent from the client to tell the server not to support xml for this specific connection.

To access XML datatypes, Open Client and Open Server implements:

- CS\_XML a datatype.
- CS\_XML\_TYPE a datatype constant to identify the data's datatype.

Setting the CS\_DATAFMT parameter's datatype to CS\_XML\_TYPE allows you to use existing API calls, such as ct\_bind, ct\_describe, ct\_param, ct\_setparam, cs\_convert and so on.

#### isql and bcp utilities

In an Open Client application, XML is always activated, with no configuration parameter required. XML is part of the Open Client and Open Server libraries and the utilities (isql & bcp) that are shipped with them. isql displays and bcp saves the server's XML in binary format.

#### Limitations

XML data can only be transmitted between client and server if the server supports XML. If there is no support, the server returns an error message. cs\_capability is used to test if the server supports XML. A client can convert other possible datatypes to or from the CS\_XML datatype.

Note the following syntax rules of XML:

- Closing XML tags cannot be omitted.
- XML tags are case sensitive.

- XML elements must be properly nested.
- XML documents must have a root element.
- XML attribute values must always be quoted.

With XML, white space is preserved and CR/LF is converted to LF.

The Open Client and Open Server does not check or validate CS\_XML documents or contents.

## What are type constants?

*Type constants* are symbolic values that identify the datatype of a program variable. Many CS-Library, Client-Library, and Server-Library routines take the address of a program variable as a CS\_VOID \* parameter. Type constants are required to identify the datatype when passing CS\_VOID \* parameters. Typically, a type constant is passed to a routine as the *datatype* field of a CS\_DATAFMT structure. (See "CS\_DATAFMT" on page 37 for more information.)

# **Datatype summary**

Table 3-3 lists Open Client and Open Server type constants, their corresponding type definitions, and their corresponding Adaptive Server datatypes.

Adaptive Server datatypes are identified by Transact-SQL keywords. See the Adaptive Server documentation for descriptions of the Adaptive Server datatypes.

Table 3-3: Datatype summary

Type category	Open Client and Open Server type constant	Description	Corresponding C datatype	Corresponding server datatype
Binary types	CS_BINARY_TYPE	Binary type	CS_BINARY	binary, varbinary
	CS_LONGBINARY_TYPE	Long binary type	CS_LONGBINARY	None
	CS_VARBINARY_TYPE	Variable-length binary type	CS_VARBINARY	None
Bit types	CS_BIT_TYPE	Bit type	CS_BIT	bit

Type category	Open Client and Open Server type constant	Description	Corresponding C datatype	Corresponding server datatype
Character types	CS_CHAR_TYPE	Character type	CS_CHAR	char, varchar
	CS_LONGCHAR_TYPE	Long character type	CS_LONGCHAR	None
	CS_VARCHAR_TYPE	Variable-length character type	CS_VARCHAR	None
	CS_UNICHAR_TYPE	Fixed-length or variable-length character type	CS_UNICHAR	unichar univarchar
	CS_XML_TYPE	Variable-length character type	CS_XML	xml
Datetime type	CS_DATE_TYPE	4-byte date type	CS_DATE	date
	CS_TIME_TYPE	4-byte time type	CS_TIME	time
	CS_DATETIME_TYPE	8-byte datetime type	CS_DATETIME	datetime
	CS_DATETIME4_TYPE	4-byte datetime type	CS_DATETIME4	smalldatetime
Numeric types	CS_TINYINT_TYPE	1-byte unsigned integer type	CS_TINYINT	tinyint
	CS_SMALLINT_TYPE	2-byte integer type	CS_SMALLINT	smallint
	CS_INT_TYPE	4-byte integer type	CS_INT	int
	CS_BIGINT_TYPE	8-byte integer type	CS_BIGINT	bigint
	CS_USMALLINT_TYPE	2-byte unsigned integer type	CS_USMALLINT	usmallint
	CS_UINT_TYPE	4-byte unsigned integer type	CS_UINT	uint
	CS_UBIGINT_TYPE	8-byte unsigned integer type	CS_UBIGINT	ubigint
	CS_DECIMAL_TYPE	Decimal type	CS_DECIMAL	decimal
	CS_NUMERIC_TYPE	Numeric type	CS_NUMERIC	numeric
	CS_FLOAT_TYPE	8-byte float type	CS_FLOAT	float
	CS_REAL_TYPE	4-byte float type	CS_REAL	real
Money types	CS_MONEY_TYPE	8-byte money type	CS_MONEY	money
	CS_MONEY4_TYPE	4-byte money type	CS_MONEY4	smallmoney
Text and image	CS_TEXT_TYPE	Text type	CS_TEXT	text
types	CS_IMAGE_TYPE	Image type	CS_IMAGE	image

Type category	Open Client and Open Server type constant	Description	Corresponding C datatype	Corresponding server datatype
	CS_UNITEXT_TYPE	Variable-length	CS_UNITEXT	unitext
		character type		

#### **Binary types**

Open Client includes three binary types, CS\_BINARY, CS\_LONGBINARY, and CS\_VARBINARY:

- CS\_BINARY corresponds to the Adaptive Server types binary and varbinary. That is, Client-Library interprets both the server binary and varbinary types as CS\_BINARY. For example, ct\_describe returns CS\_BINARY\_TYPE when describing a result column that has the server datatype varbinary.
- CS\_LONGBINARY does not correspond to any Adaptive Server type, but some Open Server applications may support CS\_LONGBINARY. An application can call ct\_capability and check the CS\_DATA\_LBIN capability to determine whether an Open Server connection supports CS\_LONGBINARY. If it does, then ct\_describe can return CS\_LONGBINARY when describing a result data item. A CS\_LONGBINARY value has a maximum length of 2,147,483,647 bytes.
- CS\_VARBINARY does not correspond to any Adaptive Server type, and Open Client routines do not return CS\_VARBINARY\_TYPE.
   CS\_VARBINARY is a structure that holds a byte array and its length:

```
typedef struct_cs_varybin
{
   CS_SMALLINT len;
   CS_BYTE array[CS_MAX_CHAR];
} CS_VARBINARY;
```

CS\_VARBINARY is provided so that programmers can write non-C programming language veneers to be written for Open Client. Typical client applications do not use CS\_VARBINARY.

#### Bit types

Open Client supports a single bit type, CS\_BIT. This type is intended to hold server bit (or Boolean) values of 0 or 1. When converting other types to bit, all nonzero values are converted to 1.

## **Character types**

Open Client has four character types, CS\_CHAR, CS\_LONGCHAR, CS\_VARCHAR, and CS\_XML:

- CS\_CHAR corresponds to the Adaptive Server types char and varchar. In
  other words, Client-Library interprets both the server char and varchar
  types as CS\_CHAR. For example, ct\_describe returns CS\_CHAR\_TYPE
  when describing a result column that has the server datatype varchar.
- CS\_LONGCHAR does not correspond to any Adaptive Server datatype, but some Open Server applications may support CS\_LONGCHAR. An application can call ct\_capability and check the CS\_DATA\_LCHAR capability to determine whether an Open Server connection supports CS\_LONGCHAR. If it does, then ct\_describe can return CS\_LONGCHAR when describing a result data item. A CS\_LONGCHAR value has a maximum length of 2,147,483,647 bytes.
- CS\_VARCHAR does not correspond to any Adaptive Server type. For this
  reason, Open Client routines do not return CS\_VARCHAR\_TYPE.
   CS\_VARCHAR is a structure provided to enable non-C programming
  language veneers to be written for Open Client. It holds a string and its
  length:

```
typedef struct_cs_varchar
{
    CS_SMALLINT len;
    CS_CHAR str[CS_MAX_CHAR];
} CS VARCHAR;
```

Typical client applications do not use CS\_VARCHAR.

 Corresponding directly to the xml datatype, CS\_XML is an addition to CS\_TEXT and CS\_IMAGE datatypes for representing XML data.
 CS\_XML represents XML data in an unparsed format and can be used anywhere CS\_TEXT and CS\_IMAGE is used, for example, in cs\_convert, ct\_bind, or ct\_param. CS\_XML only fetches data if the server supports XML datatypes. CS\_DATA\_XML (request) and CS\_DATA\_NOXML (response), are added to ct\_capability to determine the server's capability to support XML datatypes.

CS\_XML is always activated, and its datatype constant is CS\_XML\_TYPE. The xml datatype is mapped to TDS\_XML.

## **Datetime types**

Open Client supports four datetime types: CS\_DATE, CS\_TIME, CS\_DATETIME, and CS\_DATETIME4. These datatypes are intended to hold 8-byte and 4-byte datetime values:

- CS\_DATE corresponds to the Adaptive Server date datatype with a range of legal values from January 1, 0001 to December 31, 9999.
- CS\_TIME corresponds to the Adaptive Server time datatype, with a range of legal values from 12:00:00.000 to 11:59:59:999 with a precision of 1/300th of a second (3.33 ms).
- CS\_DATETIME corresponds to the Adaptive Server datetime datatype, with a range of legal values from January 1, 1753 to December 31, 9999, with a precision of 1/300th of a second (3.33 ms).
- CS\_DATETIME4 corresponds to the Adaptive Server smalldatetime datatype, with a range of legal values from January 1, 1900 to June 6, 2079, with a precision of 1 minute.

An application can call the CS-Library routine cs\_convert to initialize a datetime type from a character string. cs\_convert recognizes all of the date and time formats valid for Transact-SQL datetime character strings. See the "Datatypes" topic in the Adaptive Server Enterprise *Reference Manual* for more information about these formats.

cs\_convert can also convert a CS\_DATETIME or CS\_DATETIME4 value into a character string.

Other routines that are useful when working with datetime values include:

- cs\_cmp, which compares two data values.
- cs\_dt\_crack, which maps a datetime value to a CS\_DATEREC structure. A CS\_DATEREC contains distinct fields for the different parts of a datetime value.

 cs\_dt\_info, which retrieves language-specific datetime information such as day names. This routine also configures the format for converting datetime data values to character strings.

cs\_convert, cs\_cmp, cs\_dt\_crack, and cs\_dt\_info use locale information that is specified indirectly, using the CS\_CONTEXT, or directly, using a CS\_LOCALE structure. (See "CS\_LOCALE" on page 35.) An application can change the locale information for a CS\_CONTEXT by calling cs\_config to set the CS\_LOC\_PROP property for the context.

## **Numeric types**

Open Client supports a wide range of numeric types:

- Integer types include CS\_TINYINT, a 1-byte integer, CS\_SMALLINT, a 2-byte integer, CS\_INT, a 4-byte integer, CS\_BIGINT, an 8-byte integer, CS\_USMALLINT, an unsigned 2-byte integer, CS\_UINT, an unsigned 4byte integer and CS\_UBIGINT, an unsigned 8-byte integer.
- CS\_REAL corresponds to the Adaptive Server datatype real and is implemented as a C-language float type.
- CS\_FLOAT corresponds to the Adaptive Server datatype float and is implemented as a C-language double type.
- CS\_NUMERIC and CS\_DECIMAL correspond to the Adaptive Server datatypes numeric and decimal. These datatypes provide platformindependent support for numbers with precision and scale.

The Adaptive Server datatypes numeric and decimal are equivalent, and CS\_DECIMAL is defined as CS\_NUMERIC.

#### Money types

Open Client supports two money datatypes, CS\_MONEY and CS\_MONEY4. These datatypes are intended to hold 8-byte and 4-byte money values, respectively:

- CS\_MONEY corresponds to the Adaptive Server money datatype, with legal values between -\$922,337,203,685,477.5807 and +\$922,337,203,685,477.5807.
- CS\_MONEY4 corresponds to the Adaptive Server smallmoney datatype, with legal values between -\$214,748.3648 and +\$214,748.3647.

An application can call the CS-Library routine cs\_convert to initialize a money type from a character string. The cs\_convert routine recognizes all of the money formats valid for Transact-SQL money character strings. See "Datatypes" in the Adaptive Server Enterprise *Reference Manual* for more information about these formats.

The cs\_convert routine can also convert a CS\_MONEY or CS\_MONEY4 value into a character string.

Money values cannot be manipulated with standard C operators because they are stored in structures. To perform arithmetic operations on money values, an application can either:

- Call the CS-Library routine cs\_calc to perform the arithmetic operation, or
- Call cs\_convert to convert the money type to a datatype with a standard C equivalent (such as CS FLOAT).

The cs\_cmp routine can be called to compare money values.

#### Text and image types

Open Client supports a *text* datatype, CS\_TEXT, a *unitext* datatype, CS\_UNITEXT, an *image* datatype, CS\_IMAGE:

- CS\_TEXT corresponds to the server datatype text, which describes a variable-length column containing up to 2,147,483,647 bytes of printable character data.
- CS\_UNITEXT corresponds to the server datatype unitext. As with text, unitext describes a variable length column containing up to 2,147,483,647 bytes of printable data. The difference is that unitext character data is stored with Unicode UTF-16 encoding rather than the default character set on the server.
- CS\_IMAGE corresponds to the server datatype image, which describes a variable-length column containing up to 2,147,483,647 bytes of binary data.

Small *text*, *unitext* and *image* data values require no special handling. Result values can be bound to program variables and subsequently fetched, and input data values can be entered into a database using the Transact-SQL insert and update commands. However, when *text*, *unitext* and *image* values are large, it is usually more practical for an application to use routines that allow the text, unitext or image data to be handled one chunk at a time.

#### These routines are:

- ct\_data\_info, which sets or retrieves a CS\_IODESC structure. A
  CS\_IODESC structure describes the text, unitext or image data that is to be
  read from or written to the server.
- ct\_get\_data, which reads a chunk of data from the result stream.
- ct\_send\_data, which writes a chunk of data to the command stream.

For more information about text, unitext and image data processing, see the "text and image Data Handling" topics page in the Open Client *Client-Library/C Reference Manual*.

#### **Null substitution values**

When a row containing NULL values is fetched from a server, Client-Library substitutes specified "null substitution values" for the null columns when copying the row data to program variables.

Table 3-4 lists Client-Library's default null substitution values:

Table 3-4: Default null substitution values

Destination type	Null substitution value
CS_BINARY_TYPE	Empty array
CS_VARBINARY_TYPE	Empty array
CS_BIT_TYPE	0
CS_CHAR_TYPE	Empty string
CS_VARCHAR_TYPE	Empty string
CS_DATE_TYPE	4 bytes of zeros
CS_DATETIME_TYPE	8 bytes of zeros
CS_DATETIME4_TYPE	4 bytes of zeros
CS_TINYINT_TYPE	0
CS_SMALLINT_TYPE	0
CS_BIGINT_TYPE	0
CS_INT_TYPE	0
CS_UINT_TYPE	0
CS_UBIGINT_TYPE	0
CS_USMALLINT_TYPE	0
CS_DECIMAL_TYPE	0.0 (with default scale and precision)
CS_NUMERIC_TYPE	0.0 (with default scale and precision)
CS_FLOAT_TYPE	0.0
CS_REAL_TYPE	0.0
CS_MONEY_TYPE	\$0.0
CS_MONEY4_TYPE	\$0.0
CS_BOUNDARY_TYPE	Empty string
CS_SENSITIVITY_TYPE	Empty string
CS_TEXT_TYPE	Empty string
CS_UNITEXT_TYPE	Empty string
CS_TIME_TYPE	4 bytes of zeros
CS_XML_TYPE	Empty string
CS_IMAGE_TYPE	Empty array

To change null substitution values, an application can call the CS-Library routine cs\_setnull.

## Open Client user-defined datatypes

If an application that needs to use a datatype that is not included in the standard Open Client datatypes, you can create a user-defined datatype. For example, you might create a user-defined datatype that represents encrypted character data. To create a user-defined datatype:

1 Create the new datatype name. For example:

```
typedef char ENCRYPTED CHAR;
```

2 Define a type constant that represents the datatype. For example:

```
#define ENCRYPTED TYPE CS USERTYPE + 2;
```

Because the Open Client routines ct\_bind and cs\_set\_convert use symbolic type constants to identify datatypes, you must define a type constant for each user-defined type. User-defined type constants must be greater than or equal to CS\_USERTYPE.

- 3 Call cs\_set\_convert to install custom conversion routines to convert between standard Open Client datatypes and the user-defined datatype. For the ENCRYPTED\_CHAR user-defined datatype in the example above, you might define and install custom conversion routines that encrypt and decrypt character data. You might, for example, install an encryption routine for conversions from CS\_CHAR\_TYPE to ENCRYPTED\_TYPE, and install a decryption routine for conversions from ENCRYPTED\_TYPE to CS\_CHAR\_TYPE.
- 4 Call cs\_setnull to define a null substitution value for the user-defined datatype.

After conversion routines are installed, an application can bind server results to a user-defined datatype:

```
mydatafmt.datatype = ENCRYPTED_CHAR;
ct_bind(cmd, 1, &mydatafmt, mycodename, NULL,
NULL);
```

Custom conversion routines are called transparently, whenever required, by ct\_bind and cs\_convert.

**Note** Do not confuse Open Client user-defined datatypes with Adaptive Server user-defined datatypes. Open Client user-defined datatypes are C-language types, declared within an application. ASE user-defined datatypes are database column datatypes, created with the system stored procedure sp\_addtype.

# CHAPTER 4 Handling Errors and Messages

This chapter describes how to program your applications to handle Client-Library and server error and informational messages.

Topic	Page
About messages	65
Handling messages with callback routines	67
Handling messages inline	70
Sequencing long messages	72
Extended error data	73
Server transaction states	74

# **About messages**

Client-Library generates messages in response to a wide range of error and informational conditions. These messages are called "Client-Library messages" or "client messages."

Servers also generate messages in response to error and informational conditions. These messages are called "server messages."

## How to identify messages

Do not confuse Client-Library messages with Client-Library return codes, or server messages with message results.

#### Client-Library messages and Client-Library return codes

Client-Library messages are generated in response to Client-Library errors and other conditions of interest. Each Client-Library message includes a number, text, and severity level.

Return codes are symbolic values that indicate success, failure, or other conditions of interest. All Client-Library routines use return codes.

Generally speaking, when a Client-Library routine returns CS\_FAIL, Client-Library generates a message, but Client-Library can also generate messages at other times.

Applications need to handle messages in addition to checking return codes.

#### Server messages and message results

Do not confuse server messages and message results.

Server messages are generated by a server in response to server errors or other exceptional conditions. Each server message includes a number, text, and severity level.

Message results are a type of result that can be sent in response to normal command execution—see "Processing Message Results" on page 6-12 for more information.

Server messages and message results are not related.

### Two methods for handling messages

An application can handle Client-Library and server messages using one of two methods:

- Callbacks the application installs its own routines to handle Client-Library and server messages. When a message is generated, Client-Library calls the appropriate callback and passes details about the message using the callback's input parameters.
- Inline message handling in mainline code, the application periodically calls ct\_diag to retrieve messages.

Callbacks have these advantages:

- They are relatively automatic. Once installed, callbacks are triggered whenever a message occurs.
- They centralize message-handling code.
- They provide a way for an application to gracefully handle unexpected errors. An application that handles errors using the inline method may not successfully trap unanticipated errors.

Inline error handling, on the other hand, has the advantage of operating under an application's direct control, which allows an application to check for messages at particular times. For example, an application might call ct\_con\_props a dozen times to customize a connection but check for errors only after the last call.

Most applications use callbacks to handle messages, but an application that is running on a platform-and-language combination that does not support callbacks must use the inline method.

An application indicates which method it will use by calling ct\_callback to install message callbacks or by calling ct\_diag to initialize inline message handling.

#### Combining the methods

An application can use different methods on different connections and can switch back and forth between the two methods, but these techniques are not useful in typical applications.

When moving from the inline to the callback method, installing either type of message callback for a connection turns off inline error handling. Client-Library discards any saved messages.

When moving from the callback to the inline method, calling ct\_diag to initialize inline message handling deinstalls a connection's message callbacks. If this occurs, the connection's first call to ct\_diag retrieves a warning message.

## Handling messages with callback routines

Most applications use callbacks to handle Client-Library and server messages. The application defines and installs callback routines to handle Client-Library and server messages. When a message is generated, Client-Library calls the appropriate callback and passes details about the message using the callback's input parameters.

To use the callback method, an application must define and install:

- A client-message callback to handle Client-Library messages
- A server-message callback to handle server messages

An application calls ct\_callback to install a message callback. Once installed, the callbacks are automatically triggered when a Client-Library or server message occurs.

Client-Library stores callback locations in the CS\_CONNECTION and CS\_CONTEXT structures. Because of this, when a Client-Library error occurs that makes a CS\_CONNECTION or CS\_CONTEXT structure unusable, Client-Library cannot call the client-message callback. Instead, the routine that caused the error returns CS\_FAIL.

#### Defining a client-message callback

A client-message callback is a C function that is defined as follows:

```
CS_RETCODE clientmsg_cb(context, connection, message)

CS_CONTEXT *context;
CS_CONNECTION *connection;
CS_CLIENTMSG *message;
```

#### where:

- context is a pointer to the CS\_CONTEXT structure for which the message occurred.
- *connection* is a pointer to the CS\_CONNECTION structure for which the message occurred. *connection* can be NULL.
- message is a pointer to a CS\_CLIENTMSG structure containing Client-Library message information. For information about the CS\_CLIENTMSG structure, see the "CS\_CLIENTMSG Structure" topics page in the Open Client Client-Library/C Reference Manual.

*message* can have a new value each time the client-message callback is called.

Like other callbacks, a client-message callback is limited as to which Client-Library routines it can call. A client-message callback can call only the following routines:

- ct\_config, to retrieve information only
- ct\_con\_props, to retrieve information or to set the CS\_USERDATA property only
- ct\_cmd\_props, to retrieve information or to set the CS\_USERDATA property only

ct\_cancel(CS CANCEL ATTN)

A client-message callback must return one of the following return codes:

- CS\_SUCCEED, to instruct Client-Library to continue any processing that
  is occurring on this connection. In the case of timeout errors,
  CS\_SUCCEED causes Client-Library to wait for one additional timeout
  period. At the end of this period, Client-Library calls the client-message
  callback again.
- CS\_FAIL, to instruct Client-Library to terminate any processing that is currently occurring on this connection. A return of CS\_FAIL results in the connection being marked as dead. To continue using the connection, the application must close the connection and then reopen it.

#### Defining a server-message callback

A server-message callback is a C function that is defined as follows:

```
CS_RETCODE servermsg_cb(context, connection, message)

CS_CONTEXT *context;

CS_CONNECTION *connection;

CS_SERVERMSG *message;
```

#### where:

- context is a pointer to the CS\_CONTEXT structure for which the message occurred.
- *connection* is a pointer to the CS\_CONNECTION structure for which the message occurred. *connection* can be NULL.
- message is a pointer to a CS\_SERVERMSG structure containing server message information. See the "CS\_SERVERMSG Structure" topics page in the Open Client Client-Library/C Reference Manual for CS\_SERVERMSG field descriptions.

message can have a new value each time the server-message callback is called.

Like other callbacks, a server-message callback is limited as to which Client-Library routines it can call. A server-message callback can call only the following routines:

ct\_config, to retrieve information only

- ct\_con\_props, to retrieve information or to set the CS\_USERDATA property only
- ct\_cmd\_props, to retrieve information or to set the CS\_USERDATA property only
- ct\_cancel(CS\_CANCEL\_ATTN)
- ct\_res\_info, ct\_bind, ct\_describe, ct\_fetch, and ct\_get\_data, to process extended error data only

A server-message callback must return CS SUCCEED.

### Installing callbacks

An application calls ct\_callback to install a client or server-message callback.

If an application installs callbacks at the context level, all connection structures allocated within the context inherit the callbacks.

To "deinstall an existing callback routine, call ct\_callback with *action* as CS\_SET and *func* as NULL.

To replace an existing callback routine with a new one, call ct\_callback with *action* as CS\_SET install the new routine. ct\_callback replaces the existing callback with the new callback.

To obtain a pointer to an existing callback, call ct\_callback with *action* as CS\_SET and *func* as the address of a CS\_VOID \* variable. ct\_callback places the address of the callback in the variable.

# Handling messages inline

A Client-Library application calls ct\_diag to handle Client-Library and server messages inline.

An application can use inline error handling at the connection level only. That is, inline error handling cannot be enabled for a context. If an application has more than one connection, it must make separate ct\_diag calls for each connection.

An application calls ct\_diag to:

Initialize inline error handling.

- Clear messages.
- Get messages.
- Limit the number of saved messages.
- Find out how many messages are currently saved.
- Retrieve the CS\_COMMAND structure on which extended error data (if any) is available. For more information on extended error data, see "Extended error data" on page 73.

Client-Library does not start saving messages for a connection until inline error handling has been initialized for the connection.

An application can retrieve client-message information into a CS\_CLIENTMSG structure or a SQLCA, SQLCODE, or SQLSTATE structure. An application can retrieve server-message information with a CS\_SERVERMSG structure or a SQLCA, SQLCODE, or SQLSTATE structure. For information about these structures, see the Open Client *Client-Library/C Reference Manual*.

If a Client-Library error occurs that makes a CS\_CONNECTION structure unusable, ct\_diag returns CS\_FAIL when called to retrieve information about the original error.

## The CS\_EXTRA\_INF property

An application that is retrieving messages into a SQLCA, SQLCODE, or SQLSTATE should set the Client-Library property CS\_EXTRA\_INF to CS\_TRUE.

The CS\_EXTRA\_INF property determines whether or not Client-Library returns certain kinds of informational messages, such as the number of rows affected by a command. Normally, an application can call ct\_res\_info to obtain this information. With CS\_EXTRA\_INF set to CS\_TRUE, the information is returned as a Client-Library message.

An application that is not using the SQL structures can also set CS\_EXTRA\_INF to CS\_TRUE. In this case, the extra information is returned as standard Client-Library messages.

## The CS\_DIAG\_TIMEOUT\_FAIL property

When inline error handling is in effect, the CS\_DIAG\_TIMEOUT\_FAIL property determines whether Client-Library fails or retries on Client-Library timeout errors.

# **Sequencing long messages**

Message callback routines and ct\_diag return Client-Library and server messages in CS\_CLIENTMSG and CS\_SERVERMSG structures. In the CS\_CLIENTMSG structure, the message text is stored in the *msgstring* field. In the CS\_SERVERMSG structure, the message text is stored in the *text* field. Both *msgstring* and *text* are CS\_MAX\_MSG bytes long.

If a message longer than CS\_MAX\_MSG - 1 bytes is generated, Client-Library's default behavior is to truncate the message. However, an application can use the CS\_NO\_TRUNCATE property to instruct Client-Library to "sequence" long messages instead of truncating them.

When Client-Library is sequencing long messages, it uses as many CS\_CLIENTMSG or CS\_SERVERMSG structures as necessary to return the full text of a message. The message's first CS\_MAX\_MSG bytes are returned in one structure, its second CS\_MAX\_MSG bytes in a second structure, and so forth.

Client-Library null terminates only the last chunk of a message. If a message is exactly CS\_MAX\_MSG bytes long, the message is returned in two chunks: the first contains CS\_MAX\_MSG bytes of the message and the second contains a null terminator.

If an application is using callback routines to handle messages, Client-Library calls the callback routine once for each message chunk.

If an application use ct\_diag to handle messages, it must call ct\_diag once for each message chunk.

**Note** The SQLCA, SQLCODE, and SQLSTATE structures do not support sequenced messages. An application cannot use these structures to retrieve sequenced messages. Messages that are too long for these structures are truncated.

Operating system messages are reported in the *osstring* field of the CS\_CLIENTMSG structure. Client-Library does not sequence operating system messages.

For more information on sequenced messages, see the "Error and Message Handling" topics page in the Open Client *Client-Library/C Reference Manual*.

#### **Extended error data**

Some server messages have extended error data associated with them, which is additional information about the error. For Adaptive Server messages, the additional information usually describes which column or columns provoked the error.

Client-Library makes extended error data available to an application in the form of a parameter result set, where each result item is a piece of extended error data. A piece of extended error data can be named and can be any datatype.

An application can retrieve extended error data but is not required to do so.

#### Uses of extended error data

Applications that allow end users to enter or edit data often need to report errors to their users at the column level. However, the standard server message mechanism makes column-level information available only within the text of the server message. Extended error data provides a means for applications to conveniently access column-level information.

For example, imagine an application that allows end users to enter and edit data in the titleauthor table in the pubs2 database. titleauthor uses a key composed of two columns, au\_id and title\_id. Any attempt to enter a row with au\_id and title\_id values that match those in an existing row causes a "duplicate key" message to be sent to the application.

On receiving this message, the application must identify the problem column or columns to the end user so that the user can readily correct them. This information is also available in the text of the duplicate key message, but an application must parse the text to extract the column names.

For information about how to identify and process extended error data, see the "Error and Message Handling" topics page in the Open Client *Client-Library/C Reference Manual*.

### Server transaction states

Server transaction state information is useful when an application needs to determine the outcome of a transaction. Table 4-1 lists the symbolic values that represent transaction states.

Table 4-1: Transaction states

Symbolic value	Meaning
CS_TRAN_IN_PROGRESS	A transaction is in progress.
CS_TRAN_COMPLETED	The most recent transaction completed successfully.
CS_TRAN_STMT_FAIL	The most recently executed statement in the current transaction failed.
CS_TRAN_FAIL	The most recent transaction failed.
CS_TRAN_UNDEFINED	A transaction state is not defined.

For information about how to retrieve server transaction states in mainline code and from within a server callback routine, see the "Error and Message Handling" topics page in the Open Client *Client-Library/C Reference Manual*.

# CHAPTER 5 Choosing Command Types

Client-Library provides several command types. This chapter introduces each command type, explains how they are used, and discusses their advantages and disadvantages.

Topic	Page
Command overview	75
Types of commands	75
Executing commands	76
Language commands	78
RPC commands	80
Client-Library cursor commands	86
Dynamic SQL commands	87
Message commands	88
Package commands	90
Send-data commands	90

### **Command overview**

In a Client-Library application, a command is a stream of Tabular Data Stream (TDS) protocol symbols and data sent from a client to the server. The command describes some operation that the server is to perform and provides parameter data for the operation. In response to an application's API calls, Client-Library encodes commands in the TDS protocol.

# Types of commands

Table 5-1 summarizes the Client-Library command types.

Table 5-1: Summary of command types

Command type	Initiated by	Summary
Language	ct_command	Defines the text of a query that the server will parse, interpret, and execute.
RPC, Package	ct_command	Specifies the name of a server procedure (Adaptive Server stored procedure or Open Server registered procedure) to be executed by the server. The procedure must already exist on the server.
		Package commands are available only to client applications that connect to Open Server for CICS server applications. They are otherwise identical to RPC commands.
Cursor	ct_cursor	Initiates one of several commands to manage a Client-Library cursor.
Dynamic SQL	ct_dynamic	Initiates a command to execute a literal SQL statement (with restrictions on statement content) or to manage a prepared dynamic SQL statement.
Message	ct_command	Initiates a message command and specifies the message-command ID number.
Send-Data	ct_command	Initiates a command to upload a large text/image column value to the server.

## **Executing commands**

All commands are executed with these steps:

- 1 Initiate the command This step identifies the command type and what it executes.
- 2 Define parameter values Some commands require parameter data as input.
- 3 Send the command ct\_send writes the command symbols and data to the network. The server then reads, interprets, and executes the command.
- 4 Process the results of the command ct\_results, called in a loop, reads the results of the command. See "Structure of the basic loop" on page 94 for more information.

#### Initiating a command

An application can send several types of commands to a server:

- An application calls ct\_command to initiate a language, message, package, remote procedure call (RPC), or send-data command.
- An application calls ct\_cursor to initiate a cursor command.
- An application calls ct\_dynamic to initiate a dynamic SQL command.

### Defining parameters for a command

The following types of commands can take parameters:

- A language command, when the command text contains variables
- An RPC command, when the stored procedure takes parameters
- A cursor-declare command, when the body of the cursor contains host language parameters
- A cursor-open command, when the body of the cursor contains host language parameters
- A message command
- A dynamic SQL execute command

An application calls ct\_param or ct\_setparam once for each parameter that a command requires. These routines perform the same function, except that ct\_param copies a parameter value, while ct\_setparam copies the address of a variable that contains the value. If ct\_setparam is used, Client-Library reads the parameter value when the command is sent. The ct\_setparam method allows the application to change parameter values before resending the command.

#### **Processing results**

Each time a command is sent, the application must process or cancel the results. A typical application calls ct\_results until it returns a value other than CS\_SUCCEED. See "Structure of the basic loop" on page 94 for more information.

#### Resending a command

For most command types, Client-Library allows an application to resend the command immediately after the results of previous execution have been processed. The application resends commands as follows:

- If necessary, the application changes values in parameter source variables.
   The application must have specified the addresses of the parameter source variables with ct\_setparam when defining the command.
- The application calls ct\_send to resend the command.

An application can resend all types of commands except:

- Send-data commands initiated by ct\_command(CS\_SEND\_DATA\_CMD)
- Send-bulk commands initiated by ct\_command(CS\_SEND\_BULK\_CMD)

## Language commands

A language command sends the text of a query to the server. The server responds by parsing and executing the command.

Language commands for Adaptive Server must be written in Transact-SQL. Other servers, such as Replication Server®, use a different language.

## **Building language commands**

Your application initiates a language command by calling ct\_command with *type* as CS\_LANG\_CMD and \*buffer as the language text. For example, the call below initiates a language command to select rows from the authors table in the pubs2 database:

```
ret = ct_command(cmd, CS_LANG_CMD,
   "select au_lname, city from pubs2..authors \
   where state = 'CA'",
   CS_NULLTERM, CS_UNUSED);
```

Language commands can take parameters. For Adaptive Server client applications, parameter placement is indicated by undeclared variables in the command text. For example, a language command such as the one below takes a parameter whose value is substituted for "@state\_name":

```
select au_lname, city from pubs2..authors \
    where state = @state name"
```

Parameters are useful when your code executes the same language command more than once.

## **Results-handling for language commands**

Code your application to handle the results of a language command with a standard results loop, as discussed in "Structure of the basic loop" on page 94.

Language commands can return the result types listed in Table 5-2, for the given reasons:

Table 5-2: Result types from the execution of a language command

Result type	Meaning/when received
CS_ROW_RESULT	Regular rows, sent in response to a select statement executed by the language batch or by a called stored procedure.
CS_COMPUTE_RESULT	Compute rows, sent in response to a selectstatement that contains a compute clause. The select statement can be executed by the language batch or by a called stored procedure.
CS_PARAM_RESULT	Output parameter values, sent in response to an exec statement that passes parameter values. (Parameters must be qualified with output in the exec statement.) Output parameter values are received after the results of all statements executed by the procedure.
CS_STATUS_RESULT	A stored procedure's return status, sent in response to an exec statement. The return status is received after the results from all statements executed by the procedure.
CS_COMPUTEFMT_ RESULT, CS_ROWFMT_RESULT	Format results, seen only if the CS_EXPOSE_FMTS connection property is CS_TRUE (the default is CS_FALSE).
CS_CURSOR_ RESULT	Cursor result rows are retrievable using ct_fetch or ct_scroll_fetch.
CS_CMD_DONE	Placeholder to indicate that the results of one logical command have been processed. Seen after the following events:
	The results from each statement executed in the language batch have been processed.
	The results of each select statement executed by a called stored procedure have been completely processed.

Result type	Meaning/when received
CS_CMD_SUCCEED	Indicates the success of an insert, update, or exec statement that was executed directly by the language batch.
CS_CMD_FAIL	Indicates that the command or a statement within the language batch failed to execute.

### When to use language commands

Language commands are useful to applications that execute ad hoc queries. For example, the Sybase isql command interpreter allows an end user to enter queries, sends the queries to the server as a language command, and displays the results.

Language commands are also useful in client-side middleware applications that pass SQL queries to a Sybase server through Client-Library.

### When not to use language commands

For better performance, you can code applications that always execute the same query to invoke stored procedures instead. Instead of coding the query in the C application code, you can create a stored procedure to execute the query and use an RPC command to invoke the stored procedure. This method can be faster because the server does not need to parse and interpret the query each time it executes.

Stored procedures can be considerably faster when a single invocation of the procedure replaces several client commands.

Stored procedures can be executed either by an execute language command or by an RPC command. See "RPCs versus execute language commands" on page 85 for a discussion of the differences between these methods.

#### **RPC** commands

An RPC command sends the name of a stored procedure or registered procedure to the server, plus values for the procedure's parameters, if any. If the procedure exists, the server executes it and returns the results.

RPC commands to Adaptive Server invoke stored procedures. RPC commands to an Open Server application invoke either registered procedures or the Open Server's RPC event handlers.

See the *Transact-SQL User's Guide* for information on creating Adaptive Server stored procedures. See the "Registered Procedures" topics page in the Open Server *Server-Library/C Reference Manual* for information on registered procedures.

### **Building RPC commands**

Your application initiates an RPC command by calling ct\_command with *type* as CS\_RPC\_CMD, \*buffer as the procedure name, and option as CS\_NO\_RECOMPILE, CS\_RECOMPILE, or CS\_UNUSED. For example:

The *option* value indicates whether the server should recompile the procedure. When invoking an Adaptive Server stored procedure, CS\_RECOMPILE is equivalent to specifying the with recompile clause in an equivalent execute statement. See the Adaptive Server documentation for an explanation of when recompilation is useful.

Parameter values for an RPC command are passed with calls to ct\_param or ct\_setparam. These routines are identical, except that ct\_param copies a data value, while ct\_setparam copies pointers to data values. Both routines require a CS\_DATAFMT structure, an indicator variable, and the address of a data value. For more information, see the reference pages for ct\_param and ct\_setparam in the Open Client Client-Library/C Reference Manual.

For RPC commands, code your ct\_param or ct\_setparam calls according to the following rules:

- Pass parameter values in a datatype that matches the declaration of the parameter in the stored procedure.
  - Client-Library does not convert outgoing parameter values. If necessary, use cs\_convert to convert the parameter value into the matching datatype.
- Pass all parameters by name or all parameters by position.

To pass a parameter by name, copy its name into the *name* field of ct\_param's or ct\_setparam's *datafmt* parameter, and set *datafmt.length* to match. Parameters for which you do not call ct\_param or ct\_setparam are effectively passed as NULL.

To pass parameters by position, set *datafmt.length* to 0 and call ct\_param or ct\_setparam in the order in which the parameters appear in the procedure's definition. To pass a parameter as NULL, set the associated *indicator* variable to -1.

All parameters must be passed using the same method. RPC commands that pass parameters by position usually perform better than those that pass parameters by name.

• Set *datafmt.status* to indicate whether the parameter is a return parameter.

CS\_RETURN indicates a return parameter; use CS\_INPUTVALUE for non-return parameters.

Return parameters are similar to the "pass by reference" facility offered by some programming languages. The value of the parameter, with any changes made by the procedure code, is available to the client application after the procedure completes execution. See "Return parameter values" on page 83 for more information.

• Use ct\_setparam rather than ct\_param when the command will be sent multiple times with varying parameter values.

ct\_setparam binds a parameter source variable to the initiated command, allowing the application to change the parameter's value between calls to ct\_send.

For an example that illustrates how to define an RPC command with parameters, see the reference page for ct\_param in the Open Client *Client-Library/C Reference Manual*.

## **RPC command results handling**

Code your application to handle the results of an RPC command with a standard results loop, as discussed in "Structure of the basic loop" on page 94.

RPC commands can return the result types listed in Table 5-3, for the given reasons:

Table 5-3: Result types from the execution of an RPC command

Result type	Meaning/when received
CS_ROW_RESULT	Regular rows, sent in response to a select statement executed by the procedure.
CS_COMPUTE_RESULT	Compute rows, sent in response to a selectstatement that contains a compute by clause.

Result type	Meaning/when received
CS_PARAM_RESULT	Return (output) parameter values, received after results from all statements in the procedure have been processed.
CS_STATUS_RESULT	The procedure's return status, received after results from all statements in the procedure have been processed.
CS_COMPUTEFMT_ RESULT, CS_ROWFMT_RESULT	Format results, seen only if the CS_EXPOSE_FMTS connection property is CS_TRUE (the default is CS_FALSE).
CS_CMD_DONE	Placeholder that indicates the results of one logical command have been processed. Seen after the following events:
	The results from each statement executed in the language batch have been processed
	The results of each select statement executed by a called stored procedure have been completely processed
CS_CMD_SUCCEED	Indicates that the procedure was invoked successfully, but does not mean that all the statements in the stored procedure executed successfully. Applications must always check the stored procedure's return status value to determine whether an error occurred (see "Return status values" on page 84).
CS_CMD_FAIL	Indicates that the procedure call failed. Not all errors cause CS_CMD_FAIL to be returned. A statement may fail in the stored procedure, but the server still returns a result type of CS_CMD_SUCCEED.
	Applications must always check the stored procedure's return status value to determine whether an error occurred (see "Return status values" on page 84).

#### **Return parameter values**

The server returns parameter values in the results of an RPC command for each parameter for which both of the following statements are true:

- The parameter is passed as a return parameter in the RPC command.
- The parameter is defined as an output parameter in the definition of the procedure.

If parameter data is returned, all parameter values are returned in a CS\_PARAM\_RESULT result set.

#### Return status values

Return status values are returned as a CS\_STATUS\_RESULT result set (see "Processing return status results" on page 102).

**Note** SQL statements that return a result type of CS\_CMD\_FAIL when executed by a language command may return CS\_CMD\_SUCCEED when executed by a stored procedure. Always check a stored procedure's return status to determine whether the procedure executed successfully.

If a procedure successfully completes execution, the return status is either the value explicitly returned by the procedure or 0 if the procedure lacks an explicit return statement. However, some runtime errors cause a stored procedure to abort before it executes to completion. For example, a select statement in the procedure may refer to a table that no longer exists. For these errors, Adaptive Server aborts the execution of the procedure and returns a return status value that indicates the error—see the return reference page in the Adaptive Server Enterprise *Reference Manual* for a list of return status codes and their meaning.

When a runtime error occurs inside a stored procedure, Adaptive Server does not return a result type of CS\_CMD\_FAIL. To determine whether a server-side error has occurred inside the procedure, applications should always check the return status of the stored procedure. Adaptive Server also sends server messages that describe runtime errors.

#### When to use RPC commands

RPC commands offer the following unique benefits:

- Stored procedure parameter values do not require conversion on the server.
   When invoking a stored procedure with an RPC command, parameters are passed in their declared datatypes. The server does not need to convert the parameters from character format to their declared datatypes.
- There is no other way to execute Open Server registered procedures.

Open Server registered procedures provide a relatively simple way to develop a distributed application with Open Client and Open Server. Registered procedures can be either a function in the Open Server application code, or a special type of procedure that is created by a client application and exists only to trigger client notification events when it is executed. The latter type is created when the client application invokes the sp\_regcreate Open Server system registered procedure.

- See the Open Server Server-Library/C Reference Manual for information on defining C functions that can be called as a registered procedure.
- See the sp\_regcreate reference page in the Open Server Server-Library/C Reference Manual for details on how Client-Library applications can create a registered procedure on an Open Server.
- See the "Registered Procedures" topics page in the Open Client Client-Library/C Reference Manual for information on how Client-Library applications can receive registered procedure notifications.

### RPCs versus execute language commands

A stored procedure can be executed either by an RPC command or by an execute language statement. Remote procedure calls have a few advantages over execute statements:

- An RPC command can be used to execute an Adaptive Server stored procedure or an Open Server registered procedure.
  - A Transact-SQL language command can be used only to execute an Adaptive Server stored procedure (unless the Open Server application understands Transact-SQL).
- An RPC command passes the stored procedure's parameters in their native datatypes, in contrast to the execute statement, which passes parameters in character format, within the text of the language command. This difference means that the RPC method is faster and more efficient than the execute method, because it does not require either the application program or the server to convert between native datatypes and their characterformat equivalents.
- It is simpler and faster to accommodate stored procedure return parameters if the procedure is invoked with an RPC command instead of a language command.

With an RPC command, the return parameter values automatically become available to the application as a parameter result set. (A return parameter must be specified as such when it is originally added to the RPC command stream with ct\_param or ct\_setparam.)

With an execute statement, on the other hand, the return parameter values are available only if the language command declares local variables and passes these variables (not constants) for the return parameters. Because the language command contains more than one SQL statement, this technique involves additional parsing each time the language command is executed.

## **Client-Library cursor commands**

A cursor is a symbolic name that an application attaches to a select statement. The cursor supports operations to manipulate the select's result set. See "Cursor overview" on page 111 for a list of cursor operations.

A Client-Library cursor is created with a ct\_cursor or ct\_dynamic cursor-declare command.

### **Building Client-Library cursor commands**

Chapter 7, "Using Client-Library Cursors" explains how to use Client-Library cursor commands in your application. See "Using Client-Library cursors" on page 117 for the typical call sequence.

#### When to use Client-Library cursors

Use Client-Library cursors when you want to process two or more commands at the same time while using only one server connection.

A Client-Library cursor-open command is the only command type that allows the application to send new commands over the same connection while still retrieving rows. After sending any other type of command, your application must completely process the results of the command before another command can be sent on the same connection. If the application design requires this functionality, then there is no alternative to using Client-Library cursor commands. For more information, see "Benefits of Client-Library cursors" on page 115 and "Connection and command rules" on page 33.

Note that cursors can only be declared to execute a single select statement. See "Step 1: Declare the cursor" on page 119 for more information.

#### When not to use Client-Library cursors

Cursors do incur a performance penalty relative to executing a select statement using a language or RPC command. The difference occurs because the cursor requires internal Client-Library cursor-fetch commands to retrieve cursor rows, while a regular-row result set does not. Thus, processing the results of the cursor-open command requires more network round trips. (See "Step 2: Set cursor rows" on page 125 for more information on how cursor rows are processed internally by Client-Library.) There is also additional Adaptive Server internal overhead associated with cursor processing.

## Dynamic SQL commands

Dynamic SQL is the process of generating, preparing, and executing SQL statements at runtime using commands initiated by Client-Library's ct\_dynamic routine.

## **Building Dynamic SQL commands**

Chapter 8, "Using Dynamic SQL Commands" explains how to use Client-Library cursor commands in your application. See "Program structure for the prepare-and-execute method" on page 138 for the typical call sequence.

## When to use dynamic SQL commands

Dynamic SQL prepared statement commands are the only command type that allows the application to query the server for the inputs required to execute the command and for the format of the command's results:

- A ct\_dynamic describe-input command causes the server to send the number and format of parameters that are required to execute the statement. See "Step 2: Get a description of command inputs" on page 140 for details.
- A ct\_dynamic describe-output command causes the server to send the number and formats of result columns that the statement returns. See "Step 3: Get a description of command outputs" on page 142 for details.

### When not to use dynamic SQL

In general, dynamic SQL should not be used in applications where the design does not require the specific advantages listed under "Benefits of dynamic SQL" on page 134. Dynamic SQL commands incur more overhead than language commands. Also, since they are implemented internally as temporary stored procedures, they can cause resource-contention issues in the Adaptive Server tempdb database.

See "Limitations of dynamic SQL" on page 134 and "Alternatives to dynamic SQL" on page 136 for more information.

## Message commands

Message commands can be used with custom Open Server applications. Adaptive Server does not support message commands. From the client-application programmer's perspective, a message command is equivalent to an RPC command that is called by number rather than by name.

Your application initiates a message command by calling ct\_command with *type* as CS\_MESSAGE\_CMD and \*buffer as the address of a CS\_INT variable that contains the identifier for the message command. For example:

```
CS_INT msg_id;
if (ct_command(cmd, CS_MSG_CMD, (CS_VOID *)&msg_id,
CS_UNUSED, CS_UNUSED)
!= CS_SUCCEED)
{
fprintf(stderr, "ftclient: ct_command(MSG_CMD)
failed.\n");
return CS_FAIL;
}
```

Message identifiers must be known to both the client application and the Open Server application. Typically, the message command identifiers that a server responds to are defined in a shared header file. Sybase reserves message identifiers in the range CS\_USER\_MSGID to CS\_USER\_MAX\_MSGID (inclusive) for customer use.

Message commands can take parameters. These are supplied with ct\_param or ct\_setparam. Whether parameters are passed by name or by position depends on how the Open Server application is coded.

Code your application to handle the results of a message command with a standard results loop, as discussed in "Structure of the basic loop" on page 94. Among other result types, message commands can return message results (result type of CS\_MSG\_RESULT). See "Processing message results" on page 105 for more information.

#### When to use message commands

Message commands provide an alternative to RPC commands in the design of the client interface for a custom Open Server application. A message command uses an integer identifier rather than a string RPC name and lacks the fixed-parameter list of an Open Server registered procedure.

In the Open Server code, message commands are handled by the message event handler. See the Open Server Server-Library/C Reference Manual for more information.

### When not to use message commands

Adaptive Server does not support message commands.

## Package commands

Package commands are supported only on connections to an Open Server on CICS. Package commands are otherwise similar to RPC commands.

#### Send-data commands

Send-data commands, initiated with ct\_command(CS\_SEND\_DATA), are used to upload text or image column values in chunks.

See the "text and image Data Handling" topics page in the Open Client *Client-Library/C Reference Manual* for details on how to use send-data commands in your application.

#### When to use send-data commands

For Adaptive Server client applications, send-data commands are the only way to upload large *text* or *image* column values a chunk at a time. If your application uploads text or image values that are to large to fit in a contiguous memory buffer, then send-data commands are the only practical method to perform the update.

For *text* or *image* column values that are small enough to fit into a contiguous memory buffer, the application may achieve better performance by embedding the values in insert language commands. See the "text and image Data Handling" topics page in the Open Client *Client-Library/C Reference Manual* for details on this method.

#### When not to use send-data commands

Generally, send-data commands should be avoided when designing the client interface for a custom Open Server application. Open Server application processing for send-data commands is quite complicated. If the server must allow uploads of large values in chunks, you can design the interface so that values are uploaded with multiple invocations of a message, RPC, or language command. For example, with message commands, one message command identifier might indicate the beginning of an upload operation, and another might indicate a command that contains (as a parameter) a chunk of the data value.

# CHAPTER 6 Writing Results-Handling Code

This chapter explains Client-Library's results-processing model. It covers the following topics:

Topic	Page
Types of results	93
Structure of the basic loop	94
Processing regular row results	95
Processing cursor results	97
Processing parameter results	100
Processing return status results	102
Processing compute results	102
Processing message results	105
Processing describe results	105
Processing format results	106
Values of result_type that indicate command status	107
ct_results final return code	108

# Types of results

After an application sends a command to a server, it must process any results generated by the command. Types of results include:

- Regular row results rows returned when the server processes a select statement.
- Cursor row results rows returned when the server processes a ct\_cursor Client-Library cursor-open command.
- Parameter results fetchable data that can represent:
  - Output values for an Adaptive Server stored procedure's return parameters
  - Output values for an Open Server registered procedure's return parameters

- A new timestamp value for an updated *text/image* column (seen only when processing the results of a ct\_command send-data command)
- A new timestamp value for a row that was updated with a language command containing a browse-mode update statement
- Stored procedure return status results the return value from an Adaptive Server stored procedure or Open Server registered procedure.
- Compute row results –intermediate rows returned when the server processes a select statement with a compute by clause.
- Message results a message ID returned by an Open Server application's message command handler while processing the results of a message command.
- Describe results informational results that describe the format of a prepared dynamic SQL statement's input parameters or result columns.
- Format results informational results used by Open Server gateway applications to retrieve regular row and compute row formats before the actual data arrives.

A single command can generate more than one type of result. For example, a language command that executes a stored procedure can generate multiple regular row and compute row result sets, a parameter result set, and a return status result set. For this reason, it is important that you code applications to handle all types of results that a server can generate.

The simplest way for an application to handle all result types is to process results in a loop as described in the following section.

## Structure of the basic loop

Most synchronous Client-Library programs process results using a loop controlled by ct\_results. Inside the loop, a switch takes place on the type of result that is currently available for processing, as indicated by the value of ct\_results' parameter *result\_type*. Different types of results require different types of processing.

*result\_type* is also used to indicate the outcome of a server command that returns no results, for example, an insert or delete command.

Most synchronous applications use a program structure similar to the following one to process results:

```
while ct results returns CS SUCCEED
    (optional) ct res_info to get current
        command number
    switch on result type
        ** Values of result type that indicate
        ** fetchable results:
        case CS COMPUTE RESULT...
        case CS CURSOR RESULT...
        case CS PARAM RESULT...
        case CS ROW RESULT...
        case CS STATUS RESULT...
        ** Values of result_type that indicate
        ** non-fetchable results:
        case CS COMPUTEFMT RESULT...
        case CS MSG RESULT...
        case CS ROWFMT RESULT...
        case CS DESCRIBE RESULT...
        ** Other values of result type:
        */
        case CS CMD DONE...
            (optional) ct res info to get the
                number of rows affected by
                the current command
        case CS CMD FAIL...
        case CS CMD SUCCEED...
    end switch
end while
switch on ct results' final return code
    case CS END RESULTS...
    case CS CANCELED...
    case CS FAIL...
end switch
```

# Processing regular row results

A regular row result set is generated by the execution of a Transact-SQL select statement on a server.

A regular row result set contains zero or more rows of tabular data.

An application typically calls the following routines to process a regular row result set:

- ct\_res\_info, which returns information about the current result set. Most
  often, an application uses ct\_res\_info to get the number of columns in the
  current result set. However, ct\_res\_info also returns other types of
  information—for example, the number of rows affected by the current
  command.
- ct\_describe, which returns information about a particular result item in the current result set. An application generally needs to call ct\_describe once for each result item before binding each result item to a program variable.
- ct\_bind, which binds a result item to a program variable. Binding creates an association between a result item and a data space.
- ct\_fetch, which copies result data into bound variables.

Binding is the process of associating a result item with program data space. Fetching is the process of retrieving a data instance of a result item. If binding has been specified for a result item, then fetching causes a data instance of the item to be copied into the program data space.

Most synchronous applications use a program structure similar to the following one to process a regular row result set:

```
case CS ROW RESULT
   ct res info(CS NUMDATA) to get the number of columns
    for each column:
        ct describe to get a description of the column
        ct bind to bind the column to a program variable
    end for
    while ct fetch returns CS SUCCEED or CS ROW FAIL
        if CS SUCCEED
            process the row
        else if CS ROW FAIL
            handle the row failure
        end if
    end while
    switch on ct fetch's final return code
        case CS END DATA...
        case CS CANCELED...
        case CS FAIL...
    end switch
end case
```

# **Processing cursor results**

A cursor row result set is generated when an application executes a Client-Library cursor open command.

**Note** A cursor row result set is not generated when an application executes a language command containing a Transact-SQL open statement. The open statement opens an Adaptive Server language cursor, which returns regular rows each time the application executes a Transact-SQL fetch statement. See "Language cursors versus Client-Library cursors" on page 112 for more information.

A cursor row result set contains zero or more rows of tabular data.

In general, when an application sends a command to a server, it cannot send another command on the same connection until ct\_results indicates that the results of the first command have been completely processed (by returning CS\_END\_RESULTS, CS\_CANCELED, or CS\_FAIL).

An exception to this rule occurs when ct\_results indicates cursor results. In this case, an application can call ct\_cursor and ct\_send to send cursor-update, cursor-delete, or cursor-close commands while processing the cursor result set. Using a a different CS\_COMMAND structure, the application can also send new commands over the same connection to the server. For more information, see "Benefits of Client-Library cursors" on page 115.

In addition to ct\_res\_info, ct\_describe, ct\_bind, and ct\_fetch, an application can call ct\_keydata, ct\_cursor, ct\_param, ct\_send, ct\_results, and ct\_cancel while processing a cursor result set.

Most synchronous applications use a program structure similar to the following one to process a cursor result set:

```
case CS_CURSOR_RESULT
ct_res_info(CS_NUMDATA) to get the number of columns
    for each column:
        ct_describe to get a description of the column
        ct_bind to bind the column to a program variable
    end for
    while ct_fetch returns CS_SUCCEED or CS_ROW_FAIL
        and cursor has not been closed
    if CS_SUCCEED
        process the row
    else if CS_ROW_FAIL
        handle the row failure
```

```
end if
      /* For update or delete only:
                                                      * /
         if target row is not the row just fetched
             ct keydata to specify the target row key
         end if
                                                      * /
        /* End for update or delete only
       /* To send a nested cursor update, delete, or
close command: */
         ct cursor to initiate the cursor command
         /* For updates/deletes whose "where" clause
contains variables */
         ct param or ct setparam for each parameter
         /* End for updates/deletes whose ... */
         ct send to send the command
         while ct results returns CS SUCCEED
             (...process results...)
         end while
         /* End to send a nested cursor command */
   end while
    switch on ct fetch's final return code
         case CS END DATA...
         case CS CANCELED...
         case CS FAIL...
     end switch
    if cursor was closed
         break out of outer ct results loop
     end if
 end case
```

Calls to ct\_results are nested within a ct\_fetch loop and a larger ct\_results loop (not shown).

For nested cursor-update or cursor-delete commands, after the inner ct\_results indicates that the results from the nested command have been completely processed (by returning CS\_END\_RESULTS, CS\_FAIL, or CS\_CANCELED), any subsequent calls to ct\_results will operate on results generated by the original cursor command.

For nested cursor-close commands, there are no results remaining after the cursor is closed. In this case, the application breaks out of the outer ct\_results loop after the results of the nested cursor-close command have been processed.

To cancel the cursor rows returned by the cursor-open command, an application can call ct\_cancel with *type* as CS\_CANCEL\_CURRENT. However, it is more efficient to close the cursor with a nested cursor-close command. A CS\_CANCEL\_CURRENT ct\_cancel call retrieves the unwanted rows and discards them. (It is equivalent to clearing all binds, then calling ct\_fetch until ct\_fetch returns CS\_END\_DATA.)

**Note** In your cursor application, do not use any other type of cancel besides CS\_CANCEL\_CURRENT on a connection that has an open cursor—CS\_CANCEL\_ALL or CS\_CANCEL\_ATTN can put a connection's cursors into an undefined state. Instead of canceling, the application can simply close the cursor.

### Processing scrollable cursor results

The program structure for processing scrollable cursor results is similar to that for regular cursors. The key difference is that ct\_scroll\_fetch returns CS\_SCROLL\_CURSOR ENDS when you use the CS\_FALSE option. This is indicated as follows:

```
end while
  switch on ct_scroll_fetch's final return code
      case CS_SCROLL_CURSOR_ENDS...
  end switch
  if cursor was closed
      break out of outer ct_results loop
  end if
```

end case

**Note** ct\_scroll\_fetch never returns CS\_END\_DATA as a valid return.

**Note** A warning message is generated if certain sequences of operations cause the cursor to move beyond the resultset boundary. Examples of this are the sequential use of CS\_PREV, CS\_NEXT, CS\_ABSOLUTE or CS\_RELATIVE calls, with offsets of such magnitude (relative to the current cursor position), that the cursor moves beyond the resultset boundary.

The warning messages does not indicate that an error has occurred.

For more information, see the Client-Library/C Reference Manual.

# **Processing parameter results**

A parameter result set contains a single row of parameters.

Several types of data can be returned to an application in the form of a parameter result set, including:

Return parameter values

An Adaptive Server stored procedure or an Open Server registered procedure can return output parameter data. The CS\_PARAM\_RESULT result set contains new values for the procedure's parameters, as set by the procedure code. See "RPC commands" on page 80 for a description of how applications execute stored procedures or registered procedures.

Browse mode timestamp values

Browse mode is a scheme that interactive applications can use to perform ad hoc row updates of retrieved rows. Tables involved in browse mode require a timestamp column to control simultaneous access to the data. After a client application executes a browse-mode update statement, Adaptive Server returns a parameter result set that contains the new timestamp value for the updated row. See the "Browse Mode" topics page in the Open Client *Client-Library/C Reference Manual* for more details.

A text or image column timestamp

After a client application updates a text or image column with a send-data command, Adaptive Server returns the new text timestamp for the column as a parameter result set. See the "text and image Data Handling" topics page in the Open Client *Client-Library/C Reference Manual* for more details.

#### Message result parameters

A message result set consists of a message identifier (see "Processing message results" on page 105). The message result set can be followed immediately by a parameter result set containing parameter values that accompany the message result.

An application calls ct\_res\_info, ct\_describe, ct\_bind, and ct\_fetch to process a parameter result set.

Most synchronous applications use a program structure similar to the following one to process a parameter result set:

```
case CS PARAM RESULT
   ct res info(CS NUMDATA) to get the number of parameters
    for each parameter:
        ct describe to get a description of the parameter
        ct bind to bind the parameter to a variable
   end for
  while ct fetch returns CS SUCCEED or CS ROW FAIL
        if CS SUCCEED
            process the row of parameters
        else if CS ROW FAIL
            handle the failure
        end if
    end while
  switch on ct fetch's final return code
        case CS_END_DATA...
        case CS CANCELED...
        case CS FAIL...
   end switch
end case
```

### Processing return status results

A return status result set is generated by the execution of a stored procedure. All stored procedures return a status number. See the description of the return command in the Sybase Adaptive Server Enterprise *Reference Manual* for more information.

A return status result set consists of a single row containing a return status.

An application calls ct\_bind and ct\_fetch to process a return status.

Most synchronous applications use a program structure similar to the following one to process a return status result set:

```
case CS_STATUS_RESULT
  ct_bind to bind the status to a program variable
  while ct_fetch returns CS_SUCCEED or CS_ROW_FAIL
    if CS_SUCCEED
        process the return status
    else if CS_ROW_FAIL
        handle the failure
    end if
  end while
  switch on ct_fetch's final return code
    case CS_END_DATA...
    case CS_CANCELED...
    case CS_FAIL...
  end switch
end case
```

# **Processing compute results**

A compute result set is generated by the execution of a Transact-SQL select statement that contains a compute clause. A compute clause generates a compute result set every time the value of its bylist changes. A compute result set consists of a single row containing a number of columns equal to the number of row aggregates in the compute clause.

For example, consider the query:

```
select type, price from titles
where price > $12 and type like "%cook"
order by type, price compute sum(price) by type
```

The query returns regular rows (with columns type and price). Intermixed with the regular rows, the query returns compute result sets each time the value of type changes in the regular row results. Each compute result set contains a single row with one column for the sum(price) expression.

See the Adaptive Server Enterprise *Reference Manual* for more examples of queries with a compute clause.

In addition to ct\_res\_info, ct\_describe, ct\_bind, and ct\_fetch, an application can call ct\_compute\_info while processing compute row results. ct\_compute\_info provides a variety of compute row information. The information available from ct\_compute\_info includes:

The compute ID for a compute row

A query can have more than one compute clause. ct\_compute\_info(CS\_COMP\_ID) retrieves the number of the compute clause that generated a compute result set. A compute row ID of 1 corresponds to the first compute clause in the query.

• The compute bylist

The compute by list is the list of columns that follows the by keyword in the compute clause. In the application, the by list is represented by an array of CS\_SMALLINT values, each of which represents the position of a column in the select list. For example:

If you execute this query, then the bylist values are 1 and 2, corresponding to the positions of dept and name in the select list.

ct\_compute\_info(CS\_BYLIST\_LEN) returns the length of the bylist, and ct\_compute\_info(CS\_BYLIST) populates an application-allocated array with the bylist column numbers.

Compute row select-list column IDs

Select-list column IDs are available for each column in a compute row. The select-list column ID is the select-list position of the column from which the compute-row column was derived. For example, this query returns compute rows containing one column for the sum(price) expression:

```
select type, price from titles
where price > $12 and type like "%cook"
order by type, price compute sum(price) by type
```

The corresponding select-list column ID is 2, which is the position of the price column in the select list.

ct\_compute\_info retrieves compute column IDs when called with *type* as CS\_COMP\_COLID and *colnum* as the compute column number.

#### • Compute column operators

ct\_compute\_info, when called with *type* as CS\_COMP\_OP and *colnum* as the compute column number, retrieves a symbolic constant that indicates the operator with which the column value was computed. See the ct\_compute\_info reference page in the Open Client *Client-Library/C Reference Manual* for a list of these operators.

Most synchronous applications use a program structure similar to the following one to process a compute result set:

```
case CS COMPUTE RESULT
    (optional)ct compute info to get bylist length,
   bylist, or compute row id
    ct res info(CS NUMDATA) to get the number of columns
    for each column:
        ct describe to get a description of the column
        ct bind to bind the column to a program variable
        (optional: ct compute info to get the compute
            column id or the aggregate operator for the
            compute column)
    end for
    while ct fetch returns CS SUCCEED or CS ROW FAIL
        if CS SUCCEED
            process the compute row
        else if CS ROW FAIL
            handle the failure
        end if
    end while
    switch on ct fetch's final return code
        case CS END DATA...
        case CS CANCELED...
        case CS FAIL...
   end switch
end case
```

# **Processing message results**

All types of servers can return message results.

A message result set contains no fetchable results. Instead, a message has an ID, which an application can retrieve by calling ct\_res\_info(CS\_MSGTYPE).

Message IDs in the range 1–32,767 are reserved for Adaptive Server and Sybase internal use.

Application-defined message IDs must be in the range CS\_USER\_MSGID to CS\_USER\_MAX\_MSGID.

If parameter values are associated with a message, they are returned as a separate parameter result set following the message result set. See "Processing parameter results" on page 100.

**Note** A message result set is not the same thing as a server message. Server messages are generated in response to error conditions or to indicate server conditions of interest. They are generally handled within an application's server-message callback. For more information about server messages, see Chapter 4, "Handling Errors and Messages."

An application calls ct\_res\_info to retrieve a message ID.

Most synchronous applications use a program structure similar to the following one to process a message result set:

```
case CS_MSG_RESULT
    ct_res_info to get the message ID
    code to handle the message ID
end case
```

# **Processing describe results**

A describe result set does not contain fetchable data; rather, it indicates the existence of descriptive information returned as the result of a dynamic SQL describe-input or describe-output command.

For more information on these commands, see "Step 2: Get a description of command inputs" on page 140 and "Step 3: Get a description of command outputs" on page 142.

An application can retrieve this information by calling ct\_describe, ct\_dyndesc, or ct\_dynsqlda. For more information, see "Processing parameter descriptions" on page 140 and "Processing column descriptions" on page 142.

Most applications use a program structure similar to the following one to process a describe result set:

```
case CS_DESCRIBE_RESULT
    ct_res_info to get the number of columns
    for each column:
        ct_describe or ct_dyndesc to get a description
    end for
end case
```

# **Processing format results**

Normally, format information for regular row and compute row result sets is only available while the application is processing the result set. At that time, the application can call ct\_res\_info to retrieve the number of items in the result set, ct\_describe to get a description of each item, and ct\_compute\_info to get compute information.

This mechanism works well for most applications. Some applications, however, need to be able to get format information for a result set before they process the result set. An example of this type of application is a gateway application that repackages Adaptive Server results before sending them on to a non-Sybase client.

Client-Library makes advance format information available to an application in the form of *format results*. There are two types of format results: regular row format results and compute row format results.

Format result sets contain no fetchable results. Instead, an application can call ct\_res\_info, ct\_describe, and ct\_compute\_info to retrieve format information after ct\_results indicates format results.

To receive format results, an application must set the Client-Library CS\_EXPOSE\_FMTS property to CS\_TRUE.

An application can call ct\_describe and ct\_compute\_info to retrieve format information.

A gateway application might use a program structure similar to the following one to process format results:

```
case CS_ROWFMT_RESULT
   ct_res_info(CS_NUMDATA) to get the number of columns
   for each column:
      ct_describe to get a column description
      send the information on to the gateway client
   end for
end case

case CS_COMPUTEFMT_RESULT
   ct_res_info to get the number of columns
   for each column:
      ct_describe to get a column description
      (if required:
            ct_compute_info for compute information
      end if required)
      send the information on to the gateway client
   end for
end case
```

# Values of result\_type that indicate command status

In addition to indicating the type of result set that is available for processing, ct\_results sets *result\_type* to the values below to indicate the status of command processing:

- CS\_CMD\_DONE indicates that the results of a *logical command* have been completely processed. See "Logical commands" on page 108 for an explanation of this term.
- CS\_CMD\_SUCCEED indicates the success of a command that returns no data, such as a Transact-SQL insert or delete command.
- CS\_CMD\_FAIL indicates that, due to error, the server failed to execute
  a server command. For example, the text of a language command might
  contain a syntax error or refer to a nonexistent object. In most cases, the
  server returns a server message that describes the error.

Because a Client-Library command can execute multiple server commands, an application must either:

 Continue to call ct\_results to process results generated by any other server commands contained in the original Client-Library command, or  Call ct\_cancel(CS\_CANCEL\_ALL) to cancel the Client-Library command and discard its results.

### Logical commands

ct\_results sets *result\_type* to CS\_CMD\_DONE to indicate that the results of a logical command have been completely processed. A *logical command* is any command defined using ct\_command, ct\_dynamic, or ct\_cursor, with the following exceptions:

- Each Transact-SQL select statement that returns data inside a stored procedure is a logical command. Other Transact-SQL statements inside stored procedures do not count as logical commands (including select statements that assign values to local variables).
- Each Transact-SQL statement executed by a dynamic SQL command is a distinct logical command.
- Each Transact-SQL statement in the text of language command is a logical command.

Logical commands and Client-Library commands are not equivalent. A Client-Library command can execute multiple logical commands on the server, for example, a stored procedure can execute multiple select statements that return data, and each such statement represents one logical command. A logical command can generate one or more result sets; for example, a select statement can return multiple regular-row and compute results sets.

### ct results final return code

After handling all the results of the command, your code should check the final return code from ct\_results to see if errors are indicated.

Final return code values can be the following:

- CS\_END\_RESULT indicates a normal loop exit.
- CS\_CANCELED indicates that results were canceled: ct\_cancel(CS\_CANCEL\_ALL) or ct\_cancel(CS\_CANCEL\_ATTN) was called while processing results.

• CS\_FAIL – indicates a serious client-side or network error, such as a communication failure or a memory shortage.

# CHAPTER 7 Using Client-Library Cursors

This chapter explains Client-Library cursors. It covers the following topics:

Topic	Page
Cursor overview	111
Language cursors versus Client-Library cursors	112
When to use Client-Library cursors	115
Using Client-Library cursors	117
Client-Library cursor properties	131

### **Cursor overview**

A cursor is a symbolic name that an application attaches to a select statement. The statement can be executed and its result set manipulated by performing operations on the cursor.

Cursors support the following operations:

- Declare create a new cursor by giving it a name and defining its query.
- Set cursor rows specify the number of rows from the result table to be returned with each fetch operation.
- Open execute the cursor's query and prepare it for fetch operations.
- Fetch retrieve rows from the cursor, which must be open. Each fetch operation retrieves a single row from the query's result table. This applies to both scrollable and non-scrollable cursors. Under certain conditions (as defined by the "set cursor rows" operation), more rows can be returned per fetch call.
- Update modify the values in a fetched row. The update affects the tables from which the row was selected.
- Delete remove a fetched row from an underlying table.

- Close ready the cursor to be either reopened or deallocated.
- Deallocate free the cursor's resources.

In an Adaptive Server client application, cursors can either be created and manipulated with language commands or with ct\_cursor commands. Cursors created using Transact-SQL language commands are called *language cursors*. Cursors created with ct\_cursor commands are called *Client-Library cursors*. Table 7-1 on page 113 compares the two types of cursors.

# Language cursors versus Client-Library cursors

Table 7-1 compares Transact-SQL (language) cursor commands with Client-Library cursor commands:

Table 7-1: Transact-SQL cursor commands versus Client-Library cursor commands

Operation	Language command	Client-Library cursor command	
Declare	declare cursor	ct_cursor(CS_CURSOR_DECLARE)	
		or ct_dynamic(CS_CURSOR_DECLARE)	
Set cursor rows	set cursor rows	ct_cursor(CS_CURSOR_ROWS)	
Open	open	ct_cursor(CS_CURSOR_OPEN)	
Fetch	fetch	ct_fetch or ct_scroll_fetch, after ct_results has returned with a <i>result_type</i> of CS_CURSOR_RESULT.	
Update update where current		ct_cursor(CS_CURSOR_UPDATE)	
	of cursor_name	By default, affects the last fetched row, but can be redirected to any previously fetched row.	
Delete	delete where current	ct_cursor(CS_CURSOR_DELETE)	
	of cursor_name	By default, affects the last fetched row, but can be redirected to any previously fetched row.	
Close	close	ct_cursor(CS_CURSOR_CLOSE)	
Deallocate	deallocate cursor	ct_cursor(CS_CURSOR_DEALLOC) or ct_cursor(CS_CURSOR_CLOSE)	
		The cursor is closed and deallocated with one command if the CS_DEALLOC bit is set in ct_cursor's <i>option</i> parameter.	

### Language cursors

On Adaptive Server, a language cursor is declared with the declare cursor statement, opened with an open statement, and fetched from using fetch statements. See the Sybase Adaptive Server Enterprise *Reference Manual* for descriptions of these commands. A Client-Library program can send all of these statements as normal language commands.

Once a language cursor has been declared and opened, each fetch language command returns a set of regular rows (ct\_results *result\_type* is CS\_ROW\_RESULT) and can be handled just like the results of a select command (see "Processing regular row results" on page 95). As with any other language command, the results of each command must be processed with ct\_results (and ct\_fetch, if necessary) before another command can be sent on the connection.

When declared within a language command sent by a client connection, a language cursor has scope limited to that connection. In other words, only language commands sent over the same connection can reference the cursor.

Language cursors provide the following advantage over Client-Library cursors:

- On Adaptive Server Enterprise, you can declare a cursor and open inside a Transact-SQL stored procedure. Such a cursor is called a server cursor. Complex tasks that are implemented using a stored procedure and server cursors should perform better than an equivalent implementation that uses Client-Library cursors. The performance difference is mainly due to the fact that the Client-Library cursor requires many network round trips to fetch the cursor rows (and to execute any nested update commands), while the server cursor does not.
- Language cursors can be used with an existing client application that
  handles ad hoc language commands. For example, a user of the Sybase isql
  client application can use language cursors, even though isql contains no
  special code to support cursors.

The Adaptive Server Enterprise *Reference Manual* contains more detailed information on language cursors.

### **Client-Library cursors**

A Client-Library cursor requires application programmers to code ct\_cursor calls that declare and open the cursor. A Client-Library cursor-open command returns a single fetchable result set of type CS\_CURSOR\_RESULT.

A Client-Library cursor's scope is limited to a single command structure. In fact, once a cursor is declared with a command structure, that command structure becomes a dedicated "handle" for further operations on the cursor.

Client-Library cursors provide the following advantages over language cursors:

- Fetching from a Client-Library cursor is more simple.
  - Each fetch from a Client-Library cursor involves a single ct\_fetch or ct\_scroll\_fetch call; after each ct\_fetch or ct\_scroll\_fetch call that returns rows, the application can send new commands over the connection.
  - Each fetch from a language cursor is a separate Client-Library command that involves calls to ct\_command, ct\_send, ct\_results, ct\_fetch, and so forth. The results of the fetch language command must be completely processed before the application can send new commands over the same connection.
- A Client-Library cursor can be used to modify any previously fetched row.
   A language cursor can only be used to delete or update the most recently fetched row.
- A Client-Library cursor can be declared to execute a stored procedure (as long as the stored procedure only executes a single select statement—for more details, see "Step 1: Declare the cursor" on page 119). A language cursor must be declared with a select statement.

# When to use Client-Library cursors

Client-Library cursors offer some unique benefits, but they also may incur a performance penalty relative to other command types.

### **Benefits of Client-Library cursors**

Client-Library cursors provide the following unique benefits to an application:

- They allow the application to execute simultaneous commands on the same connection.
- They allow an application to update a table while fetching from it using only a single connection.

A ct\_cursor cursor-open command is the only command type that allows simultaneous command processing on a single connection. After sending any other type of command, the application must completely process the results of the command before sending another command. When processing the results of a cursor-open command, the client application execute two categories of new commands:

- Nested cursor commands on the same command structure
- Unrelated commands executed using a different command structure

#### **Nested cursor commands**

A *nested cursor command* is a cursor-close, cursor-delete, or cursor-update command that is sent while fetching the rows returned by a cursor-open command; the processing of these commands is "nested" within the processing of the cursor-open command that returned the cursor rows. Before sending a nested cursor command, the application must call ct\_fetch to retrieve at least one cursor row.

For more information on nested cursor commands, see "Nested cursor-update or cursor-delete commands" on page 128 and "Nested cursor-close commands" on page 130.

Client-Library's browse mode feature also allows an application to update a table while fetching from it. However, browse mode requires two connections to the server. For a description of this feature, see the "Browse Mode" topics page in the Open Client *Client-Library/C Reference Manual*.

#### Commands executed using a different command structure

While fetching the rows returned by a cursor-open command, any command can be executed using a separate command structure. For example, the application might issue a select or an update command based on the cursor data. In this case, the application must completely process the results on the separate command structure before fetching the next cursor row or sending a nested cursor command. The application could also open a new cursor. In this case, the new cursor must be opened and its command handle must be ready to return cursor rows before the application can perform another operation on the original cursor.

As an example, consider an application that selects rows from an example table employee that contains the following data:

emp_fname	emp_Iname	emp_id	mgr_id
Bob	Burnett	3349	4572
Alice	Williams	4572	5237
Thomas	Cooper	7028	3198
Samuel	Jones	6193	4572
Jennifer	Uribe	0969	4572
Joachin	Palmer	3198	4572

emp_fname	emp_Iname	emp_id	mgr_id
Jerry	Howe	5939	5237
George	Latimer	5237	NULL

Here, emp\_id is the employee ID number and mgr\_id specifies the employee ID number of each employee's manager. One of the application requirements is that for each fetched employee row, the application must issue another query to find out which employees work for the last-fetched employee.

If the application uses a Client-Library cursor to select rows from the employee table, it could send the second query by using a separate CS\_COMMAND structure. If the application was not using cursors, it would have to issue the second query by using a second connection to the server, or wait until it had processed all the results from the original query to send a new command over the same connection.

### Performance issues when using Client-Library cursors

In general, a Client-Library cursor performs worse than an equivalent select statement that is executed using a language or RPC command. An application that does not require the special benefits listed above achieves higher performance using language commands or RPC commands.

However, cursors may improve performance when the application would otherwise require several connections or some sort of row-buffering mechanism to accomplish the same task.

# **Using Client-Library cursors**

A typical application uses the steps below to declare and open a Client-Library cursor.

1 Send a cursor-declare command.

For cursors declared with a select statement:

- ct\_cursor(CS\_CURSOR\_DECLARE)
- ct\_param or ct\_setparam to define host variable formats

- ct\_send (if not batching commands)
- ct\_results, in a loop (if not batching commands)

For cursors declared with an execute statement:

- ct\_cursor(CS CURSOR DECLARE)
- ct\_send (if not batching commands)
- ct\_results, in a loop (if not batching commands)

For cursors declared with a prepared dynamic SQL statement:

- ct\_dynamic(CS\_CURSOR\_DECLARE)
- (Optional) ct\_cursor(CS\_CURSOR\_OPTION)
- ct\_send
- ct\_results, in a loop
- If a cursor is declared with a ct\_cursor command, the commands in steps 1, 2, and 3 can be batched: they can be sent to the server with a single call to ct\_send.
- 2 (Optional) Send a cursor-rows command.
  - ct\_cursor(CS\_CURSOR\_ROWS)
  - ct\_send (if not batching commands)
  - ct\_results, in a loop (if not batching commands)
- 3 Send a cursor-open command.
  - ct\_cursor(CS CURSOR OPEN)
  - ct\_param or ct\_setparam to pass parameter values
  - ct\_send
  - ct\_results, called in a standard results loop.

A successful open command returns a CS\_CURSOR\_RESULT result set. If batching commands, several calls to ct\_results are required (to retrieve the status results from the batched commands) before the cursor rows are available.

- 4 Process cursor rows.
  - ct\_bind to bind to cursor rows
  - ct\_fetch or ct\_scroll\_fetch (called in a loop to retrieve each row)

 New commands can be sent inside the ct\_fetch or ct\_scroll\_fetch loop, after at least one row has been fetched. See "Step 4: Process cursor rows" on page 128 for more information.

#### 5 Close the cursor.

- ct\_cursor(CS CURSOR CLOSE)
- ct send
- ct\_results

An application can close and deallocate the cursor with one command by setting the CS\_DEALLOC bit in the ct\_cursor *option* parameter when defining the cursor-close command. In that case, the step 6 is unnecessary.

- 6 Deallocate the cursor.
  - ct\_cursor(CS\_CURSOR\_DEALLOC)
  - ct\_send
  - ct\_results

Each step in the process above sends one Client-Library cursor command to the server. After sending each command, the application must handle the results with ct\_results. Code your application to handle the results of a cursor command with a standard results loop, as discussed in "Structure of the basic loop" on page 94.

### Step 1: Declare the cursor

There are three types of cursor-declare commands. Each one executes the cursor's select statement differently:

- The cursor executes a select statement directly.
  - The application calls ct\_cursor and passes the select statement as the ct\_cursor *text* argument.
- The cursor executes a stored procedure.

The select statement is executed by a stored procedure that has been created ahead of time, either by the application itself or by the application administrator. To declare the cursor, call ct\_cursor and pass, as the *text* argument, an execute statement that invokes the procedure. Cursors can be declared only on a stored procedure that contains a single select statement.

• The cursor executes a prepared dynamic SQL statement.

The application calls ct\_dynamic(CS\_PREPARE) to create a prepared statement that executes the select statement. Then the application calls ct\_dynamic(CS\_CURSOR\_DECLARE) and passes the statement identifier as the ct\_dynamic *id* argument.

#### Declaring a cursor to directly execute a select statement

To create a cursor or scrollable cursor that directly executes a select statement, call ct\_cursor with *type* as CS\_CURSOR\_DECLARE and *text* as a select statement.

A simple cursor declaration

The following code declares a Client-Library cursor. Return code checking is omitted for simplicity:

The following code declares a Client-Library scrollable cursor. Return code checking is omitted for simplicity:

Declaring a cursor that takes parameters

The select statement can also contain host language variables of the form @variable\_name to indicate where parameters will be substituted in the statement when the cursor is opened. Adaptive Server allows variables to substitute for values in the cursor's where clause. For example, the following statement could be used to declare a cursor that takes a variable int value:

```
SELECT title_id, title, price FROM titles WHERE total_sales > @sales_val
```

In this case, you must specify the parameter format by calling ct\_param or ct\_setparam with a NULL *data* pointer after declaring the cursor. Each time the cursor is opened, the application supplies parameter values by calling ct\_param or ct\_setparam again. This case is demonstrated by the example below:

```
CS_CHAR body[1024];
CS_DATAFMT intfmt;
CS_INT sales val;
```

```
strcpy(body, "select title id, title, price from
       titles where total sales > @sales val
       for read only");
 ret = ct cursor(cmd, CS CURSOR DECLARE,
          "a cursor", CS NULLTERM,
          body, CS NULLTERM, CS UNUSED);
 ... error checking deleted ...
(CS VOID) memset (&intfmt, 0, sizeof(intfmt));
 ** Define the format of @sales val.
 * /
 intfmt.datatype = CS INT TYPE;
 intfmt.name[0] = ' \setminus 0';
 intfmt.namelen = 0;
 intfmt.maxlength = CS SIZEOF(CS INT);
 intfmt.locale = (CS LOCALE *)NULL;
 intfmt.status = CS INPUTVALUE;
ret = ct param(cmd, &intfmt, (CS_VOID *)NULL,
              CS UNUSED, 0);
 ... error checking deleted ...
ret = ct cursor(cmd, CS CURSOR OPEN, NULL,
               CS UNUSED, NULL, CS UNUSED,
               CS UNUSED);
 ... error checking deleted ...
 ** Supply a value for @sales val. intfmt fields
 ** were set above.
 * /
sales val = 1;
 ret = ct param(cmd, &intfmt,
              (CS VOID *)&sales val, CS UNUSED, 0);
 ... error checking deleted ...
 ** Send the batched cursor declare and open
 ** commands.
 */
 ret = ct send(cmd);
 ... error checking deleted ...
```

Specifying which columns can be updated

For applications that connect to Adaptive Server, use the for read only or for update of clauses in the select statement to specify which columns, if any, will be updated. In the ct\_cursor(CS\_CURSOR\_DECLARE) call, pass the ct\_cursor *option* parameter as CS\_UNUSED to indicate that the server should decide which columns can be updated. For example, a cursor declared with this following statement allows updates of the price column:

```
SELECT title_id, title, price FROM titles FOR UPDATE OF price
```

Other servers, such as custom Open Servers, may not recognize or use the for read only or for update of clauses in the select statement. These servers require the client application to indicate which columns are to be updated with separate calls to ct\_param or ct\_setparam. For details, see the reference page for ct\_cursor in the Open Client Client-Library/C Reference Manual.

#### Declaring a cursor to execute a stored procedure

You can declare cursors to execute a stored procedure that in turn executes a single select statement. You create this style of cursor by calling ct\_cursor with *type* as CS\_CURSOR\_DECLARE and *text* as an execute statement that invokes the procedure.

For example, the select statement in the example above could be invoked by a stored procedure:

```
CREATE PROCEDURE titlecursorproc
@sales_val INT
AS
SELECT title_id, price, title FROM titles
WHERE ( total_sales > @sales_val )
FOR READ ONLY
```

For Client-Library cursors that execute an Adaptive Server stored procedure, you do not use host language variables and do not define any variable formats with ct\_param—the server determines parameter formats from the declaration of the stored procedure. The steps required to declare and open the cursor are otherwise similar to those illustrated under "Declaring a cursor that takes parameters" on page 120. The example below shows how to declare and open a Client-Library cursor on the *titlecursorproc* stored procedure:

```
** Supply a value for the @sales val parameter for
 ** titlecursorproc.
 * /
 (CS VOID) memset (&intfmt, 0, sizeof(intfmt));
 intfmt.datatype = CS INT TYPE;
 intfmt.name[0] = ' \ 0';
 intfmt.namelen = 0;
 intfmt.maxlength = CS SIZEOF(CS INT);
 intfmt.locale = (CS LOCALE *)NULL;
 intfmt.status = CS INPUTVALUE;
sales val = 1;
 ret = ct param(cmd, &intfmt,
              (CS VOID *) & sales val, CS UNUSED, 0);
 ... error checking deleted ...
 ** Send the batched cursor declare and open
 ** commands.
 * /
ret = ct send(cmd);
 ... error checking deleted ...
... results processing deleted ...
```

#### Declaring a cursor to execute a prepared dynamic SQL statement

You can declare cursors on a prepared dynamic SQL statement that executes a single select statement. For example, you could prepare a statement to execute the select statement below:

```
SELECT title_id, title, price FROM titles WHERE total sales > ? FOR READ ONLY
```

The "?" character (the dynamic parameter marker) is a placeholder for a parameter value that will be provided when the cursor is opened. Dynamic SQL statements are created by sending a ct\_dynamic(CS\_PREPARE) command to the server and handling the results. See "Step 1: Prepare the statement" on page 140 for details.

After preparing the statement, the application can call ct\_dynamic with *type* as CS\_CURSOR\_DECLARE and *id* as the statement identifier.

Use the for read only or for update of clauses in the select statement to specify which columns, if any, to be updated. If the statement does not have one of these clauses, the application can call ct\_cursor(CS\_CURSOR\_OPTION) immediately after calling ct\_dynamic to initiate the cursor-declare command.

You cannot batch the ct\_dynamic cursor-declare command c with ct\_cursor cursor-rows or ct\_cursor cursor-open commands.

The following example fragment shows how to declare and open a cursor with a prepared statement:

```
/*
 ** Prepare the statement.
 */
 strcpy(body, "SELECT title id, title, price FROM titles
                WHERE price > ? FOR READ ONLY");
 strcpy(stmt_id, "dyn_a");
 retcode = ct dynamic(cmd, CS PREPARE, stmt id, CS NULLTERM,
             body, CS NULLTERM);
 if (retcode != CS_SUCCEED)
   ex error("DoCursor: ct dynamic(prepare) failed");
   return retcode;
if ((retcode = ct send(cmd)) != CS SUCCEED)
   ex error("DoCursor: ct send() failed");
   return retcode;
  ... ct results() loop goes here. No fetchable results are
     returned ...
 ** Declare the cursor
 */
 retcode = ct dynamic(cmd, CS CURSOR DECLARE,
                       stmt id, CS NULLTERM,
                       "cursor_a", CS_NULLTERM);
 if (retcode != CS SUCCEED)
   ex error("DoCursor: ct dynamic(cursor declare) failed");
   return retcode;
if ((retcode = ct send(cmd)) != CS SUCCEED)
   ex error("DoCursor: ct send() failed");
   return retcode;
  ... ct results() loop goes here. No fetchable results are
```

returned by the cursor-declare command ...

#### Step 2: Set cursor rows

After a Client-Library cursor is declared, an application can call ct\_cursor to specify a cursor-rows setting for the cursor. The value of the cursor-rows setting defines the number of rows that the server returns to Client-Library per internal fetch request, not the number of rows returned to an application per ct\_fetch call. An internal fetch request is made when more rows are needed from the server to satisfy ct\_fetch requests.

By default, the cursor-rows setting is 1. If the application does not send a cursor-rows command that precedes the cursor-open command, the cursor rows setting is 1. For cursors declared with ct\_cursor commands, the cursor-rows command can be batched with the cursor-open command.

The cursor-rows settings determines how many rows Client-Library receives from the server in response to each internal Client-Library fetch request. For example, if cursor-rows is set to 5 and the application does not use array binding, Client-Library makes an internal fetch request when an application calls ct\_fetch the first time, the sixth time, and so on.

To facilitate a multi-row return from ct\_scroll\_fetch, you must use a cursor-row setting greater than 1. For maximum efficiency, you must also use array binding. Your array bind count should be equal to the CS\_CURSOR\_ROWS value.

**Note** Array binding is required for ct\_scroll\_fetch if the CS\_CURSOR\_ROWS setting is greater than 1. Array binding can be used with both ct\_fetch and ct\_scroll\_fetch. If CS\_CURSOR\_ROWS is set to the default value of 1, normal program variables may be used with either API call.

If you specify a cursor-rows setting greater than 1, Client-Library buffers also handles additional internal row fetches transparently. When an application calls ct\_fetch to fetch a cursor row, Client-Library may read the row directly from the network, send an internal fetch request to the server to get more rows, or retrieve the row from an internal row buffer. Two situations require Client-Library to buffer cursor rows internally:

 When the application sends a nested cursor-update or cursor-delete command.  When the application sends a command on a different command structure than the cursor's.

In these situations, Client-Library must read and buffer any unread rows to clear the connection for writing.

In general, a higher cursor-rows setting can benefit application performance when processing a read-only cursor. A higher cursor-rows setting decreases the number of network round trips required to fetch rows. However, if cursor-rows is set too high and Client-Library must buffer rows, the buffering overhead can outweigh the gains achieved by decreasing the number of round trips.

To minimize the likelihood that Client-Library will need to buffer rows, use array binding with an array size that matches the cursor-rows setting. For more information on array binding, see the reference page for ct\_bind in the Open Client Client-Library/C Reference Manual.

### Step 3: Open the cursor

You initiate a cursor-open command by calling ct\_cursor(CS\_CURSOR\_OPEN). If the cursor requires input parameters, define them by calling ct\_param or ct\_setparam once for each parameter value. Parameter values are required if any of the following conditions are true:

- The body of the cursor is a SQL text string that contains host variables.
- The body of the cursor is a stored procedure that requires input parameter values.
- The body of the cursor is a dynamic SQL statement that contains dynamic parameter markers.

Applications that restore cursor-open commands should call ct\_setparam rather than ct\_param to specify parameter values for the cursor-open command. When ct\_setparam is used, the application can change the parameter values for the restored cursor-open command. (See "Reopening a cursor" on page 127.)

### **Cursor command batching**

Cursors declared with ct\_cursor can be batched. The first time a cursor is opened, an application can send the cursor-declare, cursor-rows, and cursor-open commands with a single call to ct\_send and process the results with a single results loop.

When a cursor is reopened, the application can batch a cursor-rows command with the cursor-open command.

Batching the commands reduces the number of network round trips required to open the cursor.

#### Reopening a cursor

After the results of a cursor-open command have been processed, the previous cursor-open command can be restored with a single ct\_cursor call (with the syntax described below). The restore operation readies the command structure to send the previous cursor-open command. The following command information is restored:

- Any cursor-rows commands that were batched with the cursor-open command.
- Parameter values for the cursor-open command that were passed with ct\_param.
- Bindings to parameter source variables that were established with ct\_setparam. ct\_send reads the current values when the restored command is sent.

Cursor-declare commands that were batched with the cursor-open command are not restored.

An application restores a cursor-open command by calling ct\_cursor with *type* as CS\_CURSOR\_OPEN and *option* as CS\_RESTORE\_OPEN. Most applications use the program structure below to restore and send a cursor-open command.

```
/*
  ** Assign new variables in the program variables
  ** bound with ct_setparam.
  */
   ... assignment statement for each parameter
        source variable ...
ct_cursor(CS_CURSOR_OPEN, ..., CS_RESTORE_OPEN)
  ct_send
   ... handle cursor results ...
```

You can also reopen a cursor by initiating a new cursor open command (preceded by a cursor-rows command if necessary). However, applications that restore the previous command can eliminate several Client-Library calls.

### Step 4: Process cursor rows

Cursor results should be processed by calling ct\_results in a standard loop structure (see "Structure of the basic loop" on page 94). Cursor rows are available when ct\_results returns with *result\_type* equal to CS\_CURSOR\_RESULT. Cursor rows are handled like any other fetchable result set. (See "Processing cursor results" on page 97.)

The difference from other result types is that the application can issue new commands while fetching cursor rows. These commands can be either of two types:

- Nested cursor commands cursor-close, cursor-delete, or cursor-update commands executed using the command structure that controls the cursor, or
- All other commands any command executed using a separate command structure.

#### Nested cursor-update or cursor-delete commands

While processing a cursor result set, an application can update or delete any previously fetched row in the cursor result set. The modification is propagated back to the base tables from which the cursor result set derives.

A cursor update command is initiated by calling ct\_cursor with *type* as CS\_CURSOR\_UPDATE, *name* as the name of the base table, and *text* as a SQL update clause. For example, the following call builds a command to update a row in the *authors* table of the pubs2 database:

The cursor update can update columns from one table only. Separate commands can be sent to update columns from more than one table.

A cursor-delete command is initiated by calling ct\_cursor with *type* as CS\_CURSOR\_DELETE, *name* as the name of the base table from which to delete the row, and *text* as NULL.

After sending a cursor-update or cursor-delete command, the application must completely process the update or delete operation before calling ct\_fetch again.

Key columns

An application should avoid updating columns that are part of the cursor result set's primary key. ct\_describe sets the CS\_KEY bit in the *datafmt.status* field to indicate that a column is a primary key for the result set.

Redirected updates or deletes

By default, a cursor-update or a cursor-delete affects the last-fetched row. However, you can redirect the update or delete to affect any previously fetched row. Redirected updates or deletes are most commonly used by applications that perform array binding to process the cursor rows.

Cursor updates or deletes are redirected by calling ct\_keydata before sending the command.

For an application that redirects updates, you must ensure that the command structure's CS\_HIDDEN\_KEYS property is CS\_TRUE before opening the cursor. (Use ct\_cmd\_props to set the property for the command structure before opening the cursor, or use ct\_con\_props to set it at the connection level before allocating command structures.) CS\_HIDDEN\_KEYS determines whether the cursor's hidden-key columns are exposed to the application.

A *hidden-key column* is returned with a cursor's result set but was not specified in the cursor's select list. ct\_describe sets the CS\_HIDDEN bit in the *datafmt.status* field to indicate that a column was not part of the cursor's select list.

Hidden-key columns provide additional information that the server requires to find the destination rows for cursor updates and deletes. Normally, Client-Library handles these additional columns internally and does not expose them to the application. However, applications that perform redirected updates or deletes must handle the hidden-key columns explicitly.

To redirect a cursor update or delete, an application must call ct\_keydata and specify values for every column in the row that is a version key or a primary key (including hidden columns). These terms are explained below:

- A primary-key column is part of the primary key for the cursor result set.
   ct\_describe sets the CS\_KEY bit in the datafmt.status field to indicate that a column is a primary key for the result set.
- A version-key column is a real table column (not an expression in the select list) that is not part of the primary key for the cursor result set. ct\_describe sets the CS\_VERSION\_KEY bit in the datafmt.status field to indicate that a column is a version key for the result set.

A hidden-key column can be either a primary-key column or a version-key column.

Applications that redirect cursor updates must be coded according to the rules below:

- Make sure the CS\_HIDDEN\_KEYS property is CS\_TRUE for the command structure before the cursor is opened.
- When processing the cursor rows, call ct\_describe to obtain CS\_DATAFMT information for all cursor columns, including hidden columns. Save the information for use with later updates.
- In interactive applications, use the CS\_HIDDEN bit in the CS\_DATAFMT status field to determine whether a column should be displayed.
- When retrieving rows, save column values for all rows that can be updated. These values are required as input to ct\_keydata.
- To update a previously fetched row, call ct\_keydata for every column in the row whose matching CS\_DATAFMT status field has either the CS\_KEY or CS\_VERSION\_KEY bit set.
- Avoid updating key columns. Check the CS\_KEY bit in the CS\_DATAFMT status field to determine whether a column is a key column.

#### **Nested cursor-close commands**

An application can close a cursor before fetching all its rows by sending a cursor-close command and handling the results. See "Step 5: Close the cursor" on page 131 for more details.

Closing a cursor is preferred over calling ct\_cancel to discard unwanted cursor rows for the following reasons:

- Calling ct\_cancel(CS\_CANCEL\_ALL) or ct\_cancel(CS\_CANCEL\_ATTN) can cause a connection's cursors to go into an undefined state.
- Calling ct\_cancel(CS\_CANCEL\_CURRENT) can waste network bandwidth. This call causes Client-Library to fetch the remaining rows over the network and discard them.

### Sending commands on a different command structure

An application can send commands, which are unrelated to the original cursor, on a separate command structure while fetching the rows from the original cursor.

For example, the application might issue a select or an update based on the cursor data. In this case, the application must completely process the results of the new command before fetching the next cursor row. The application could also open a new cursor. In this case, the new cursor must be opened and its command handle must be ready to return cursor rows before the application can perform another operation on the original cursor.

### Step 5: Close the cursor

An application initiates a cursor-close command by calling ct\_cursor with *type* as CS\_CURSOR\_CLOSE. If the application will not use the cursor again, it can close and deallocate the cursor with one command by passing ct\_cursor's *option* parameter as CS\_DEALLOC. Otherwise, *option* should be CS\_UNUSED.

### Step 6: Deallocate the cursor

An application initiates a cursor-deallocate command by calling ct\_cursor with type as CS\_CURSOR\_DEALLOC. If an application does not explicitly deallocate a cursor, it is deallocated when the application disconnects.

# **Client-Library cursor properties**

Once a Client-Library cursor is declared, it is associated with only one command structure. Applications can obtain information about the cursor associated with a command structure by calling ct\_cmd\_props to retrieve the following properties:

- CS\_CUR\_ID contains the cursor's server identification number. A
  cursor's identification number can be retrieved after calling
  ct\_cmd\_props(CS\_CUR\_STATUS) to confirm that a cursor exists in a
  particular command space.
- CS\_CUR\_NAME contains the cursor's name. An application can use
  the CS\_CUR\_NAME property to retrieve a cursor's name any time after
  its ct\_cursor(CS\_CURSOR\_DECLARE) call returns CS\_SUCCEED.

- CS\_CUR\_ROWCOUNT contains the cursor-rows setting. This setting
  is the number of rows returned to Client-Library per internal fetch request.
  A cursor's row count can be retrieved after calling
  ct\_cmd\_props(CS\_CUR\_STATUS) to confirm that a cursor exists in a
  particular command space.
- CS\_CUR\_STATUS indicates the cursor status. An application can use the CS\_CUR\_STATUS property to determine:
  - Whether a cursor exists within a command space
  - Whether the cursor is open
  - Whether the cursor can be used for updates
  - Whether the cursor is read-only, has sensitivity, and has scrollability.

Calling ct\_cancel can cause a connection's cursors to enter an undefined state. An application can use the cursor status property to determine how a cancel operation has affected a cursor.

 CS\_HAVE\_CUROPEN – indicates whether the command structure has a cursor-open command that can be restored. See "Reopening a cursor" on page 127 for more information.

All of these properties are retrieve-only command structure properties whose values can be retrieved by calling ct\_cmd\_props. See the reference page for ct\_cmd\_props in the Open Client *Client-Library/C Reference Manual* for more information.

# CHAPTER 8 Using Dynamic SQL Commands

This chapter explains Dynamic SQL, including:

Topic	Page
Dynamic SQL overview	133
Benefits of dynamic SQL	134
Limitations of dynamic SQL	134
Alternatives to dynamic SQL	136
Using the execute-immediate method	136
Using the prepare-and-execute method	137
Dynamic SQL versus stored procedures	144

# **Dynamic SQL overview**

Dynamic SQL is the process of generating, preparing, and executing SQL statements at run time using commands initiated by Client-Library's ct\_dynamic routine.

Dynamic SQL is primarily useful for precompiler support, but it can also be used by interactive applications.

Client-Library and Adaptive Server Enterprise allow two methods of dynamic SQL command execution:

- Execute-immediate the client application sends the server a
  ct\_dynamic command that executes a literal statement. This is
  essentially the same process as sending a language command, but
  with more restrictions. (See "Language commands" on page 78 for
  more information on sending language commands.)
- Prepare-and-execute the client application sends the server a
  sequence of server commands that prepares a statement and executes
  it one or more times. The application can send additional commands
  to query the server for the formats of the statement's input parameters
  and the result set that it returns.

With the prepare-and-execute method, the client application sends a ct\_dynamic(CS\_PREPARE) command to the server to create a *prepared statement*. A prepared statement is similar to an Adaptive Server stored procedure. When either is created, the server checks the SQL statement syntax, builds an optimized query plan, and stores the query plan in preparation for later execution. The key differences are as follows:

- The prepared statement is dropped automatically when the client program disconnects, while the stored procedure is not.
- The prepared statement is referenced by an identifier that is visible only to
  the connection that created the statement, while a stored procedure name
  is visible to any client connection. However, the procedure's permissions
  may restrict which users can execute it.
- The client program can easily determine the input (parameter) and output (result) column formats for a prepared statement without executing it.

# Benefits of dynamic SQL

Using dynamic SQL commands, an application can prepare a "generic" SQL statement once and execute it multiple times. Statements can also contain markers for parameter values to be supplied at execution time, so that the statement can be executed with varying inputs.

# Limitations of dynamic SQL

Dynamic SQL has some significant limitations.

### Performance of dynamic SQL commands

A dynamic SQL implementation of an application generally performs worse than an implementation where permanent Adaptive Server stored procedures are created and the client program invokes them with RPC commands.

When you create Adaptive Server stored procedures for an application, SQL statement compilation and optimization are performed once when the procedure is created. On the other hand, a dynamic SQL application incurs compilation and optimization overhead every time the client program runs. A dynamic SQL implementation also incurs database space overhead because each instance of the client program must create separate compiled versions of the application's prepared statements. In contrast, when you design an application to use stored procedures and RPC commands, all instances of the client program can share the same stored procedures.

### **Adaptive Server restrictions and database requirements**

Adaptive Server Enterprise implements dynamic SQL using temporary stored procedures. A temporary stored procedure is created when a SQL statement is prepared, and destroyed when that prepared statement is deallocated. A prepared statement can be deallocated either explicitly with a ct\_dynamic(CS\_DEALLOC) call or implicitly when a connection is closed.

As a consequence of this implementation, an application accessing Adaptive Server and using dynamic SQL is subject to the restrictions of Adaptive Server stored procedures. Some of the implications of this are:

- Temporary tables are destroyed when the prepared statement is deallocated.
- Parameters of text and image datatypes are not supported.
- The maximum number of parameters supported is 255.
- If the dynamic SQL statement itself executes a stored procedure (with a Transact-SQL execute statement), output parameter values and the return status are unavailable to the client application.
- The datatype of the parameters represented by placeholders must be known at parsing time. The following statements are not valid:

```
? <op> ?, (? is null)
CONVERT(<type>, ?)
```

See the *Transact-SQL User's Guide* for a complete discussion of stored procedures.

# Alternatives to dynamic SQL

Developers who learn Sybase after learning another DBMS system should not confuse Sybase's dynamic SQL implementation with that of other vendors. With Adaptive Server, most command types are "dynamic." The closest analogy that Adaptive Server offers to "static SQL commands" are stored procedures. However, any client application can invoke a stored procedure, as long as the procedure's permissions allow the client program's user to execute it. Other DBMS systems may limit the scope of a precompiled static SQL command to the precompiled application.

For Adaptive Server applications, many tasks that require you to use dynamic SQL with another DBMS can be implemented with Client-Library command types other than dynamic SQL. For example:

- For an application that must execute SQL statements whose text is not known prior to runtime, you can code the client program to define language commands by calling ct\_command. This method is appropriate for commands that are only executed once or a small number of times.
- For an application that must execute commands whose text is known before runtime and where performance is important, you can create an Adaptive Server stored procedure and code the client program to invoke the procedure with RPC commands (defined with ct\_command).
- For an application that must interactively define and open cursors, you can code the client program to define the cursor-declare commands with ct\_cursor.

# Using the execute-immediate method

The execute-immediate method executes a single SQL statement by sending a single command to the server.

### When to use the execute-immediate method

A dynamic SQL statement can be executed immediately only if it meets the following criteria:

• It does not return fetchable data (it is not a select statement).

• It does not contain placeholders for parameters (indicated by a question mark (?) in the text of the statement).

Dynamic parameter markers act as placeholders that allow users to specify actual data to be substituted into a SQL statement at run time.

Generally, you should use the execute-immediate method when the application executes a statement only once. Using the execute-immediate method, an application can execute a statement more than once, but this method incurs the overhead associated with repeated statement preparations.

### Coding an execute-immediate command

To execute a dynamic SQL statement using the execute-immediate method, code your application to:

- 1 Store the text of the dynamic SQL statement in a character string host variable.
- 2 Call ct\_dynamic with *type* as CS\_EXEC\_IMMEDIATE to initiate a command to execute the statement, *buffer* as the address of the string containing the SQL statement, and *id* as NULL.
- 3 Call ct\_send to send the command to the server.
- 4 Call ct\_results in a standard loop, as described in "Structure of the basic loop" on page 94. The value of the \*result\_type parameter indicates whether the command succeeded (CS\_CMD\_SUCCEED) or failed (CS\_CMD\_FAIL).

# Using the prepare-and-execute method

For the prepare-and-execute method, the server performs the compilation and execute operations separately in response to distinct commands.

### When to use prepare-and-execute method

An application must use this method if the dynamic SQL statement meets any of the following criteria:

- It returns data.
- It contains placeholders for values to be supplied at execution time, represented by a question mark (?) character in the text of the statement.

An application should use this method if it will execute the statement multiple times because it incurs the overhead associated with statement preparation only when it first prepares the statement. Each subsequent execution of the statement does not incur the cost of recompiling the statement.

The prepare-and-execute method offers the following advantages over the execute-immediate method:

- select statements can be executed.
- Performance is better when statements are executed more than once.
- The statement can take parameters whose values can change each time the statement executes.

### Program structure for the prepare-and-execute method

Most applications will use the steps below to prepare and execute a dynamic SQL statement:

- 1 Prepare the dynamic SQL statement.
  - ct\_dynamic(CS\_PREPARE)
  - ct send
  - ct\_results, in a loop

The prepare command returns no fetchable results.

- 2 (Optional) Get a description of the parameters required to execute the prepared statement.
  - ct\_dynamic(CS\_DESCRIBE\_INPUT)
  - · ct send
  - ct\_results, in a loop

ct\_results returns with a *result\_type* of CS\_DESCRIBE\_RESULT to indicate that the parameter descriptions are available.

3 (Optional) Get a description of the result columns returned by the prepared statement.

- ct\_dynamic(CS\_DESCRIBE\_OUTPUT)
- ct\_send
- ct\_results, in a loop

ct\_results returns with a *result\_type* of CS\_DESCRIBE\_RESULT to indicate that the description is available.

4 Execute the prepared statement or declare and open a cursor on the prepared statement.

To execute the prepared statement (without a cursor):

- ct\_dynamic(CS\_EXECUTE).
- If necessary, define parameter values with ct\_param, ct\_setparam, ct\_dyndesc, or ct\_dynsqlda.
- · ct send.
- ct\_results, in a loop. Fetchable results may require processing.

For a description of how to execute a prepared statement with a cursor, see "Using Client-Library cursors" on page 117.

5 Deallocate the prepared statement.

If a cursor is declared on the statement, first close and deallocate the cursor:

- ct\_cursor(CS\_CURSOR\_CLOSE, CS\_DEALLOC) or, if the cursor is not open, ct\_cursor(CS\_CURSOR\_DEALLOC)
- ct\_send
- ct\_results, in a loop
- Initiate and send a command to deallocate the prepared statement:
- ct\_dynamic(CS\_DEALLOC)
- ct send
- ct\_results, in a loop

The deallocate command returns no fetchable results.

Each step in the process above sends one dynamic SQL command to the server. After sending each command, the application must handle the results with ct\_results. Code your application to handle the results of a dynamic SQL command with a standard results loop, as discussed in "Structure of the basic loop" on page 94.

### **Step 1: Prepare the statement**

To initiate a command that prepares a dynamic SQL statement, an application calls ct\_dynamic with *type* as CS\_PREPARE, *id* as a character string statement identifier, and *buffer* as the statement to prepare. For example:

Statement identifiers must be unique among other dynamic SQL statements prepared on the same connection.

ct\_send sends the prepare command to the server, and a standard ct\_results loop handles the results.

### Step 2: Get a description of command inputs

After a statement is prepared, the application can send a describe-input command to the server to obtain a description of any parameters that are required to execute the statement. This description includes the number of input values, as well as their datatypes, lengths, and so on. The application can then use this information to prompt the end user for input values. After prompting for input values, it can pass those values to the prepared statement just prior to executing the statement.

### Initiating a describe-input command

To initiate a describe-input command, the application calls ct\_dynamic with *type* as CS\_DESCRIBE\_INPUT and *id* as the statement identifier. ct\_send sends the command to the server, and a standard ct\_results loop handles the results.

### **Processing parameter descriptions**

ct\_results returns with *result\_type* of CS\_DESCRIBE\_RESULT to indicate that the input parameter formats are available. Applications can retrieve the parameter formats in one of two ways:

With ct\_res\_info and ct\_describe

The application calls ct\_res\_info to determine the number of parameters; then, for each parameter, it calls ct\_describe to initialize a CS\_DATAFMT structure with a description of the parameter.

Typically, an application using this method keeps the CS\_DATAFMT structures in an array or list for use with later calls to ct\_param or ct\_setparam.

With ct\_dyndesc or ct\_dynsqlda

Both these routines allow the application to retrieve formats into a structure that can later be used to pass parameters for the command that executes the statement. Both of these routines:

- Retrieve a description of the input parameters required to execute a prepared dynamic SQL statement
- Define input parameter values for the execution of a prepared statement
- Retrieve a description of the data results that will be returned when a prepared statement is executed
- Retrieve data values in the result set returned by the execution of a prepared statement

The differences between the routines are:

- ct\_dynsqlda retrieves formats into a SQLDA structure. The
  application must allocate the memory for this structure before
  retrieving formats into it. ct\_dynsqlda requires only a single call to
  perform each operation.
- ct\_dyndesc retrieves formats into an internal Client-Library data structure that is hidden from the application. ct\_dyndesc requires several calls to perform a single operation.

ct\_dyndesc and ct\_dynsqlda both call ct\_res\_info and ct\_describe internally. When used to pass parameter values, ct\_dyndesc and ct\_dynsqlda both call ct\_param internally.

### Step 3: Get a description of command outputs

The application can send a describe-output command to get the format of the result columns that will be returned when the prepared statement executes. For example, an interactive application might use a describe-output command to determine the number and format of result columns to prepare data structures that are used when displaying the query results. A describe-output command allows the application to determine the results format without executing the prepared statement.

**Note** A single dynamic SQL batch may contain multiple SQL statements. The description of the prepared statement output, however, only describes the first resultset. You will receive full descriptions of each resultset only when the dynamic SQL statement is executed.

### Initiating a describe-output command

To initiate a describe-output command, the application calls ct\_dynamic with *type* as CS\_DESCRIBE\_OUTPUT and *id* as the statement identifier. ct\_send sends the command to the server, and a standard ct\_results loop handles the results.

### **Processing column descriptions**

ct\_results returns with *result\_type* of CS\_DESCRIBE\_RESULT to indicate that the result column formats are available. Applications can retrieve the column formats in one of two ways:

With ct\_res\_info and ct\_describe

The application calls ct\_res\_info to get the number of columns, then, for each parameter, calls ct\_describe to initialize a CS\_DATAFMT structure with a description of the column.

Typically, an application using this method maintains an array or list of CS DATAFMT structures for use with later calls to ct\_bind.

With ct\_dyndesc or ct\_dynsqlda

Both these routines allow the application to retrieve formats into a structure that can later be used to retrieve row data when the prepared statement executes.

- ct\_dynsqlda retrieves formats into a SQLDA structure. The application must allocate the memory for this structure before retrieving formats into it.
- ct\_dyndesc retrieves formats into an internal Client-Library data structure that is hidden from the application.

ct\_dyndesc and ct\_dynsqlda both call ct\_res\_info and ct\_describe internally. When used to retrieve row data, ct\_dyndesc and ct\_dynsqlda both call ct\_bind internally.

### Step 4: Execute the prepared statement

To initiate a command to execute the prepared statement, the application calls ct\_dynamic with *type* as CS\_EXECUTE and *id* as the statement identifier. The application must define any parameters required to execute the prepared statement. Parameter values can be defined in one of several ways:

- By calling ct\_param once for each parameter. ct\_param and ct\_setparam
  offer the best performance. ct\_param does not allow the application to
  change parameter values before resending the command.
- By calling ct\_setparam once for each parameter. ct\_setparam takes
  pointers to parameter source values. This method is the only one that
  allows parameter values to be changed before resending the command.
- By calling ct\_dyndesc several times to allocate a dynamic descriptor area, populate it with data values, and apply it to the command.
   ct\_dyndesc(CS\_USE\_DESC) calls ct\_param internally.
- By calling ct\_dynsqlda to apply the contents of a user-allocated SQLDA structure to the command. Note that ct\_dynsqlda(CS\_SQLDA\_PARAM) calls ct\_param internally.

The application can determine the number and format of a prepared statement's parameters by sending a describe-input command and handling the results before executing the prepared statement. See "Step 2: Get a description of command inputs" on page 140.

ct\_send sends the command to the server, and a standard ct\_results loop handles the results. Code your application to handle the results with a standard results loop, as discussed in "Structure of the basic loop" on page 94.

### Step 5: Deallocate the prepared statement

Deallocating a prepared statement frees any resources associated with it. Explicit deallocation is optional; if the application does not explicitly deallocate prepared statements, the server deallocates them when the client program disconnects.

If a cursor is declared on the prepared statement, the application must first deallocate the cursor before deallocating the statement. See "Step 6: Deallocate the cursor" on page 131 for details.

To initiate a command to deallocate the prepared statement, the application calls ct\_dynamic with *type* as CS\_DEALLOC and *id* as the statement identifier. ct\_send sends the command to the server, and a standard ct\_results loop handles the results.

# Dynamic SQL versus stored procedures

For improved performance compared to dynamic SQL, application designers can use Adaptive Server stored procedures as an alternative where the application requirements allow it.

There are similarities between dynamic SQL and stored procedures:

- Creating a stored procedure is analogous to preparing a dynamic SQL statement.
- A stored procedure's input parameters serve the same purpose as dynamic parameter markers.
- Executing a stored procedure is equivalent to executing a prepared statement

Stored procedures and dynamic SQL prepared statements offer identical functionality, with the following exceptions:

 Dynamic SQL allows retrieval of a prepared statement's parameter formats, while stored procedures do not. See "Step 2: Get a description of command inputs" on page 140.

- The format for stored procedure results cannot easily be determined programmatically without executing the procedure. Dynamic SQL allows retrieval of a prepared statement's result column formats without executing the statement. See "Step 3: Get a description of command outputs" on page 142.
- User-created stored procedures are permanent database objects, while
  prepared statements are automatically deallocated when the user
  disconnects from the server.

A dynamic SQL statement can be replaced by a stored procedure that returns the same results. For example, the following dynamic SQL statement queries the *pubs2..titles* table for books of a certain type in a certain price range:

```
select * from pubs2..titles
  where type = ?
  and price between ? and ?
```

Here, the dynamic SQL statement has dynamic parameter markers (?) for a *type* value and two *price* values.

You can create an equivalent stored procedure as follows:

```
create proc titles_type_pricerange
  @type char(12),
  @price1 money,
  @price2 money
as
  select * from titles
   where
     type = @type
     and price between @price1 and @price2
```

When executed with the same input parameter values, the prepared statement and the stored procedure return the same rows. In addition, the stored procedure returns a return status result.

# CHAPTER 9 Using Directory Services

This chapter describes how Client-Library applications can use a directory service.

Topic	Page
Directory service overview	147
How do applications use a directory service?	148
Searching the directory	148
Step 1: Starting the search	149
Step 2: Collecting search results in the directory callback	154
Step 3: Inspecting directory objects	158
Step 4: Cleaning up	172

# **Directory service overview**

A **directory** stores information as *directory entries* and associates a logical name with each entry. Each directory entry contains information about some network entity, such as a user, a server, or a printer.

A **directory service** (sometimes called a naming service) manages creation, modification, and retrieval of directory entries.

By default, Client-Library uses the Sybase interfaces file as the directory source. Sybase also provides directory drivers for several network-based directory services such as DCE's Cell Directory Service (CDS) and the Windows Registry service. For information about the directory drivers that are available on your platform, see the Open Client and Server *Configuration Guide* for Microsoft Windows and Open Client and Server *Configuration Guide* for UNIX.

# How do applications use a directory service?

Information about Sybase servers is stored in the directory. When an application calls ct\_connect to open a connection to a server, it passes the name of the server's directory entry as the ct\_connect *server\_name* parameter. ct\_connect looks up the entry and retrieves the server's network address and any other information needed to establish the connection.

Applications can also search for available servers using Client-Library routines.

# Searching the directory

Before an application can search a directory, it must have set up the Client-Library programming environment and allocated a CS\_CONNECTION structure. See Chapter 1, "Getting Started with Client-Library" if you do not already know how to initialize Client-Library and allocate a connection structure.

### **Example code**

The *usedir.c* sample program demonstrates how Client-Library applications perform a directory search. All of the code fragments in this chapter are taken from *usedir.c*.

### **Program structure**

To perform directory search, code your application to follow the steps below:

- 1 Begin the search.
  - ct\_con\_props to set directory service properties
  - ct\_callback to install a pointer to the application's directory callback in the connection structure

Execute application code to initialize a list or array that will collect directory objects

ct\_ds\_lookup to begin the search

Note that instead of calling ct\_callback here, the application could have installed the callback in the connection's parent context structure before allocating the connection. Then it would become the default directory callback for all connections allocated from the context.

- 2 Collect search results in the directory callback.
  - (Optional) ct\_ds\_objinfo to inspect the object
  - (Optional) ct\_ds\_dropobj to drop unwanted objects

Execute application code to collect directory objects with an application defined list or array.

During the directory search, ct\_ds\_lookup invokes the directory callback once for each entry that is found in the search.

- 3 Inspect the directory objects. For each directory object:
  - ct\_ds\_objinfo to get the object's fully qualified name
  - ct\_ds\_objinfo to get the number of attributes
  - ct\_ds\_objinfo to get each attribute's metadata and values
- 4 Clean up.

For each object, ct\_ds\_dropobj to deallocate the directory object

# Step 1: Starting the search

An application starts a directory search by initializing the application data structures that will hold the results, installing a directory callback, and calling ct\_ds\_lookup.

### Initialize data structures

The example code in this chapter collects directory objects in a data structure called SERVER\_INFO\_LIST, which can be implemented as an array or list of CS\_DS\_OBJECT pointers.

The code calls the following example routines to collect directory object structures:

sil\_init\_list – allocate and initialize an empty SERVER\_INFO\_LIST.

- sil\_add\_object add a directory object to the end of a SERVER\_INFO\_LIST.
- sil\_extract\_object given a 1-based index number, retrieve a directory object from the SERVER INFO LIST.
- sil\_list\_len get the number of objects stored in a SERVER\_INFO\_LIST.
- sil\_drop\_list deallocate a SERVER\_INFO\_LIST and all its constituents. Calls ct\_ds\_dropobj to deallocate each directory object in the list.

These routines simply manage a list of CS\_DS\_OBJECT pointers. Their implementation is not shown here, but complete code can be found in the *usedir.c* sample file in the Client-Library sample programs.

### **Setting directory service properties**

Applications call ct\_con\_props to set directory service properties for a connection. Applications most commonly set the following properties to control a directory search:

- CS\_DS\_DITBASE specifies the node in the directory where the search begins. DIT-base values must follow the syntax rules of the directory service. See the "Directory Services" topics page in the Open Client Client-Library/C Reference Manual for example DIT-base values.
- CS\_DS\_SEARCH constrains the depth that the search descends beneath the DIT base. The possible values of CS\_DS\_SEARCH are as follows:

Value	Meaning
CS_SEARCH_ONE_LEVEL (default)	Search includes only the leaf entries that are immediate descendants of the node specified by CS_DS_DITBASE.
CS_SEARCH_SUBTREE	Search the entire subtree whose root is specified by CS_DS_DITBASE.

**Note** The DCE directory driver does not allow CS\_DS\_SEARCH to be set to a value other than the default, CS\_SEARCH\_ONE\_LEVEL.

All directory service properties have a symbolic name that begins with "CS\_DS". See the "Properties" topics page in the Open Client *Client-Library/C Reference Manual* for a complete list of Client-Library properties.

### Installing the directory callback

An application installs a directory callback by calling ct\_callback with the *action* parameter as CS\_SET, the *type* parameter as CS\_DS\_LOOKUP\_CB, and *func* as the address of the applications directory callback routine.

A directory callback can be installed at the context level or the connection level. Connections that are allocated from a context inherit the context's directory callback. These steps install the callback at the connection level.

Coding of the callback routine is discussed under "Step 2: Collecting search results in the directory callback" on page 154.

### Calling ct\_ds\_lookup

Applications begin a search by calling ct\_ds\_lookup with action as CS\_SET.

ct\_ds\_lookup takes a CS\_DS\_LOOKUP\_INFO structure as its <code>lookup\_info</code> parameter that describes the search request. <code>lookup\_info->objclass</code> must point at a CS\_OID structure that indicates the directory object class CS\_OID\_OBJSERVER. The other CS\_DS\_LOOKUP\_INFO fields are currently unused and should be all passed as NULL.

ct\_ds\_lookup also takes a pointer to user-allocated data as its *userdata* parameter. When ct\_ds\_lookup invokes the application's directory callback, the callback receives the same pointer value as an input parameter.

### Example code to start a directory search

The following fragment declares an application routine, get\_servers, that searches for server directory class objects:

```
/*
** get servers() -- Query the directory for servers and
      get a list of directory objects that contain details
**
      for each.
** Parameters
    conn -- Pointer to allocated connection structure.
    pserver list -- Address of a pointer to a SERVER INFO LIST.
* *
**
         Upon successful return, the list will be initialized
**
         and contain an object for each server found in the
* *
         search.
* *
```

```
**
        NOTE: The caller must clean up the list with sil drop list()
        when done with it.
**
**
** Returns
** CS SUCCEED or CS FAIL.
CS_RETCODE get_servers (conn, pserver list)
CS CONNECTION *conn;
SERVER_INFO_LIST **pserver_list;
 CS RETCODE
                     ret;
 CS INT
                     regid;
 CS VOID
                     *oldcallback;
 CS OID
 CS_DS_LOOKUP_INFO lookup_info;
 /*
 ** Steps for synchronous-mode directory searches:
 ** 1. If necessary, initialize application specific data structures
       (Our application collects directory objects in *pserver list).
 ** 2. Save the old directory callback and install our own.
 ** 3. Set the base node in the directory to search beneath
       (CS DS DITBASE property).
 ** 4. Call ct ds lookup to begin the search, passing any application
       specific data structures as the userdata argument.
 ** 5. Client-Library invokes our callback once for each found object
       (or once to report that no objects were found). The callback
       (directory cb) receives pointers to found servers and appends
       each to the list of servers.
 ** 6. Check the return status of ct ds lookup.
 ** 7. Restore callbacks and properties that we changed.
 * /
 /*
 ** Step 1. Initialize the data structure (*pserver list).
 ret = sil_init_list(pserver_list);
 if (ret != CS SUCCEED | (*pserver list) == NULL)
   ex error("get servers: Could not initialize list.");
   return CS FAIL;
 /*
 ** Step 2. Save the old directory callback and install our own callback,
     directory cb(), to receive the found objects.
 * /
```

```
ret = ct callback(NULL, conn, CS GET,
                  CS DS LOOKUP CB, &oldcallback);
if (ret == CS SUCCEED)
 ret = ct callback(NULL, conn, CS SET,
                    CS_DS_LOOKUP_CB, (CS_VOID *)directory_cb);
if (ret != CS SUCCEED)
 ex error ("get servers: Could not install directory callback.");
 return CS FAIL;
/*
** Step 3. Set the base node in the directory to search beneath
     (the CS DS DITBASE connection property).
*/
ret = provider setup(conn);
if (ret != CS SUCCEED)
 ex error("get servers: Provider-specific setup failed.");
 return CS FAIL;
}
/*
** Step 4. Call ct ds lookup to begin the search, passing the server list
      pointer as userdata.
** Step 5. Client-Library invokes our callback once for each found object
**
     (or once to report that no objects were found). Our callback,
**
      directory cb, will receive a pointer to each found server object
      and appends it to the list.
** Step 6. Check the return status of ct ds lookup.
* /
/*
** Set the CS DS LOOKUP INFO structure fields.
lookup info.path = NULL;
lookup info.pathlen = 0;
lookup info.attrfilter = NULL;
lookup info.attrselect = NULL;
strcpy(oid.oid buffer, CS OID OBJSERVER);
oid.oid length = STRLEN(oid.oid buffer);
lookup info.objclass = &oid;
```

```
/*
  ** Begin the search.
  ret = ct ds lookup(conn, CS SET, &reqid,
                     &lookup info, (CS VOID *)pserver list);
  if (ret != CS_SUCCEED)
   ex error("get servers: Could not run search.");
   return CS_FAIL;
  ** Step 7. Restore callbacks and properties that we changed.
  */
  ret = ct callback(NULL, conn, CS SET,
                    CS DS LOOKUP CB, oldcallback);
  if (ret != CS SUCCEED)
   ex_error("get_servers: Could not restore directory callback.");
   return CS FAIL;
return CS_SUCCEED;
} /* get_servers() *
```

# Step 2: Collecting search results in the directory callback

During the directory search, ct\_ds\_lookup invokes the directory callback once for each entry that is found in the search.

### **Defining the directory callback**

A directory callback has the following prototype:

```
CS_INT numentries;
CS_DS_OBJECT *ds_object;
CS_VOID *userdata;
```

### where:

- *connection* is the pointer to the CS\_CONNECTION structure used for the directory lookup.
- *reqid* is the request identifier returned by the ct\_ds\_lookup call that began the directory lookup.
- *status* is the status of the directory lookup request. *status* can be one of the following values:

Status value	Meaning
CS_SUCCEED	Search was successful
CS_FAIL	Search failed
CS_CANCELED	Search was canceled with
	ct_ds_lookup(CS_CLEAR)

- *numentries* is the count of directory objects remaining to be examined. If entries were found, *numentries* includes the current object. If no entries were found, *numentries* is 0.
- *ds\_object* is a pointer to information about one directory object. *ds\_object* is (CS\_DS\_OBJECT \*)NULL if either of the following is true:
  - The directory lookup failed (indicated by a *status* value that is not equal to CS\_SUCCEED), or
  - No matching objects were found (indicated by a *numentries* value that is 0 or less).
- userdata is a pointer to a user-supplied data area. If the application passes
  a pointer as ct\_ds\_lookup's userdata parameter, then the directory callback
  receives the same pointer when it is invoked.

userdata provides a way for the callback to communicate with mainline code.

The callback can return CS CONTINUE or CS SUCCEED.

- A return of CS\_SUCCEED truncates the search results: Client-Library discards any remaining directory objects and stops invoking the callback.
- A return of CS\_CONTINUE causes Client-Library to invoke the callback with the next directory object in the search results.

### **Directory callback example**

The following example fragment defines a directory callback. This callback:

- Confirms that the directory object pointer is valid.
- Adds the directory object to the application's list of servers by calling the sil\_add\_object example routine. When the mainline code calls ct\_ds\_lookup, it passes the address of an initialized SERVER\_INFO\_LIST as the ct\_ds\_lookup *userdata* parameter. The callback receives the same address as its own *userdata* parameter.
- If the list of servers is full, the callback returns CS\_SUCCEED to truncate the search results. Otherwise, the callback returns CS\_CONTINUE.

```
/*
** directory cb() -- Directory callback to install in Client-Library.
     When we call ct ds lookup(), Client-Library calls this function
* *
     once for each object that is found in the search.
**
**
**
     This particular callback collects the objects in
* *
     the SERVER_INFO_LIST that is received as userdata.
**
** Parameters
     conn -- The connection handle passed to ct_ds_lookup() to
        begin the search.
**
     regid -- The request id for the operation (assigned by Client-Library).
**
     status -- CS SUCCEED when search succeeded (ds object is valid).
**
        CS FAIL if the search failed (ds object is not valid).
**
     numentries -- The count of objects to be returned for the
**
        search. Includes the current object. Can be 0 if search
**
        failed.
**
     ds object -- Pointer to a CS DS OBJECT structure. Will
* *
        be NULL if the search failed.
     userdata -- The address of user-allocated data that was
        passed to ct ds lookup().
        This particular callback requires userdata to be the
**
        address of a valid, initialized SERVER INFO LIST pointer.
**
        (SERVER INFO LIST is an application data structure defined
        by this sample).
* *
**
** Returns
**
     CS CONTINUE unless the SERVER INFO LIST pointed at by userdata fills
**
       up, then CS SUCCEED to truncate the search results.
*/
S RETCODE
                   CS PUBLIC
```

```
directory cb(conn, reqid, status, numentries, ds object, userdata)
CS CONNECTION
                 *conn;
CS INT
                  regid;
CS RETCODE
                   status;
CS INT
                   numentries;
CS DS OBJECT
                  *ds object;
CS VOID
                  *userdata;
    CS RETCODE
                       ret;
    SERVER INFO LIST *server list;
    if (status != CS_SUCCEED || numentries <= 0)</pre>
       return CS SUCCEED;
    /*
    ** Append the object to the list of servers.
    server list = *((SERVER INFO LIST **)userdata);
    ret = sil add object(server list, ds object);
    if (ret != CS SUCCEED)
    {
        /*
        ** Return CS SUCCEED to discard the rest of the objects that were
        ** found in the search.
        */
        ex error(
           "directory cb: Too many servers! Truncating search results.");
        return CS SUCCEED;
    /*
    ** Return CS CONTINUE so Client-Library will call us again if more
    ** entries are found.
    */
    return CS_CONTINUE;
} /* directory cb() */
```

# Step 3: Inspecting directory objects

Applications inspect the contents of a directory object with several calls to ct\_ds\_objinfo. To an application, a directory object consists of the following visible pieces:

- The object class that the object belongs to
- The object's fully qualified name
- A numbered set of attributes

An object's directory object class determines the object's attributes and the expected syntax (that is, datatype) for each attributes' values.

Although object attributes appear as a numbered set, an application should be coded to work independently of the order in which attributes are returned. A directory object class does not define an ordering of attributes, and most directory services do not guarantee that attributes will be ordered consistently for different directory objects in the same object class.

Most applications use a program structure similar to the one below to inspect a directory object:

```
ct ds objinfo to get the directory object class (optional)
ct_ds_objinfo to get the fully qualified name
... application code to process fully qualified name ...
for each desired attribute type
 ct_ds_objinfo to get number of attributes
 i = 0
 while i is less than number of attributes
   i = i + 1
   ct ds objinfo to retrieve the metadata for attribute i
   compare returned attribute type to desired attribute type
   if attribute types match
       /* i is the number of the desired attribute */
      break while
   end if
 end while
 allocate sufficient space for attribute i's values
 ct ds objinfo to retrieve attribute i's values
  ... application code to process attribute values ...
end for
```

### Attribute data structures

An attribute's metadata is represented by a CS\_ATTRIBUTE structure:

#### where:

- attr\_type is a CS\_OID structure that uniquely describes the type of the attribute. This field tells the application which of an object's attributes it has received.
- *attr\_syntax* is a syntax specifier that tells how the attribute value is expressed. Attribute values are passed within a CS\_ATTRVALUE union, and the syntax specifier tells which member of the union to use.
- attr\_numvals tells how many values the attribute contains. This
  information can be used to size an array of CS\_ATTRVALUE unions to
  hold the attribute values.

An attribute's value(s) are represented by a CS\_ATTRVALUE union:

Applications check the *syntax* field of the CS\_ATTRIBUTE structure to determine which member of a CS\_ATTRVALUE union contains the actual value. The following table shows the correspondence:

CS_ATTRIBUTE syntax specifier	CS_ATTRVALUE union member
CS_ATTR_SYNTAX_STRING	value_string
CS_ATTR_SYNTAX_BOOLEAN	value_boolean
CS_ATTR_SYNTAX_INTEGER	value_integer
CS_ATTR_SYNTAX_TRANADDR	value_tranaddr
CS_ATTR_SYNTAX_OID	value_oid

Figure 9-1 shows an exploded view of the CS\_ATTRVALUE union and its member structures:

CS ATTRVALUE Union CS\_STRING value\_string; CS\_STRING Structure CS BOOL value boolean; CS\_INT str\_length; CS\_CHAR str\_buffer CS\_INT value\_enumeration; [CS\_MAX\_DS\_STRING]; CS\_INT value\_integer; CS\_OID Structure CS\_OID value\_oid; CS\_INT oid\_length; CS TRANADDRR value\_tranaddr; CS\_CHAR oid\_buffer [CS\_MAX\_DS\_STRING]; CS\_TRANADDR Structure CS\_INT addr\_accesstype; CS\_STRING addr\_trantype; CS\_STRING addr\_trantype;

Figure 9-1: An exploded CS\_ATTRVALUE union

### Example code to inspect a directory object

The following fragment declares an example routine, show\_server\_info, that prints the contents of a directory object as text.

The code uses a static array, *AttributesToDisplay*, that lists the attribute types (as OID strings) for the attributes whose values should be retrieved, in the order that they should be printed.

For each row in *AttributesToDisplay*, the example retrieves the values for the attribute type (if any) and prints them.

```
/*
** AttributesToDisplay is a read-only static array used by
** the show server info() function. It contains the Object
** Identifier (OID) strings for the server attributes to
** display, in the order that they are to be displayed.
* /
typedef struct
    CS CHAR
                        type string[CS MAX DS STRING];
    CS CHAR
                        english name [CS MAX DS STRING];
} AttrForDisplay;
#define N ATTRIBUTES 7
CS STATIC AttrForDisplay AttributesToDisplay[N ATTRIBUTES + 1] =
    {CS_OID_ATTRSERVNAME, "Server name"},
    {CS OID ATTRSERVICE, "Service type"},
    {CS OID ATTRVERSION, "Server entry version"},
    {CS OID ATTRSTATUS, "Server status"},
    {CS OID ATTRADDRESS, "Network addresses"},
    {CS OID ATTRRETRYCOUNT, "Connection retry count"},
    {CS OID ATTRLOOPDELAY, "Connection retry loop delay"},
    {"", ""}
};
/*
** show server info()
**
     Selectively display the attributes of a server directory
     object.
**
** Parameters
**
     ds object -- Pointer to the CS DS OBJECT that describes the
**
       server's directory entry.
**
     outfile -- Open FILE handle to write the output to.
**
** Dependencies
* *
     Reads the contents of the AttributesToDisplay global array.
**
** Returns
     CS SUCCEED or CS FAIL.
*/
CS RETCODE
show server info(ds object, outfile)
CS DS OBJECT
                   *ds object;
```

```
FILE
                  *outfile;
   CS RETCODE
                       ret;
   CS CHAR
                       scratch str[512];
   CS INT
                       outlen;
   CS INT
                       cur attr;
   CS ATTRIBUTE
                       attr metadata;
   CS ATTRVALUE
                     *p attrvals;
/*
   ** Distinguished name of the object.
   */
   ret = ct_ds_objinfo(ds_object, CS_GET, CS_DS_DIST_NAME, CS_UNUSED,
                       (CS VOID *) scratch str, CS SIZEOF(scratch str),
                        &outlen);
   if (ret != CS SUCCEED)
       ex error ("show server info: qet distinquished name failed.");
       return CS FAIL;
    }
   fprintf(outfile, "Name in directory: %s\n", scratch str);
for (cur attr = 0; cur attr < N ATTRIBUTES; cur attr++)</pre>
        /*
        ** Look for the attribute. attr get by type() fails if the object
        ** instance does not contain a value for the attribute. If this
        ** happens, we just go on to the next attribute.
        * /
        ret = attr_get_by_type(ds_object,
                               AttributesToDisplay[cur attr].type string,
                               &attr metadata, &p attrvals);
        if (ret == CS_SUCCEED)
            fprintf(outfile, "%s:\n",
                    AttributesToDisplay[cur attr].english name);
            ** Display the attribute values.
            ret = attr display values(&attr metadata, p attrvals, outfile);
            if (ret != CS SUCCEED)
                ex error (
                  "show server info: display attribute values failed.");
```

```
free(p_attrvals);
    return CS_FAIL;
}

free(p_attrvals);
} /* if */
} /* for */
return CS_SUCCEED;
} /* show server info() */
```

### Retrieving an attributes value

The example fragment below contains the code for the attr\_get\_by\_type example utility routine. attr\_get\_by\_type takes an OID string that specifies the desired attribute type, searches for the desired attribute in the directory object's attribute set, and returns the attribute's metadata and values if they are found.

```
/*
** get attr by type()
**
     Get metadata and attribute values for a given attribute type.
**
** Parameters
**
     ds object -- Pointer to a valid CS DS OBJECT hidden structure.
**
     attr type str -- Null-terminated string containing the OID for the
**
              desired attribute type.
**
     attr metadata -- Pointer to a CS ATTRIBUTE structure to
**
              fill in.
**
     p attrvals -- Address of a CS ATTRVALUE union pointer.
**
              If successful, this routine allocates an array
**
              of size attr metadata->numvalues, retrieves values into
**
              it, and returns the array address in *p attr values.
**
              NOTE: The caller must free this array when it is no longer
**
              needed.
++
** Returns
     CS FAIL if no attribute of the specified type was found.
**
     CS SUCCEED for success.
*/
CS RETCODE
attr get by type(ds object, attr type str, attr metadata, p attrvals)
CS DS OBJECT
                   *ds object;
CS CHAR
                   *attr type str;
```

```
CS ATTRIBUTE
                 *attr metadata;
CS ATTRVALUE
                **p attrvals;
   CS RETCODE
                       ret;
   CS INT
                       num attrs;
   CS INT
                       cur attr;
   CS INT
                       outlen;
   CS INT
                       buflen;
   CS_BOOL
                       found = CS_FALSE;
   /*
   ** Check input pointers. If not NULL, make them fail safe.
   if (attr metadata == NULL | p attrvals == NULL)
       return CS FAIL;
   attr metadata->attr numvals = 0;
    *p attrvals = NULL;
   /*
    ** Get number of attributes.
   */
   ret = ct ds objinfo(ds object, CS GET, CS DS NUMATTR, CS UNUSED,
                        (CS VOID *) # attrs, CS SIZEOF(num attrs),
                        NULL);
   if (ret != CS SUCCEED)
       ex error("attr get by type: get number of attributes failed.");
       return CS FAIL;
    }
    ** Look for the matching attribute, get the values if found.
   for (cur attr = 1;
        cur attr <= num attrs && found != CS TRUE;</pre>
        cur_attr++)
    {
        /*
        ** Get the attribute's metadata.
        ret = ct_ds_objinfo(ds_object, CS_GET, CS_DS_ATTRIBUTE, cur_attr,
                            (CS VOID *)attr metadata,
                            CS SIZEOF(CS ATTRIBUTE), NULL);
        if (ret != CS SUCCEED)
```

```
{
            ex error("attr get by type: get attribute failed.");
            return CS FAIL;
        }
        ** Check for a match.
        if (match OID(&(attr metadata->attr type), attr type str))
            found = CS TRUE;
            ** Get the values -- we first allocate an array of
            ** CS ATTRVALUE unions.
            *p attrvals = (CS ATTRVALUE *) malloc(sizeof(CS ATTRVALUE)
                                         * (attr metadata->attr numvals));
            if (p attrvals == NULL)
                ex_error("attr_get_by_type: out of memory!");
                return CS FAIL;
            buflen = CS SIZEOF(CS ATTRVALUE) * (attr metadata->attr numvals);
            ret = ct ds objinfo(ds object, CS GET, CS DS ATTRVALS, cur attr,
                               (CS VOID *)(*p attrvals), buflen, &outlen);
            if (ret != CS SUCCEED)
                ex_error("attr_get_by_type: get attribute values failed.");
                free(*p attrvals);
                *p attrvals = NULL;
                attr_metadata->attr_numvals = 0;
                return CS FAIL;
            }
        }
}
    ** Got the attribute.
    */
    if (found == CS TRUE)
        return CS SUCCEED;
    ** Not found.
```

```
*/
     attr metadata->attr numvals = 0;
     return CS FAIL;
 } /* attr get by type() */
/*
  match OID()
**
              Compare a pre-defined OID string to the contents of a
              CS OID structure.
** Parameters
**
             oid -- Pointer to a CS OID structure. OID->oid length should be
              the length of the string, not including any null-terminator.
              oid string -- Null-terminated OID string to compare.
**
**
** Returns
          Non-zero if contents of oid->oid buffer matches contents
          of oid string.
* /
int
match OID(oid, oid string)
                            *oid:
CS OID
CS CHAR
                            *oid string;
          return ((strncmp(oid string, oid->oid buffer, oid->oid length) == 0)
                  && ((oid->oid length == strlen(oid string)
              );
} /* match OID() */
```

### Processing attribute values

The code fragment below declares an example routine, attr\_display\_values, which prints the values of an attribute as text. attr\_display\_values calls two other utility routines to perform its work:

- attr\_val\_as\_string formats an attribute value as text and puts the result in a character array.
- attr\_enum\_english\_name converts an integer or enumerated attribute value into a printable character string

.

```
/*
** attr display values()
     Writes an attribute's values to the specified text
**
     file.
**
** Parameters
     attr metadata -- address of the CS ATTRIBUTE structure that
**
         contains metadata for the attribute.
     attr vals -- address of an array of CS ATTRVALUE structures.
**
         This function assumes length is attr metadata->attr numvals
**
         and value syntax is attr metadata->attr syntax.
**
     outfile -- Open FILE handle to write to.
**
** Returns
     CS SUCCEED or CS FAIL.
* /
CS RETCODE
attr display values(attr metadata, attr vals, outfile)
CS ATTRIBUTE
                   *attr metadata;
CS ATTRVALUE
                   *attr vals;
                   *outfile;
FILE
    CS INT
                         i:
    CS CHAR
                        outbuf[CS MAX DS STRING * 3];
    CS RETCODE
                        ret;
    ** Print each value.
    * /
    for (i = 0; i < attr metadata->attr numvals; i++)
         ret = attr val as string(attr metadata, attr vals + i,
                                  outbuf, CS MAX DS STRING * 3, NULL);
         if (ret != CS SUCCEED)
             ex_error("attr_display_values: attr_val_as_string() failed.");
             return CS FAIL;
         fprintf(outfile, "\t%s\n", outbuf);
     }
    return CS_SUCCEED;
} /* attr display values() */
/*
** attr val as string() -- Convert the contents of a CS ATTRVALUE union to
```

```
**
      a printable string.
 **
 ** Parameters
     attr metadata -- The CS ATTRIBUTE structure containing metadata
 **
         for the attribute value.
     val -- Pointer to the CS ATTRVALUE union.
 **
     buffer -- Address of the buffer to receive the converted value.
     buflen -- Length of *buffer in bytes.
     outlen -- If supplied, will be set to the number of bytes written
        to *buffer.
 ** Returns
 ** CS SUCCEED or CS FAIL.
 */
CS RETCODE
 attr val as string(attr metadata, val, buffer, buflen, outlen)
CS ATTRIBUTE
                 *attr metadata;
CS ATTRVALUE
                   *val;
CS CHAR
                  *buffer;
 CS INT
                    buflen;
 CS INT
                  *outlen;
    CS CHAR
                        outbuf[CS MAX DS STRING * 4];
    CS CHAR
                        scratch[CS MAX DS STRING];
    CS RETCODE
                        ret;
if (buflen == 0 | buffer == NULL)
        return CS FAIL;
     if (outlen != NULL)
        *outlen = 0;
switch ((int)attr metadata->attr syntax)
     case CS_ATTR_SYNTAX_STRING:
         sprintf(outbuf, "%.*s",
                 (int) (val->value string.str length),
                 val->value string.str buffer);
         break;
     case CS ATTR SYNTAX BOOLEAN:
         sprintf(outbuf, "%s",
                 val->value boolean == CS TRUE ? "True" : "False");
        break;
```

```
case CS ATTR SYNTAX INTEGER:
     case CS ATTR SYNTAX ENUMERATION:
        /*
         ** Some enumerated or integer attribute values should be converted
         ** into an english-language equivalent. attr enum english name()
         ** contains all the logic to convert #define's into human
         ** language.
         * /
         ret = attr enum english name((CS INT)(val->value enumeration),
                                      &(attr metadata->attr type),
                                       scratch, CS MAX DS STRING, NULL);
         if (ret != CS SUCCEED)
             ex_error("attr_val_as_string: attr_enum_english_name() failed.");
             return CS FAIL;
         sprintf(outbuf, "%s", scratch);
         break;
case CS ATTR SYNTAX TRANADDR:
         /*
         ** The access type is an enumerated value. Get an english language
         ** string for it.
         */
         switch ((int)(val->value tranaddr.addr accesstype))
         case CS ACCESS CLIENT:
             sprintf(scratch, "client");
             break:
         case CS ACCESS ADMIN:
             sprintf(scratch, "administrative");
             break:
         case CS ACCESS MGMTAGENT:
             sprintf(scratch, "management agent");
             break:
         default:
             sprintf(scratch, "%ld",
                     (long) (val->value tranaddr.addr accesstype));
             break:
         }
sprintf(outbuf,
             "Access type '%s'; Transport type '%s'; Address '%s'",
                 val->value tranaddr.addr trantype.str buffer,
                 val->value tranaddr.addr tranaddress.str buffer);
```

```
break;
case CS_ATTR_SYNTAX_OID:
         sprintf(outbuf, "%.*s",
                 (int) (val->value oid.oid length),
                 val->value oid.oid buffer);
         break:
     default:
         sprintf(outbuf, "Unknown attribute value syntax");
         break:
     } /* switch */
if (strlen(outbuf) + 1 > buflen || buffer == NULL)
        return CS FAIL;
     else
         sprintf(buffer, "%s", outbuf);
         if (outlen != NULL)
             *outlen = strlen(outbuf) + 1;
     return CS_SUCCEED;
 } /* attr val as string() */
/*
 ** attr enum english name()
      Based on the attribute type, associate an english phrase with
 * *
      a CS INT value. Use this function to get meaningful names for
      CS ATTR SYNTAX ENUMERATION or CS ATTR SYNTAX INTEGER attribute
 **
      values.
 **
 **
      If the attribute type represents a quantity and not a numeric code,
 **
 **
      then the value is converted to the string representation of the
      number. Unknown codes are handled the same way.
 **
 ** Parameters
 **
      enum val -- The integer value to convert to a string.
 **
      attr type -- Pointer to an OID structure containing the OID string
 **
         that tells the attribute's type.
```

```
**
     buffer -- Address of the buffer to receive the converted value.
 **
     buflen -- Length of *buffer in bytes.
 **
      outlen -- If supplied, will be set to the number of bytes written
 **
        to *buffer.
 **
 ** Returns
      CS SUCCEED or CS FAIL
 */
CS RETCODE
 attr enum english name(enum val, attr type, buffer, buflen, outlen)
CS INT
                     enum val;
CS OID
                    *attr_type;
CS CHAR
                    *buffer;
CS INT
                    buflen;
CS INT
                    *outlen;
                         outbuf[CS MAX DS STRING];
     CS CHAR
if (buffer == NULL | | buflen <= 0)</pre>
        return CS FAIL;
     if (outlen != NULL)
        *outlen = 0;
     }
     /*
     ** Server version number.
     if (match OID(attr type, CS OID ATTRVERSION))
         sprintf(outbuf, "%ld", (long)enum val);
     }
     /*
     ** Server's status.
     else if (match OID(attr type, CS OID ATTRSTATUS))
         switch ((int)enum val)
         case CS STATUS ACTIVE:
             sprintf(outbuf, "running");
             break;
         case CS STATUS STOPPED:
             sprintf(outbuf, "stopped");
             break;
```

```
case CS STATUS FAILED:
            sprintf(outbuf, "failed");
            break;
        case CS STATUS UNKNOWN:
            sprintf(outbuf, "unknown");
        default:
            sprintf(outbuf, "%ld", (long)enum val);
            break;
        }
    }
    ** Anything else is either an enumerated type that we don't know
    ** about, or it really is just a number. We print the numeric value.
    */
    else
        sprintf(outbuf, "%ld", (long)enum_val);
    ** Transfer output to the caller's buffer.
    */
    if (strlen(outbuf) + 1 > buflen || buffer == NULL)
        return CS FAIL;
   else
        sprintf(buffer, "%s", outbuf);
        if (outlen != NULL)
            *outlen = strlen(outbuf) + 1;
return CS SUCCEED;
} /* attr_enum_english_name() */
```

# Step 4: Cleaning up

An application can call ct\_ds\_dropobj to deallocate each directory object that it received through its directory callback.

Alternatively, directory objects are dropped implicitly when the application calls ct\_con\_drop to drop the parent connection.

# APPENDIX A Logical Sequence of Calls

Client-Library uses a *state machine* to enforce a logical order of operations. It stores information about the last call that an application made and limits the calls that can follow to those that are legal. For example, an application must call ct\_connect to connect to a server before it can call ct send to send commands.

# Client-Library state machines

The application programming interface (API) layer of Client-Library consists of three state machines, each corresponding to one of the three basic control structures: CS\_CONTEXT, CS\_CONNECTION, or CS\_COMMAND. See "Hidden structures" on page 31 for a discussion of the basic control structures.

At the context level, an application sets up its environment by: allocating one or more context structures, setting CS-Library properties for the contexts, initializing Client-Library, and setting Client-Library properties for the contexts. See "Step 1: Set up the Client-Library programming environment" on page 19.

At the connection level, an application connects to a server by: allocating one or more connection structures, setting properties for the connections, opening the connections, and setting any server options for the connections. An application can allocate a connection structure only after a context structure has been allocated. See "Step 3: Connect to a server" on page 23.

At the command level, an application allocates one or more command structures, sends commands, and processes results. An application can allocate a command structure only after a connection structure has been allocated. See "Step 4: Send commands to the server" on page 25.

#### Command-level sequence of calls

It is at the command level that the logical sequence of calls becomes complex, due to the larger number of routines that are managed at the command level.

Client-Library's command state machine gets help from two other state tables when it attempts to verify that a call to a particular routine is permitted: the initiated-commands state table and the result-types state table.

#### Commands state table

The commands table defines the *states* of an application. For example, it defines a command-sent state to indicates that the last call an application made was ct\_send.

The commands table also maps each state to valid Client-Library routines that an application can call while in that state. For example, in the Command Sent state, an application can cancel the command or the result set, get or set command structure properties, perform operations on a dynamic SQL descriptor area, receive a TDS packet from the server, or set up results for processing.

See "Command states" on page 178 for a detailed description of each of the command states. See "Callable routines in each command state" on page 181 for a list of legal calls in each command state.

#### Initiated-commands state table

The initiated-commands table controls the use of routines that initiate and set up commands to be sent to a server (ct\_command, ct\_cursor, ct\_dynamic, ct\_param, and so on). It provides a finer level of enforcement than is possible with the commands table.

For example, the command state machine ensures that ct\_param is called only after a command has been initiated. However, it cannot prevent an application from calling ct\_param when the initiated command does not take parameters (as in the case of a ct\_cursor(CS\_CURSOR\_CLOSE)). It is in cases like these that the initiated-commands table enforces the logical sequence of calls.

As another example, assume that a Client-Library cursor is declared using the *cmd1* CS\_COMMAND structure. After the cursor-declare command is sent to the server and the results are processed, the state machine is in the Idle state.

From the Idle state, the command state machine permits an application to initiate a new command. It cannot prevent an application from declaring a second cursor using the same CS\_COMMAND structure that it used to declare the first cursor (*cmd1*).

The Initiated Commands table, however, keeps track of the state of a cursor on a command handle. It recognizes that, if a cursor has been previously declared using a particular CS\_COMMAND structure, a second attempt to declare a cursor using the same CS\_COMMAND structure is illegal.

See "Initiated commands" on page 193 for a detailed description of each of the initiated command states. See "Callable routines for initiated commands" on page 195 for a mapping of initiated command states with Client-Library routines.

### Result-types state table

The result-types table focuses on routines that return information about result sets. The command state machine defines states (like Fetchable Results and Fetchable Cursor Results) that indicate when results are available. The result-types table goes a step further by indicating the type of available results.

This information is important because certain routines make sense only for certain result types. For example, calling ct\_compute\_info is only logical when compute results are available, and calling ct\_br\_column is only logical when regular row results are available. In cases like these, the result-types table enforces the logical sequence of calls.

See "Result types" on page 198 for a detailed description of each of the result type states. See "Callable routines for each result type" on page 200 for a mapping of result type states with Client-Library routines.

### **Summary**

The information that follows is a reference for valid Client-Library application behavior. Use it when you want to verify that a particular sequence of routine calls is valid or when you need to know "where to go from here."

**Note** Client-Library returns descriptive error messages at runtime if an application has not called routines in a logical sequence.

# **Command states**

Client-Library keeps track of a command's current state. A command can be in any one of the following states.

Table A-1: Command states

Command state	Meaning
Idle	The application:
	Has not yet initiated a command,
	Has completely processed the results of the last command,
	Has fetched all cursor rows but has not closed the Client- Library cursor, or
	Has closed a Client-Library cursor that is still associated with unprocessed results.
Command initiated	The application called ct_command, ct_cursor, or ct_dynamic to initiate a command, but it has not yet sent it to the server.
Command sent	The application called ct_send to send a command to the server, but it has not yet called ct_results to set up result data for processing.
Non-fetchable	The application called ct_results and the result set contains
results available	no actual result data. Additional calls to ct_results are
avanable	necessary. Or:
	The application called ct_fetch, which returned CS END DATA.
ANSI-style cursor end-data	The application called ct_fetch, which returned CS_END_DATA, and the CS_ANSI_BINDS property is set.
Fetchable results	The application called ct_results and the result set contains fetchable non-cursor results (compute results, return parameter results, regular row results, and stored procedure return status results). ct_fetch has not been called yet.
Fetchable cursor results	The application called ct_results and the result set contains fetchable cursor results. ct_fetch has not yet been called.
Fetchable nested command	The application initiated a cursor-close command (ct_cursor(CS_CURSOR_CLOSE)) before fetching from a result set that contains fetchable cursor results.
Sent fetchable nested command	The application called ct_send to send the cursor-close command to the server before fetching from a result set that contains fetchable cursor results.
Processing fetchable nested command	The application called ct_results to process the results of the cursor-close command before fetching from a result set that contains fetchable cursor results.

Command state	Meaning
Fetching results	The application called ct_fetch at least once and is currently in the process of fetching results (compute results, return parameter results, regular row results, and stored procedure return status results).
Fetching cursor results	The application called ct_fetch at least once and is currently in the process of fetching cursor row results.
Fetching nested command	The application initiated one of the following commands while fetching from a result set that contains cursor results:
	Cursor-close (ct_cursor(CS_CURSOR_CLOSE))
	• Cursor-update (ct_cursor(CS_CURSOR_UPDATE))
	Cursor-delete (ct_cursor(CS_CURSOR_DELETE))
Sent fetching nested command	The application called ct_send to send the cursor- close, cursor-update, or cursor-delete command to the server while fetching from a result set that contains cursor results.
Processing fetching nested command	The application called ct_results to process the results of the cursor-close, cursor-update, or cursor-delete command while fetching from a result set that contains cursor results.
Result set canceled	The application canceled the current command (ct_cancel(CS_CANCEL_ALL)). An application can call ct_results once more to return the command to an Idle state.
Undefined	The command structure is in an undefined state. Call ct_cancel(CS_CANCEL_ALL).
In receive passthrough	The application called ct_recvpassthru and CS_PASSTHRU_MORE was returned.
In send passthrough	The application called ct_sendpassthru and CS_PASSTHRU_MORE was returned.

# **Command-level routines**

These Client-Library routines are managed at the command level:

ct_bind	ct_data_info	ct_param
ct_br_column	ct_describe	ct_recvpassthru
ct_br_table	ct_dynamic	ct_res_info
ct_cancel	ct_dyndesc	ct_results
ct_cmd_drop	ct_dynsqlda	ct_send
ct_cmd_props	ct_fetch	ct_send_data
ct_command	ct_get_data	ct_sendpassthru

ct_compute_info	ct_getformat	ct_setparam
ct_cursor	ct_keydata	

#### Callable routines in each command state

Table A-2 maps each command state to the Client-Library routines that an application can call while in that state. It also identifies the state of the command after the routine has completed.

Table A-2: Callable routines at each command state

Beginning state	Callable routines	Resulting command state
Idle	ct_cancel(CS_CANCEL_ALL)	Idle, if CS_SUCCEED.
	ct_cancel(CS_CANCEL_ATTN)	Undefined, if CS_FAIL.
	ct_cmd_drop	Idle.
	ct_cmd_props	Idle.
Idle	ct_command	Command initiated, if CS_SUCCEED.
		• Idle, if CS_FAIL.
	ct_cursor	Command initiated, if CS_SUCCEED.
		• Idle, if CS_FAIL.
	ct_dynamic	Command initiated, if CS_SUCCEED.
		• Idle, if CS_FAIL.
	ct_dyndesc	Idle.
	ct_dynsqlda	Idle.
	ct_sendpassthru	In send passthrough, if     CS_PASSTHRU_MORE.
		Command sent, if CS_PASSTHRU_EOM.
		Undefined, if CS_FAIL.

Beginning state	Callable routines	Resulting command state
Command	ct_cancel(CS_CANCEL_ALL)	Idle, if CS_SUCCEED.
initiated		Command initiated, if CS_FAIL.
	ct_cancel(CS_CANCEL_ATTN)	Command initiated.
	ct_cmd_props	Command initiated.
	ct_cursor	Command initiated.
	ct_data_info(CS_SET)	Command initiated.
	ct_dyndesc	Command initiated.
	ct_dynsqlda	Command initiated.
	ct_param	Command initiated.
	ct_setparam	Command initiated.
	ct_send	Command sent, if CS_SUCCEED.
		• Idle, if CS_CANCELED.
		Undefined, if CS_FAIL.
	ct_send_data	Command initiated, if CS_SUCCEED.
		Undefined, if CS_FAIL.

Beginning state	Callable routines	Resulting command state
Command	ct_cancel(CS_CANCEL_ALL)	Result set canceled, if CS_SUCCEED.
sent		Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_ATTN)	Command sent, if CS_SUCCEED.
		Undefined, if CS_FAIL.
	ct_cmd_props	Command sent.
	ct_dynsqlda	Command sent.
	ct_dyndesc	Command sent.
	ct_recvpassthru	In receive passthrough, if     CS_PASSTHRU_MORE.
		Idle, if CS_PASSTHRU_EOM, CS_CANCELED.
		Undefined, if CS_FAIL.
	ct_results	Non-fetchable results available, if     CS_SUCCEED and *result_type equals     CS_MSG_RESULT, CS_CMD_SUCCEED,     CS_CMD_FAIL, CS_CMD_DONE,     CS_ROWFMT_RESULT,     CS_COMPUTEFMT_RESULT, or     CS_DESCRIBE_RESULT.
		Fetchable results, if CS_SUCCEED and     *result_type* equals CS_ROW_RESULT,     CS_COMPUTE_RESULT,     CS_PARAM_RESULT, or     CS_STATUS_RESULT.
		• Fetchable cursor results, if CS_SUCCEED and *result_type equals CS_CURSOR_RESULT.
		Idle, if CS_CANCELED or CS_END_RESULTS.
		Undefined, if CS_SUCCEED and *result_type equals CS_CMD_FAIL.
Non-fetchable	ct_br_column	Non-fetchable results available.
results	ct_br_table	Non-fetchable results available.
available	ct_cancel(CS_CANCEL_ALL)	Result set canceled, if CS_SUCCEED.
		Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_ATTN)	Non-fetchable results available, if CS_SUCCEED.
		Undefined, if CS_FAIL.

Beginning state	Callable routines	Resulting command state
Non-fetchable results	ct_cancel(CS_CANCEL_CURRENT)	Non-fetchable results available, if CS_SUCCEED.
available		• Undefined, if CS_FAIL.
	ct_cmd_props	Non-fetchable results available.
	ct_compute_info	Non-fetchable results available.
	ct_describe	Non-fetchable results available.
	ct_dyndesc	Non-fetchable results available.
	ct_dynsqlda	Non-fetchable results available.
	ct_getformat	Non-fetchable results available.
	ct_res_info	Non-fetchable results available.
ANSI-style cursor end-data	ct_results	Fetchable results, if CS_SUCCEED and     *result_type equals CS_ROW_RESULT,     CS_COMPUTE_RESULT,     CS_PARAM_RESULT, or     CS_STATUS_RESULT.
		• Fetchable cursor results, if CS_SUCCEED and *result_type equals CS_CURSOR_RESULT.
		• Idle, if CS_CANCELED or CS_END_RESULTS.
		• Undefined, if CS_FAIL.
	ct_bind	ANSI-style cursor end-data.
	ct_br_column	ANSI-style cursor end-data.
	ct_br_table	ANSI-style cursor end-data.
	ct_cancel(CS_CANCEL_ALL)	Result set canceled, if CS_SUCCEED.
		• Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_ATTN)	ANSI-style cursor end-data if CS_SUCCEED.
		• Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_CURRENT)	ANSI-style cursor end-data.
	ct_cmd_props	ANSI-style cursor end-data.
	ct_compute_info	ANSI-style cursor end-data.
	ct_describe	ANSI-style cursor end-data.
	ct_dyndesc	ANSI-style cursor end-data.
	ct_dynsqlda	ANSI-style cursor end-data.
	ct_fetch	ANSI-style cursor end-data, if CS_END_DATA.
		• Idle, if CS_CANCELED.
		• Undefined, if CS_FAIL.

Beginning state	Callable routines	Resulting command state
ANSI-style cursor	ct_getformat	ANSI-style cursor end-data.
end-data	ct_res_info	ANSI-style cursor end-data.
	ct_results	Non-fetchable results available, if     CS_SUCCEED and *result_type equals     CS_MSG_RESULT or CS_CMD_DONE.
		• Idle, if CS_CANCELED.
		• Undefined, if CS_FAIL.
Fetchable	ct_bind	Fetchable results.
results	ct_br_column	Fetchable results.
	ct_br_table	Fetchable results.
	ct_cancel(CS_CANCEL_ALL)	• Result set canceled, if CS_SUCCEED.
		• Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_ATTN)	Fetchable results, if CS_SUCCEED.
		• Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_CURRENT)	Non-fetchable results available, if CS_SUCCEED.
		• Idle, if CS_CANCELED.
		• Undefined, if CS_FAIL.
	ct_cmd_props	Fetchable results.
	ct_compute_info	Fetchable results.
	ct_describe	Fetchable results.
	ct_dyndesc	Fetchable results.
	ct_dynsqlda	Fetchable results.
	ct_fetch	Fetching results, if CS_SUCCEED or CS_ROW_FAIL.
		Non-fetchable results available, if CS_END_DATA.
		• Idle, if CS_CANCELED.
		• Undefined, if CS_FAIL.
	ct_getformat	Fetchable results.
	ct_res_info	Fetchable results.

Beginning state	Callable routines	Resulting command state
Fetchable	ct_bind	Fetchable cursor results.
cursor results	ct_cancel(CS_CANCEL_ALL)	Result set canceled, if CS_SUCCEED.
		Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_ATTN)	Fetchable cursor results, if CS_SUCCEED.
		Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_CURRENT)	Non-fetchable results available, if CS_SUCCEED.
		• Idle, if CS_CANCELED.
		Undefined, if CS_FAIL.
	ct_cmd_props	Fetchable cursor results.
	ct_cursor	Fetchable nested command, if CS_SUCCEED.
		• Fetchable cursor results, if CS_FAIL.
	ct_describe	Fetchable cursor results.
	ct_dyndesc	Fetchable cursor results.
	ct_dynsqlda	Fetchable cursor results.
	ct_fetch	Fetching cursor results, if CS_SUCCEED or CS_ROW_FAIL.
		• Idle, if CS_CANCELED.
		Non-fetchable results available, if CS_END_DATA.
		ANSI-style cursor end-data, if CS_END_DATA and CS_ANSI_BINDS property is set.
		Undefined, if CS_FAIL.
	ct_getformat	Fetchable cursor results.
	ct_res_info	Fetchable cursor results.
Fetchable	ct_cancel(CS_CANCEL_ALL)	Fetchable cursor results, if CS_SUCCEED.
nested		Fetchable nested command, if CS_FAIL.
command	ct_cancel(CS_CANCEL_ATTN)	Fetchable nested command, if CS_SUCCEED.
		Undefined, if CS_FAIL.
	ct_cmd_props	Fetchable nested command.
	ct_dyndesc	Fetchable nested command.
	ct_dynsqlda	Fetchable nested command.
	ct_param	Fetchable nested command.
	ct_setparam	Fetchable nested command.
	ct_send	Sent fetchable nested, if CS_SUCCEED.
		• Idle, if CS_CANCELED.
		Undefined, if CS_FAIL.

Beginning state	Callable routines	Resulting command state
Sent fetchable	ct_cancel(CS_CANCEL_ALL)	Result set canceled, if CS_SUCCEED.
nested		• Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_ATTN)	Sent fetchable nested, if CS_SUCCEED.
		• Undefined, if CS_FAIL.
	ct_cmd_props	Sent fetchable nested.
	ct_results	Processing fetchable nested command, if CS_CMD_SUCCEED or CS_CMD_FAIL.
		• Idle, if CS_CANCELED.
		• Undefined, if CS_FAIL.
Processing	ct_cancel(CS_CANCEL_ALL)	Result set canceled, if CS_SUCCEED.
fetchable		• Undefined, if CS_FAIL.
nested command	ct_cancel(CS_CANCEL_ATTN)	Processing fetchable nested command, if CS_SUCCEED.
		• Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_CURRENT)	Processing fetchable nested command, if CS_SUCCEED.
		• Undefined, if CS_FAIL.
	ct_cmd_props	Processing fetchable nested command.
	ct_dyndesc	Processing fetchable nested command.
	ct_dynsqlda	Processing fetchable nested command.
	ct_res_info	Processing fetchable nested command.
	ct_results	Fetchable cursor results, if     CS_END_RESULTS.
		• Idle, if CS_CANCELED.
		• Undefined, if CS_FAIL.

Beginning state	Callable routines	Resulting command state
Fetching	ct_bind	Fetching results.
results	ct_br_column	Fetching results.
	ct_br_table	Fetching results.
	ct_cancel(CS_CANCEL_ALL)	Result set canceled, if CS_SUCCEED.
		• Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_ATTN)	Fetching results, if CS_SUCCEED.
		• Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_CURRENT)	Non-fetchable results available, if CS_SUCCEED.
		• Idle, if CS_CANCELED.
		• Undefined, if CS_FAIL.
	ct_cmd_props	Fetching results.
	ct_compute_info	Fetching results.
	ct_data_info(CS_GET)	Fetching results.
	ct_describe	Fetching results.
	ct_dyndesc	Fetching results, if CS_SUCCEED.
		• Idle, if CS_CANCELED.
		Undefined, if CS_FAIL.
Fetching	ct_dynsqlda	Fetching results, if CS_SUCCEED.
results		• Idle, if CS_CANCELED.
		Undefined, if CS_FAIL.
	ct_fetch	Fetching results, if CS_SUCCEED.
		Non-fetchable results available, if CS_END_DATA.
		• Idle, if CS_CANCELED.
		• Undefined, if CS_FAIL.
	ct_get_data	Fetching results, if CS_SUCCEED.
		• Idle, if CS_CANCELED.
		• Undefined, if CS_FAIL.
	ct_getformat	Fetching results.
	ct_res_info	Fetching results.

Beginning state	Callable routines	Resulting command state	
Fetching	ct_bind	Fetching cursor results.	
cursor	ct_cancel(CS_CANCEL_ALL)	• Result set canceled, if CS_SUCCEED.	
results		Undefined, if CS_FAIL.	
	ct_cancel(CS_CANCEL_ATTN)	Fetching cursor results, if CS_SUCCEED.	
		Undefined, if CS_FAIL.	
	ct_cancel(CS_CANCEL_CURRENT)	Non-fetchable results available, if CS_SUCCEED.	
		Idle, if CS_CANCELED.	
		Undefined, if CS_FAIL.	
	ct_cmd_props	Fetching cursor results.	
	ct_cursor	Fetching nested command, if CS_SUCCEED.	
		Fetching cursor results, if CS_FAIL.	
	ct_describe	Fetching cursor results.	
	ct_dyndesc	Fetching cursor results, if CS_SUCCEED.	
		• Idle, if CS_CANCELED.	
		Undefined, if CS_FAIL.	
	ct_dynsqlda	Fetching cursor results, if CS_SUCCEED.	
		Idle, if CS_CANCELED.	
		Undefined, if CS_FAIL.	
	ct_fetch	Fetching cursor results, if CS_SUCCEED.	
		Non-fetchable results available, if CS_END_DATA.	
		ANSI-style cursor end-data, if CS_END_DATA and CS_ANSI_BINDS property is set.	
		Idle, if CS_CANCELED.	
		Undefined, if CS_FAIL.	
	ct_get_data	Fetching cursor results, if CS_SUCCEED.	
		Idle, if CS_CANCELED.	
		Undefined, if CS_FAIL.	
	ct_getformat	Fetching cursor results.	
	ct_keydata	Fetching cursor results.	
	ct_res_info	Fetching cursor results.	

Beginning state	Callable routines	Resulting command state	
Fetching	ct_cancel(CS_CANCEL_ALL)	Fetching cursor results, if CS_SUCCEED.	
nested		• Fetching nested command, if CS_FAIL.	
command	ct_cancel(CS_CANCEL_ATTN)	Fetching nested command, if CS_SUCCEED.	
		• Undefined, if CS_FAIL.	
	ct_cmd_props	Fetching nested command.	
	ct_dyndesc	Fetching nested command.	
	ct_dynsqlda	Fetching nested command.	
	ct_param	Fetching nested command.	
	ct_setparam	Fetching nested command.	
	ct_send	Sent fetching nested command, if CS_SUCCEED.	
		• Idle, if CS_CANCELED.	
		• Undefined, if CS_FAIL.	
Sent fetching	ct_cancel(CS_CANCEL_ALL)	Result set canceled, if CS_SUCCEED.	
nested		• Undefined, if CS_FAIL.	
command	ct_cancel(CS_CANCEL_ATTN)	Sent fetching nested command, if CS_SUCCEED.	
		• Undefined, if CS_FAIL.	
	ct_cmd_props	Sent fetching nested command.	
	ct_results	Processing fetching nested command, if CS_CMD_SUCCEED or CS_CMD_FAIL.	
		• Idle, if CS_CANCELED.	
		• Undefined, if CS_FAIL.	

Beginning state	Callable routines	Resulting command state
Processing	ct_cancel(CS_CANCEL_ALL)	Result set canceled, if CS_SUCCEED.
fetching		• Undefined, if CS_FAIL.
nested command	ct_cancel(CS_CANCEL_ATTN)	Processing fetching nested command, if CS_SUCCEED.
		• Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_CURRENT)	Processing fetching nested command, if CS_SUCCEED.
		Undefined, if CS_FAIL.
	ct_cmd_props	Processing fetching nested command.
	ct_dyndesc	Processing fetching nested command.
	ct_dynsqlda	Processing fetching nested command.
	ct_keydata	Processing fetching nested command.
	ct_res_info	Processing fetching nested command.
	ct_results	Processing fetching nested command, if CS_SUCCEED.
		• Fetching cursor results, if CS_END_RESULTS.
		Idle, if CS_CANCELED.
		• Undefined, if CS_FAIL.

Beginning state	Callable routines	Resulting command state	
Result set	ct_cancel(CS_CANCEL_ALL)	Idle, if CS_SUCCEED.	
canceled		• Undefined, if CS_FAIL.	
	ct_cancel(CS_CANCEL_ATTN)	Idle, if CS_SUCCEED.	
		• Undefined, if CS_FAIL.	
	ct_cmd_drop	Idle.	
	ct_cmd_props	Idle.	
	ct_command	Command initiated, if CS_SUCCEED.	
		• Idle, if CS_FAIL.	
	ct_cursor	Command initiated, if CS_SUCCEED.	
		• Idle, if CS_FAIL.	
	ct_dynamic	Command initiated, if CS_SUCCEED.	
		• Idle, if CS_FAIL.	
	ct_dyndesc	Idle, if CS_SUCCEED, CS_ROW_FAIL, or CS_CANCELED.	
		• Undefined, if CS_FAIL.	
	ct_dynsqlda	Idle, if CS_SUCCEED, CS_ROW_FAIL, or CS_CANCELED.	
		• Undefined, if CS_FAIL.	
	ct_results	Result set canceled, if CS_SUCCEED or CS_FAIL.	
		• Idle, if CS_CANCELED.	
	ct_sendpassthru	Result set canceled.	
Undefined	ct_cancel(CS_CANCEL_ALL)	Idle, if CS_SUCCEED.	
		• Undefined, if CS_FAIL.	
	ct_cancel(CS_CANCEL_ATTN)	Undefined.	
	ct_cmd_props	Undefined.	
	ct_dyndesc	Undefined.	
	ct_dynsqlda	Undefined.	
In receive	ct_cancel(CS_CANCEL_ALL)	Idle, if CS_SUCCEED.	
passthrough		• Undefined, if CS_FAIL.	
	ct_cancel(CS_CANCEL_ATTN)	In receive passthrough, if CS_SUCCEED.	
		• Undefined, if CS_FAIL.	
	ct_cmd_props	In receive passthrough.	
	ct_recvpassthru	Idle, if CS_PASSTHRU_EOM or CS_CANCELED.	
		• Undefined, if CS_FAIL.	

Beginning state	Callable routines	Resulting command state
In send	ct_cancel(CS_CANCEL_ALL)	Idle, if CS_SUCCEED.
passthrough		Undefined, if CS_FAIL.
	ct_cancel(CS_CANCEL_ATTN)	In send passthrough, if CS_SUCCEED.
		• Undefined, if CS_FAIL.
	ct_cmd_props	In send passthrough.
	ct_sendpassthru	Command sent, if CS_PASSTHRU_EOM.
		Idle, if CS_CANCELED.
		• Undefined, if CS_FAIL.

# **Initiated commands**

In addition to command states, Client-Library keeps track of initiated commands. An initiated command can be in any one of the following states:

Table A-3: Initiated command states

Initiated command state	Meaning
Idle	The application either has not yet initiated a command or has completely processed the results of the last command.
Idle, with declared cursor	The application initiated a cursor-declare command (ct_cursor(CS_CURSOR_DECLARE)), sent the command to the server, and completely processed the results.
Idle, with opened cursor	The application initiated a cursor-open command (ct_cursor(CS_CURSOR_OPEN)), sent the command, and fetched all the results (ct_results returned CS_END_RESULTS), but has not yet closed the cursor.
Opened cursor, no rows fetched	The application called ct_results but has not yet processed any of the results.
Opened cursor, fetching rows	The application called ct_fetch at least once and is currently in the process of fetching results.
ct_command command initiated	The application initiated a language, message, package, or RPC command using ct_command.
Initiated send-data	The application initiated a send-data or send-bulk-data command using ct_command.
Initiated cursor-declare	The application initiated a cursor-declare command (ct_cursor(CS_CURSOR_DECLARE)) but has not yet sent it to a server using ct_send.
Initiated cursor-rows	The application initiated a cursor-rows command using ct_cursor(CS_CURSOR_ROWS).

Initiated command state	Meaning
Initiated cursor-open	The application initiated a cursor-open command (ct_cursor(CS_CURSOR_OPEN)) but has not yet sent it to a server.
Initiated cursor-close	The application initiated a cursor-close command (ct_cursor(CS_CURSOR_CLOSE)) but has not yet sent it to a server.
Initiated cursor-deallocate	The application initiated a cursor-deallocate command (ct_cursor(CS_CURSOR_DEALLOC)) but has not yet sent it to a server.
Initiated cursor-update	The application initiated a cursor-update command (ct_cursor(CS_CURSOR_UPDATE)) but has not yet sent it to a server.
Initiated cursor-delete row	The application initiated a cursor-delete command (ct_cursor(CS_CURSOR_DELETE)) but has not yet sent it to a server.
Initiated dynamic cursor-declare	The application initiated a cursor-declare command on a prepared dynamic SQL statement (ct_dynamic(CS_CURSOR_DECLARE)) but has not yet sent it to a server.
Initiated dynamic deallocate	The application initiated a command to deallocate a prepared SQL statement (ct_dynamic(CS_DEALLOC)) but has not yet sent it to a server.
Initiated dynamic describe	The application initiated a command to retrieve input parameter information (ct_dynamic(CS_DESCRIBE_INPUT)) or column list information (ct_dynamic(CS_DESCRIBE_OUTPUT)) but has not yet sent it to a server.
Initiated dynamic execute	The application initiated a command to execute a prepared SQL statement (ct_dynamic(CS_EXECUTE)) but has not yet sent it to a server.
Initiated dynamic execute immediate	The application initiated a command to execute a literal SQL statement (ct_dynamic(CS_EXEC_IMMEDIATE)) but has not yet sent it to a server.
Initiated dynamic prepare	The application initiated a command to prepare a SQL statement (ct_dynamic(CS_PREPARE)) but has not yet sent it to a server.
ct_send_data succeeded	The application successfully called ct_send_data at least once.
Initiated send-bulk command	The application initiated a send-bulk-data command (ct_command(CS_SEND_BULK_CMD)) but has not yet sent it to a server.

#### **Initiated command routines**

The following Client-Library routines are useful for processing initiated commands:

ct_cmd_drop	ct_dynamic	ct_send_data
ct_command	ct_dyndesc	ct_setparam
ct_cursor	ct_dynsqlda	ct_sendpassthru
ct_data_info	ct_param	

#### Callable routines for initiated commands

Table A-4 maps each initiated command state to the Client-Library routines that an application can call while in that state.

Where "none" is specified, an application can call none of the routines listed under "Initiated command routines" on page 194. From states that map to a "none" value in the Callable Routines column, an application's options are to send (ct\_send) or cancel (ct\_cancel) the initiated command.

Table A-4: Callable routines for initiated command states

Initiated Command	Callable Routines	
Idle	ct_cmd_drop	
	ct_command(CS_LANG_CMD)	
	ct_command(CS_MSG_CMD)	
	ct_command(CS_PACKAGE_CMD)	
	ct_command(CS_RPC_CMD)	
	ct_command(CS_SEND_BULK_CMD)	
	ct_command(CS_SEND_DATA_CMD)	
	ct_cursor(CS_CURSOR_DECLARE)	
	ct_dynamic(CS_CURSOR_DECLARE)	
	ct_dynamic(CS_DEALLOC)	
	ct_dynamic(CS_DESCRIBE_INPUT)	
	ct_dynamic(CS_DESCRIBE_OUTPUT)	
	ct_dynamic(CS_EXECUTE)	
	ct_dynamic(CS_EXEC_IMMEDIATE)	
	ct_dynamic(CS_PREPARE)	
	ct_sendpassthru	
Idle, with	ct_cursor(CS_CURSOR_ROWS)	
declared cursor	ct_cursor(CS_CURSOR_OPEN)	
	ct_cursor(CS_CURSOR_CLOSE, CS_DEALLOC)	
	ct_cursor(CS_CURSOR_DEALLOC)	
	ct_dynamic(CS_DEALLOC)	
Idle, with	ct_cursor(CS_CURSOR_CLOSE)	
opened cursor	ct_cursor(CS_CURSOR_CLOSE, CS_DEALLOC)	
	ct_dynamic(CS_DEALLOC)	
Opened cursor,	ct_cursor(CS_CURSOR_CLOSE)	
no rows fetched	ct_cursor(CS_CURSOR_CLOSE, CS_DEALLOC)	
Opened cursor,	ct_cursor(CS_CURSOR_CLOSE)	
fetching rows	ct_cursor(CS_CURSOR_CLOSE, CS_DEALLOC)	
8	ct_cursor(CS_CURSOR_UPDATE)	
	ct_cursor(CS_CURSOR_DELETE)	
ct_command command	ct_dyndesc(CS_USE_DESC)	
initiated	ct_dynsqlda(CS_SQLDA_PARAM)	
	ct_param	
	ct_setparam	
Initiated send-data	ct_data_info(CS_SET)	
	ct_send_data	

Initiated Command	Callable Routines
Initiated cursor-declare	ct_cursor(CS_CURSOR_ROWS) ct_cursor(CS_CURSOR_OPEN) ct_cursor(CS_CURSOR_OPTION) ct_dyndesc(CS_USE_DESC) ct_dynsqlda(CS_SQLDA_PARAM) ct_param ct_setparam
Initiated cursor-rows	ct_cursor(CS_CURSOR_OPEN)
Initiated cursor-open	ct_dyndesc(CS_USE_DESC) ct_dynsqlda(CS_SQLDA_PARAM) ct_param ct_setparam
Initiated cursor-close	None
Initiated cursor- deallocate	None
Initiated cursor-update	ct_dyndesc(CS_USE_DESC) ct_dynsqlda(CS_SQLDA_PARAM) ct_param ct_setparam
Initiated cursor-delete	None
Initiated dynamic cursor-declare	None
Initiated dynamic deallocate	None
Initiated dynamic describe	None
Initiated dynamic execute	ct_dyndesc(CS_USE_DESC) ct_dynsqlda(CS_SQLDA_PARAM) ct_param ct_setparam
Initiated dynamic execute immediate	None
Initiated dynamic prepare	ct_dyndesc(CS_USE_DESC) ct_dynsqlda(CS_SQLDA_PARAM) ct_param ct_setparam
ct_send_data succeeded	ct_send_data
Initiated send-bulk command	ct_send_data

# **Result types**

Client-Library restricts the routines that can be called based on the result type if a command is in one of the following states:

- Results available
- Fetchable results
- Fetchable cursor results
- Fetchable nested command
- Sent fetchable nested command
- Processing fetchable nested command
- Fetching results
- Fetching cursor results
- Fetching nested command
- · Sent fetching nested command
- · Processing fetching nested command

Table A-5 briefly describes the different result types:

Table A-5: Result type definitions

Result type	Meaning	
Regular row results	Zero or more rows of tabular data generated by the execution of a Transact-SQL select statement.	
Cursor row results	Zero or more rows of tabular data generated when an application executes a Client-Library cursor-open command.	
Parameter results	A single row of message parameters or stored procedure return parameters.	
Stored procedure return status results	A single row containing a single value (a return status).	
Message results	No data is available, but an application can call ct_res_info to get the message's ID.	
Compute row results	A single row of tabular data with a number of columns equal to the number of columns listed in the compute clause that generated the compute row.	
CS_CMD_DONE	The results of a command have been completely processed.	
CS_CMD_SUCCEED	A command that returns no data (such as a language command containing a Transact-SQL insert statement) was successful.	
CS_CMD_FAIL	The server encountered an error while executing a command.	
Regular row format results	Format information for an associated regular row result set.	
Compute row format results	Format information for an associated compute row result set.	
Describe results	Descriptive information returned as the result of a dynamic SQL describe input or output command.	
Extended error data results	A single row of extended error data.	
Notification results	A single row of arguments with which a registered procedure was called.	

See Chapter 6, "Writing Results-Handling Code" for detailed information about the various types of results.

## Result type processing routines

The following Client-Library routines are useful for processing various types of results:

ct_bind	ct_data_info	ct_getformat
ct_br_column	ct_describe	ct_keydata
ct_br_table	ct_dyndesc	ct_res_info
ct_compute_info	ct_dynsqlda	

### Callable routines for each result type

When an application calls ct\_results to find out what kind of results are available, Client-Library defines which routines are callable based on the value of the ct\_results \*result\_type\* parameter.

Table A-6 maps each result type to the Client-Library routines that an application can legally call to process that result type.

Table A-6: Callable routines for each result type

Result type	Callable routines
Regular row results	ct_bind
	ct_br_column
	ct_br_table
	ct_data_info(CS_GET)
	ct_describe
	ct_getformat
	ct_res_info(CS_BROWSE_INFO)
	ct_res_info(CS_CMD_NUMBER)
	ct_res_info(CS_NUMDATA)
	ct_res_info(CS_NUMORDERCOLS)
	ct_res_info(CS_ORDERBY_COLS)
	ct_res_info(CS_TRANS_STATE)
	ct_dyndesc(CS_USE_DESC)
	ct_dynsqlda(CS_SQLDA_BIND)
Cursor row results	ct_bind
	ct_describe
	ct_getformat
	ct_keydata
	ct_res_info(CS_CMD_NUMBER)
	ct_res_info(CS_CMD_NUMDATA)
	ct_res_info(CS_TRANS_STATE)
	ct_dyndesc(CS_USE_DESC)
	ct_dynsqlda(CS_SQLDA_BIND)
Parameter results	ct_bind
	ct_describe
	ct_res_info(CS_CMD_NUMBER)
	ct_res_info(CS_NUMDATA)
	ct_res_info(CS_TRANS_STATE)
	ct_dyndesc(CS_USE_DESC)
	ct_dynsqlda(CS_SQLDA_BIND)
Stored procedure	ct_bind
return status results	ct_describe
	ct_res_info(CS_CMD_NUMBER)
	ct_res_info(CS_CMD_NUMDATA)
	ct_res_info(CS_TRANS_STATE)
	ct_dyndesc(CS_USE_DESC)
	ct_dynsqlda(CS_SQLDA_BIND)
Message results	ct_res_info(CS_CMD_NUMBER)
0	ct_res_info(CS_MSGTYPE)
	ct_res_info(CS_TRANS_STATE)
	555_IIIO(CD_114111D_51111D)

Result type	Callable routines
Compute row results	ct_bind
	ct_compute_info
	ct_describe
	ct_res_info(CS_CMD_NUMBER)
	ct_res_info(CS_NUM_COMPUTES)
	ct_res_info(CS_NUMDATA)
	ct_res_info(CS_TRANS_STATE)
	ct_dyndesc(CS_USE_DESC)
	ct_dynsqlda(CS_SQLDA_BIND)
CS_CMD_DONE	ct_res_info(CS_CMD_NUMBER)
	ct_res_info(CS_ROW_COUNT)
	ct_res_info(CS_TRANS_STATE)
CS_CMD_SUCCEED	ct_res_info(CS_CMD_NUMBER)
	ct_res_info(CS_ROW_COUNT)
	ct_res_info(CS_TRANS_STATE)
CS CMD FAIL	ct_res_info(CS_CMD_NUMBER)
	ct_res_info(CS_ROW_COUNT)
	ct_res_info(CS_TRANS_STATE)
Regular row format	ct describe
results	ct_res_info(CS_CMD_NUMBER)
	ct_res_info(CS_CMD_NUMDATA)
	ct_res_info(CS_TRANS_STATE)
Compute row format	ct_compute_info
results	ct_describe
	ct_res_info(CS_CMD_NUMBER)
	ct_res_info(CS_NUM_COMPUTES)
	ct_res_info(CS_NUMDATA)
	ct_res_info(CS_TRANS_STATE)
Describe results	ct_describe
	ct_res_info(CS_CMD_NUMBER)
	ct_res_info(CS_NUMDATA)
	ct_res_info(CS_TRANS_STATE)
	ct_dyndesc(CS_GETATTR)
	ct_dyndesc(CS_GETCNT)
	ct_dynsqlda(CS_GET_IN)
	ct_dynsqlda(CS_GET_OUT)
Extended error data	ct_bind
results	ct_describe
	ct_res_info(CS_NUMDATA)
	ct_res_info(CS_TRANS_STATE)

Result type	Callable routines
Notification results	ct_bind
	ct_describe
	ct_res_info(CS_NUMDATA)
	ct_res_info(CS_TRANS_STATE)

## **Pending results**

Multiple command structures sharing the same connection can block one another when results are pending on the connection. "Pending results" is a term that indicates that the results of a command have not yet been completely processed.

For example, assume that two command structures (A and B) share the same connection structure. If A is in the Results Available state, B is blocked from sending a command to the server because there are results pending on the connection. B remains blocked until A processes all the results of the current command and transitions into a state that indicates that no results are pending.

States that indicate pending results are:

- · Command sent
- Results available
- ANSI-style cursor end-data
- Fetchable results
- Sent fetchable nested command
- Processing fetchable nested command
- Fetching results
- · Sent fetching nested command
- Undefined
- In receive passthrough
- In send passthrough

States that do not indicate pending results are:

- Idle
- Command initiated
- Fetchable cursor results

- Fetchable nested command
- Fetching cursor results
- Fetching nested command
- Processing fetching nested command
- Result set canceled

For a definition of each command state, see Table A-1 on page 179.

# Index

A	combined with inline message handling 67
action parameter 43	deinstalling 70
Adaptive Server Enterprise	installing 70
implementation of dynamic SQL 135	replacing 70
messages and extended error data 73	See also Client message callback 22
transaction states 74	storing callback locations 68
user-defined datatypes 63	using to handle messages 67
Adaptive Server Enterprise Reference Manual xi	chapters in this manual, summary of ix
allocating	character datatypes 57
a CS_BLKDESC structure 35	chunked messages 72
	Client message callback
	Client-Library routines it can call 68
	defining 68
	valid return values 69
applications	when Client-Library fails to call 68
compiling and linking x, 6	Client messages 65
finishing up 28	Client-Library
runtime requirements 6	compiling and linking applications 6
steps in a simple program 6	errors and messages 36
	exiting 28
	extended error data 73
В	generation of messages 65
_	initializing 19, 20
binary datatypes 56	messages 65
binding	return codes 65
definition of 96	column-level data access 73
bit datatype 57	command structure 33, 34
blk_alloc 35	allocating 25
blk_drop 35	deallocating 28
browse-mode column information 36	setting and retrieving properties 25
buffer parameter 44	commands
buflen parameter 44	defining parameters for 77
bulk copy	initiating 26, 76
and CS_BLKDESC structure 35	sending to a server 25
	compiling and linking 6
	compute format results
C	how to process 106
C	compute results
callbacks 22	how to process 102
advantages over inline message handling 66	routines for processing 102

connecting to a server 6, 23	CS_CUR_NAME property 131
connection structure 32, 34	CS_CUR_ROWCOUNT property 131
allocating 23	CS_CUR_STATUS property 132
deallocating 28	CS_DATAFMT structure 36, 37
setting and retrieving properties 23	and Client-Library routines 37
storing information as properties 33	and CS-Library routines 37
constants 39, 41	CS_DATE datatype 58
format constants 39	CS_DATEREC structure 36
miscellaneous constants 40	CS_DATETIME datatype 58
type constants 39	CS_DATETIME4 datatype 58
context structure 32	CS_DECIMAL datatype 59
allocating 19	CS_DIAG_TIMEOUT_FAIL property
CICS restriction 32	and inline message handling 71
deallocating 29	CS_DS_OBJECT hidden structure 32
setting Client-Library properties 21	ct describe
setting CS-Library properties 19	and CS_DATEREC structure 37
storing information as properties 32	CS_EXTRA_INF property
control structures	and inline message handling 71
basic control structures 33	CS_FAIL symbol 41
conventions	CS_FALSE symbol 41
font xi	CS_FLOAT datatype 59
parameter 41, 46	CS_FMT_PADBLANK format constant 40
CS_BINARY datatype 56	CS_FMT_PADNULL format constant 40
CS_BIT datatype 57	CS_FMT_UNUSED format constant 40
CS_BLKDESC structure 32, 34	CS_IMAGE datatype 60
CS_BROWSEDESC structure 35, 36	CS_INT datatype 59
CS_CLIENTMSG structure 36	CS_IODESC structure 36, 37
storing message text 72	CS_LOC_PROP property 20
CS_CMD_DONE result type	CS_LOCALE structure 32, 35
meaning of 107	CS_LOGINFO structure 31, 34
CS_CMD_FAIL result type	CS_LONGBINARY datatype 56
meaning of 107	CS_LONGCHAR datatype 57
CS_CMD_SUCCEED result type	CS_MAX_NAME symbol 41
meaning of 107	CS_MESSAGE_CB property 20
CS_COMMAND structure. See command structure 25	2 2 2
cs_config 19	CS_MONEY4 datatype 59
when to call 6	CS_NO_TRUNCATE property 72
CS_CONNECTION structure 31	and sequenced messages 72
See also connection structure 23	CS_NULLTERM symbol 41
CS_CONTEXT structure 31	CS_NUMERIC datatype 59
See also context structure 19	CS_REAL datatype 59
cs ctx alloc	CS_SERVERMSG structure 36, 38
when to call 6	storing message text 72
cs_ctx_drop	CS_SMALLINT datatype 59
when to call 7	CS_TEXT datatype 60
CS_CUR_ID property 131	CS_TIME datatype 58
= - r ·r· · J	=

CS_TINYINT datatype 59	when to call 7
CS_TRAN_COMPLETED transaction state 74	ct_describe 96
CS_TRAN_FAIL transaction state 74	and CS_DATAFMT structure 37
CS_TRAN_IN_PROGRESS transaction state 74	when to call 7
CS_TRAN_STMT_FAIL transaction state 74	ct_diag
CS_TRAN_UNDEFINED transaction state 74	handling messages inline 70
CS_UNITEXT datatype 60	uses of 70
CS_VARBINARY datatype 56	ct_dynamic 77, 138
CS_VARCHAR datatype 57	declaring a cursor to execute a prepared statement
CS-Library	123
installing a CS-Library message callback 23	when to call 7
setting context properties 19	ct_exit
cstypes.h header file 47	when to call 7
ct_bind 96	ct_fetch 96
and CS_DATAFMT structure 37	when to call 7
when to call 7	ct_getloginfo
ct_br_column 36	and CS_LOGINFO structure 34
ct callback 70	ct init 20
when to call 6	when to call 6, 20
ct_cancel	ct_keydata
cancel cursor results 99	when to call 129
ct_close	ct_options
when to call 7	when to call 6
ct_cmd_alloc 25	ct_param 77
when to call 7	and CS_DATAFMT structure 37
ct_cmd_drop	ct_res_info 96
when to call 7	when to call 7
ct_cmd_props 26	ct_results 94
ct_command 26, 77	completely processed results 97
initiating a language command 78	and CS_CMD_DONE 107
when to call 7	and CS_CMD_FAIL 107
ct_compute_info 103	and CS_CMD_SUCCEED 107
when to call 103, 104	cursor results 97
ct_con_alloc	other values of result_type 106
when to call 6	when to call 7
ct_con_props 23	ct_send 26
when to call 6	when to call 7
ct_config 21	ct_setloginfo
when to call 6	and CS_LOGINFO structure 34
ct_connect 24	ct_setparam 77
when to call 6	ctpublic.h header file
ct_cursor 77, 117	contents 19
declaring a cursor to directly execute a select	and datatype definitions 47
statement 120	cursor commands
declaring a cursor to execute a stored procedure	initiating 77, 117
122	cursor results

1	CO TINIVINITY 50
how to process 96	CS_TINYINT 59
cursors	CS_UNITEXT 60
and prepared dynamic SQL statements 123	CS_VARBINARY 56
declaring to execute a select statement 120	CS_VARCHAR 57
declaring to execute a stored procedure 122	datetime 57
declaring with ct_cursor 120, 122	decimal 59
declaring with ct_dynamic 123	float 59
properties 131	money 59
retrieving a cursor's name 131	numeric 59
retrieving a cursor's server ID number 131	real 59
retrieving status of 132	SMALLINT 59
retrieving the current value of cursor rows 132	summary of datatypes 54
setting cursor rows 125	text and image 60
custom data conversion routines	type constants 39
installing 63	user-defined types 63
	datetime datatypes 57
	deallocating
<b>D</b>	a CS_BLKDESC structure 35
D	a CS_COMMAND structure 28
data	a CS_CONNECTION structure 28
describing data and program variables 37	a CS_CONTEXT structure 29
data conversion	decimal datatype 59
installing custom conversion routines 63	describe results
datatype definitions 47	how to process 105
datatypes	routines for processing 105
Adaptive Server user-defined types 63	directory object structure 34
binary 56	document conventions xi
bit 57	dynamic SQL
character 57	Adaptive Server Enterprise restrictions and
CS BINARY 56	requirements 135
CS_BIT 57	advantages 134
CS DATE 58	alternative to 144
CS_DATETIME 58	and cursors 123
CS_DATETIME4 58	cannot retrieve stored procedure output parameters
CS_DECIMAL 59	and return values 135
CS_FLOAT 59	how Adaptive Server implements it 135
CS_IMAGE 60	limitations 134
CS_INT 59	performance limitations 134
CS_LONGBINARY 56	purpose 133
CS_LONGCHAR 57	restrictions 134
CS_MONEY 59	stored procedures as alternatives 144
<del>_</del>	dynamic SQL commands
_	initiating 77, 138
	initiating 77, 130
CS_REAL 59	
CS_TEXT 60	
CS_TIME 58	

E	Н
error and message handling	header files 19
callback method 67	ctpublic.h 47
defining 6	hidden structures
inline method 70	CS_COMMAND 31
necessity of 6	CS_CONNECTION 31
preventing message truncation 72	CS_CONTEXT 31
and sequenced messages 72	CS_DS_OBJECT 32
two methods 66	CS_LOCALE 32
errors. See messages 65	CS LOGINFO 32
execute immediate operation	hierarchy of control structures 33
criteria 136	
exiting Client-Library 28	
exposed structures 35	
CS_BROWSEDESC 36	
CS_CLIENTMSG 36	initializing
CS_DATAFMT 36	Client-Library 20
CS_DATAREC 36	example of 19
CS_IODESC 36	initiating
CS_SERVERMSG 36	commands 26, 76
SQLCA 36	inline message handling 70
SQLCODE 36	advantages over callbacks 67
SQLSTATE 36	and ct_diag 67
extended error data 73	and SQLCA, SQLCODE, SQLSTATE structures
extended error data 73	38
	combined with callbacks 67
	and CS_DIAG_TIMEOUT_FAIL property 72
F	and CS_EXTRA_INF property 71
fetching	international support 35
definition of 96	item number parameters 43
	nem number parameters 45
file names, of libraries 6 files	
header files 19	
	L
float datatype 59 font conventions xi	
format constants 39	language command
	initiating 76
	localization
CS_FMT_PADBLANK 40 CS_FMT_PADNULL 40	CS_LOCALE structure 35
CS_TWI_I ADNOLL 40 CS_FMT_UNUSED 40	routines for manipulating CS_LOCALE structure
	35
format results and CS EXPOSE FMTS property 106	logging in to a server 24
	login properties 34
how to process 106	loop for processing results 94
routines for processing 106	

65 Client-Library 22 CS-Library 23 nessage command initiating 76 nessage results different from server messages 66 how to process 104 routines for processing 104 nessages chunked 72 client messages 36, 65 Client-Library messages 65 operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages 105 sequenced 72 server messages 38, 65, 66 money datatypes 59  N  WULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BINARY_TYPE default 62 CS_CHAR_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_MAGE_TYPE default 62	M	CS_TINYINT_TYPE default 62
numeric datatype 59  numeric datatype 59  numeric datatype 59  numeric datatype 59  Open Client initiating 76 nessage results different from server messages 66 how to process 104 routines for processing 104 messages chunked 72 client messages 36, 65 Client-Library messages 65 operating system messages 65 operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages 105 sequenced 72 server messages 38, 65, 66 money datatypes 59  N  NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BOUNDARY_TYPE default 62 CS_CS_CHAR_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME4_TYPE default 62 CS_FLOAT_TYPE default 62 CS_FLOAT_TYPE default 62 CS_INACR_TYPE default 62 CS_INACR_TYPE default 62 CS_INACR_TYPE default 62 CS_INT_TYPE default 62 CS_MAGE_TYPE default 62 CS_MAGE_TYPE default 62 CS_MONEY_TYPE default 62	message and error handling. See error and message handling 65	CS_VARCHAR_TYPE default 62
CS-Library 23 message command initiating 76 message results different from server messages 66 how to process 104 routines for processing 104 messages chunked 72 client messages 36, 65 Client-Library messages 65 operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages 105 sequenced 72 server messages 38, 65, 66 money datatypes 59  N NULL parameters 41 NULL substitution values 61 and cs_setnul 62 CS_BIT_TYPE default 62 CS_CBAR_TYPE default 62 CS_CBAR_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_INT_TYPE default 62	message callback	•
message command initiating 76 message results different from server messages 66 how to process 104 routines for processing 104 messages chunked 72 client messages 36, 65 Client-Library messages 65 operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages 105 sequenced 72 server messages 38, 65, 66 money datatypes 59  P  package command initiating 76 parameter 44  NULL parameters 41 NULL parameters 42 S. BINARY_TYPE default 62 CS_DATETIMEA_TYPE	Client-Library 22	numeric datatype 39
message results different from server messages 66 how to process 104 routines for processing 104 messages chunked 72 client messages 36, 65 Client-Library messages 65 operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages server messages 38, 65, 66 money datatypes 59  N NULL parameters 41 NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BIN_ARY_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_FLOAT_TYPE default 62 CS_FLOAT_TYPE default 62 CS_INAGE_TYPE default 62 CS_MONEY_TYPE default 62	CS-Library 23	
message results different from server messages 66 how to process 104 routines for processing 104 messages chunked 72 client messages 36, 65 Client-Library messages 65 operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages 105 sequenced 72 server messages 38, 65, 66 money datatypes 59  N NULL parameters 41 NULL parameters 44 buffen parameter 44 buffen parameter 44 buffen parameter 50 caching parameters 50 per Client and Server Programmer's Supplement for Microsoft Windows x Open Client and Server Programmer's Supplement for UNIX x Open Client and Server Programmer's Supplement for UNIX x Open Client and Server Programmer's Supplement for UNIX x Open Client and Server Programmer's Supplement for UNIX x Open Client and Server Programmer's Supplement for UNIX x Open Client DB-Library Reference Manual xi Open Server Server-Library/C Reference Manual xi Open Server Server-L	message command	
different from server messages 66 how to process 104 routines for processing 104 messages chunked 72 client messages 36, 65 Client-Library messages 65 operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages sequenced 72 server messages 38, 65, 66 money datatypes 59  N  NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BIT_TYPE default 62 CS_CAR_TYPE default 62 CS_CAR_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_IMAGE_TYPE de	_	0
user-defined datatypes 63  Open Client and Server Programmer's Supplement for Microsoft Windows x  Open Client and Server Programmer's Supplement for UNIX av  Open Client and Server Programmer's Supplement for UNIX av  Open Client and Server Programmer's Supplement for UNIX av  Open Client and Server Programmer's Supplement for UNIX av  Open Client and Server Programmer's Supplement for UNIX av  Open Client and Server Programmer's Supplement for UNI		Open Client
routines for processing 104 messages chunked 72 client messages 36, 65 Client-Library messages 65 operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages 105 sequenced 72 server messages 38, 65, 66 money datatypes 59  N NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BIT_TYPE default 62 CS_BOUNDARY_TYPE default 62 CS_CHAR_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_LOAT_TYPE default 62 CS_LOAT_TYPE default 62 CS_IMAGE_TYPE default 62 CS_IMAGE_TYPE default 62 CS_IMAGE_TYPE default 62 CS_MONEY_TYPE default 62 CS_MONEY_TYP	<del>-</del>	-
Microsoft Windows x Open Client and Server Programmer's Supplement for UNIX x Open Client DB-Library Reference Manual xi Open Server Server-Library/C Reference Manual xi Open Server Se		
chunked 72 client messages 36, 65 Client-Library messages 65 operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages 105 sequenced 72 server messages 38, 65, 66 money datatypes 59  N NULL parameters 41 NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BUNDARY_TYPE default 62 CS_CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_IMAGE_TYPE default 62 CS_IMAGE_TYPE default 62 CS_IMAGE_TYPE default 62 CS_MONEY_TYPE default 62		
client messages 36, 65 Client-Library messages 65 operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages 105 sequenced 72 server messages 38, 65, 66 money datatypes 59  N NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BIT_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_INT_TYPE default 62 CS_MONEY_TYPE default 62	<u> </u>	Open Client and Server Programmer's Supplement for
Client-Library messages 65 operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages 105 sequenced 72 server messages 38, 65, 66 money datatypes 59  N NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BIT_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_SINT_TYPE default 62 CS_INT_TYPE default 62 CS_MONEY_TYPE default 62		UNIX x
operating system messages 73 preventing truncation 72 ranges of Sybase- and user-defined messages sequenced 72 server messages 38, 65, 66 money datatypes 59  NULL parameters 41 NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BOUNDARY_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_INAGE_TYPE default 62 CS_INAGE_TYPE default 62 CS_INAGE_TYPE default 62 CS_INAGE_TYPE default 62 CS_INT_TYPE default 62 CS_INT_TYPE default 62 CS_MONEY_TYPE default 62		Open Client DB-Library Reference Manual xi
preventing truncation 72 ranges of Sybase- and user-defined messages 105 sequenced 72 server messages 38, 65, 66 money datatypes 59  NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BOUNDARY_TYPE default 62 CS_CHAR_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_IMAGE_TYPE default 62 CS_INT_TYPE default 62 CS_MONEY_TYPE default 62	•	Open Server Server-Library/C Reference Manual xi
ranges of Sybase- and user-defined messages sequenced 72 server messages 38, 65, 66 money datatypes 59  NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BOUNDARY_TYPE default 62 CS_CHAR_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME4_TYPE default 62 CS_DATETIME4_TYPE default 62 CS_IMAGE_TYPE default 62 CS_IMAGE_TYPE default 62 CS_INT_TYPE default 62 CS_IMAGE_TYPE default 62 CS_INT_TYPE default 62 CS_IN		operating system messages 73
sequenced 72 server messages 38, 65, 66 money datatypes 59  P  package command initiating 76 parameter results how to process 100 routines for processing 100 parameters action parameter 43 buffer parameter 44 buffen parameter 44 conventions 41, 46 defining parameters for a command 77 input parameters strings 42 interaction between action, buffer, buffen, outlen parameters 44 item numbers 43 non-pointer parameters 41  NULL substitution values 61 parameter results how to process 100 routines for processing 100 parameters action parameter 43 buffer parameter 44 conventions 41, 46 defining parameters for a command 77 input parameter strings 42 interaction between action, buffer, buffen, outlen parameters 44 item numbers 43 non-pointer parameters 42 NULL parameters 41 outlen parameter 44	•	outlen parameter 44
P  NULL parameters 41  NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BOUNDARY_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME4_TYPE default 62 CS_FLOAT_TYPE default 62 CS_INAGE_TYPE default 62 CS_INT_TYPE default 62 CS_MONEY_TYPE default 62  VP  package command initiating 76 parameter results how to process 100 routines for processing 100 parameters action parameter 44 buflen parameters 44 conventions 41, 46 defining parameters for a command 77 input parameters for a command 77 input parameter strings 42 interaction between action, buffer, buflen, outlen parameters 44 item numbers 43 non-pointer parameters 42 NULL parameters 41 outlen parameter 44		
P package command initiating 76 parameter results how to process 100 routines for processing 100 parameters 41 substitution values 61 and cs_setnull 62 cS_BINARY_TYPE default 62 cS_BOUNDARY_TYPE default 62 cS_CS_DATETIME_TYPE default 62 cS_DATETIME_TYPE default 62 cS_DATETIME4_TYPE default 62 cS_FLOAT_TYPE default 62 cS_INAGE_TYPE default 62 cS_INAGE_TYPE default 62 cS_INT_TYPE default 6	-	
package command initiating 76  NULL parameters 41  NULL substitution values 61  and cs_setnull 62  CS_BINARY_TYPE default 62  CS_BOUNDARY_TYPE default 62  CS_CS_DATETIME_TYPE default 62  CS_DATETIME4_TYPE default 62  CS_DATETIME4_TYPE default 62  CS_FLOAT_TYPE default 62  CS_IMAGE_TYPE default 62  CS_IMAGE_TYPE default 62  CS_INT_TYPE default 62  CS_MONEY_TYPE default 62  Date of the parameter and the parameter strings and the parameters		D
NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BOUNDARY_TYPE default 62 CS_CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME4_TYPE default 62 CS_IMAGE_TYPE default 62 CS_IMAGE_TYPE default 62 CS_IMAGE_TYPE default 62 CS_INT_TYPE default 62 CS_MONEY_TYPE default 62  ONULL parameters 41  initiating 76  parameter results  how to process 100  routines for processing 100  parameters  action parameter 44  buffer parameter 44  conventions 41, 46  defining parameters for a command 77  input parameter strings 42  interaction between action, buffer, buflen, outlen  parameters 44  item numbers 43  non-pointer parameters 42  NULL parameters 41  outlen parameter 44	3	•
NULL parameters 41 NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BOUNDARY_TYPE default 62 CS_CS_DATETIME_TYPE default 62 CS_DATETIME4_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_FLOAT_TYPE default 62 CS_INAGE_TYPE default 62 CS_INAGE_TYPE default 62 CS_INT_TYPE default 62 CS_INT_TYPE default 62 CS_MONEY_TYPE defau		
NULL parameters 41  NULL substitution values 61  and cs_setnull 62  CS_BINARY_TYPE default 62  CS_BIT_TYPE default 62  CS_BOUNDARY_TYPE default 62  CS_CHAR_TYPE default 62  CS_DATETIME_TYPE default 62  CS_DATETIME_TYPE default 62  CS_DECIMAL_TYPE default 62  CS_FLOAT_TYPE default 62  CS_INAGE_TYPE default 62  CS_INT_TYPE default 62  CS_INT_TYPE default 62  CS_INT_TYPE default 62  CS_MONEY_TYPE default 62  CS_ULL parameters 41  NULL parameters 41  outlen parameter 44  conventions 41, 46  defining parameters for a command 77  input parameter strings 42  interaction between action, buffer, buflen, outlen  parameters 44  item numbers 43  non-pointer parameters 42  NULL parameters 41  outlen parameter 44	11	
NULL substitution values 61 and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BIT_TYPE default 62 CS_BOUNDARY_TYPE default 62 CS_CHAR_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_FLOAT_TYPE default 62 CS_IMAGE_TYPE default 62 CS_INT_TYPE default 62 CS_INT_TYPE default 62 CS_MONEY_TYPE default 62 CS_ULL parameters 41  routines for processing 100  parameters action parameter 44 buflen parameter 44 conventions 41, 46 defining parameters for a command 77 input parameter strings 42 interaction between action, buffer, buflen, outlen parameters 44 item numbers 43 non-pointer parameters 42 NULL parameters 41 outlen parameter 44	N	-
and cs_setnull 62 CS_BINARY_TYPE default 62 CS_BIT_TYPE default 62 CS_BOUNDARY_TYPE default 62 CS_CS_CHAR_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_FLOAT_TYPE default 62 CS_IMAGE_TYPE default 62 CS_IMAGE_TYPE default 62 CS_INT_TYPE default 62 CS_MONEY_TYPE default 62 CS_MONEY_TYPE default 62 CS_MONEY_TYPE default 62 CS_MONEY_TYPE default 62 CS_UTLD TYPE default 62 CS_MONEY_TYPE default 62 CS_MONEY_TYPE default 62 CS_UTLD TYPE default 62 CS_MONEY_TYPE default 62 CS_UTLD TYPE default 62 CS_UTLD	NULL parameters 41	•
and cs_sethul 62  CS_BINARY_TYPE default 62  CS_BIT_TYPE default 62  CS_BOUNDARY_TYPE default 62  CS_CHAR_TYPE default 62  CS_DATETIME_TYPE default 62  CS_DATETIME_TYPE default 62  CS_DECIMAL_TYPE default 62  CS_FLOAT_TYPE default 62  CS_IMAGE_TYPE default 62  CS_INT_TYPE default 62  CS_MONEY_TYPE default 62  CS_MONEY_TYPE default 62  CS_MONEY_TYPE default 62  CS_ULL parameters 41  action parameter 43  buffer parameter 44  conventions 41, 46  defining parameters for a command 77  input parameter strings 42  interaction between action, buffer, buflen, outlen parameters 44  item numbers 43  non-pointer parameters 42  NULL parameters 41  outlen parameter 44	NULL substitution values 61	
CS_BINARY_TYPE default 62  CS_BOUNDARY_TYPE default 62  CS_CHAR_TYPE default 62  CS_CHAR_TYPE default 62  CS_DATETIME_TYPE default 62  CS_DATETIME_TYPE default 62  CS_DECIMAL_TYPE default 62  CS_FLOAT_TYPE default 62  CS_FLOAT_TYPE default 62  CS_IMAGE_TYPE default 62  CS_INT_TYPE default 62  CS_MONEY_TYPE default 62  CS_MONEY_TYPE default 62  Duffer parameter 44  buflen parameter 44  buflen parameter 44  buflen parameter 44  buflen parameter 44  conventions 41, 46  defining parameters for a command 77  input parameter strings 42  interaction between action, buffer, buflen, outlen parameters 44  item numbers 43  non-pointer parameters 42  NULL parameters 41  outlen parameter 44	and cs_setnull 62	•
CS_BOUNDARY_TYPE default 62 CS_CHAR_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME4_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_FLOAT_TYPE default 62 CS_IMAGE_TYPE default 62 CS_INT_TYPE default 62 CS_MONEY_TYPE default 62 CS_MONEY_TYPE default 62  Usual State of the state of t	CS_BINARY_TYPE default 62	*
CS_BOUNDARY_TYPE default 62 CS_CHAR_TYPE default 62 CS_DATETIME_TYPE default 62 CS_DATETIME4_TYPE default 62 CS_DECIMAL_TYPE default 62 CS_FLOAT_TYPE default 62 CS_IMAGE_TYPE default 62 CS_INT_TYPE default 62 CS_MONEY_TYPE default 62 CS_MONEY_TYPE default 62 CS_MONEY_TYPE default 62 CS_UTLD AT A CONVENTION OF THE CON		•
CS_CHAR_I TYPE default 62  CS_DATETIME_TYPE default 62  CS_DATETIME4_TYPE default 62  CS_DECIMAL_TYPE default 62  CS_FLOAT_TYPE default 62  CS_IMAGE_TYPE default 62  CS_INT_TYPE default 62  CS_MONEY_TYPE default 62  CS_MONEY_TYPE default 62  CS_UTLD AT A COMMAND A C		T
CS_DATETIME_TYPE default 62  CS_DECIMAL_TYPE default 62  CS_DECIMAL_TYPE default 62  CS_FLOAT_TYPE default 62  CS_IMAGE_TYPE default 62  CS_INT_TYPE default 62  CS_MONEY_TYPE default 62  input parameter strings 42  interaction between action, buffer, buflen, outlen parameters 44  item numbers 43  non-pointer parameters 42  NULL parameters 41  outlen parameter 44		
CS_DATETIME4_TYPE default 62  CS_DECIMAL_TYPE default 62  CS_FLOAT_TYPE default 62  CS_IMAGE_TYPE default 62  CS_INT_TYPE default 62  CS_MONEY_TYPE default 62  content of the following interaction between action, buffer, buflen, outlen parameters 44  item numbers 43  non-pointer parameters 42  NULL parameters 41  outlen parameter 44		
CS_BECIMAL_TTPE default 62 parameters 44  CS_FLOAT_TYPE default 62 item numbers 43  CS_IMAGE_TYPE default 62 non-pointer parameters 42  CS_MONEY_TYPE default 62 NULL parameters 41  outlen parameter 44		· ·
CS_IMAGE_TYPE default 62 non-pointer parameters 42 CS_INT_TYPE default 62 NULL parameters 41 CS_MONEY_TYPE default 62 outlen parameter 44		
CS_INT_TYPE default 62 non-pointer parameters 42 CS_MONEY_TYPE default 62 NULL parameters 41  outlen parameter 44		item numbers 43
CS_MONEY_TYPE default 62 NULL parameters 41		non-pointer parameters 42
outlen narameter $AA$		NULL parameters 41
	CS_MONEY4_TYPE default 62 CS_MONEY4_TYPE default 62	outlen parameter 44
CS_NUMERIC_TYPE default 62 output parameter strings 42		output parameter strings 42
CS_REAL_TYPE default 62 pointer parameters 41		pointer parameters 41
CS_SENSITIVITY_TYPE_default 62 unused parameters 41		-
CS_SMALLINT_TYPE default 62 prepare and execute operations		
CS_TEXT_TYPE default 62 advantages 138		advantages 138

criteria 137	S
steps to perform 138	
prepared statement	sample programs x scope of control structures 33
definition of 134, 140	•
when to use 137	send-data command initiating 76
processing results 7, 26	•
program structure 6, 29	sending commands to a server 6, 25 sequenced messages 72
connecting to a server 23	sequenced messages 72 and CS_NO_TRUNCATE property 72
finishing up 28	
installing callbacks 22	server message callback Client-Library routines it can call 69
processing results 26	Client-Library routines it can call 69 defining 69
sending commands 25	valid return value 70
setting up 19	
steps in a simple program 6	server message results 66 server messages 38, 65
program variables	
describing 37	1
properties	difference between server messages and message results 105
login properties 34	extended error data 73
setting Client-Library context properties 21	server results
setting command properties 25	how to process 26
setting connection properties 23	servers
setting CS-Library context properties 19	connecting to a server 6, 23
	logging in to a server 24
	sending commands to 6, 25
R	transaction states 74
N	setting
real datatype 59	Client-Library context properties 21
regular row format results	command structure properties 25
how to process 106	connection structure properties 23
regular row results	CS-Library context properties 19
how to process 94	setting up a program's environment 19
remote procedure calls	SQL
advantages 85	dynamic SQL 133
comparing RPCs and execute statements 85	SQLCA structure 36, 38
results	and CS_EXTRA_INF property 71
how to process 7, 26	no support for sequenced messages 73
return codes 65	SQLCODE structure 36, 38
return status results	and CS_EXTRA_INF property 71
how to process 101	no support for sequenced messages 73
routines for processing 101	SQLSTATE structure 36, 38
row results	and CS_EXTRA_INF property 71
how to process 94	no support for sequenced messages 73
RPC command	stored procedures
initiating 76	and Client-Library cursors 122
	declaring cursors to execute 122
	structures 31, 39

CS\_TRAN\_FAIL 74

allocating a CS_COMMAND structure 25 allocating a CS_CONNECTION structure 23 allocating a CS_CONTEXT structure 19 basic control structures 33	CS_TRAN_IN_PROGRESS 74 CS_TRAN_STMT_FAIL 74 CS_TRAN_UNDEFINED 74 type constants 39
command structure 31	definition of 54
connection structure 31	types
context structure 31	definitions of 47
control structure hierarchy 33	
CS_BLKDESC 34	
CS_BROWSEDESC 36	U
CS_CLIENTMSG 36	
CS_COMMAND 33	unused parameters 41
CS_COMMAND structure 31	user-defined datatypes 63
CS_CONNECTION 32	Adaptive Server Enterprise user-defined types 6.
CS_CONTEXT 32	
CS_CONTEXT 32 CS_CONTEXT structure 31	
CS_DATAFMT 36	V
CS_DATAIMI 30 CS_DATEREC 37	version behavior of Client I ibrary
CS_DS_OBJECT 34	version behavior of Client-Library setting 20
CS_IODESC 37	setting 20
CS_LOCALE 35	
CS_LOGINFO 34	
CS_SERVERMSG 38	
exposed structures 35	
hidden structures 31	
SQLCA 38	
SQLCODE 38	
SQLDA 38	
SQLSTATE 38	
symbolic constants 40	
values subject to change 41	
symbols	
CS_FALSE 41	
CS_SUCCEED 41	
CS_TRUE 41	
т	
-	
text and image	
describing data 38	
routines to manipulate data 60	
text and image datatypes 60	
transaction states 74	