# Release Bulletin EAServer 6.3 for IBM AIX

Document ID: DC38027-01-0630-01

Last revised: November 2009

Торіс	Page
1. Accessing current release bulletin information	2
2. Product summary	2
2.1 Version contents	3
2.2 Required system patches	3
3. Special installation instructions	4
3.1 Valid browser required for installation	4
4. Special upgrade instructions	4
5. New features in this version	4
5.1 Creating EAServer as an application server in Lomboz	5
5.2 Setting up BLOB messages	6
6. Known issues	9
6.1 Upgrading of Jetty	9
6.2 Incorrect decoding of Chinese characters	9
6.3 Getting OracleConnection in EAServer	9
6.4 Cannot access the Management Console	9
6.5 Ant configuration fails after deploying EJB file	10
6.6 Log files in Eclipse plug-in Management Console	10
6.7 JDK does not include Sun JDBC-ODBC driver	10
6.8 Obsolete HTTP server properties	11
6.9 Security risk	11
6.10 Configuring a database type	12
6.11 SQL Anywhere database issues	12
6.12 Adaptive Server Enterprise 12.5.x	12
6.13 Migration tool issue	13
6.14 Web Services Toolkit issues	13
6.15 Miscellaneous issues	14
7. Documentation updates and clarifications	14

Copyright 2009 by Sybase, Inc. All rights reserved. Sybase trademarks can be viewed at the Sybase trademarks page

at http://www.sybase.com/detail?id=1011207. Sybase and the marks listed are trademarks of Sybase, Inc. (1) indicates registration in the United States of America. Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. Unicode and the Unicode Logo are registered trademarks of Unicode, Inc. All other company and product names mentioned may be trademarks of the respective companies with which they are associated.

Торіс	Page
7.1 Automated Configuration Guide	15
7.2 CORBA Components Guide	19
7.3 Enterprise JavaBeans User's Guide	21
7.4 Installation Guide	22
7.5 New Features Guide	22
7.6 Security Administration and Programming Guide	22
7.7 System Administration Guide	24
7.8 Troubleshooting Guide	27
7.9 Web Services Toolkit User's Guide	28
8. Technical support	29
9. Other sources of information	29
9.1 Sybase certifications on the Web	30
9.2 Sybase EBFs and software maintenance	30
10. Accessibility features	31

# 1. Accessing current release bulletin information

A more recent version of this release bulletin may be available on the Web. To check for critical product or document information added after the product release, use the Sybase® Product Manuals Web site.

#### \* Accessing release bulletins at the Sybase Product Manuals Web site

- 1 Go to Product Manuals at http://www.sybase.com/support/manuals/.
- 2 Select a product and language and click Go.
- 3 Select a product version from the Document Set list.
- 4 Select the Release Bulletins link.
- 5 From the list of individual documents, select the link to the release bulletin for your platform. You can either download the PDF version or browse the document online.

## 2. Product summary

Enclosed is Sybase EAServer version 6.3, which is compatible with this platform and operating system configuration:

• IBM AIX 5.3 (32-bit and 64-bit). The 64-bit is used for pure Java code.

## 2.1 Version contents

Enclosed is Sybase EAServer version 6.3, Build 63009. You may have a later build number if you have installed ESD patches for this release. If so, the cover letters provided with each patch contain the build number and additional documentation.

The EAServer 6.3 software is provided on a DVD.

Table 1 describes the products that EAServer 6.3 supports.

Product	Supported versions/builds
Adaptive Server® Enterprise	12.5. <i>x</i> and 15.0. <i>x</i>
C++ compiler	IBM XL C/C++ 8.0
Eclipse	3.4.2
Java Development Kits (JDKs):	Versions:
1.5	1.5.0_SR3
1.6	1.6.0_00
Jetty	6.1.14
Oracle client	9.2.0.1 and 10g
Apache Web server redirector plug-in	2.0.55 and 2.2.11
SQL Anywhere®	11.0
Web browsers	Internet Explorer 6.0
	Firefox 3.0

#### Table 1: Product support

## 2.2 Required system patches

Before installing EAServer, make sure your system has the required patches described in this section.

**For AIX 5.3** AIX 5300-03 Recommended Maintenance Level (Maintenance Level 3) must be installed. This maintenance package can be downloaded from the IBM Web site.

For information on obtaining maintenance files, see the IBM Fix Delivery Center at http://www-933.ibm.com/eserver/support/fixes/.

To verify the maintenance level of your system, run:

oslevel -r

On AIX 5.3 systems, the command should return:

5300-03

Release Bulletin for IBM AIX

## 3. Special installation instructions

The *EAServer 6.2 Installation Guide* of your platform describes how to install the software.

## 3.1 Valid browser required for installation

**[CR #466892]** Before running the EAServer installer, a valid browser must exist on the target installation machine. Otherwise, selections on the Finish pane to launch the Readme and the Sybase Product Download Center (SPDC) Web site will not work.

## 4. Special upgrade instructions

You can install EAServer 6.3 as a new installation, or as an upgrade to an EAServer 6.x installation.

Before you upgrade from EAServer 6.2 to EAServer 6.3, rename \_shared.properties to shared.properties in <6.2\_installed\_directory>/ Repository/Instance/com/sybase/djc/security/DataProtection. This ensures that the keystore, truststore, and datasource passwords are all set correctly.

The EAServer migration tool enables you to migrate a subset of entity types from a 5.x repository to the 6.3 repository, saving time by scanning only those entity types that you require. For details, see:

- *EAServer 6.0 Migration Guide* on the Sybase Product Manuals Web site at http://www.sybase.com/support/manuals/.
- *EAServer 6.0.2 New Features Guide* on the Sybase Product Manuals Web site at http://www.sybase.com/support/manuals/. This book describes migration tool features that were introduced in version 6.0.2.

"Migration tool issue" on page 13 in this release bulletin describes problem that is known to occur during migration.

# 5. New features in this version

EAServer 6.3 includes these new features:

• Lomboz in Eclipse plug-in – Lomboz enables a complete development cycle for J2EE developers: coding, deploying, testing, and debugging. See "Creating EAServer as an application server in Lomboz" on page 5.

- Binary large objects (BLOBs) message in the EAServer message service

   a new BLOB message API allows BLOBs to be sent by way of an out-of-band transport mechanism. Possible out-of-band mechanisms include HTTP, File Transfer Protocol (FTP), Session Control Protocol (SCP), or some other point-to-point protocol. See "Setting up BLOB messages" on page 6.
- Support SQL Server Native Client for EAServer –

You can connect to SQL Server databases using JDBC, ODBC, or the SQL Server Native Client (SNC). EAServer does not include JDBC or ODBC drivers for Oracle, or the SNC libraries. EAServer provides dedicated support for the SQL Server proprietary C interface, SNC version 9. SNC connections that are cached by EAServer are used like any other SNC connection, except that EAServer opens the connection for you.

You can create SQL Server data sources that use ODBC or JDBC as for any other ODBC or JDBC data source. See "Other databases" in Chapter 4, "Database Access" in the *EAServer 6.0 System Administration Guide*.

## 5.1 Creating EAServer as an application server in Lomboz

#### Creating EAServer as an application server in Lomboz

- 1 Change to \$*EAServer\_Home/../Shared/eclipse\_342/eclipse/* and execute *starteclipse.sh.*
- 2 In Eclipse, open the Servers view:
  - a Select Window | Show View | Other.
  - b In the Show View dialog box, choose Servers under the Server category.
- 3 Right-click the Servers view and select New | Server to add a new server runtime.
- 4 In the New Server Define a New Server dialog box:
  - a Enter the server's host name. For example, *zeus-desktop*.
  - b Expand the Sybase folder and select EAServer 6.0 as its server type.
  - c Click Next.
- 5 In the New Server New Server 6.0 Runtime dialog box, enter:
  - EAServer6 location EAServer\_Home

- EAServer client jar EAServer\_Home/lib/eas-client-15.jar
- Additional client jar EAServer\_Home/lib/servlet-rt.jar

Click Next.

- 6 Complete these fields using your EAServer installation setting details:
  - HTTP port
  - IIOP host
  - IIOP port
  - User ID
  - Password

Click Next. The Add and Remove Projects dialog box appears.

- 7 Click Next in the Add and Remove Projects dialog box.
- 8 Click Finish.

The EAServer 6 server runtime in Eclipse has been added successfully. Rightclick the server and select Start item. In the Console view, a message will display to indicate that EAServer 6 server is able to start successfully.

## 5.2 Setting up BLOB messages

This section provides information about creating, sending, and receiving BLOB messages.

- Creating BLOB messages new method, createBlobMessage(), has been added to com.sybase.jms.client class. Use SybSession to create BLOB messages.
- Sending BLOB messages either:
  - Send by URL use the following code to send a file or URL that exists on a shared file system or Web server, around the Java Message Service (JMS) network:

```
BlobMessage message = session.createBlobMessage(new
URL("http://some.shared.site.com"));
    producer.send(message);
```

 Send by file or input stream – you are creating files or streams dynamically on the client, you may want to upload the file to some server such as Jetty, FTP, and so forth. Use one of these methods: • Upload the file using a Web application:

```
//set upload url,fileserver is file uploaded using web application
((SybConnection)connection).setRemoteUploadURL("http://hostname/
8000:/fileserver/");
```

• Use a local file:

```
// Use a local file
```

```
BlobMessage message = session.createBlobMessage(new
File("d:/upload.txt/"));
    producer.send(message);
```

• Use an input stream:

```
// Use an input stream
InputStream in = ...;
BlobMessage message = session.createBlobMessage(in);
producer.send(message);
```

 Receiving BLOB messages – BLOB message is a regular JMS message, so it can be received just like any other message. This example shows how to receive BLOB messages:

```
public class MyListener implements MessageListener {
  public void onMessage(Message message)
    {
        if (message instanceof BlobMessage)
        {
           BlobMessage blobMessage = (BlobMessage) message;
           InputStream in = blobMessage.getInputStream();
           // process the stream...
        }
    }
}
```

 This example shows how to write a client application to send and receive BLOB messages:

```
String url = "iiop://" + hostname + ":" + port;
Properties prop = new Properties();
prop.put(Context.INITIAL_CONTEXT_FACTORY, CTXFACTORY);
prop.put(javax.naming.Context.PROVIDER_URL, url);
```

```
prop.put(javax.naming.Context.SECURITY PRINCIPAL, username);
        prop.put(javax.naming.Context.SECURITY CREDENTIALS, password);
        context = new InitialContext(prop);
        String queueName = "testQueue";
        QueueConnectionFactory factory = (QueueConnectionFactory)
          context
                .lookup("javax.jms.QueueConnectionFactory");
        QueueConnection connection = factory.createQueueConnection
                (username, password);
((SybConnection) connection).setRemoteUploadURL("http://hostname:8000/
   fileserver/");
         QueueSession session = connection.createQueueSession(false,
                  Session.AUTO ACKNOWLEDGE);
        // Create a message producer and consumer.
           Queue queue = session.createQueue(queueName);
           QueueSender sender = session.createSender(queue);
           OueueReceiver receiver = null;
           receiver = session.createReceiver(queue);
           connection.start();
        // Prepare a text message to send http://syberspace.sybase.com/
           BlobMessage message =((SybSession)
           session).createBlobMessage(new File("d:/apachem.txt"));
          // Send the Msg
            sender.send(message);
            sender.close();
         // Receive the message. Wait until msg arrives.
          if (receiver != null)
           {
              Message msg = receiver.receive();
              BlobMessage blobmsg= (BlobMessage)msg;
              InputStream input= blobmsg.getInputStream();
              //process the iputstream
              receiver.close();
         }
```

```
if (connection != null)
{
  connection.close();
}
```

## 6. Known issues

This section describes known problems in this version of EAServer.

## 6.1 Upgrading of Jetty

**[CR #569870]** Jetty 6.1.14 has fixed an issue (JETTY-635) that may result in an EAServer test failure when you upgrade Jetty 6.1.5 to Jetty 6.1.14. If you are using jspParamForwardTest code in Jetty 6.1.14 in EAServer, update the code based on Jetty functional specification. For details, see the Jetty documentation at http://jira.codehaus.org/browse/JETTY-635.

## 6.2 Incorrect decoding of Chinese characters

**[CR #566763]** When you decode Chinese characters in a Java Server Page (JSP), there is a redundant "+" sign in the result.

*Workaround:* This is a known issue in Jetty which is scheduled to be addressed in the next release. For details, see the Jetty documentation at http://jira.codehaus.org/browse/JETTY-969.

## 6.3 Getting OracleConnection in EAServer

**[CR #538605]** EAServer supports OracleConnection and its update batching mechanism in a multithreaded environment with high concurrency. For example, after obtaining the container-managed data source connection, c, the API at the client side calls the getRealConnection method, as follows:

OracleConnection oc =
(OracleConnection)((com.sybase.djc.sql.ConnectionWrapper)C).getRealConnection();

## 6.4 Cannot access the Management Console

**[CR #537700]** If the EAServer installed path includes Chinese characters, you cannot access the Management Console.

Workaround: Before starting the server, execute:

Release Bulletin for IBM AIX

\$EAS63/bin/configure.sh disable-builtin-jsf

## 6.5 Ant configuration fails after deploying EJB file

**[CR #498829]** You cannot complete the Ant configuration after you have deployed an EJB-JAR file in Eclipse plug-in. No information appears when you click Details in the Progress Information window.

Workaround: Restart EAServer after deploying a new EJB-JAR file.

### 6.6 Log files in Eclipse plug-in Management Console

**[CR #497641]** The Eclipse plug-in Management Console does not allow you to view the log files remotely.

## 6.7 JDK does not include Sun JDBC-ODBC driver

**[CR #484121 and CR #393342]** IBM does not ship a Sun JDBC-ODBC driver with its JDK. You can use the SQL Anywhere JDBC-ODBC driver instead.

*Workarounds*: Select one of the following options. Sybase recommends the first option:

- Set these database property values:
  - Database Type: Unknown
  - Database URL: jdbc:odbc:EAS Demo DB V3
  - User: dba
  - Password: sql
  - Driver Class: ianywhere.ml.jdbcodbc.jdbc3.IDriver
- Or, set these database property values:
  - Database Type: SQL\_Anywhere
  - Database URL: jdbc:odbc:driver=
     ~/ASA100/client/lib32/libdbodbc10\_r.so;uid=dba;
     pwd=sql;dsn=EAS Demo DB V3
  - User: dba
  - Password: sql

- Driver Class: ianywhere.ml.jdbcodbc.jdbc3.IDriver
- Or, use one of the drivers that IBM recommends—see the IBM Java Web site at http://www.ibm.com/developerworks/aix/library/au-javaphpaix3/.

### 6.8 Obsolete HTTP server properties

**[CR #452369]** Beginning in version 6.2, EAServer no longer supports these HTTP properties:

- httpUseCustomGetServerInfo
- httpProxyProtocol
- httpProxyPort
- httpGetServerInfoFrom

Instead, EAServer reads these HTTP header fields:

- host to determine the host and port the client used to connect.
- sybaseredirectorheader to determine the protocol that was used to connect to a Web redirector.

If you call any of the HttpRequest methods, getServerName, getServerPort, or getProtocol, the values are retrieved from the browser. This is the same behavior that was achieved by setting httpGetServerInfoFrom to "source" in versions of EAServer earlier than 6.3.

## 6.9 Security risk

**[CR #434293]** Do not use HTTP to connect to the Management Console; the administrative user ID and password are passed in plain-text format during the login process, thus posing a security risk.

*Workaround*: Use HTTPS to log in to the Management Console. To use HTTPS, you first need to obtain a certificate. If you use the sample (test) certificate that is included with EAServer, anyone with EAServer 6.0 has access to your private (test) key. Therefore, Sybase recommends that you use your own certificate.

## 6.10 Configuring a database type

If you specify values for both the dataSourceClass and driverClass properties when you configure a database type, the system uses the class defined by dataSourceClass, and ignores these properties:

- driverClass
- databaseURL, because it is used only by the driver class

## 6.11 SQL Anywhere database issues

When you upgrade to EAServer 6.3, Adaptive Server® Anywhere (ASA) version 9.0.2 is upgraded to version 11.0, and the name of the database server changes from ASA to SQL Anywhere.

### 6.11.1 ODBC driver version

**[CR #470030]** The ODBC driver that you use with EAServer must be either the driver packaged with EAServer or a later version.

#### 6.11.2 Setting the databaseURL property

**[CR #467797]** If the value of the databaseURL property is "[default]" when you create a new data source for either a Sybase\_ASA or SQL\_Anywhere database type, attempts to ping the database fail and this message displays:

Ping failed due to exception: Use of the JIT driver wrapper for SQL Anywhere requires use of the underlying IAnywhere JDBC/ODBC driver - please reconfigure data source 'asal0demo' to include the odbcDataSource property. Please see the server log file for additional details.

*Workaround*: Set the databaseURL property to "jdbc:odbc:driver=EAS 6.0 ASA;uid=dba;pwd=sql;eng=<*asa10\_db\_alias*>," where <*asa10\_db\_alias*> is the value of the -n parameter that is used when starting the database.

## 6.12 Adaptive Server Enterprise 12.5.x

**[CR #447543]** If you are using Adaptive Server Enterprise (ASE) version 12.5.*x* with EAServer, you may see this error:

"SELECT INTO command not allowed within multi-statement transaction"

Workaround: On the machine where Adaptive Server is installed, run:

\$DJC\_HOME/extras/jconnect-6.05/sp/sql\_server12.5.sql

## 6.13 Migration tool issue

**[CR #437181]** When you are migrating EAServer entities from version 5.x to version 6.3, the migrate tool does not migrate *sql.ini* content for Open Client<sup>TM</sup> Client-Library connections.

*Workaround*: Manually copy Open Client Client-Library connection information from the 5.*x* version of *sql.ini* to the 6.3 version.

## 6.14 Web Services Toolkit issues

#### 6.14.1 Refreshing Web services collection causes an OutofMemory error

**[CR #494522]** When you refresh a Web services collection using the Refresh button in the Eclipse plug-in, or using jagtool, you see an OutofMemory error.

Workaround: To reduce memory leakage:

- 1 Log in to the Management Console.
- 2 Select Servers | <*name of your instance*>.
- 3 In the right pane, select the Module tab.
- 4 Under the User Start Modules, click Select and clear the Ejbjardatawindow check box.

### 6.14.2 Datatype mapping

**[CR #449109]** In EAServer 6.0, the Web services datatype-mapping version is set to 1.3, so xsd:short may be mapped to either the short or unsignedByte Java datatype. This causes some Web service tests to fail.

*Workaround*: Set the datatype-mapping version to 1.2, so xsd:short will always be mapped to the short datatype:

- 1 Start EAServer, and connect to the server using the Management Console.
- 2 Expand the Servers folder, and select the server.
- 3 On the General tab, find the WebServices Type Mapping Version field. The default value is 1.3.
- 4 Change the value to 1.2, and click Save.

### 6.14.3 Activating and deactivating Web services

**[CR #448806]** The wstool commands for activating and deactivating Web services, wstool activate and wstool deactivate, do not work.

### 6.14.4 Apache Scout

**[CR #448380]** The Apache Scout client method BusinessLifeCycleManager.saveAssociations fails, and a null pointer exception is returned.

### 6.14.5 Web services display in random order

**[CR #422161]** Selecting the Management Console options to display Web services either alphabetically or in descending order by date fail. Web services display in random order.

## 6.15 Miscellaneous issues

### 6.15.1 Untranslated exception

**[CR #474902]** When you deploy an EAServer entity, this line displays in the server log:

svc: java.lang.Error: Untranslated exception
but the function works correctly.

#### 6.15.2 Permission required to use JIT data sources

**[CR #465348]** You can use a JIT (just-in-time) data source to access a database only if you have permission to create tables in the database.

### 6.15.3 SSLServiceProvider.getGlobalProperty

**[CR #436638]** The SSLServiceProvider method for checking the status of FIPS, SSLServiceProvider.getGlobalProperty("fips140"), has not been implemented in EAServer 6.3.

# 7. Documentation updates and clarifications

This section contains updates and clarifications for the EAServer product manuals.

## 7.1 Automated Configuration Guide

## 7.1.1 Chapter 2, "Ant-Based Configuration"

#### Embedding configuration scripts in J2EE archives

**[CR #574077]** The text in the second paragraph of the "Embedding configuration scripts in J2EE archives" section is incorrect. The corrected text is:

Place the configuration file in the archive's META-INF subdirectory, using the file name that matches the archive type, as listed in the second column of Table 2-3. For *sybase-webapp-config.xml*, place this configuration file in the *WEB-INF* subdirectory.

#### Predefined configuration scripts

**[CR #581809]** EAServer 6.x supports JavaServer Faces (JSF) 1.1. By default, the JSF 1.1 classes in EAServer are enabled and loaded at EAServer start-up. Table 2-4 of the "Predefined configuration scripts" in Chapter 2, "Ant-Based Configuration" in the *Automated Configuration Guide* does not include the two JSF predefined scripts, which allow you to enable and disable JSF classes. The two missing scripts are:

Name	Configures defaults for
disable-builtin-jsf.xml	Disables the EAServer built-in JSF versions and
	classes.
enable-builtin-jsf.xml	Enables the EAServer built-in JSF versions and classes.

To disable JSF 1.1 these classes, use:

\$EAS6/bin/configure.sh disable-builtin-jsf

To enable JSF 1.1 these classes, use:

\$EAS6/bin/configure.sh enable-builtin-jsf

## 7.1.2 Chapter 3, "Using Scheduled Tasks"

**[CR #477285]** "Predefined tasks" does not include task, which you can schedule to remove unwanted PowerBuilder® cookies from your machine.

### 7.1.3 Chapter 4, "Creating Service Components"

**[CR #500334]** In Table 4-1 of "Service component entity properties," the Component property that specifies how to define the remote interface for a service component is incorrect. The corrected text is:

ejb.components.mypackage.MyComponentRemote

or, for a local interface for a service component:

```
ejb.components.mypackage.MyComponentLocal
```

#### Writing a Java class as a service component

This procedure shows how to write a Java class as a service component using these methods:

- start()
- run()
- stop()
- 1 Use a text editor to write a Java file that includes the three Java methods. For example:

```
package serviceTest;
public class oneService {
    boolean bstop = false;
    public void start()
{
            System.out.println("oneService start!");
            bstop = false;
}
    public void run()
         while(!bstop)
                System.out.println("oneService runing...");
                 try {
                          Thread.sleep(1000);
              }catch (InterruptedException e) {
         }
    }
     public void stop()
     {
          bstop = true;
```

	,	System	<pre>n.out.println("oneService stop!");</pre>
}	}		
		2	Save and compile this Java file to a class file.
		3	Create a JAR file for the class file.
		4	Place the JAR file in \$EAServer/lib/ext/.
		5	Log in to the Management Console.
		6	Select the Service Components folder, right-click, and select Add.
			a Type the name of the service component, for example, <i>oneservice</i> .
			b Choose Finish.
		7	Select <i>oneservice</i> from the Service Components subfolders.
			a Type the name of the component in the Component property field on the right side of the Management Console window. For example, <i>serviceTest.oneService</i> .
			b Select the Start Before Binding check box.
			c Select Apply to save the new settings.
		8	Select the Servers folder.
			a Select the server where EAServer is running. For example, <i>zeus- deskwxp</i> .
			b Select the Services tab.
			c Select the service component that you have just created, for example, <i>oneservice</i> from the list.
			d Select Apply to save the new settings.
		9	Restart EAServer.
			hen you run the service component, the log file or console displays these essages:
			oneService start!
			oneService runing",
		If	you stop EAServer, the log file or console displays this message:
			oneService stop!"

## 7.1.4 Chapter 6, "Using jagtool and jagant"

#### **Deploying applications**

**[CR #481055]** When you use jagtool to deploy a self-contained application, you can configure the application to use all the classes from the internal class loader by setting the disableResolveFirstBySystem property to true. For example:

jagtool.sh deploy -type war -disableResolveFirstBySystem true foo.war

#### **Obsolete jagtool commands**

**[CR #465796 and #447432]** These jagtool commands are documented in the *Automated Configuration Guide*, but the commands are not supported in EAServer 6.0 and later:

- configure
- export
- exportconfig
- grantroleauth
- mergeprops
- props
- removeroleauth
- set\_props

#### **Generating stubs**

**[CR #462838]** To generate stubs for a package or component, you can use the jagtool gen\_stubs command. See the *Automated Configuration Guide* for more information about jagtool commands.

Syntax

gen\_stubs [-javastubs true|false] [-cppstubs true|false] [-javastubjarname *file-name*] [-javastubcodebase *path*] [-cppstubcodebase *path*] [-compilejavastubs true|false] [-verbose true|false] *entity* 

Option	Description
javastubs	Whether to generate Java stubs; the default is true.
cppstubs	Whether to generate C++ stubs; the default is true.

Option	Description
javastubjarname	If specified, the Java stubs are placed in a JAR file of the specified name. The file name must include the full path.
	If not specified, Java files are generated (the default).
javastubcodebase	The location of the code base for Java stubs; the default is \$DJC_HOME/genfiles/java/stubs.
cppstubcodebase	The location of the code base for C++ stubs; the default is <i>\$DJC_HOME/include</i> .
compilejavastubs	Whether to compile the generated Java stubs; the default is true.
verbose	Whether to produce verbose output while generating stubs; the default is false.
entity	The name of the entity for which stubs are being generated, in the form <i>EntityType:EntityName</i> , where <i>EntityType</i> is either "Package" or "Component."

Return values

Return value	Indicates
0	The command ran successfully; the result is true/success.
2	The command did not run successfully; an exception was thrown.

## 7.2 CORBA Components Guide

### 7.2.1 Chapter 4, "Managing CORBA Packages and Components"

**[CR #437366]** You cannot use hyphens ("-") in CORBA-component package names. CORBA-component packages are those that contain CORBA/C++, CORBA/Java, or PowerBuilder components.

## 7.2.2 Chapter 5, "Developing and Deploying PowerBuilder Components"

**[CR #405138]** You cannot use a hyphen ("-") in the name of a PowerBuilder nonvisual object (NVO) method or variable. EAServer wraps NVOs as EJBs, and Java does not support method or variable names that contain hyphens.

#### Accessing data sources

**[CR #533120]** When accessing these predefined EAServer data sources from PowerBuilder components, set the default transaction object (SQLCA) to use the appropriate database type as shown in Table 2 on page 20.

Database type	Description
JCM_Sybase	For ASE database:
	sqlca.dbms="SYJ"
JCM_Oracle or	Oracle database which corresponds to the
JCM_Oracle_Unicode	EAServer 5.x Oracle Call Interface (OCI) 9 and
	OCI10 native connection caches.
	sqlca.dbms="090", or
	sqlca.dbms="010"
JCM_Odbc or	For any databases using ODBC driver:
JCM_Odbc_Unicode	sqlca.dbms="ODBC"
JCM_non-JCM JDBC-	For any non-JCM JDBC-compliant database type:
compliant	sqlca.dbms ="JDBC"

Table	2:	Database	type
-------	----	----------	------

#### Implementing method-level security for PowerBuilder components

**[CR #488947]** You can implement method-level security after deploying PowerBuilder components. To implement method-level security for a PowerBuilder component:

- 1 Add two users. For example, "Pass" and "Fail".
- 2 Change the role of the user "Pass" to admin-role. You can also define and use your role.
- 3 Deploy the *final\_test* NVO into EAServer from PowerBuilder.
- 4 Deploy *final\_test.jar* into EAServer from Web console or command line.
- 5 Run PowerBuilder client and click the Pass and Fail buttons.
- 6 Modify the *\$EAServer/config/ejbjar-final\_test-user.xml* file, as follows:

7 Run the Ant Refresh followed by the Run Ant Recompile from the Management Console.

8 Run the PowerBuilder client.

If the implementation is successful, the Pass button works.

If you click Fail, the NO\_PERMISSION exception occurs.

## 7.3 Enterprise JavaBeans User's Guide

### 7.3.1 Chapter 3, "Developing EJB Clients"

[CR #498818] In the "Client runtime requirements" section, includes this:

When using JDK 1.6, add this option in \$JAVA\_HOME/bin/java:

-Dsun.lang.ClassLoader.allowArraySyntax=true

This is because the JDK 1.6 on the client side provides the allowArraySyntax option to convert array from the server result data.

If clients run with a JRE, instead of a full JDK, you can prevent the client from trying to generate and compile stubs by setting the system property djc.allowRuntimeCompile to false for the Java command that starts the client application.

### 7.3.2 Chapter 4, "Creating Application Clients"

**[CR #472302]** In the section "Starting the runtime container," this example for starting an application client's runtime container is incorrect:

runclient.sh -client my\_appclient -login true

The correct syntax is:

run-appclient.sh -client my\_appclient -login true

## 7.4 Installation Guide

### 7.4.1 Chapter 2, "Installing EAServer"

**[CR #587037]** The following note should be included in step 5 of the "Adding components" procedure in "Reinstalling or adding components" in Chapter 2, "Installing EAServer:"

**Note** You cannot start the license server until there is at least one valid served license installed in the licenses directory: *\$SYBASE/sysam-2.1/licenses*.

For an unserved license, place the license file in \$SYBASE/EAServer/licenses.

## 7.5 New Features Guide

**[CR #493619]** The introduction in the ".NET client support" section in the *EAServer 6.1 New Features Guide* is incorrect. The corrected introduction is:

EAServer 6.1 includes .NET client support, and enables IIOP/IIOPS communication between .NET and J2EE distributed objects in EAServer.

## 7.6 Security Administration and Programming Guide

## 7.6.1 Chapter 6, "Using TLS and FIPS"

**[CR #474337]** The section "SSL/TLS and FIPS Support" describes how to enable FIPS support, "Enabling FIPS using the Certicom Java libraries." Step 2 says to set the com.sybase.ejb.fips connection property to specify FIPS usage, but fails to specify the value. To enable FIPS support, set the value of com.sybase.ejb.fips to true; to disable, set the value to false.

## 7.6.2 Chapter 11, "Managing Keys and Certificates"

**[CR #535090]** The "Set-certificate" section of Chapter 11, "Managing Keys and Certificates" does not provide sufficient information. You must run a setup procedure before you can use the set-certificate script.

• If necessary, install the certificate authority (CA) root certificate into the server's truststore. This enables the server to trust the client's certificate.

By default, some CA root certificates are preinstalled, but you may need to add one or more for testing purposes.

- a If the root certificate is not preinstalled, obtain a root certificate from the certificate authority at http://www.cacert.org/certs/root.txt.
- b Copy the certificate text, including BEGIN and END lines, and save in a file named *root.crt* in *SDIC\_HOME/Banagitam/Security/trustators ibs*

*\$DJC\_HOME/Repository/Security/truststore.jks.* 

-----BEGIN CERTIFICATE-----

c The administrative user must install root certificates into the server's truststore. To execute:

```
keytool -import -alias cacert.org -file root.crt
    -keystore $DJC_HOME/Repository/Security/truststore.jks
```

• Obtain client certificates.

. . .

- a Request the client certificates from the CA at http://wiki.cacert.org/wiki/ClientCerts. Follow the instructions provided at this Web site to complete the request.
- Click Install Your Certificate to install the certificates into your Web browser.
- c For nonbrowser clients (including IIOPS), export the certificate from the browser with a private key in PKCS #12 format, then import into client's certificate keystore as appropriate.

Use the keytool command to perform these tasks. For more details about the keytool command, see "Managing keys and certificates on EAServer" in Chapter 11, "Managing Keys and Certificates."

d Obtain the certificate in RFC 1421-form (Base64-encoded X.509). Use the keytool -help command.

For other cases, consult with your CA to determine how to obtain the RFC 1421-form of certificate.

e In *root.txt*, copy the certificate text, including BEGIN and END lines, and save in a file named *root.crt* in *\$DJC\_HOME/Repository/Security/truststore.jks* on the client side.

This is to set up client's trust certification.

f The administrative user must register this certificate with an EAServer user using:

set-certificate test -file test.crt

## 7.7 System Administration Guide

## 7.7.1 Chapter 3, "Creating and Configuring Servers"

#### Hiding the default HTTP response header

**[CR #546416]** By default, EAServer 6.*x* sends the default HTTP response header to the HTTP client. For example, HTTP/1.1....Server: Jetty (EAServer/6.2.0.12 Build 62012. This may expose the Web server identity to all HTTP clients. To hide the default HTTP response header:

- 1 Log in to the Management Console.
- 2 Select your Server instance.
- 3 Select the HTTP tab.
- 4 Unselect Send the Server Version in HTTP header property.
- 5 Restart EAServer.

#### Adding and configuring service components

**[CR #500334]** The configuration property name for the Component property in Table 3-7 is incorrect. The correct property name is serviceComponents, as indicated below:

Property	Description
Component	The name of the component that implements the service.
	For a user-defined service component, enter either:
	• The class name of a simple Java class (must be in the server class path), or
	• The fully-qualified name of an EJB local or remote interface; for example,
	ejb.components.mypackage.MyCompLocal Or
	ejb.components.mypackage.MyCompRemote.
	The configuration property name is serviceComponents.

#### Adding and configuring listeners

**[CR #549163]** To prevent EAServer from trying to allocate too many Windows handles, Sybase recommends that you set the number of listener connections to a maximum of 1,000. If you are using a 64-bit JVM, EAServer can support about 5,000 connections instead of 1,000. You can set this configuration using the Management Console. On the listener's General tab, set the Maximum Number of Threads listener property to 1,000.

#### **Enabling password sharing**

**[CR #487210]** By default, multiple users can start EAServer. However, to allow single user to start EAServer, configure EAServer with the shared-data-protection-off option. For example:

cd \$EAServer/bin configure.sh shared-data-protection-off

To allow multiple users to start EAServer, use the shared-data-protection-on option. For example:

cd \$EAServer/bin configure.sh shared-data-protection-on

#### Configuring system logging

**[CR #473658]** "Configuring system logging" describes how to customize the location of the system log files, but the name of the variable (DJC\_JVM\_ARGS) is incorrect. The correct variable is DJC\_JVM\_USER\_ARGS; for example:

```
set DJC_JVM_USER_ARGS=$DJC_JVM_USER_ARGS -Ddjc.logFile=/myserver/myserver.log
-Ddjc.logFileMaxSize=5m -Ddjc.logFileRotation=true
```

**Note** If you customize the location of the system log files, only the HTTP log is rotated; the server log is not.

### 7.7.2 Chapter 4, "Database Access"

The section that describes how to configure a database type fails to explain that if you define both a dataSourceClass and a driverClass, EAServer uses only the dataSourceClass value—see "Configuring a database type" on page 12 in this release bulletin.

#### Configuring data sources

**[CR #531900]** When using servers in a cluster, make sure these predefined data sources are all connected to the same database:

- cluster.db
- message.db
- tx\_manager

You can change the data sources using the Management Console.

### 7.7.3 Chapter 11, "Runtime Monitoring"

**[CR #546885]** The "Monitoring Web application and EJB statistics" section of Chapter 11, "Runtime Monitoring," provides information about viewing statistics for Web applications and EJBs by accessing the Statistics node beneath an individual entity. However, this information is incorrect. There is no Statistics node available in the selected Web application component and EJB component.

### 7.7.4 Chapter 12, "Command Line Tools"

deploy

**[CR #481055]** When you deploy a self-contained application, you can configure the application to use all the classes from the internal class loader by setting the disableResolveFirstBySystem property to true. For example:

deploy.sh -disableResolveFirstBySystem foo.war

**[CR #475511]** EAServer 6.3 does not support the -jsr154filter option for the deploy.sh command line tool. -jsr154filter may be supported in a later version of EAServer.

### 7.7.5 Chapter 13, "JNI Compiler"

**[CR #472818]** Before calling a generated proxy class, standalone clients must call either:

- JNICC\_CreateJavaVM to initialize the JVM, or
- JNICC\_SetJavaVM(JavaVM\* vm) if the JVM has already been initialized.

### 7.7.6 Chapter 14, "Systems Management"

**[CR #437261]** EAServer supports Simple Network Management Protocol (SNMP) features that conform to the Java Specification Request JSR 77. The status of a server and its components are reported as Management Information Base objects, which can be polled, and can also be reported as SNMP traps.

## 7.8 Troubleshooting Guide

### 7.8.1 Chapter 1, "Monitoring Techniques"

This example shows how to configure the log4j.properties file.

#### Configuring Log4j

1 Use a text editor to create a *log4j.properties* file.

```
# Set root category priority to INFO and its only appender to CONSOLE.
#log4j.rootCategory=FATAL, CONSOLE
log4j.rootCategory=DEBUG, LOGFILE
```

```
# Set the enterprise logger category to FATAL and its only appender to CONSOLE.
# log4j.logger.org.apache.axis.enterprise=DEBUG, LOGFILE
```

# CONSOLE is set to be a ConsoleAppender using a PatternLayout. log4j.appender.CONSOLE=org.apache.log4j.ConsoleAppender log4j.appender.CONSOLE.Threshold=DEBUG log4j.appender.CONSOLE.layout=org.apache.log4j.PatternLayout log4j.appender.CONSOLE.layout.ConversionPattern=- %m%n

```
# LOGFILE is set to be a File appender using a PatternLayout.
log4j.appender.LOGFILE=org.apache.log4j.FileAppender
log4j.appender.LOGFILE.File=<install_directory>/axisserver.log
log4j.appender.LOGFILE.Append=true
log4j.appender.LOGFILE.Threshold=DEBUG
log4j.appender.LOGFILE.layout=org.apache.log4j.PatternLayout
log4j.appender.LOGFILE.layout.ConversionPattern=%-4r [%t] %-5p %c %x - %m%n
```

2 Put the *log4j.properties* file into *\$EAServer\_Home/lib*.

3 Change to *\$EAServer\_Home/bin* and execute:

run-server Dorg.apache.commons.logging.Log=org.apache.commons.logging.impl.Log4JLogger

4 Write a class named "Hello":

package sayhello;

```
public class Hello {
```

```
public String hello() {
        return "hello";
     }
}
```

- 5 Use Sybase Web Services Toolkit to deploy this class as a Web service and generate a client.
- 6 Run Hello\_ServiceTestClient.java.
- 7 Find the log file in *<install\_directory>\aixsserver.log* and view the contents which should look similar to:

953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle loadBundle: Ignoring MissingResourceException: Can't find bundle for base name org.apache.axis.resource, locale zh CN 953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle Created org.apache.axis.i18n.resource, linked to parent null 953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle getBundle(org.apache.axis,org.apache.axis.utils,resource,null,...) 953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle loadBundle: Ignoring MissingResourceException: Can't find bundle for base name org.apache.axis.utils.resource, locale zh CN 953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle loadBundle: Ignoring MissingResourceException: Can't find bundle for base name org.apache.axis.resource, locale zh CN 953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle - Root package not found, cross link to org.apache.axis.il8n.resource 953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle - Root package not found, cross link to org.apache.axis.i18n.resource 953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle org.apache.axis.i18n.resource::handleGetObject(engineFactory) 1047 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle org.apache.axis.i18n.resource::handleGetObject(attachEnabled) 1063 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle org.apache.axis.i18n.resource::handleGetObject(oddDigits00)

## 7.9 Web Services Toolkit User's Guide

#### 7.9.1 Chapter 9, "Using wstool and wstant"

**[CR #464242]** The Ant build example for the exposeComponent command is incorrect:

```
<wst_antTask command="exposeComponent"
entity="component:myPackage/myComponent"/>
```

The correct command is:

<wst\_antTask command="exposeComponent" entity="myPackage/myComponent"/>

# 8. Technical support

Each Sybase installation that has purchased a support contract has one or more designated people who are authorized to contact Sybase Technical Support. If you have any questions about this installation or if you need assistance during the installation process, ask the designated person to contact Sybase Technical Support or the Sybase subsidiary in your area.

## 9. Other sources of information

Use the Sybase Getting Started CD, the SyBooks<sup>TM</sup> CD, and the Sybase Product Manuals Web site to learn more about your product:

- The Getting Started CD contains release bulletins and installation guides in PDF format, and may also contain other documents or updated information not included on the SyBooks CD. It is included with your software. To read or print documents on the Getting Started CD, you need Adobe Acrobat Reader, which you can download at no charge from the Adobe Web site using a link provided on the CD.
- The SyBooks CD contains product manuals and is included with your software. The Eclipse-based SyBooks browser allows you to access the manuals in an easy-to-use, HTML-based format.

Some documentation may be provided in PDF format, which you can access through the PDF directory on the SyBooks CD. To read or print the PDF files, you need Adobe Acrobat Reader.

Refer to the *SyBooks Installation Guide* on the Getting Started CD, or the *README.txt* file on the SyBooks CD for instructions on installing and starting SyBooks.

 The Sybase Product Manuals Web site is an online version of the SyBooks CD that you can access using a standard Web browser. In addition to product manuals, you will find links to EBFs/Maintenance, Technical Documents, Case Management, Solved Cases, newsgroups, and the Sybase Developer Network.

To access the Sybase Product Manuals Web site, go to Product Manuals at http://www.sybase.com/support/manuals/.

## 9.1 Sybase certifications on the Web

Technical documentation at the Sybase Web site is updated frequently.

#### \* Finding the latest information on product certifications

- 1 Point your Web browser to Technical Documents at http://www.sybase.com/support/techdocs/.
- 2 Click Partner Certification Report.
- 3 In the Partner Certification Report filter select a product, platform, and timeframe and then click Go.
- 4 Click a Partner Certification Report title to display the report.

#### \* Finding the latest information on component certifications

- 1 Point your Web browser to Availability and Certification Reports at http://certification.sybase.com/.
- 2 Either select the product family and product under Search by Base Product; or select the platform and product under Search by Platform.
- 3 Select Search to display the availability and certification report for the selection.

# Creating a personalized view of the Sybase Web site (including support pages)

Set up a MySybase profile. MySybase is a free service that allows you to create a personalized view of Sybase Web pages.

- 1 Point your Web browser to Technical Documents at http://www.sybase.com/support/techdocs/.
- 2 Click MySybase and create a MySybase profile.

## 9.2 Sybase EBFs and software maintenance

#### \* Finding the latest information on EBFs and software maintenance

- 1 Point your Web browser to the Sybase Support Page at http://www.sybase.com/support.
- 2 Select EBFs/Maintenance. If prompted, enter your MySybase user name and password.
- 3 Select a product.

4 Specify a time frame and click Go. A list of EBF/Maintenance releases is displayed.

Padlock icons indicate that you do not have download authorization for certain EBF/Maintenance releases because you are not registered as a Technical Support Contact. If you have not registered, but have valid information provided by your Sybase representative or through your support contract, click Edit Roles to add the "Technical Support Contact" role to your MySybase profile.

5 Click the Info icon to display the EBF/Maintenance report, or click the product description to download the software.

## 10. Accessibility features

This document is available in an HTML version that is specialized for accessibility. You can navigate the HTML with an adaptive technology such as a screen reader, or view it with a screen enlarger.

EAServer and the HTML documentation have been tested for compliance with U.S. government Section 508 Accessibility requirements. Documents that comply with Section 508 generally also meet non-U.S. accessibility guidelines, such as the World Wide Web Consortium (W3C) guidelines for Web sites.

The online help for this product is also provided in HTML, which you can navigate using a screen reader.

For information on using EAServer without a mouse, see "Keyboard navigation" in Chapter 2, "Management Console Overview," in the *EAServer System Administration Guide*.

**Note** You might need to configure your accessibility tool for optimal use. Some screen readers pronounce text based on its case; for example, they pronounce ALL UPPERCASE TEXT as initials, and MixedCase Text as words. You might find it helpful to configure your tool to announce syntax conventions. Consult the documentation for your tool.

For information about how Sybase supports accessibility, see Sybase Accessibility at http://www.sybase.com/accessibility. The Sybase Accessibility site includes links to information on Section 508 and W3C standards.

For a Section 508 compliance statement for EAServer, go to Voluntary Product Assessments at http://www.sybase.com/detail\_list?id=52484, and click the link for EAServer.