

SYBASE®

Installation Guide

Enterprise Connect™ Data Access

15.0

[Microsoft Windows]

DOCUMENT ID: DC39550-01-1500-01

LAST REVISED: August 2007

Copyright © 1991-2007 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

To order additional documents, U.S. and Canadian customers should call Customer Fulfillment at (800) 685-8225, fax (617) 229-9845.

Customers in other countries with a U.S. license agreement may contact Customer Fulfillment via the above fax number. All other international customers should contact their Sybase subsidiary or local distributor. Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase trademarks can be viewed at the [Sybase trademarks page](http://www.sybase.com/detail?id=1011207) at <http://www.sybase.com/detail?id=1011207>. Sybase and the marks listed are trademarks of Sybase, Inc. ® indicates registration in the United States of America.

Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

All other company and product names used herein may be trademarks or registered trademarks of their respective companies.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568.

Contents

About This Book	vii
CHAPTER 1 Enterprise Connect Data Access.....	1
ECDA Options descriptions.....	1
ECDA Option for ODBC	1
ECDA Option for Oracle	2
Using DirectConnect Manager	2
CHAPTER 2 Preparing to Install.....	5
Installation process	5
Gather your installation team	6
Prepare the environment.....	7
Connectivity tasks	7
Critical administrative tasks	8
CHAPTER 3 Installing ECDA	11
Installing ECDA	11
SySAM licensing requirements	11
Using the installation program.....	12
Installing ECDA Options.....	12
Uninstalling ECDA.....	19
CHAPTER 4 Installing DirectConnect Manager	23
Installing DirectConnect Manager	23
CHAPTER 5 Using the Create Server Wizard.....	25
Create Server wizard overview	25
Creating servers using the Create Server wizard.....	25
Configuring ECDA Option for ODBC.....	26
Configuring ECDA Option for Oracle.....	27

CHAPTER 6	Using ECDA Utilities.....	29
	ECDA Option for ODBC utilities	29
	Creating a new DirectConnect server	29
	Creating a new access service.....	30
	Starting an access service	30
	Verifying an access service.....	31
	Stopping an access service.....	32
	Stopping a DirectConnect server	32
	Starting an access service	33
	Adding a new service to the sql.ini file	33
	ECDA Option for Oracle utility.....	33
	Configuring ECDA using the DCOConfig utility	34
	Adding and removing a service	35
	Shutting down ECDA Option for Oracle	35
CHAPTER 7	Using DirectConnect Manager	37
	Configuring servers and access services.....	37
	Creating a new access service	38
	Starting an access service	38
	Stopping an access service	38
CHAPTER 8	Configuring ECDA	39
	Configuring client connectivity to ECDA.....	39
	Configuring the DirectConnect server and services.....	40
	ECDA support for back-end drivers	40
	Microsoft SQL Server ODBC driver.....	41
CHAPTER 9	Troubleshooting Installation	43
	General problems.....	43
	ODBC-specific problems.....	44
	ODBC driver errors.....	44
	ODBC data source errors.....	44
	ODBC driver manager errors	45
	DirectConnect problems.....	46
	DirectConnect server fails to start after installation	46
	Connectivity problems.....	47
	Using the odbct tool for ODBC problems	47
APPENDIX A	Connectivity Tasks for AS/400	49
	Enable DRDA capability of AS/400	49
	Set security levels	50
	Change the CCSID	51

	Changing the CCSID at the User Profile level.....	51
	Create the Sybase collection on the AS/400 (for DB2 UDB)	52
	Creating the SYBASE collection using the AS/400 SEU utility	53
	Creating the SYBASE collection through DB2/AS400	55
	Authorizing users for the SYBASE collection	55
APPENDIX B	Installation Worksheets.....	57
	How to use the worksheets	57
	ECDA for ODBC worksheet	58
	DirectConnect for Oracle worksheet	59
APPENDIX C	ECDA Utilities.....	61
	Creating and starting a DCDirector server	61
	DCDirector utility	62
	Creating a new DirectConnect server	62
	AddServer utility	62
	Starting a DirectConnect server	63
	DCStart utility	63
APPENDIX D	Configuring Data Sources to Connect to Targets Using DataDirect	65
	To configure the data sources to connect to the targets	66
	Connecting to DB2 UDB	66
	Add the WorkArounds2 String Key to pad DB2 character data	70
	Connecting to Microsoft SQL Server.....	71
	Creating and configuring a data source	71
	Glossary	75
	Index	91

About This Book

This book describes how to install Sybase® Enterprise Connect™ Data Access products on Microsoft Windows.

Audience

This book is for System Administrators or other qualified persons familiar with their system environment, resources, and devices.

How to use this book

See the following chapters for information about installing, setting up connectivity, and configuring the ECDA Options.

See	To
Chapter 1, “Enterprise Connect Data Access”	Understand ECDA Option for ODBC, ECDA Option for Oracle, and DirectConnect Manager.
Chapter 2, “Preparing to Install”	Identify all the tasks required to get ready for installing ECDA
Chapter 3, “Installing ECDA”	Install and uninstall ECDA Option for ODBC and ECDA Option for Oracle.
Chapter 4, “Installing DirectConnect Manager”	Install and use DirectConnect Manager.
Chapter 5, “Using the Create Server Wizard”	Create and start a DirectConnect server using a GUI.
Chapter 6, “Using ECDA Utilities”	Create, start, and stop a server, and to create, start, and stop a service.
Chapter 7, “Using DirectConnect Manager”	Create and start a server, and create and start an access service.
Chapter 8, “Configuring ECDA”	Configure client connectivity and to configure the DirectConnect server and access services.
Chapter 9, “Troubleshooting Installation”	Identify and resolve problems that can occur when you install an ECDA product.
Appendix A, “Connectivity Tasks for AS/400”	Set up the AS/400 to communicate with ECDA products.
Appendix B, “Installation Worksheets”	Access worksheets and instructions for recording installation information for ECDA products.
Appendix C, “ECDA Utilities”	Identify utilities to simplify the execution of ECDA on multiple platforms.

Appendix D, “Configuring Data Sources to Connect to Targets Using DataDirect”	Describes how to configure data sources for various targets.
Glossary	Find definitions of technical terms used in this guide.

Related documents

For more information about configuring and administering DirectConnect products, use the following guides:

- Enterprise Connect Data Access 15.0 for Microsoft Windows *Release Bulletin*
- Enterprise Connect Data Access *Users Guide for Access Services*
- Enterprise Connect Data Access and Mainframe Connect *Server Administration Guide*
- Enterprise Connect Data Access Option for Oracle *Server Administration and Users Guide*

For ODBC information, use the following document:

- *Microsoft ODBC 3.5 Programmer’s Reference and SDK Guide*

For additional references, use the following documents:

- Open Client™ *Client-Library/C Reference Manual*
- Open Server™ *Server-Library/C Reference Manual*
- Open ClientConnect™ and Open ServerConnect™ *Messages and Codes*
- *Component Integrated Services User’s Guide* for Adaptive Server® Enterprise
- *Adaptive Server Enterprise Reference Manual*
- *Sybase Adaptive Server Reference Manual*, volumes 1 and 2

To install and administer DirectConnect using DirectConnect Manager, use InstallShield and the DirectConnect Manager online help.

Other sources of information

Use the Sybase Getting Started CD, the SyBooks™ CD, and the Sybase Product Manuals Web site to learn more about your product:

- The Getting Started CD contains release bulletins and installation guides in PDF format, and may also contain other documents or updated information not included on the SyBooks CD. It is included with your software. To read or print documents on the Getting Started CD, you need Adobe Acrobat Reader, which you can download at no charge from the Adobe Web site using a link provided on the CD.
- The SyBooks CD contains product manuals and is included with your software. The Eclipse-based SyBooks browser allows you to access the manuals in an easy-to-use, HTML-based format.

Some documentation may be provided in PDF format, which you can access through the PDF directory on the SyBooks CD. To read or print the PDF files, you need Adobe Acrobat Reader.

Refer to the *SyBooks Installation Guide* on the Getting Started CD, or the *README.txt* file on the SyBooks CD for instructions on installing and starting SyBooks.

- The Sybase Product Manuals Web site is an online version of the SyBooks CD that you can access using a standard Web browser. In addition to product manuals, you will find links to EBFs/Maintenance, Technical Documents, Case Management, Solved Cases, newsgroups, and the Sybase Developer Network.

To access the Sybase Product Manuals Web site, go to Product Manuals at <http://www.sybase.com/support/manuals/>.

Sybase certifications on the Web

Technical documentation at the Sybase Web site is updated frequently.

❖ Finding the latest information on product certifications

- 1 Point your Web browser to Technical Documents at <http://www.sybase.com/support/techdocs/>.
- 2 Click Certification Report.
- 3 In the Certification Report filter select a product, platform, and timeframe and then click Go.
- 4 Click a Certification Report title to display the report.

❖ Finding the latest information on component certifications

- 1 Point your Web browser to Availability and Certification Reports at <http://certification.sybase.com/>.
- 2 Either select the product family and product under Search by Base Product; or select the platform and product under Search by Platform.

-
- 3 Select Search to display the availability and certification report for the selection.

❖ **Creating a personalized view of the Sybase Web site (including support pages)**

Set up a MySybase profile. MySybase is a free service that allows you to create a personalized view of Sybase Web pages.

- 1 Point your Web browser to Technical Documents at <http://www.sybase.com/support/techdocs/>.
- 2 Click MySybase and create a MySybase profile.

Sybase EBFs and software maintenance

❖ **Finding the latest information on EBFs and software maintenance**

- 1 Point your Web browser to the Sybase Support Page at <http://www.sybase.com/support>.
- 2 Select EBFs/Maintenance. If prompted, enter your MySybase user name and password.
- 3 Select a product.
- 4 Specify a time frame and click Go. A list of EBF/Maintenance releases is displayed.

Padlock icons indicate that you do not have download authorization for certain EBF/Maintenance releases because you are not registered as a Technical Support Contact. If you have not registered, but have valid information provided by your Sybase representative or through your support contract, click Edit Roles to add the “Technical Support Contact” role to your MySybase profile.

- 5 Click the Info icon to display the EBF/Maintenance report, or click the product description to download the software.

Syntax conventions

Syntax statements that display options for a command look like this:

```
COMMAND [object_name, [ {TRUE | FALSE} ] ]
```

The following table explains the syntax conventions used in this guide.

Table 1: Syntax conventions

Symbol	Convention
()	Include parentheses as part of the command.
{ }	Braces indicate that you must choose at least one of the enclosed options. Do not type the braces when you type the option.
[]	Brackets indicate that you can choose one or more of the enclosed options, or none. Do not type the brackets when you type the options.
	The vertical bar indicates that you can select only one of the options shown. Do not type the bar in your command.
,	The comma indicates that you can choose one or more of the options shown. Separate each choice by using a comma as part of the command.

Style conventions

The following table explains the style conventions used in this guide.

Table 2: Style conventions

This type of information	Looks like this
Gateway-Library function names	TDINIT, TDCANCEL
Client-Library™ function names	CTBINIT, CTBCANCEL
Other executables (DB-Library™ routines, SQL commands) in text	the dbrpcparam routine, a select statement
Directory names, path names, and file names	<i>/usr/bin directory, interfaces file</i>
Variables	<i>n bytes</i>
SQL Server® datatypes	datetime, float
Sample code	<code>01 BUFFER PIC S9(9) COMP SYNC</code>
User input	<i>01 BUFFER PIC X(n)</i>
Client-Library and Gateway-Library function argument names	<i>BUFFER, RETCODE</i>
Names of objects stored on the mainframe	SYCTSAA5
Symbolic values used with function arguments, properties, and structure fields	CS_UNUSED, FMT_NAME, CS_SV_FATAL
Client-Library property names	CS_PASSWORD, CS_USERNAME
Client-Library and Gateway-Library datatypes	CS_CHAR_TYPE

Accessibility features

This document is available in an HTML version that is specialized for accessibility. You can navigate the HTML with an adaptive technology such as a screen reader, or view it with a screen enlarger.

Enterprise Connect Data Access and the HTML documentation have been tested for compliance with U.S. government Section 508 Accessibility requirements. Documents that comply with Section 508 generally also meet non-U.S. accessibility guidelines, such as the World Wide Web Consortium (W3C) guidelines for Web sites.

Note You might need to configure your accessibility tool for optimal use. Some screen readers pronounce text based on its case; for example, they pronounce ALL UPPERCASE TEXT as initials, and MixedCase Text as words. You might find it helpful to configure your tool to announce syntax conventions. Consult the documentation for your tool.

For information about how Sybase supports accessibility, see Sybase Accessibility at <http://www.sybase.com/accessibility>. The Sybase Accessibility site includes links to information on Section 508 and W3C standards.

See Section 508 compliance statement for DirectConnect Manager for Voluntary Product Assessment Templates at http://www.sybase.com/detail_list?id=52484.

If you need help

Each Sybase installation that has purchased a support contract has one or more designated people who are authorized to contact Sybase Technical Support. If you cannot resolve a problem using the manuals or online help, please have the designated person contact Sybase Technical Support or the Sybase subsidiary in your area.

Topic	Page
ECDA Options descriptions	1
Using DirectConnect Manager	2

This chapter introduces basic ECDA concepts and describes the process that provides access to distributed data.

ECDA Options descriptions

Two options are available for ECDA:

- ECDA Option for ODBC
- ECDA Option for Oracle

ECDA Option for ODBC

ECDA version 15.0, the Option for DB2 UDB and the Option for Microsoft SQL Server have been merged into the ECDA Option for ODBC. In addition, the Option for Informix is no longer available.

ECDA Option for ODBC provides basic connectivity to DB2 UDB, Microsoft SQL Server, and ODBC-accessible databases.

Note The ODBC driver for ECDA Option for ODBC (the back-end driver connecting to the target) is not provided by Sybase; you must obtain, install, and configure it.

ECDA Option for ODBC provides access to non-Sybase data sources, using the ODBC back-end (server-side) driver that you obtain for your target database, such as IBM or Microsoft SQL. Following the vendor's instructions, install the ODBC driver on the same server as ECDA Option for ODBC and then configure ECDA Option for ODBC to use the ODBC driver for access to your database.

Note Be sure to verify that your ODBC driver is compatible with Sybase driver manager software or that it contains a driver manager.

Because ODBC drivers have varying degrees of functionality, it is important that when working with non-Sybase-provided, third-party ODBC drivers, you carefully integrate and test them to be sure they meet your needs.

ECDA Option for Oracle

ECDA Option for Oracle provides Open Client access to Oracle databases. It operates in conjunction with the Adaptive Server Enterprise Component Integration Services feature (ASE/CIS) and as a standalone gateway. For more detailed information, see the ECDA Option for Oracle *Server Administration and Users Guide*.

Using Adaptive Server, you can join Oracle tables with tables in Adaptive Server, DB2 UDB, or other database servers. Access to these objects through Adaptive Server is transparent to the application.

In standalone mode, ECDA Option for Oracle provides client applications with an Open Client interface to Oracle databases. To the client, ECDA Option for Oracle appears as an Open Server application that understands Oracle SQL.

Using DirectConnect Manager

DirectConnect Manager graphically represents each DirectConnect object on a tree list or an "icon map," a customizable workspace where you can add or remove objects. When you add a DirectConnect server to DirectConnect Manager, its server name, access service library, and any access services appear on the tree list or the icon map.

DirectConnect Manager graphically represents each DirectConnect object on a tree list or an “icon map,” a customizable workspace where you can add or remove objects. When you add a DirectConnect server to DirectConnect Manager, its server name, access service library, and any access services appear on the tree list or the icon map.

DirectConnect Manager communicates with DirectConnect servers asynchronously, which means you can continue to use DirectConnect Manager while a command is being processed.

You can configure properties using DirectConnect Manager or a text editor. However, Sybase recommends using DirectConnect Manager for these reasons:

- Changes that you make with a text editor do not take effect until you restart the server.
- Most changes that you make with DirectConnect Manager can be made to take effect immediately.
- You can use DirectConnect Manager as a guide to the properties that can be changed, as well as the valid values for each property.
- DirectConnect Manager can perform all of its management functions remotely. With DirectConnect Manager, you do not need physical access to the DirectConnect server machine or directory.
- DirectConnect Manager provides management services to multiple servers at the same time, including the ability to copy access service configurations from one server to another.

For more information about DirectConnect Manager features, use the DirectConnect Help available under the online Help menu option.

You can install DirectConnect Manager and its required components from the DC Client CD.

Note When you install a ECDA product on a Windows or UNIX platform or machine, you may install DirectConnect Manager on a separate platform or machine. This allows you to control any ECDA product from any machine.

Preparing to Install

Topic	Page
Installation process	5
Gather your installation team	6
Prepare the environment	7

Installation process

This section lists the pre-installation, installation, and post-installation steps, including the chapter or appendix where you will find the detailed instructions.

Note To resolve problems that occur when you install ECDA, see Chapter 9, “Troubleshooting Installation.”

Table 2-1: Installation steps for ECDA

Step	Resource
<i>Pre-Installation</i>	
1 Setup connectivity to the target database.	<ul style="list-style-type: none"> • Appendix A, “Connectivity Tasks for AS/400.” • Appendix D, “Configuring Data Sources to Connect to Targets Using DataDirect.”
2 Fill out the installation worksheets.	Appendix B, “Installation Worksheets.”
3 Gather your information and prepare the environment.	Chapter 2, “Preparing to Install.” (this Chapter)
<i>Installation</i>	
1 Obtain a SySAM license.	Chapter 3, “Installing ECDA.”
2 Install ECDA Option for ODBC and ECDA Option for Oracle.	Chapter 3, “Installing ECDA.”

Step		Resource
3	Install DirectConnect Manager.	Chapter 4, “Installing DirectConnect Manager.”
4	Create and start a DirectConnect server.	Chapter 5, “Using the Create Server Wizard.”
5	Start, configure, and stop DirectConnect servers and access services.	<ul style="list-style-type: none"> Chapter 6, “Using ECDA Utilities.” Chapter 7, “Using DirectConnect Manager.”
<i>Post-Installation</i>		
1	Configure client connectivity to ECDA.	Chapter 8, “Configuring ECDA.”
2	Configure the DirectConnect server and access services.	Chapter 8, “Configuring ECDA.”

Gather your installation team

To install ECDA, you need a team with specific skills and experience— as well as the authority to carry out the variety of tasks in the installation process. At your site, identify the people who have the following skill sets and keep them informed of any changes.

Table 2-2: ECDA team skill requirements

Role	Skill set
Operating system administrator	<ul style="list-style-type: none"> Understanding of the operating systems for your site’s platforms Knowledge of standards and conventions at the installation site
Communications administrator	<ul style="list-style-type: none"> Understanding of connectivity products used at your site Ability to design, establish, test, and troubleshoot remote physical communications between ECDA and the mainframe host for DB2 UDB DirectConnect access Understanding of your network configuration
DirectConnect administrator	<ul style="list-style-type: none"> Understanding of the ECDA environment DirectConnect Server Administrator privileges
Target database administrator	<ul style="list-style-type: none"> Knowledge of the target database Knowledge of target environment, including security operations Database administrator privileges

Role	Skill set
LAN administrator	<ul style="list-style-type: none">• Understanding of LAN communications at your site• Ability to design, establish, test, and troubleshoot remote physical communications between the client and the DirectConnect server• Understanding of the site's network configuration

Prepare the environment

Before you begin, you must build the foundation that will support your ECDA installation and the subsequent access services that you create. If you complete these tasks first, the installation process should be successful.

This section describes the following:

- Connectivity tasks
- Critical administrative tasks

Connectivity tasks

Before you begin installation, you must have some preliminary network connections in place and operational.

Following are some recommended tasks you should perform before you set up connectivity. This is not a complete list; your team should prepare a list that is pertinent to your site and connectivity setup.

- Set up connectivity to the target database
- Check the system requirements
- Research connectivity parameters

Set up connectivity to the target database

To set up connectivity to the target database, you need to refer to vendor documentation for connectivity protocols that your site supports.

Check the system requirements

Verify that you have the platform and operating system components listed in the ECDA 15.0 *Release Bulletin* for Microsoft Windows. Also, be sure to determine whether any new release levels or bug fixes of Sybase or vendor connectivity protocol products are required.

Research connectivity parameters

You need the data source name (DSN) values for each ODBC target when you set up connectivity for ECDA.

Be sure to record the DSN values on your installation worksheet.

Sybase does not ship drivers with ECDA to provide connectivity to non-Sybase target databases. You must purchase a separate license from IBM, Microsoft, DataDirect, or other vendors, for the ODBC driver that is needed on the particular platform where ECDA is running.

Note In some cases, you may already be licensed for ODBC drivers for the databases you are accessing. Refer to the vendor contract and documentation.

Do not continue installation until connectivity is running successfully between the machine that will host the DirectConnect server and the target database.

Critical administrative tasks

Complete the following administrative tasks:

- Read the ECDA 15.0 *Release Bulletin*. This document provides product information that might not be included in this ECDA guide, as well as information about known issues or problems.
- Make a backup copy of your current Sybase software, particularly if you plan to keep ECDA versions that were previously installed.
- Make a copy of the installation worksheet for your platform for each server that you will install.
- Verify that you have authority to sign in as user sybase or other user having administrative privileges on the machine on which ECDA is being installed.

- Verify that the host server is connected to the LAN and that network protocols are configured correctly. For instructions, see your LAN administrator documentation.
- Verify previously installed Sybase products. When you install ECDA into an existing directory structure, be aware of any previously installed Sybase software and the version of that software.

Installing ECDA

Topic	Page
Installing ECDA	11
Uninstalling ECDA	19

This chapter describes how to install and uninstall ECDA Option for ODBC and ECDA Option for Oracle. It also describes how to create a DirectConnect server and services.

Installing ECDA

This section describes:

- SySAM licensing requirements
- Using the installation program
- Installing ECDA in GUI mode

SySAM licensing requirements

ECDA version 15.0 includes a Sybase Software Asset Management System (SySAM) implementation to perform license administration and asset management tasks. Sybase recommends that you get your license files from the Sybase Product Download Center (SPDC) at <https://sybase.subscribenet.com> before you begin installation. Accessing SPDC requires a separate login and password information through e-mail.

Warning! If a product license cannot be obtained during the grace period (usually 30 days), ECDA will cease to operate.

For information about SySAM 2.0, see the Sybase Software Asset Management *User's Guide*.

Using the installation program

The installation program creates the target directory (if necessary) and loads all of the selected components into that directory.

Installation options

Install ECDA using one of the options:

- GUI (graphical user interface) mode, which allows you to install the components using the Installation program described in “Installing ECDA in GUI mode” on page 12.
- Console mode, which allows you to install components using a command line interface described in “Installing ECDA in console mode” on page 16.
- Response file mode, which allows you to record or create a response file described in “Installing using a response file” on page 17. Using a response file, you can install ECDA two different ways:
 - Silent, which lets you install the product without any interaction required on your part. This is convenient if you are performing identical installations on multiple machines.
 - Interactive installation using response file, which lets you install interactively, but with all the responses already filled in, so that you can accept or change the default values and install ECDA according to the responses in the response file. This can be convenient if several sites are installing ECDA and must conform to a standard installation.

Each of these options is described in the following sections.

Note Sybase recommends that you use the GUI mode for installing ECDA Options.

Installing ECDA Options

The following describes the ECDA Option for ODBC and the ECDA Option for Oracle installation process in GUI mode.

Installing ECDA in GUI mode

The following describes the ECDA Option for ODBC and the ECDA Option for Oracle installation process in GUI mode.

❖ To install in GUI mode

- 1 Verify that the drive on which you will install the products has enough free disk space for the products being installed, and at least 10MB extra disk space for the installation program. The program frees this extra space after the installation is complete.

- 2 Insert the ECDA CD-ROM into the CD-ROM drive.

The installation program should start automatically. If it does not, select Start | Run, and enter the following, where *x*: is your CD drive:

```
x:\setup.exe
```

The Welcome window appears.

- 3 Click Next to proceed with the installation.

You may see the following error message:

```
Error writing file = There may not be enough
temporary disk space. Try using -is:tempdir to use a
temporary directory on a partition with more disk
space.
```

If so, set the temporary directory to another directory that has more disk space by entering the following at the command line:

```
x:\setup.exe -is:tempdir <directory_name>
```

where *directory_name* is the name of the temporary directory to which the installation program will write its temporary files.

- 4 Read the License and Copyright Agreement. Using the drop-down list at the top of the window, select the geographic location where you are installing ECDA to display the agreement appropriate to your region. Select “I agree” and click Next.

You must agree to the license and copyright agreement before you can continue.

- 5 In the installation directory window, click Next to accept the default directory for the installation, or enter a different directory where you want to install ECDA. One of the following occurs:

- If the installation directory you chose does not exist, the installation program prompts:

```
The directory does not exist. Do you want to
create it?
```

Click Yes.

- If the installation directory exists and contains files, the software prompts:

You have chosen to install into an existing directory. Any older versions of the products you choose to install that are detected in this directory will be replaced.

Note You will not see this message if the directory exists but is empty.

If you are prompted to overwrite any DLLs, select *Yes only* if the version of the new DLL is later than the one you are attempting to overwrite.

Note In certain cases when ECDA is installed with other Sybase products, you may see warnings about overwriting newer versions of files. In these cases, simply instruct the installer to overwrite these files and proceed with the installation by selecting *Yes to All*.

6 Select one of the two installation types:

- Custom, which allows you to select the ECDA options and components to install.
- Full, which installs all ECDA products and components from the CD.

Click Next.

7 Based on your selection:

- If you selected Custom install, the next window displays all the ECDA options and all the components “checked” or selected. You must “uncheck” or deselect the components that you do *not* want to install.

Note Be aware that if you deselect a component that is required, it is automatically installed if it is needed to run other selected components.

After you have selected either the ECDA Option for ODBC or ECDA Option for Oracle, and selected the desired components, Click Next.

- If you selected Full install, the next window displays all the ECDA options including ECDA Option for ODBC and ECDA Option for Oracle, and all the components “checked” or selected. Click Next.

Before proceeding to the next window, the installation program verifies the selections, and checks for dependencies and available disk space. The Product Summary window displays every component that is to be installed and the total disk space required for all the selected components.

Note If the target directory does not have enough free space, the space-required and the space-available information is displayed. If you click Next without sufficient hard disk space, an error occurs that stops the installation.

- 8 Verify that you have selected the correct type of installation, and that you have enough disk space to complete the process. Click Next to continue the installation.

The installation program unloads all the components from the CD and displays a progress indicator. When the installation is complete, a message appears indicating that the installation program wizard has completed installing your product.

- 9 Click Next. The SySAM License Server window opens and displays this prompt:

Will licenses be obtained from the License Server?

- Select Yes if you have a pre-existing SySAM network license server installed or install a new license server using “Installing a new license server.”

Enter the host name and the port number of the license server.

- Select No if you do not have a SySAM license server installed and are going to use a local license file. A message displays telling you to download the license file.

If you select Yes and the license server is not found, or you select No and the local license file is not installed on your local machine, this message displays:

Installer can't check out a license. Do you want to continue without a license?

- 10 Click Yes to complete the installation. If you select No, this message displays:

Please remember to download and install the license file after this installation.

Click OK.

The SySAM Notification window asks you to configure your server for e-mail notification. When configuration is enabled, you will receive information about license management events requiring attention.

11 Enter the following:

- SMTP server host name
- SMTP server port number
- E-mail Return Address
- Recipient e-mail addresses
- Message severity that triggers e-mail messages

Click Next.

12 A window displays a message indicating that the installation was successful and advising you to check for software updates.

Click Finish.

Installing ECDA in console mode

If you want to run the installer without the graphical user interface (GUI), you can launch the installation program the installation program in console mode. In cases where the installation program launches automatically, click Cancel to cancel the GUI installation and then launch the setup program from a terminal or console.

❖ To install in console mode

The steps for installing components in console mode are the same as those described in “Installing ECDA in GUI mode” on page 12, except that you execute the installation program from the command line using the setup - console command, and you enter text to select the installation options, as follows:

1 Enter the following at the command line:

```
x:\setupConsole.exe
```

The installation program starts and displays a Welcome message.

- 2 The flow of the installation is identical to a regular GUI installation, except that the display is written to a terminal window, and you enter the responses using the keyboard. Follow the remaining prompts to install ECDA.

Installing using a response file

A silent installation (sometimes referred to as an unattended install) is done by running installation program and providing a response file that contains answers to all of installation program questions.

Creating a response file

There are two methods of generating a response file for the installation program:

- *Record* mode: In this mode, the installation program performs an installation of the product, and records all of your responses and selections in the specified response file. You must complete the installation to generate a response file. To create a response file, enter the following:

```
x:\setup.exe -options-record <responseFileName>
```

Note There should be no space between *-options* and *-record*.

where *responseFileName* is a name you choose for the response file.

The following are the results:

- An installation of ECDA on your computer
 - A response file containing all of your responses from the installation
- If this response file is used for a silent installation, the resulting installation is identical to the one from which the response file was created: the same installation location, same feature selection, and all the same remaining information. The response file is a text file that you can edit to change any responses prior to using it in any subsequent installations.
- *Template* mode: In this mode, the installation program creates a response file containing commented-out values for all required responses and selections. However, you do not need to install the product, and you can cancel the installation after the response file has been created. To create this template file, enter the following:

```
x:\setup.exe -console -options-template <responseFileName>
```

where *responseFileName* is the absolute file name you chose for the response file, for example:

```
C:\DC\OptionsTemplate.txt
```

Note In this example the directory *C:\DC* must already exist.

If run in console mode, as shown in the previous example, the installation program provides a message indicating that the template creation was successful. If run in GUI mode, no message is provided.

Then, if you use this response file for a silent installation, the default values for all responses are used. Edit the template with the values you want to use during installation.

Warning! If you created a response file using a Custom installation, you need to edit the response file to allow the custom selections to be chosen correctly during installation. The following is a workaround for an installer issue when using a response file.

Use a text editor and delete the word "Custom" in the setup type in the following line

```
-W setupTypes.selectedSetupTypeId=Custom
```

The resultant line should look similar to the following:

```
-W setupTypes.selectedSetupTypeId=
```

Failure to delete the "Custom" setup type results in a Full installation of the product.

Interactive installation using a response file An interactive installation using a response file allows you to accept the default values obtained from the response file that you have set up, or to change any of those values for the specific installation. This is useful when you want multiple similar installations but with some minor differences that you want to change at installation time.

At the command line, execute the following command (enter the command all on one line):

```
x:\setup.exe -console -options <responseFileName>  
-W SybaseLicense.agreeToLicense=True
```

Installing in silent mode A silent mode installation, sometimes referred to as an unattended installation, allows you to install the product with all responses being taken from the response file that you have set up. There is no user interaction. This is useful when you want multiple identical installations or when you want to automate the installation process.

At the command line, execute the following command (enter the command all on one line):

Note Enter the command all on one line.

```
x.\setupConsole.exe -silent -options <responseFileName>
-W SybaseLicense.agreeToLicense=true
```

where *responseFileName* is the name of the file containing the installation options you chose. The *-W* option specifies that you agree with the Sybase License Agreement text.

Warning! Sybase recommends that you use the *setupConsole.exe* executable which runs in the foreground, when running a silent installation. The normal *setup.exe* executable runs in the background, giving you the false impression that the installation has terminated immediately, without a completion status. This could result in duplicate installation attempts.

Except for the absence of the GUI screens, all actions of the installation program are the same, and the result of an installation in silent mode is exactly the same as one done in GUI mode with the same responses.

Uninstalling ECDA

To uninstall an ECDA installation, use the installation program *uninstall* feature. This removes all servers, all common files, and all required components. After the *uninstall* runs, you may need to delete any remaining files and directories in the directory where ECDA was installed only if this is the only product installed.

Note Before uninstalling Sybase software, shut down all Sybase applications and processes.

You can invoke the uninstall procedure using either the GUI or the console method. Sybase recommends that you use the GUI method.

Log in to your machine using an account with “administrator” privileges, then shut down all other processes for the components you are uninstalling.

Note The installation program removes only those files that were loaded from the installation media. Some Sybase files, such as log and configuration files, are left intact for administrative purposes.

❖ **To uninstall in GUI mode**

- 1 Enter one of the following:
 - Using Windows explorer:
 - a Go to the directory where your application is installed.
 - b Select the uninstall directory.
 - c Select the application you want to uninstall.
 - d Double-click the uninstall icon. The wizard appears.
 - Using the Add/Remove program:
 - a Go to Start | Setting | Control panel | Add/Remove Programs dialog box
 - b Select the application you want to remove.
 - c Click on Change/Remove. The wizard appears.
- 2 The Welcome window appears.
- 3 Click Next to display the list of selected products and components that were installed.
- 4 All the products and components that were installed are displayed and already checked to allow you to remove the total installation. If you do not want to remove a product or component, deselect or “uncheck” that product or component. Click Next.
- 5 A summary of all the products and components is displayed. Click Next.
- 6 A message indicating that an uninstall of z/OS is in progress. When this is completed, a message is displayed indicating a successful uninstall. Click Next to end the uninstall.

❖ To uninstall in console mode

- 1 Go to the `<install_dir>\DC-15_0` directory, enter the following:

```
<install_dir>\uninstall\ECDASuite\uninstall.exe -console
```

The uninstall program starts.

- 2 Choose the ECDA software product you want to uninstall.
- 3 The ECDA software product you chose is uninstalled.

This chapter contains the following topics:

Topic	Page
Installing DirectConnect Manager	23

This chapter describes how to install and use DirectConnect Manager to create a server and service, and how to start a server and service.

Installing DirectConnect Manager

This section describes the DirectConnect Manager installation process.

❖ To install DirectConnect Manager

- 1 Insert the PC client CD into the CD drive.
- 2 Go to the DirectConnect Manager directory.
- 3 The Welcome window appears. Click Next to proceed with the installation.
- 4 Read the License and Copyright Agreement. Using the drop-down list at the top of the window, select the geographic location where you are installing to display the agreement appropriate to your region. Select “I agree” and click Next.
- 5 On the Choose Directory dialog box, enter the directory path for the installation, and click Next.

You must agree to the license and copyright agreement before you can continue.

- 6 Select one of the two types of installation:
 - Install a new version of Sybase Central and render the other install invalid. Click Next.

This type of installation will install DirectConnect Manager as well as all the other necessary components and create a new set of icons and Registry entries.

Note This option will make your current Sybase Central installation invalid.

- Register with existing Sybase Central. Click Next.

This type of installation will install the DirectConnect Manager plug-in and register it with the existing Sybase Central Application.

- 7 A Summary window appears and lists all the features that you are going to install. Click Next.
- 8 The installation process begins and a Setup window appears.
The Setup window shows the percentage (%) of installation that is complete, and monitors the decompressing and installing of the DirectConnect Manager files. The installation will register the plug-in with Sybase Central.
- 9 When installation is completed, a DirectConnect Manager *README* file appears. After reading the file, click Finish to clear the window.

Using the Create Server Wizard

Topic	Page
Create Server wizard overview	25
Creating servers using the Create Server wizard	25

The Create Server Wizard allows you to create a server and complete the connection to the target database based on the driver and driver manager you want to use.

Create Server wizard overview

The Create Server wizard is a Java program that provides the ability to create and start a server. It supports these products:

- ECDA Option for ODBC
- ECDA Option for Oracle

After you create the server, to complete the configuration you can use DirectConnect Manager to configure a service to connect to a specific target database and to test the configuration. For DirectConnect Manager information, see Chapter 4, “Installing DirectConnect Manager.”

Creating servers using the Create Server wizard

The following subsection describes how to create a server for ECDA Option for ODBC and ECDA Option for Oracle.

The Create Server wizard, which is installed with ECDA, is located in these directories:

- `<install_dir>\DC-15_0\DCWizard` for ECDA Option for ODBC

- `<install_dir>\DCO-15_0\DCWizard` for ECDA Option for Oracle

Configuring ECDA Option for ODBC

The following describes server creation for the ODBC-accessible target database for ECDA Option for ODBC.

❖ To create a server for ODBC

- 1 Start the Create Server wizard by entering:

```
DCWizard.bat
```
- 2 The Welcome Create Server Wizard window appears. Click Next. The Create DirectConnect Server Options window appears.
- 3 Select the ECDA Option for ODBC option. Click Next. The Server Name and Port Information window appears.
- 4 Enter the Server Name for the new DirectConnect server and the Port Number that you want the server to “listen” on. Click Next. The DirectConnect Service Name window appears.
- 5 Enter the ECDA access service name that you want to use for this server. Click Next. The ECDA Server Summary and Build window appears.
- 6 Verify the ECDA Server information that appears.

If correct select Create Server. The Start DirectConnect Server (Optional) window appears.

If incorrect, select the Back button to change the information.
- 7 Optionally, start the DirectConnect server that you created. Click Finish

Note The service requires additional configuration to connect to the target database. This additional configuration can be added using DirectConnect Manager. For basic connectivity to the target database, the next step is to start DirectConnect Manager and set ConnectionSpec1 to a data source name (DSN) contained in the *odbc.ini* file located at:

```
<dc_install_dir>\DC-15_0\odbc.ini.
```

- 8 Set the Configuration property, `SQLDBCCursors` to driver in the `dcany.cfg` file.

Configuring ECDA Option for Oracle

The following describes server creation for an Oracle target database for ECDA Option for Oracle.

❖ To create a server for Oracle

- 1 Start the Create Server wizard by entering:

```
DCWizard.bat
```
- 2 The Welcome Create Server Wizard window appears, Click Next. The Create DirectConnect Server Options window appears.
- 3 Select the ECDA Option for Oracle option. Click Next. The Server Name and Port Information window appears.
- 4 Enter the Server Name for the new DirectConnect server and the Port Number that you want the server to “listen” on. Click Next. The DirectConnect Server Admin Account and Password window appears.
- 5 Enter the Admin Account Name. Click Next The Oracle Target Information window appears.
- 6 Enter the following information:
 - Oracle Connect String
 - Path to the `tnsnames.ora` file including the file name

Click Next. The Oracle DirectConnect Server Summary and Build window appears.

- 7 Verify the ECDA Server information that appears.

If correct select Create Server. The Oracle DirectConnect Server Summary and Build window appears.

If incorrect, select the Back button to change the information.

- 8 Verify the ECDA Config information that appears. If correct select Create Server. The Start DirectConnect Server (Optional) window appears.
If incorrect, select the Back button to change the information.
- 9 Optionally, start the DirectConnect server that you created. This is an optional step that can be used to validate the server configuration. If you exit from this wizard the DirectConnect server you have started will continue to execute. If you wish to skip this step Click Finish.

Note Additional configuration changes can be added using DirectConnect Manager.

Topic	Page
ECDA Option for ODBC utilities	29
ECDA Option for Oracle utility	33

After installing ECDA Option for ODBC or the ECDA Option for Oracle, you need to create, start, and stop a server, and to create, start, and stop a service. There are several utilities that are available:

- ECDA Option for ODBC utilities
- ECDA Option for Oracle utility

ECDA Option for ODBC utilities

The following describes how to start a server and service using the ECDA utilities and the command line for ECDA Option for ODBC. For additional ECDA utility information, see Appendix C, “ECDA Utilities.”

Creating a new DirectConnect server

At this point, the installation program has automatically created the subdirectories and files needed for ECDA. You must perform a number of tasks to create a new server and access services. The first step is to create a new server by running the utility `AddServer.bat` from `<install_dir>\DC-15_0\bin` using the syntax in the following example:

```
cd <install_dir>\DC-15_0\bin
AddServer srvname 1234
```

where:

- *srvname* is the name of the new server.
- *1234* is the port that it will listen on.

- AddServer is the utility that will:
 - Set the environment
 - Create the server
 - Start the server

Note You must be in the `<install_dir>\DC-15_0\connectivity\bin` directory for this batch file to work properly.

Log in to your machine using an account with “administrator” privileges, then shut down all other processes for the components you are uninstalling.

Creating a new access service

You can use a text editor to configure the access service library configuration files, which reside in the `cfg` subdirectory under the `ServerName` directory.

❖ To configure the access service using a text editor

- 1 Navigate to the `<install_dir>\DC-15_0\servers\svrname\cfg` subdirectory of the `ServerName` directory.
- 2 At the end of the configuration file, enter a name for the access service in brackets, for example, for Microsoft SQL Server:

```
[mss_acs]
```
- 3 Enter the required parameters and their values from your worksheet, as well as other values for parameters you might need.

For more information about access service configuration properties, see the Enterprise Connect Data Access Options *Users Guide for Access Services*.

Starting an access service

The only way you can start the new access service without stopping and restarting ECDA is by using DirectConnect Manager.

To start your new service without using DirectConnect Manager, be sure that the `EnableAtStartup=Yes` property is set in the service configuration (`.cfg`) file, which starts the service automatically when the server is started, and then restarts the server.

Verifying an access service

Verify that the access service is connecting to its target data source and working properly by using one of the SQL utilities.

Using isql from a command line

Note If you are using `isql` on the same machine on which you installed ECDA, you must add a access service entry to the `sql.ini` file that points to the access service you are testing.

❖ To verify the access service configuration using `isql`

- 1 On the client machine, use `dsedit` to create a `sql.ini` file entry for the access service.

Be sure to enter the access service name exactly as you defined it in the configuration file or using DirectConnect Manager.

- 2 Set the environment variables from a command line prompt by running one of the following environment scripts, as appropriate for your platform:

```
DC_SYBASE.bat
```

- 3 Run `isql` from the command line by entering the following:

```
isql -SServiceName -Userid -Ppassword
```

where:

- *ServiceName* is the name of the access service exactly as you defined it in the `sql.ini` file.
- *userid* is a valid user ID for the target database.
- *password* is a valid password for the user ID in the target database.

If the connection is successful, a 1> prompt appears.

Note If you cannot connect, the access service might not be running. Start the access service with DirectConnect Manager or edit the configuration file, and then verify that the Enable at Startup parameter is set to Yes. This starts the access service automatically when the server is started.

4 At the 1> prompt, query a table in the target database by entering a select statement and pressing Return.

5 At the 2> prompt, enter:

```
go
```

Press Return.

The query should run and return a result set, followed by a >1 prompt.

6 To exit isql, enter the following at the 1> prompt:

```
exit
```

Press Return.

A regular operating system command appears.

Note At this point, you can stop the DirectConnect server using the stopsvr utility, which shuts down the server and terminates all client connections. However, if you plan to perform post-installation tasks for the client and server, leave both the server and access service running.

Stopping an access service

You can stop the access service only through DirectConnect Manager. The procedure is described in Chapter 4, “Installing DirectConnect Manager.”

Stopping a DirectConnect server

At this point, you can stop the DirectConnect server using the stopsrvr utility, which shuts down the server and ends all client connections.

Set the environment variables from a command line prompt by running one of the following environment scripts, as appropriate for your platform:

```
DC_SYBASE.bat
```

The stopsrvr format is as follows:

```
stopsrvr [-v|-?|-h] -Sserver_name [-ddelay]
```

where:

- -v displays the program version only.
- -? or -h displays help screen.
- -S defines the name of the server to be shut down.
- -d is the delay, in seconds, before client connections are terminated. The default is 3.

Starting an access service

The only way you can start the new access service without stopping and restarting ECDA is by using DirectConnect Manager.

To start your new service without using DirectConnect Manager, be sure that the EnableAtStartup=Yes property is set in the service configuration (.cfg) file, which starts the service automatically when the server is started, and then restart the server.

Adding a new service to the sql.ini file

Use the dsedit utility to allow an Open Client application, such as isql, to connect to the Open Client installation that will be used by your client application. Add the new service to the *sql.ini* file as a Server Object using the dsedit utility, specifying the same connectivity information for this Server Object as specified in the *sql.ini* file for the DirectConnect server.

ECDA Option for Oracle utility

When ECDA Option for Oracle is created for the first time, a configuration file is automatically created for it.

You can change the configuration of the ECDA Option for Oracle by modifying the configuration file using the command line. If you need to display or edit the configuration options after installation, refer to the command called `sp_configure` in Chapter 2, “Configuring and Operating ECDA Option for Oracle” in the *Enterprise Connect Data Access Option for Oracle Administration and Users Guide*.

Configuring ECDA using the DCOConfig utility

You can use the `DCOConfig.bat` script to configure and start the server. The `DCOConfig.bat` script can be found at:

```
<install_dir>\DCO-15_0\install\DCOConfig.bat
```

Before starting the configuration, you must have the following available:

- A copy of the existing `tnsnames.ora` file currently being used to connect to Oracle, which you will copy to a temporary file location
- The Oracle connect string
- The name for a valid Oracle account, which is the administrator for ECDA Option for Oracle
- The number of an unused port to be used by ECDA Option for Oracle

❖ To invoke the configuration utility

- 1 Change directories to `<install_dir>\DCO-15_0\install`.
- 2 Execute `DCOConfig.bat`.
- 3 Enter the server name for ECDA Option for Oracle.
- 4 Enter an unused port on the machine that ECDA Option for Oracle will be listening on.
- 5 Enter a valid ECDA Option for Oracle Administrator Name.
- 6 Enter the Oracle connection string as previously defined in the `tnsnames.ora` file.
- 7 Enter the path (including the file name) to the previously defined temporary location of the `tnsnames.ora` file.

8 ECDA Option for Oracle is now started in a separate window.

Note In the window where the ECDA Option for Oracle is started, the following informational message appears. It appears when the ECDA Option for Oracle is started from DCOConfig.bat and can be ignored.

```
Option [traceflags] not found in configuration file
'<path to configuration file>'. Generating new
configuration file.
```

Adding and removing a service

The ECDA Option for Oracle utility to add a service is `sp_addservice` and to remove a service is `sp_dropservice`. The commands and syntax is described in Chapter 2, “Configuring and Operating ECDA Option for Oracle” in the ECDA Option for Oracle *Administration and Users Guide*.

Shutting down ECDA Option for Oracle

The utility to shut down ECDA Option for Oracle is `sp_shutdown`. The command and syntax is described in Chapter 2, “Configuring and Operating ECDA Option for Oracle” in the ECDA Option for Oracle *Administration and Users Guide*.

Using DirectConnect Manager

Topic	Page
Configuring servers and access services	37
Creating a new access service	38
Starting an access service	38
Stopping an access service	38

DirectConnect Manager allows you to create and start a server, and create and start an access service. Before you can use DirectConnect Manager, you must identify and establish a connection between the server and DirectConnect Manager.

Configuring servers and access services

After you create a DirectConnect server or a DCDirector, you can configure the server through DirectConnect Manager. For a description of all the configuration properties, refer to the following:

- For the DirectConnect server:
 - For the ECDA Option for ODBC, refer to the *Enterprise Connect Data Access and Mainframe Connect Server Administration Guide*
 - For the ECDA Option for Oracle, refer to the *Enterprise Connect Data Access Option for Oracle Server Administration and Users Guide*
- For the access service:
 - For the ECDA Option for ODBC, refer to the *ECDA Users Guide for Access Services*.
 - For the ECDA Option for Oracle, refer to the *ECDA Option for Oracle Server Administration and Users Guide*

Creating a new access service

For instructions on how to use DirectConnect Manager to create a service, go to the DirectConnect Manager online Help and select Managing Access Services | Creating a New Service or Copying a Service.

Note If you use service name redirection, the connectivity parameters must match the connectivity parameters or the default, and the access service name must map through the redirection file to the DirectConnect server.

For more information about service name redirection, see Enterprise Connect Data Access and Mainframe Connect *System Administration Guide*.

Starting an access service

The only way you can start the new access service without stopping and restarting ECDA is by using DirectConnect Manager. For instructions on how to use DirectConnect Manager to start a service, go to the DirectConnect Manager online Help and select Managing Access Services | Starting a Service.

Stopping an access service

For instructions on how to use DirectConnect Manager to stop a service, go to the DirectConnect Manager online Help and select Managing Access Services | Stopping a Service.

Configuring ECDA

Topic	Page
Configuring client connectivity to ECDA	39
Configuring the DirectConnect server and services	40
ECDA support for back-end drivers	40

After you install ECDA, you must configure:

- Configuring client connectivity to ECDA
- Configuring the DirectConnect Server and services
- ECDA for back-end driver (Microsoft SQL Server ODBC Driver)

Note Be sure that both the DirectConnect server and the access services are running.

Configuring client connectivity to ECDA

Note If you verified the ECDA access service in the previous section using `isql`, you have already created an entry in the `sql.ini` file on that machine.

The following procedure ensures that the client environment is properly connected to the LAN and to the DirectConnect server.

❖ **To add, edit or delete entries in the *sql.ini* and *libtcl.cfg* files on client machines**

- 1 In dsedit, verify that the service name and port number match the entry for the access service.

Note Be sure to use the access *service* name, not the DirectConnect *server* name.

If you use service name redirection, refer to the *DirectConnect Server Administration Guide*.

- 2 Configure the *libtcl.cfg* configuration file that contains information for each installed Net-Library driver.

Use dsedit to view a list of the drivers installed on your machine. You can view a description of any driver by selecting it from the list.

Client applications use the information in this file, along with information in the *sql.ini* file, to connect to a DirectConnect server using the correct file.

Configuring the DirectConnect server and services

To configure the DirectConnect server and access services:

- For the ECDA Option for ODBC, refer to *ECDA Option for ODBC Users Guide for Access Services*
- For the ECDA Option for Oracle, refer to *ECDA Option for Oracle Administration and Users Guide*.

ECDA support for back-end drivers

Because Sybase no longer provides ODBC drivers for back-end access to the target database, you need to obtain your own driver from your database vendor. However, Sybase does certify with and support the Microsoft SQL Server ODBC Driver.

Microsoft SQL Server ODBC driver

ECDA Option for ODBC supports the Microsoft SQL Server ODBC Driver.

❖ **To configure the DSN for the Microsoft SQL Server ODBC Driver**

- 1 Go to the Microsoft SQL Server Data Source Administrator.
- 2 Select the SQL Server Driver. If the driver does not appear, download and install the Microsoft Data Access Software Developer's Kit.
- 3 The required components will be installed.

For more information regarding the Microsoft SQL Server ODBC driver and configuration, see the Microsoft SQL Server documentation.

Troubleshooting Installation

This chapter tells you how to identify and resolve problems that occur when you install a DirectConnect product. Also, it describes several diagnostic tools that you can use.

This chapter covers the following topics:

Topic	Page
General problems	43
ODBC-specific problems	44
DirectConnect problems	46

If you try the suggested methods described in this chapter and still have problems, notify your company's contact person for Sybase. Each Sybase installation that has purchased a support contract has one or more designated people who are authorized to contact Sybase Technical Support or the Sybase subsidiary in your area.

General problems

In general, there are several sources from which error messages can be generated, including:

- DirectConnect
- Open Client and Open Server
- The network
- The target database
- ODBC drivers

For problems that are connectivity-related, see the documentation for your network protocol or "Connectivity problems" on page 47 in this chapter.

For problems related to ODBC drivers, see the following section.

ODBC-specific problems

This section describes the following types of problems:

- ODBC driver errors
- ODBC data source errors
- ODBC driver manager errors

ODBC driver errors

An error reported on an ODBC driver has the following format:

[vendor] [ODBC_component] message

where:

- *vendor* is the name of the ODBC vendor.
- *ODBC_component* is the component in which the error occurred.
- *message* is the content of the error message.

For example, an error message from the DataDirect SQL Server driver looks like this:

```
[DataDirect] [ODBC SQL Server driver] Invalid
precision specified.
```

If you receive this type of error, check the last ODBC call made by your application for possible problems, or contact your ODBC application vendor.

ODBC data source errors

This type of error occurs in the data source and includes the data store name, as shown in the following format:

[vendor] [ODBC_component] [data_store] message

where:

- *vendor* is the name of the ODBC vendor.
- *ODBC_component* is the component that received the message from the data store indicated.

- *data_store* is the name of the location in the data source where the error occurred.
- *message* is the content of the error message.

For example, you might receive the following message from an Oracle data store:

```
[DataDirect] [ODBC Oracle driver] [Oracle] ORA-0919:  
specified length too long for CHAR column.
```

If you receive this type of error, something is incorrect regarding the database system. Check your database system documentation for more information, or consult your database administrator. In this example, you need to check your Oracle documentation.

ODBC driver manager errors

The driver manager is a DLL that establishes connections with drivers, submits requests to drivers, and returns results to applications. An error that occurs in the driver manager has the following format:

```
[vendor] [ODBC XXX] message
```

where:

- *vendor* is the name of the ODBC vendor.
- *ODBC XXX* is the driver manager and its version number.
- *message* is the content of the error message.

For example, an error from the Microsoft driver manager might look like this:

```
[Microsoft] [ODBC Driver Manager] Driver does not  
support this function.
```

If you receive this type of error, consult the *Programmer's Reference* for the Microsoft ODBC Software Development Kit, available from Microsoft.

DirectConnect problems

If your system does not work properly after you install DirectConnect, and if you already performed the connection steps in Chapter 2, “Preparing to Install,” try the following:

- Confirm the release number of Open Server software. DirectConnect is compatible with the Open Server release and Adaptive Server release identified in the release bulletin.
- Check the log and trace files in the *log* file of the *ServerName* for more information. Following is an example of an error message that can occur:

```
Error: 16029 Severity: 20 State: 0 OS Error: -1:  
Failed to start any network listeners OS Error Text:  
<srv-lib>
```

One of the following causes is possible:

- One of the specified port numbers is in use. Change the port number to one that is not in use and try again.
- The wrong machine name or IP address was specified. Enter the machine name or the IP address running the DirectConnect server.

Refer to the DirectConnect *Error Message Guide* for errors that occur.

If the server fails before the log files initialize, error messages can be written to either the console or the Windows event log. If this occurs, see the DirectConnect *Server Administration Guide* for explanations of these “pre-log” messages.

DirectConnect server fails to start after installation

If the DirectConnect server fails to start after installation and the SNA library files are listed in error in the DirectConnect log, the following message appears:

```
The application has failed to start because  
WAPPC32.dll was not found. Re-installing the  
application may fix this problem.
```

Fix for error condition

To fix the error condition, install the *stub* libraries for DC 12.6 on Windows by executing the following:

```
%SYBASE%\%SYBASE_ECON%\bin\DCConfig.bat.
```

Connectivity problems

This section describes some tools you can use to diagnose connectivity problems.

Using the odbct tool for ODBC problems

To help you diagnose ODBC connectivity problems, the odbct tool verifies that your system configuration is by attempting to make a simple connection to the target.

Note Be sure to run the odbct tool in the same environment in which you plan to use DirectConnect Option for ODBC targets by executing the DC_SYBASE.bat.

The odbct tool has three parameters: a data source name (DSN), user ID, and password. The following example shows a connection to the *dcmssql* DSN using the user ID "joe" and password "joe21".

```
odbct <DSN> <USERID> <PASSWORD>
odbct dcmssql joe joe21
> Would you also like the output saved to a file?
(YN) : y
      Attempting Connection
-----
---
> Allocating Environment
> Allocating Connection
> Attempting Connection
      DSN          :dcmssql
      USER        : joe
      PASSWORD: joe21

> CONNECTION SUCCEEDED
> Allocating Statement
```

```
> Connection succeeded, would you like to proceed  
with
```

```
    datasource and datatype reporting? (YN): n
```

```
                Connection Cleanup
```

```
-----  
---
```

```
> Free Statement
```

```
> Attempting Disconnection
```

```
    + Disconnection succeeded
```

```
> Free Connection
```

```
> Free Environment
```

```
belford [ 23 ]
```

Connectivity Tasks for AS/400

Topic	Page
Enable DRDA capability of AS/400	49
Set security levels	50
Change the CCSID	51
Create the Sybase collection on the AS/400 (for DB2 UDB)	52

The ECDA product that accesses DB2 UDB for AS/400 is ECDA for ODBC. It uses TCP/IP for connectivity. To set up the AS/400 to communicate with these ECDA products, you must perform the connectivity tasks described in this appendix after logging on to the target AS/400 server as the System Administrator:

Note SNA/APPC connectivity is not supported.

Enable DRDA capability of AS/400

To use an AS/400 service, you must enable the Distributed Relational Database Architecture (DRDA) capability of the AS/400. The service communicates with the AS/400 through a TCP/IP connection to DB2 UDB.

To confirm that your AS/400 has DRDA capability:

- Verify that you are using OS/400 V5R2 or higher.
- Be sure that you define the local relational database using the add relational database directory entry ADDRDBDIRE command.

Enter this name for the appropriate platform as the Database Name. The Database Name is requested during installation and is the DatabaseName property in the service library configuration file called *dcany.cfg*, which is located in the *ServerName\cfg* subdirectory.

Set security levels

The AS/400 has four security levels, each of which is described in Table A-1.

Note Sybase recommends that you use AS/400 security level 20 or higher.

Table A-1: AS/400 security levels

Level	Description
10	Requires only a user ID. If you enter a user ID that does not exist, AS/400 automatically creates it. You can access all system resources.
20	Requires a user ID and password. The user ID must already exist in AS/400. Once you sign on to AS/400, you have access to all system resources.
30	Requires a user ID and password and includes further measures to secure objects on the system. Objects are secured by a user's class (*SECOFR, *SECADM, *PGMR, *SYSOPR, AND *USER) by default.
40	Requires a user ID and password, and includes further measures to secure objects on the system. Objects are secured by a user's class (*SECOFR, *SECADM, *PGMR, *SYSOPR, AND *USER) by default. Unsupported interfaces cannot access the system.

The access service enforces security only through level 20. It returns an error only if the user ID and password do not exist on the AS/400.

Error messages relating to higher security levels on the AS/400 are returned from the AS/400. If your AS/400 security is set at a level higher than 20 and you experience problems with the access service, please have the designated person at your site contact Sybase Technical Support or the Sybase subsidiary in your area.

❖ To check the AS/400 security settings

- 1 Log on to the AS/400 at the main console, a 5250 terminal, or a 5250 terminal emulator.
- 2 At the Main menu, enter the following:

```
WRKSYSVAL QSECURITY
```

The Work With System Value window appears.

- 3 Enter the following to display your security settings:

```
DSPSYSVAL QSECURITY
```

❖ To change the security settings

- 1 Be sure you have System Security Officer (QSECOFR) authority.

- 2 From the Work with System Values menu, enter the following:

```
CHGSYSVAL QSECURITY
```

- 3 Enter the value.
- 4 Restart the AS/400 to make the change effective.

Change the CCSID

The CCSID (coded character set ID) designates the binary code page in which the AS/400 returns data. The default is 65535. If you do not change the CCSID, the access service returns character data from the AS/400 in binary form. When mapped to ASCII format, this data appears as hexadecimal characters.

Changing the CCSID does not affect how the AS/400 stores data. AS/400 programs set the CCSID to a value appropriate to its function. The ECDA access service does not require a specific CCSID. For English installations, use code page 37 or 500.

Changing the CCSID at the User Profile level

To change the CCSID at the user profile level, your user ID must have QSECOFR authority.

❖ To change the CCSID at the user profile level

- 1 Log on to the AS/400 at the main console, a 5250 terminal, or a 5250 emulator.
- 2 To display the Work with User Profile window, enter the following:

```
WRKUSRPRF USER_ID
```

where *USER_ID* is a valid user ID for the AS/400 with QSECOFR authority.
- 3 Select option 2.
- 4 Press F10 to view additional parameters. Page down until you find the CCSID setting.
- 5 Change the CCSID and press Enter.

Any physical file that is created with this user profile has the new CCSID assigned to the file character fields.

Create the Sybase collection on the AS/400 (for DB2 UDB)

The access service requires certain files on the AS/400. ECDA for ODBC access service looks for these files in a collection called “SYBASE.” You must create this collection and name it “SYBASE” before installing the access service.

Note The owner of the SYBASE collection must have QSECOFR privileges.

The SYBASE collection contains a package for the DC DB2 UDB driver that is created when the drivers are installed. After you create the packages, you need to grant permissions to PUBLIC for the end users to access the Sybase collection located on the target AS/400. This can be done with `isql` (which comes with the ECDA installation), or directly on the AS/400 machine.

❖ To grant permissions from `isql`

- Issue the following command:

```
GRANT EXECUTE ON PACKAGE SYBASE.DEF000x TO PUBLIC
```

The ECDA service used to issue this command must be in `sybase` mode for SQL transformation (SQL transformation is an access service property with one of two settings, `passthrough` or `sybase`). To ensure this, enter the following command in the `isql` session before you issue the `GRANT EXECUTE` command:

```
set sqltransformation sybase
```

Because the AS/400 allows you to change security levels and ownership of objects, you can use another user ID to create the SYBASE collection. For example, you can use one ID to create the SYBASE collection, then grant other users create and execute authorization for the collection and its objects.

You can create the SYBASE collection in one of two ways:

- If you have DB2 (or DB2/400) Query Manager and SQL Development Kit (SDK) installed on the AS/400, you can run the SQL utility using a 5250 session.
 - If not, you need to use the AS/400 SEU utility program to create the SYBASE collection.
- ❖ **To grant permissions directly on the AS/400**
- 1 Log on to the AS/400 at the main console, a 5250 terminal, or a 5250 terminal emulator, using the user ID that will be the owner of the SYBASE collection.
 - 2 To display the Sybase packages, on the command line, enter:

```
WRKOBJOWN SYBASE
```
 - 3 On the Work with Object by Owner window, locate and select a package from the attribute column and in the corresponding OPT column, enter the following:

```
2
```
 - 4 On the Edit Object Authority window, in the User column, locate *PUBLIC, and in the corresponding Object Authority column, enter:

```
ALL
```
 - 5 Press F12 to return to the Work with Object by Owner window, and repeat steps 2 and 3 until all packages are completed. To exit, press F3 repeatedly, followed by 90.

Creating the SYBASE collection using the AS/400 SEU utility

The user ID for creating the SYBASE collection must have a valid CCSID for your language installation.

- ❖ **To create the SYBASE collection through the AS/400 SEU utility**
- 1 Log on to the AS/400 at the main console, a 5250 terminal, or a 5250 terminal emulator, using the user ID that is to be the owner of the SYBASE collection.
 - 2 Start the SEU program by entering the following command:

```
STRSEU
```
 - 3 Press F4. The Work With Members Using SEU window appears.

- 4 Provide the following information:
 - In the Source File field, enter:
`QQMQRYSRC`
 - In the Source Member field, enter:
`*SELECT`
 - In the Library File field, enter:
`QGPL`

If the source file does not exist, you must create it using the CRTSRCPF command.
- 5 Press Enter. The members of the source file are listed.
Build the query that creates the collection by creating a source member for the query:
 - In the New Member field, enter:
`SYBASE`
 - In the Type for New Member field, enter:
`TXT`
- 6 Press Enter. The Edit window appears.
- 7 Create the query member by entering the following in the first line of the source file:
`CREATE COLLECTION SYBASE`
- 8 Press F3. Verify that the Change/Create Member field is set to Y, and the Member field is SYBASE.
- 9 Press Enter to exit the editor. Now you can work with the query you created.
- 10 Press F3 again to exit and return to the Main menu.

❖ **To build the query that creates the SYBASE collection**

- 1 Enter the following on the command line:
`CRTQMORY QMORY (QGPL/SYBASE) SRCFILE (QGPL/QQMQRYSRC)`

Press Enter. The AS/400 utility creates the query

Note You might receive a warning message that the source length exceeds 79 characters. Disregard this message, as it does not affect the access service

- 2 To run the query that creates the SYBASE collection, enter the following on the command line:

```
STRQMORY QMORY (QGPL/SYBASE)
```

Press Enter. The SYBASE collection is created.

Building the collection might take a few minutes. During this time, you will receive messages indicating the status of the operation.

Creating the SYBASE collection through DB2/AS400

The user ID for creating the SYBASE collection must have a valid CCSID for your language installation.

❖ To create the SYBASE collection through SQL/400

- 1 Log on to the AS/400 at the main console, a 5250 terminal, or a 5250 terminal emulator, using the ID that you want to own the collection (usually SYBASE).
- 2 On the command line, enter:

```
STRSQL
```

The STRSQL program begins.

- 3 On the SQL command line, enter:

```
CREATE COLLECTION SYBASE
```

The collection process requires a few minutes to complete. You can create other collections by using this same syntax and substituting the name of the collection for "SYBASE."

Authorizing users for the SYBASE collection

You must have the following minimum authorizations to access the AS/400 through the access service:

- USE authorization to the service package in the SYBASE collection
 - CHANGE authorization to:
 - Journal object QSQJRN
 - Journal receivers QSQJRN0001, QSQJRN002, and any other additional journal receivers
- ❖ **To confirm that authorizations are set properly**
- 1 Verify that the *SQLPKG objects in SYBASE are set to *PUBLIC, *USE, or higher authorization level.
 - 2 Verify that the journal objects are set to *PUBLIC, *CHANGE, or higher authorization level.

Installation Worksheets

This appendix provides worksheets and instructions for recording information you will need to complete installation and connectivity tasks. You are prompted for this information during installation.

Topic	Page
How to use the worksheets	57
ECDA for ODBC worksheet	58
DirectConnect for Oracle worksheet	59

How to use the worksheets

Fill out one of these worksheets for each DirectConnect server that you plan to install. Keep it with you for each step of the installation process.

The worksheets cover:

- Information from Sybase and non-Sybase products that must be installed before and after installing ECDA.
- Information that is requested during installation, connectivity setup, and configuration of ECDA access service configuration files.

The worksheets present the list of parameters you will be prompted for during installation, give you a place for you to write down the parameter values to use, and provide a short description of the parameter.

ECDA for ODBC worksheet

Use the following worksheet to identify information that you should designate and record prior to installing ECDA Option for ODBC. You are prompted for this information during installation.

Table B-1: ECDA Option for ODBC worksheet

Your installation information	Description
<i>DSN(s):</i>	<i>DSN:</i> ODBC data source name.
<i>CONNECTIVITY PARAMETERS:</i>	<i>Connectivity:</i> Record the parameters for the connection protocol at your site. For example, if TCP/IP is the protocol, you record the IP address and port number. Check with your administrator for these parameter values

DirectConnect for Oracle worksheet

Use the following worksheet to identify information that you should designate and record prior to installing ECDA Option for Oracle. You are prompted for this information during installation.

Table B-2: ECDA Option for Oracle worksheet

Your installation information	Description
<i>SERVER NAME:</i>	<i>DirectConnect Server Name:</i> Name of the DirectConnect server you want to create or update.
<i>PORT NUMBER:</i>	<i>ECDA Port Number:</i> Name of the ECDA port number you are using.
<i>ORACLE CONNECT STRING:</i>	<i>Oracle connect string:</i> The entry for the Oracle instance of the <i>tnsnames.ora</i> file.
<i>ENTER LOCATION OF TNSNAMES.ORA FILE:</i>	<i>Location of the tnsnames.ora file:</i> Full path (including filename) of the existing <i>tnsnames.ora</i> file – usually located in the network <i>admin</i> directory under the ORACLE_HOME directory. The <i>tnsnames.ora</i> identified must be accessible to this machine. If the file is not available, then it must be copied on to a local drive before configuring ECDA Option for Oracle. ECDA copies the existing <i>tnsnames.ora</i> into its directory.
<i>CREATE A WINDOWS SERVICE:</i>	<i>Add a service:</i> Select whether you are going to create DCO as a service on Windows. Sybase recommends that ECDA Option for Oracle be set up as a service on Windows.
<i>SERVICE NAME:</i>	<i>Service Name:</i> The name to be used for the Windows service.

ECDA Utilities

To simplify the execution of ECDA on multiple platforms, Sybase provides utilities to start a server, create and start a new server, and migrate files from one server to another.

Note These utilities cannot be used for ECDA Option for Oracle.

These utilities are batch files that can be found in the `<install_dir>\DC-15_0\bin` directory, where they should be kept to run properly. It is from this directory that the utilities can derive the paths to the other files they need to perform their tasks.

This appendix contains the following topics:

Topic	Page
Creating and starting a DCDirector server	61
Creating a new DirectConnect server	62
Starting a DirectConnect server	63

Creating and starting a DCDirector server

ECDA 15.0 provides a feature that allows DirectConnect Manager to connect to a “directing” server, called a DCDirector, that is capable of creating, starting, and stopping DirectConnect servers. To create a new DCDirector for an installation, use the *DCDirector.bat* batch file.

This batch file creates a new server with the default name “DCDirector” and sets the port number it listens on to a default port of 7711. The batch file then starts the server. No parameters are required or allowed, just enter:

```
DCDirector
```

You may change the default server name and default port number. If you need to use different values to identify the directors, you can use a text editor to modify the DCDirector batch file by assigning different values.

DCDirector utility

This utility creates a default DCDirector server in the installation area. This batch file does not accept any parameters and uses the server name “DCDirector,” and the port 7711 by default. You can change these values in the DCDirector batch file with a text editor.

Usage

```
DCDirector
```

Example

```
DCDirector
```

Once created, DCDirector will be able to start, stop, and provide other server functions.

Creating a new DirectConnect server

The AddServer utility sets the environment and creates the necessary entries in the *sql.ini* file before starting the DirectConnect server. AddServer requires two parameters to identify the name of the new server and to provide the port number for the server to listen on. One important limitation of AddServer: It does not check the *sql.ini* file for duplicate server names or ports in the same way that DCDirector does.

AddServer utility

This utility provides a way to create a server entry in the *sql.ini* file. It makes changes to the *sql.ini* file, but it does not verify that the *servername* or the *port number* are already being used.

Usage

```
AddServer [servername] [port number]
```

Example

```
AddServer srvname 1133
```

Starting a DirectConnect server

In the past, you started a DirectConnect server using a command that used the `direct` executable itself. For example, the command, `direct -Ssrvname`, was the standard way to start an existing DirectConnect server. This method is still supported, but it has some limitations: For this command to work, all of the appropriate environment variables need to be set properly before the command is executed. Also, if multiple installations of DirectConnect exist on a single machine, each installation will need its own environment.

To provide some help with this, a batch file is provided with ECDA version 15.0 that sets the installation-specific variables before executing the `direct -Ssrvname` command. This script, called `DCStart`, requires that all the non-Sybase variables be set properly, and ensures that the environment variables that are specific to a ECDA installation are all correctly set.

To start a server, see “Starting the DirectConnect server” section in Chapter 4, “Installing DirectConnect Manager.”

DCStart utility

This utility is similar to using the `direct` executable. `DCStart.bat` runs the appropriate `DC_SYBASE.bat` file to ensure that all the appropriate Sybase-specific environment variables are set properly. This is the required method to start a DirectConnect server, for one or multiple versions, since ECDA no longer sets the system environment.

Usage

`DCStart [direct executable Parameters]`

Syntax

`DCStart -Ssrvname`

Configuring Data Sources to Connect to Targets Using DataDirect

Topic	Page
To configure the data sources to connect to the targets	66
Connecting to DB2 UDB	66
Connecting to Microsoft SQL Server	71

This Appendix describes how to configure data sources to targets for a DataDirect driver and driver manager.

Note This driver is no longer provided by Sybase but the following information can be helpful in connecting to the various targets.

You must create and configure the data source name (DSN) for each ECDA component to connect to the following targets:

- DB2 UDB
- Microsoft SQL Server
- ODBC-accessible targets

Use the attributes listed in the section for each ECDA product and a text editor to define the data source entries. The *odbc.ini* file is installed in the `<install_dir>\DC-15_0` directory.

Note This section is for ECDA Option for ODBC only

To configure the data sources to connect to the targets

Note ECDA 15.0 requires the most current MDAC. For earlier versions, MDAC must be upgraded on the machine that is running Microsoft SQL Server. This machine may or may not be the machine that is running ECDA.

❖ **To install MDAC**

- Go to the following location and follow Microsoft's instructions for installation for the latest MDAC version at <http://www.microsoft.com>.

After installing MDAC, you must configure the DSN for each ECDA product that is described in the following sections.

Connecting to DB2 UDB

❖ **To add and configure a new data source name (DSN) for a DRDA service**

- 1 From your control panel, click on the ODBC Administrator icon to start it.
- 2 Select the User DSN or System DSN (recommended) and click Add.
- 3 Select the DB2 DRDA driver for your installation.
- 4 Click Finish.

The ODBC Administrator provides three dialog boxes in which connectivity, package binding, and other options take place. Each section has a Help button, which provides detailed descriptions of each parameter.

❖ **To configure a data source**

- 1 Select the General tab and enter the connectivity parameters and test them. Be sure you have consulted your database administrator for the Collection and Package names that are required. (Packages are created in the Bind section that follows.)

Table D-1 contains the General parameters, with the required parameters indicated by an asterisk (*), for this window:

Table D-1: General parameters

Parameter	Comments
*Data Source Name	Type a string that identifies this DB2 data source configuration in the system information. If you are creating a new data source definition, type a unique name of up to 32 characters. If you specify the name of an existing data source definition, the new settings will replace the existing ones.
Description	Type an optional descriptive comment for this data source definition.
*Ip address	Type the IP (Internet Protocol) address of the machine where the catalog tables are stored. Specify the address using the machine's numeric address (for example, 123.456.78.90) or specify its host name. If you enter a host name, the driver must find this name (with the correct address assignment) in the <i>HOSTS</i> file on the workstation or in a DSN server.
*TCP Port	Enter the port number that is assigned to the DB2 server on the machine where the catalog tables are stored. Specify either this port's numeric address or its service name. The default numeric port address varies depending on the OS of the DB2 server machine. For DB2, the default may be 50000. For AS/400, the default is 446. If you specify a service name, the driver must find this name (with the correct port assignment) in the <i>SERVICES</i> file on the workstation.
*Location Name	This field is valid only if you are connecting to a DB2 database running on OS/390 or AS/400. Type the DB2 location name, using the name defined during the local DB2 installation. Note This field is disabled if the Database Name field is populated.
*Collection	This field is valid only if you are connecting to a DB2 database running on OS/390 or AS/400. Type the name that identifies a group of packages. These packages include the DB2 DRDA driver packages. The default for DB2 is DATADIRECT00, and the default for AS/400 is SYBASE. Note This field is disabled if the Database Name field is populated.
*Database Name	This field is valid only if you are connecting to a DB2 database running on Windows. Type the name of the database to which you want to connect. Note This field is disabled if the Location Name field is populated.
*Package	Enter the name of the package that the driver uses to process static and dynamic SQL for applications that use this data source definition. The default name is DEFxx, where xx is the version number.
Default User ID	Not used by ECDA.
WorkArounds2	The name of the string key to allow the driver to pad the DB2 char for bit data field with spaces. The value is 131072. To add the WorkArounds2 string key, refer to the procedure "To add the WorkArounds2 String Key" on page 70.

- 2 After you enter this information, click Test Connect. If the connection fails, check for accurate information.
- 3 Select the ODBC Administrator Advanced tab, which contains optional fields that can affect performance and resource use.

Note The default values for the remaining optional parameters should be sufficient for most DRDA installations.

Enter values for the required parameters, indicated by an asterisk (*).

Table D-2: Advanced parameters

Parameter	Comments
<i>Add to Create Table</i>	Use the Add to Create Table option if you want to append the in tablespace clause to create table commands.
<i>Alternate ID</i>	Enter a value to be substituted at connect time for the current schema. This sets the default qualifier for unqualified object names in SQL statements. If the attempt to change the current schema fails, the connection fails with "Invalid value for Alternate ID." DB2 permissions should be set to SYSADM. (Not valid for AS/400 V4R5 and V5R1.)
<i>*WithHold Cursors</i>	This option needs to be selected for ECDA. It determines whether cursors are preserved or deleted after a commit or rollback.
<i>*Application Using Threads</i>	This option is required for ECDA.

- 4 Select the Bind tab of the DRDA Driver Setup window to define the package.

The Bind tab allows you to create the bind packages on the server that will be used by the driver. The Bind tab also allows you to specify the behavior of the package.

Before the DRDA driver can be used, you must create the required packages and bind them to the DB2 system. The driver will not work properly with any server that does not have the packages created. After the packages are created, you can rebind them with new bind parameters as needed.

Note Please consult your DB2 database administrator when attempting to create packages. You will need a login with sufficient authorization to create packages and grant execution privileges. DB2 database administration experience may also be needed to capture and analyze package creation errors.

Enter values for the required parameters, indicated by an asterisk (*). The default values for the remaining optional parameters should be sufficient for most DRDA installations.

Table D-3: Bind parameters

Parameters	Comments
<i>*Grant Execute</i>	Indicate whether or not to grant privileges on the package that you are creating. The default value is grant execute privileges on the package to PUBLIC. You can also specify to whom to grant execute privileges.
<i>*Isolation Level</i>	<p>Select the Isolation Level method by which locks are acquired and released by the system. Valid values are:</p> <ul style="list-style-type: none"> • All – prevents any other process from accessing data that your application has read or modified. All read or modified data is locked until the end of the transaction. • Change – allows other processes to read from the database. Only modified data is locked until the end of the transaction • Cursor Stability (the default) – allows other processes to change a row that your application has read if the cursor is not on the row you want to change. Prevents other processes from changing records that your application has changed until your program commits them or terminates. Prevents your program from reading a modified record that has not been committed by another process. • No Commit – allows your program to read modified records even if they have not been committed by another person. • Repeatable Read – prevents other processes from changing records that are read or changed by your application (including phantom records) until your program commits them or terminates. Prevents the application from reading modified records that have not been committed by another process. If your program opens the same query during a single unit of work under this isolation level, the results table will be identical to the previous table; however, it can contain updates made by your program.

Parameters	Comments
* <i>Package Owner</i>	Type the AuthID assigned to the package. This DB2 AuthID must have authority to execute all the SQL in the package
* <i>Dynamic Sections</i>	Type the number of statements that the DB2 Wire Protocol driver package can prepare for a single user. The default is 32. This value determines the maximum cursors or dynamic statements that a single connection may have open simultaneously.

5 Create a package.

When you click Create Package, a logon window appears. Enter your user ID and password. Then, click Login.

A message appears if the package is created successfully.

A separate package is not needed for each access service; however, if the access service has different characteristics in its parameters that suit it for a specific solution, you can create other packages for other solutions.

Add the WorkArounds2 String Key to pad DB2 character data

For DB2 only, you need to verify that a special string key is defined in the Windows Registry to allow the driver to pad DB2 char for bit data fields with spaces, instead of binary zeros.

Warning! Be cautious when using *regedit.exe* or *regedt32.exe*, you can disable your machine. Make a backup of your registry before making any changes.

❖ **To add the WorkArounds2 String Key**

1 Using the Windows Registry editor (*regedit.exe* or *regedt32.exe*), open one of the following sections in the Registry:

- For User DSN:
HKEY_CURRENT_USER \SOFTWARE\ODBC\ODBC.INI
- For System DSN:
HKEY_LOCAL_MACHINE\SOFTWARE\ODBC\ODBC.INI

In this section, locate an entry for the DSN you created.

- 2 If the WorkArounds2 string key is not there, select Edit | New | String Value from the Edit menu, to add a String Value named WorkArounds2 (case sensitive). After it has been created, modify the new entity and give it a value of 131072.
- 3 Click OK.

Repeat this process for each DB2 UDB DSN that you are going to use with ECDA.

Connecting to Microsoft SQL Server

At this time, you need to install the Microsoft Data Access Component (MDAC). The MDAC contains required ODBC components, such as the ODBC driver manager and the ODBC Administrator, as well as OLE/DB, used by Microsoft SQL Server 2000.

Creating and configuring a data source

To create a new Microsoft SQL Server data source or configure an existing data source, use the ODBC Administrator, which contains several setup boxes.

❖ **To access the Driver Setup dialog boxes**

- 1 From your control panel, click on the ODBC Administrator icon to start it.
- 2 Select the System DSN (recommended) or the User DSN and do one of the following:
 - If you are configuring a new data source, click Add. (New DSNs are required for releases that contain driver updates.)
 - If you are configuring an existing data source, select the data source name and click Configure.
- 3 Select the ECDA SQL Server wire protocol driver.
- 4 Click Finish.

The ECDA SQL Server wire protocol driver provides several dialog boxes where connectivity and other options take place.

❖ **To configure a data source to the SQL Server**

- 1 Click the General parameters tab and enter values for the required parameters, indicated by an asterisk (*).

Table 9-1: General parameter required values

Parameter	Comments
<i>*Data Source Name</i>	A string that identifies this SQL Server Wire Protocol data source configuration in the system information. Examples include "Accounting" or "SQL Server-Serv1."
<i>Description</i>	An optional long description of a data source name. For example, "My Accounting Database" or "SQL Server on Server number 1."
<i>*Server Name</i>	Name of the server that contains the database you want to access.
<i>Database Name</i>	Name of the database to which you want to connect by default. If you do not specify a value, the default database defined by the SQL Server is used.

- 2 Click the Advanced parameter tab and enter values for the required parameters indicated by an asterisk (*).

Table 9-2: Advanced parameter required values

Parameter	Comments
<i>Language</i>	National language to be used by the client. The default is English.
<i>Application Name</i>	Name the SQL Server uses to identify your application.
<i>Workstation ID</i>	Workstation ID used by the client.
<i>Default Logon ID</i>	Default logon ID used to connect to your SQL Server database. This ID is case sensitive. A logon ID is required only if security is enabled on your database. Your ODBC application may override this value, or you may override this value in the Logon dialog box or connection string.
<i>Use Windows Authentication</i>	Enables Windows security. When enabled, the Default Logon ID field is inactive because Windows security passes the logon ID and password. Selecting this check box also activates the corresponding check box on the Logon Dialog. Sybase recommends that you do not use this Windows security parameter.

Parameter	Comments
<i>*Enable Quoted Identifiers</i>	<p>Allows quoted identifiers; that is, identifiers in SQL Server that you can quote using a quoting character. By default, the check box is not selected.</p> <hr/> <p>Note Select only if using ASE/CIS client version 12.5.0.3 and later. These later versions of ASE/CIS send quoted identifiers to Microsoft SQL Server.</p> <hr/>
<i>Translate</i>	<p>Allows you to display the Select Translator dialog box, which lists the translators specified in the ODBC Translators section of the system information. DataDirect provides a translator named "OEM to ANSI" that translates your data from the IBM PC character set to the ANSI character set. Select a translator; then click OK to close this dialog box and perform the translation.</p>

- 3 After you enter this information, click Test Connect. If the connection fails, check for accurate information.
- 4 If the test connection is successful, click Apply and then click OK.

Glossary

accept	Establishment of a SNA or TCP/IP connection between Mainframe Connect Server Option and Mainframe Connect DirectConnect for z/OS Option.
access service	The named set of properties, used with an access service library, to which clients connect. Each DirectConnect server can have multiple services.
access code	A number or binary code assigned to programs, documents, or folders that allows authorized users to access them.
access service library	A service library that provides access to non-Sybase data contained in a database management system or other type of repository. Each such repository is called a “target.” Each access service library interacts with exactly one target and is named accordingly. See also service library .
ACSLIB	See access service library .
Adaptive Server Enterprise	The server in the Sybase client/server architecture. It manages multiple databases and multiple users, tracks the actual location of data on disks, maintains mapping of logical data description to physical data storage, and maintains data and procedure caches in memory.
Adaptive Server Enterprise/Component Integration Services	Includes a variation of ASE that provides a Transact-SQL interface to various sources of external data. Component Integration Services allows ASE to present a uniform view of enterprise data to client applications.
administrative service library	A service library that provides remote management capabilities and server-side support. It supports a number of remote procedures, invoked as RPC requests, that enable remote DirectConnect server management. See also remote procedure call , service library .
ADMLIB	See administrative service library .
Advanced Interactive Executive	The IBM implementation of the UNIX operating system. The RISC System/6000, among other workstations, runs the AIX operating system.
advanced program-to-program communication	Hardware and software that characterize the LU 6.2 architecture and its implementations in products. See also logical unit 6.2 .

AIX	See Advanced Interactive Executive .
AMD2	The component of the Mainframe Connect DB2 UDB Option that allows clients to submit SQL statements to DB2 UDB. It is a CICS transaction that receives SQL statements sent from Mainframe Connect DirectConnect for z/OS Option and submits them to DB2 UDB, using the DB2 UDB dynamic SQL facility. It also receives the results and messages from DB2 UDB and returns them to Mainframe Connect DirectConnect for z/OS Option.
American Standard Code for Information Interchange	The standard code used for information interchange among data processing systems, data communication systems, and associated equipment. The code uses a coded character set consisting of 7-bit coded characters (including a parity check, 8 bits).
API	See application program interface .
APPC	See advanced program-to-program communication .
application program interface	The programming language interface between the user and Mainframe Connect Client Option or Mainframe Connect Server Option. The API for Mainframe Connect Client Option is Client-Library. The API for Mainframe Connect Server Option is Gateway-Library.
ASCII	See American Standard Code for Information Interchange .
ASE	See Adaptive Server Enterprise .
ASE/CIS	See Adaptive Server Enterprise/Component Integration Services .
batch	A group of records or data processing jobs brought together for processing or transmission.
bind	In the Sybase environment, this term has different meanings depending on the context: <ul style="list-style-type: none">• In CICS, it is an SNA command used to establish a connection between LUs, or a TCP/IP call that connects an application to a port on its system.• In DB2 UDB, it compiles the Database Request Module, the precompiler product that contains SQL statements in the incoming request, and produces an access plan, a machine code version of the SQL statements that specifies the optimal access strategy for each statement.• In the mainframe access product set, it establishes a connection between a TRS port and a CICS or IMS region.

bulk copy transfer	A transfer method in which multiple rows of data are inserted into a table in the target database. Compare with destination-template transfer and express transfer .
call level interface	A programming style that calls database functions directly from the top level of the code. Contrast with embedded SQL .
catalog	A system table that contains information about objects in a database, such as tables, views, columns, and authorizations.
catalog RPC	A component of the Mainframe Connect DB2 UDB Option that allows clients to access DB2 UDB system catalogs. It uses an interface compatible with the catalog interface for the ODBC API.
catalog stored procedure	A procedure used in SQL generation and application development that provides information about tables, columns, and authorizations.
character set	A set of specific (usually standardized) characters with an encoding scheme that uniquely defines each character. ASCII is a common character set.
CICS	See Customer Information Control System .
CICS region	The instance of CICS.
client	In client/server systems, the part of the system that sends requests to servers and processes the results of those requests. See also client/server . Compare with server .
client application	Software responsible for the user interface that sends requests to applications acting as servers. See also client/server .
Client-Library	A library of routines that is part of Mainframe Connect Client Option.
client request	An RPC or language request sent by a client to a server.
client/server	An architecture in which the client is an application that handles the user interface and local data manipulation functions, and the server is an application providing data processing access and management. See also client application .
Client Services Application	A customer-written CICS program initiated on the host that uses the API to invoke the Mainframe Connect Client Option as a client to the DirectConnect server or to ASE. See also application program interface, Client Services for CICS .

Client Services for CICS	A Sybase host API that invokes the Mainframe Connect Server Option as a client to an access service for DB2 UDB or ASE. See also application program interface, Customer Information Control System, Client Services Application, Mainframe Connect Server Option.
clustered index	An index in which the physical order and the logical (indexed) order is the same. Compare with nonclustered index.
code page	An assignment of graphic characters and control function meanings to all code points.
commit	A process that makes permanent all changes made to one or more database files since the initiation of the application program, the start of an interactive session, or the last commit or rollback operation. Compare with rollback.
Common Programming Interface	Specifies the languages and services used to develop applications across SAA environments. The elements of the CPI specification are divided into two parts: processing logic and services.
configuration file	A file that specifies the characteristics of a system or subsystem.
configuration set	A section into which service library configuration files are divided.
conversion	The transformation between values that represent the same data item but which belong to different datatypes. Information can be lost due to conversion, because accuracy of data representation varies among different datatypes.
connection	A network path between two systems. For SNA, the path connects a logical unit (LU) on one machine to an LU on a separate machine. For TCP/IP, the path connects TCP modules on separate machines.
connection router	A program provided with Mainframe Connect Client Option that directs requests to particular remote servers. Mainframe system programmers use the connection router to define remote servers and server connections to Mainframe Connect Client Option.
Connection Router Table	A memory-resident table maintained by a Mainframe Connect Client Option system programmer that lists servers and the connections that a Client-Library transaction can use to access them.
control section	The part of a program specified by the programmer to be a relocatable unit, all elements of which are to be loaded into adjoining main storage locations.
control statement	In programming languages, a statement that is used to alter the continuous sequential execution of statements. A control statement can be a conditional statement or an imperative statement.

conversation-level security	The passing of client login information to the mainframe by TRS when it allocates a conversation.
CSA	See Client Services Application .
CSP	See catalog stored procedure .
cursor	In SQL, a named control structure used by an application program to point to a row of data.
Customer Information Control System	An IBM licensed program that enables transactions entered at remote terminals to be processed concurrently by user-written application programs.
DASD	See direct access storage device .
data definition statement	An IBM mainframe statement used to relate a name with a file.
data definition language	A language for describing data and data relationships in a database.
data set name	The term or phrase used to identify a data set.
database management system	The term or phrase to identify a data set. A computer-based system for defining, creating, manipulating, controlling, managing, and using databases.
database operation	A single action against the database. For Mainframe Connect DirectConnect for z/OS Option, a database operation is usually a single SQL statement. One or more database actions can be grouped together to form a request. See also request .
Database 2	An IBM relational database management system.
datatype	A keyword that identifies the characteristics of stored information on a computer.
DB-Library	A Sybase and Microsoft API that allows client applications to interact with ODS applications. See also application program interface .
DBMS	See database management system .
DB2 UDB	See Database 2 .
DDL	See data definition language .
DD statement	See data definition statement .
default language	The language that displays a user's prompts and messages.

destination-template transfer	A transfer method in which source data is briefly put into a template where the user can specify that some action be performed on it before execution against a target database. See also transfer . Compare with bulk copy transfer and express transfer .
direct access storage device	A device in which access time is effectively independent of the location of the data.
direct request	A request sent directly from a client workstation through Transaction Router Service to the DirectConnect server without going through ASE. Contrast with indirect request .
direct resolution	A type of service name resolution that relies upon a client application specifying the exact name of the service to be used. See also service name resolution . Compare with service name redirection .
DirectConnect Manager	A Java application from Sybase that can be used in Windows and UNIX environments. It provides remote management capabilities for DirectConnect products, including starting, stopping, creating, and copying services.
DirectConnect server	The component of Mainframe Connect DirectConnect for z/OS Option that provides general management and support functions to service libraries.
dll	See dynamic link library .
DSN	See data set name .
dynamic link library	A file containing executable code and data bound to a program at load time or runtime, rather than during linking.
dynamic SQL	The preparation and processing of SQL source statements within a program while the program runs. The SQL source statements are contained in host-language variables rather than being coded directly into the application program. Contrast with static SQL .
ECDA	See Enterprise Connect Data Access .
ECDA Option for ODBC	A Sybase solution that allows client applications to access ODBC data. It combines the functionality of the ECDA Option for ODBC architecture with ODBC to provide dynamic SQL access to target data, as well as the ability to support stored procedures and text and image pointers.
ECDA Option for Oracle	A Sybase solution that provides Open Client access to Oracle databases. When used in combination with ASE, it provides many of the features of a distributed database system, such as location transparency, copy transparency, and distributed joins.

embedded SQL	SQL statements that are embedded within a program and are prepared in the process before the program runs. After it is prepared, the statement itself does not change, although values of host variables specified within the statement might change.
end user	A person who connects to a DirectConnect server using an application to access databases and perform transfers. See also transfer .
Enterprise Connect Data Access	An integrated set of software applications and connectivity tools that allow access to data within a heterogeneous database environment, such as a variety of LAN-based, non-Sybase data sources, as well as mainframe data sources.
environment variable	A variable that describes how an operating system runs and the devices it recognizes.
exit routine	A user-written routine that receives control at predefined user exit points.
express transfer	A form of bulk copy transfer that uses ODBC bulk APIs to improve performance when transferring bulk data between data sources. Because it uses the same syntax as bulk copy transfer, no modification of applications is required.
external call interface	A CICS client facility that allows a program to call a CICS application as if the calling program had been linked synchronously from a previous program instead of started from a terminal.
External Security Manager	An add-on security package for the z/OS mainframe, licensed by Computer Associates.
FCT	See forms control table .
forms control table	An object that contains the special processing requirements for output data streams received from a host system by a remote session.
gateway	Connectivity software that allows two or more computer systems with different network architectures to communicate.
Gateway-Library	A library of communication, conversion, tracing, and accounting functions supplied with Mainframe Connect Server Option.
globalization	The combination of internationalization and localization. See internationalization , localization .
global variable	A variable defined in one portion of a computer program and used in at least one other portion of the computer program. Contrast with local variable .

handler	A routine that controls a program's reaction to specific external events, for example, an interrupt handler.
host	The mainframe or other machine on which a database, an application, or a program resides. In TCP/IP, this is any system that is associated with at least one Internet address. See also Transmission Control Protocol/Internet Protocol .
host ID	In Mainframe Connect Server Option, the ID that the TRS passes to the mainframe with a client request. The host ID is part of the client login definition at the TRS.
host password	In Mainframe Connect Server Option, the password that the client passes to the mainframe with a client request.
host request library	A DB2 UDB table that contains host-resident SQL statements that can be executed dynamically. See also host-resident request .
host-resident request	A SQL request that resides in a DB2 UDB table called the host request library. See also host request library .
IMS	See Information Management System .
indirect request	A client request that is routed through a stored procedure on a SQL Server, which forwards the request to TRS as an RPC. Compare with direct request .
Information Management System	A database/data communication system that can manage complex databases and networks.
interfaces file	An operating system file that determines how the host client software connects to a Sybase product. An <i>interfaces</i> file entry contains the name of any DirectConnect server and a list of services provided by that server.
internationalization	The process of extracting locale-specific components from the source code and moving them into one or more separate modules, making the code culturally neutral so it can be localized for a specific culture. See also globalization . Compare with localization .
keyword	A word or phrase reserved for exclusive use by Transact-SQL.
language RPC	The name TRS uses to represent a client's language request. TRS treats a language request as a remote procedure call (RPC) and maps it to a language transaction at the remote server.

language transaction	The server transaction that processes client language requests. The Mainframe Connect DB2 UDB Option language transaction for CICS is AMD2, which uses the DB2 UDB dynamic SQL facilities to process incoming SQL strings. The Mainframe Connect DB2 UDB Option for IMS uses SYRT by default.
linkage	In computer security, combining data or information from one information system with data or information from another system with the intention to derive additional information; for example, the combination of computer files from two or more sources.
linkage editor	A computer program that creates load modules from one or more object modules or creates load modules by resolving cross references among the modules, and if necessary, adjusts those addresses.
link-edit	To create a loadable computer program by using a linkage editor. See also linkage editor .
localization	The process of preparing an extracted module for a target environment, in which messages are displayed and logged in the user's language. Numbers, money, dates, and time are represented using the user's cultural convention, and documents are displayed in the user's language. See also globalization .
local variable	A variable that is defined and used only in one specified portion of a computer program. Contrast with global variable .
logical unit	A type of network addressable unit that enables a network user to gain access to network facilities and communicate remotely. A connection between a TRS and a CICS region is a connection between logical units.
logical unit 6.2	A type of logical unit that supports general communication between programs in a distributed processing environment. See also advanced program-to-program communication .
login ID	In Mainframe Connect Server Option, the ID that a client user uses to log in to the system.
login packet	Client information made available to Mainframe Connect Server Option. The client program sets this information in a login packet and sends it to TRS, which forwards it to the mainframe.
long-running transaction	A transaction that accepts more than one client request. Whereas short transactions end the communication after returning results to a client, a long-running transaction can await and process another request. Compare with short transaction .
LU 6.2	See logical unit 6.2 .

mainframe access products	Sybase products that enable client applications to communicate with mainframes in a client/server environment. See client/server .
Mainframe Connect	The Sybase product set that provides access to mainframe data.
Mainframe Connect Client Option	A Sybase product that, using Client-Library, allows mainframe clients to send requests to SQL Server, Open Server, the Mainframe Connect DB2 UDB Option and Mainframe Connect Server Option. Mainframe Connect Client Option provides capability for the mainframe to act as a client to LAN-based resources in the CICS or the IMS and MVS environment.
Mainframe Connect DB2 UDB Option	A Sybase mainframe solution that provides dynamic access to DB2 UDB data. It is available in the CICS or IMS environment. See also Customer Information Control System, Database 2, Multiple Virtual Storage .
Mainframe Connect DirectConnect for z/OS Option	A Sybase Open Server application that provides access management for non-Sybase databases, copy management (transfer), and remote systems management.
Mainframe Connect Server Option	A Sybase product that provides capability for programmatic access to mainframe data. It allows workstation-based clients to execute customer-written mainframe transactions remotely. It is available for the CICS and the IMS and MVS environments
Multiple Virtual Storage	An IBM operating system that runs on most System/370 and System/390 mainframes. It supports 24-bit addressing up to 16 megabytes.
network protocol	A set of rules governing the way computers communicate on a network.
nonclustered index	An index that stores key values and pointers to data. Compare with clustered index .
null	Having no explicitly assigned value. NULL is not equivalent to 0 or to blank.
ODBC	See Open Database Connectivity .
ODS	See Open Data Services .
Open Client	A Sybase product that provides customer applications, third-party products, and other Sybase products with the interfaces required to communicate with Open Client and Open Server applications.
Open Data Services	A product that provides a framework for creating server applications that respond to DB-Library clients.
Open Database Connectivity	A Microsoft API that allows access to both relational and non-relational databases. See also application program interface .

Open Server	A Sybase product that provides the tools and interfaces required to create a custom server. Clients can route requests to the DirectConnect server through an Open Server configured to meet specific needs, such as the preprocessing of SQL statements.
parameter	A variable that is given a constant value for a specified application and can denote the application. Compare with property .
Partner Certification Reports	Sybase publications that certify third-party or Sybase products to work with other Sybase products.
Password Expiration Management	An IBM password management program with CICS Version 3.3 through an optional program temporary fix, and as an integral part of CICS with version 4.1 and higher.
PEM	See Password Expiration Management .
PL/1	See Programming Language /1 .
primary database	The database management system that the DirectConnect server is always connected to. It is implied in the transfer statement.
Programming Language/1	A programming language designed for use in a wide range of commercial and scientific computer applications.
property	A setting for a server or service that defines the characteristics of the service, such as how events are logged. Compare with parameter .
protocol	The rules for requests and responses used to manage a network, transfer data, and synchronize the states of network components.
query	A request for data from a database, based upon specified conditions.
Registry	The part of the Windows operating system that holds configuration information for a particular machine.
relational database	A database in which data is viewed as being stored in tables consisting of columns (data items) and rows (units of information).
relational operators	Operators supported in search conditions.
relops	See relational operators .
remote procedure call	A call to execute a stored procedure on a remote server. For Mainframe Connect Server Option, an RPC is a direct request from a client to TRS. For Mainframe Connect Client Option, a Client-Library transaction that calls a procedure on a remote server acts like an RPC.

remote stored procedure	A customer-written CICS program using an API that resides on the mainframe and communicates with Mainframe Connect DB2 UDB Option. See also Customer Information Control System, stored procedure . Compare with Client Services Application .
remote systems management	A feature that allows a system administrator to manage multiple DirectConnect servers and multiple services from a client.
Replication Server	A Sybase SQL Server application that maintains replicated data and processes data transactions received from a data source.
request	One or more database operations an application sends as a unit to the database. Depending upon the response, the application commits or rolls back the request. See also commit, rollback, unit of work .
resource table	A main storage table that associates each resource identifier with an external logical unit (LU) or application program.
rollback	An instruction to a database to back out of changes requested in a unit of work. Compare with commit .
router	An attaching device that connects two LAN segments, which use similar or different architectures, at the Open System Interconnection (OSI) reference model network layer. Contrast with gateway .
RPC	See remote procedure call .
RSP	See remote stored procedure .
SAA	See System Application Architecture .
secondary connection	The connection specified in the transfer statement. It represents anything that can be accessed using Mainframe Connect Client Option, such as ASE or another access service.
secondary database	In transfer processing, the supported database that is specified in the transfer statement. Compare with primary database .
server	A functional unit that provides shared services to workstations over a network. See also client/server . Compare with client .
server process ID	A positive integer that uniquely identifies a client connection to the server.
service	A functionality available in Mainframe Connect DirectConnect for z/OS Option. It is the pairing of a service library and a set of specific configuration properties.

service library	In Mainframe Connect DirectConnect for z/OS Option, a set of configuration properties that determine service functionality. See also access service library , administrative service library , Transaction Router Service library , transfer service library .
service name redirection	A type of service name resolution that allows a system administrator to create an alternative mechanism to map connections with services. See also service name resolution . Compare with direct resolution .
service name redirection file	The default name of the file used for the service name redirection feature. See service name redirection .
service name resolution	The DirectConnect server mapping of an incoming service name to an actual service. See also direct resolution , service name redirection .
session	A connection between two programs or processes. In APPC communications, sessions allow transaction programs to have conversations between the partner LUs. See also advanced program-to-program communication .
short transaction	A mainframe transaction that ends the communication when it finishes returning results to the client. Compare with long-running transaction .
SNA	See Systems Network Architecture .
SNRF	See service name redirection file .
SPID	See server process ID .
SQL	See structured query language .
SQLDA	See SQL descriptor area .
sqledit	A utility for creating and editing <i>sql.ini</i> files and file entries.
sql.ini	The interfaces file containing definitions for each DirectConnect server to which a workstation can connect. The file must reside on every client machine that connects to ASE.
SQL descriptor area	A set of variables used in the processing of SQL statements.
SQL stored procedure	A single SQL statement that is statically bound to the database. See also stored procedure .
static SQL	SQL statements that are embedded within a program and prepared during the program preparation process before the program runs. Compare with dynamic SQL .

stored procedure	A collection of SQL statements and optional control-of-flow statements stored under a particular name. Adaptive Server stored procedures are called “system procedures.” See also remote stored procedure, system procedures.
structured query language	An IBM industry-standard language for processing data in a relational database.
stub	A program module that transfers remote procedure calls (RPCs) and responses between a client and a server.
SYRT	The component of Mainframe Connect DB2 UDB for IMS that allows clients to submit SQL language requests to DB2 through IMS.
System Administrator	The person in charge of server system administration, including installing and maintaining DirectConnect servers and service libraries.
System Application Architecture	An IBM proprietary plan for the logical structure, formats, protocols, and operational sequences for transmitting information units through networks and controlling network configuration and operation. See also advanced program-to-program communication.
system procedures	A stored procedure that ASE supplies for use in system administration. System procedures serve as shortcuts for retrieving information from system tables, or a mechanism for accomplishing database administration. See also stored procedure.
Systems Network Architecture	An IBM proprietary plan for the structure, formats, protocols, and operational sequences for transmitting information units through networks. See also advanced program-to-program communication.
table	An array of data or a named data object that contains a specific number of unordered rows. Each item in a row can be unambiguously identified by means of one or more arguments.
Tabular Data Stream	A Sybase application-level protocol that defines the form and content of relational database requests and replies.
target	A system, program, or device that interprets, rejects, satisfies, or replies to requests received from a source.
target database	The database to which the DirectConnect server transfers data or performs operations on specific data.
TCP/IP	See Transmission Control Protocol/Internet Protocol.
TDS	See Tabular Data Stream.

transaction	A unit of processing initiated by a single request. A transaction consists of one or more application programs that, when executed, accomplish a particular action. In Mainframe Connect Server Option, a client request (RPC or language request) invokes a mainframe transaction. In Mainframe Connect Client Option, a mainframe transaction executes a stored procedure on a remote server.
transaction processing	A sequence of operations on a database that is viewed by the user as a single, individual operation.
Transaction Router Service	A Mainframe Connect DirectConnect for z/OS Option program used when the mainframe acts as a transaction server to route requests from remote clients to the Mainframe Connect Server Option and return results to the clients.
Transaction Router Service library	A service library that facilitates access to remote transactions, allowing customers to execute transactions from virtually any mainframe data source. See also service library .
Transact-SQL	A Sybase-enhanced version of the SQL database language used to communicate with ASE.
transfer	A Mainframe Connect DirectConnect for z/OS Option feature that allows users to move data or copies of data from one database to another.
transfer service library	A service library that provides copy management functionality. See also service library .
Transmission Control Protocol/Internet Protocol	A set of communication protocols that supports peer-to-peer connectivity functions for both local and wide area networks.
trigger	A form of stored procedure that automatically executes when a user issues a change statement to a specified table.
TRS	See Transaction Router Service .
TRS library	See Transaction Router Service library .
T-SQL	See Transact-SQL .
unit of work	One or more database operations grouped under a commit or rollback. A unit of work ends when the application commits or rolls back a series of requests, or when the application terminates. See also commit , rollback , transaction .
user ID	User identification. The ID number by which a user is known in a specific database or system.

variable	An entity that is assigned a value. Mainframe Connect DirectConnect for z/OS Option has two kinds of variables: <i>local</i> and <i>global</i> .
view	An alternate representation of data from one or more tables. A view can include all or some of the columns contained the table or tables on which it is defined.
Virtual Storage Access Method	An IBM-licensed program that controls communication and the flow of data in an SNA network.
Virtual Telecommunications Access Method	IBM mainframe software that allows communication on an SNA network between mainframes and allows the mainframe to have multiple sessions per connection.
VSAM	See Virtual Storage Access Method .
VTAM	See Virtual Telecommunications Access Method .
wildcard	A special character that represents a range of characters in a search pattern.

Index

A

- Add to Create Table parameter 68
- ADDRDBDIRE command
 - used to define a local relational database 49
- administrative tasks 8
- AS/400
 - connectivity tasks vii, 49
 - enabling DRDA 49
 - security levels 50

B

- bind parameters 69
- Bind tab 68

C

- changing
 - AS/400 security setting 51
 - coded character set ID (CCSID) 51
- collection name 66
- Collection parameter 67
- commands
 - create table 68
- configuration checklist
 - holding the preliminary planning session 7
- configuring
 - access services 40
 - DirectConnect server 40
- configuring server and services 40
- connectivity
 - parameters 8
 - preparing for DirectConnect installation 7
 - tasks for AS/400 vii, 49
- console mode installation 16
- conventions used in this book
 - style x

- syntax xi
- Create Server wizard 25
 - connecting a server to a target 25
- create table command 68
- creating
 - package 70

D

- data source name 67
- Database Name parameter 67
- DatabaseName configuration property
 - used in AS/400 setup 49
- Default User ID parameter 67
- defining
 - packages 68
- deinstalling a DirectConnect Server 46
- description parameter 67
- DirectConnect
 - configuring server and services 40
- DirectConnect Manager
 - features 3
- DirectConnect Server
 - how to deinstall 46
- DirectConnect software
 - installing 11
- DRDA
 - enabling for AS/400 49
- Dynamic Sections parameter 70

F

- files
 - HOSTS 67
 - SERVICES 67

Index

G

Grant Execute parameter 69

H

HOSTS file 67

I

installing

administrative tasks 8

DirectConnect software 11

using a response file 17

using console mode 16

IP address parameter 67

L

Location Name parameter 67

log and trace files

post-installation troubleshooting with 46

M

MFC server option

preinstallation for HP 9000(8xx) 57

O

ODBC Administrator

Advanced tab 68

DirectConnect for DB2 UDB 66

P

package definitions 68

package name 66

Package parameter 67

parameters

Add to Create Table 68

bind 69

Collection 67

data source name 67

Database Name 67

Default User ID 67

Description 67

Dynamic Sections 70

Grant Execute 69

IP address 67

Location Name 67

Package 67

Query Block Size 68

researching for connectivity 8

TCP Port 67

performance 68

planning

administrative tasks 8

pre-installation

verify previously installed Sybase products 9

pre-installation checklist for HP 9000(8xx)

MFC server option 57

pre-log error messages

explanation 46

Q

Query Block Size parameter 68

R

related product documentation

Adaptive Server viii

ODBC viii

OmniConnect viii

Open Client and Open Server viii

requirements

installation team 6

response file installation 17

S

security levels

- AS/400 50
- SERVICES file 67
- setting
 - performance parameters 68
- setting up
 - AS/400 security setting 51
 - connectivity to the target database 7
- settings 68
- SySAM
 - licensing requirements 11
- system requirements
 - verifying 8

T

- tablespace clause 68
- TCP Port parameter 67
- the 12
- troubleshooting for Windows platforms 46
 - checking server log and trace files 46
 - confirming the Open Server software release number 46

V

- verifying
 - system requirements 8

