

Utility Guide

# Adaptive Server<sup>®</sup> Enterprise

15.7

#### DOCUMENT ID: DC30191-01-1570-01

#### LAST REVISED: September 2011

Copyright © 2011 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

To order additional documents, U.S. and Canadian customers should call Customer Fulfillment at (800) 685-8225, fax (617) 229-9845.

Customers in other countries with a U.S. license agreement may contact Customer Fulfillment via the above fax number. All other international customers should contact their Sybase subsidiary or local distributor. Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase trademarks can be viewed at the Sybase trademarks page at http://www.sybase.com/detail?id=1011207. Sybase and the marks listed are trademarks of Sybase, Inc. (1) indicates registration in the United States of America.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP AG in Germany and in several other countries all over the world.

Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

IBM and Tivoli are registered trademarks of International Business Machines Corporation in the United States, other countries, or both.

All other company and product names mentioned may be trademarks of the respective companies with which they are associated.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568.

# Contents

CHAPTER 1	Building Servers Using dataserver       1         Introduction       1         Building a new master device       2         Environments when using dataserver       3         Examples of building a new Adaptive Server       3         Starting an existing Adaptive Server       6         Upgrade to a server with larger page sizes       7         View the current server limits       7	
CHAPTER 2	Using Interactive isgl from the Command Line	•
-	Before vou begin	)
	Starting and stopping isal	)
	How to use Transact-SQL in isol	)
	Formatting isol output	
	Correcting input	<u>,</u>
	set options that affect output 12	<u>,</u>
	Changing the command terminator	3
	Performance statistics interaction with command terminator values 1	4
	Setting the network packet size	5
	Input and output files15	5
	UNIX command line redirection 15	;
CHAPTER 3	Using Interactive SQL in Graphics Mode	7
	Starting Interactive SQL	3
	The main Interactive SQL window 19	)
	Plan dialog tab19	)
	The Interactive SQL toolbar 21	
	Open multiple windows 21	
	Keyboard shortcuts 21	
	Using Interactive SQL to display data 22	<u>)</u>
	Edit table values in Interactive SQL 23	3
	Copy rows from the Interactive SQL result set 24	ł
	Edit table values from the Interactive SQL result set 24	ŀ

		sei
	23 Delata rows from the database using Interactive SOI	25
	SOL statements in Interactive SOL	20
	SQL Statements in Interactive SQL	20
	Canceling an Interactive SQL command	20
	Combining multiple statements	21
	Looking up tables, columns, and procedures	28
	Recail commands	29
	Log commands	29
		30
	General dialog box	30
	Result dialog box	31
	Import/Export dialog box	32
	Messages dialog tab	33
	Editor	33
	Query Editor	34
	Run command files	35
	Write output to a file	35
	Execute command files	35
	Save, load, and run command files	36
	The SQL escape syntax in Interactive SQL	37
	Interactive SQL commands	38
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp	<b>39</b> 40
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp	<b>39</b> 40 40
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp bcp requirements	<b>39</b> 40 40 41
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp bcp requirements bcp modes	<b>39</b> 40 40 41 43
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp bcp requirements bcp modes Copy data to a file	<b>39</b> 40 40 41 43 43
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp bcp requirements bcp modes Copy data to a file Examples	<b>39</b> 40 40 41 43 43 43
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp bcp requirements bcp modes Copy data to a file Examples Bulk copying encrypted data	<b>39</b> 40 40 41 43 43 43 44
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp bcp requirements bcp modes Copy data to a file Examples Bulk copying encrypted data bcp performance	<b>39</b> 40 40 41 43 43 44 44 44
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp bcp requirements bcp modes Copy data to a file Examples Bulk copying encrypted data bcp performance Using fast or slow bcp	<b>39</b> 40 40 41 43 43 44 44 46 47
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp bcp requirements bcp modes Copy data to a file Examples Bulk copying encrypted data bcp performance Using fast or slow bcp Copving in data with fast bcp	<b>39</b> 40 40 41 43 43 44 44 46 47 50
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp.         Methods for moving data.         Import and export data with bcp.         bcp requirements         bcp modes.         Copy data to a file         Examples.         Bulk copying encrypted data         bcp performance         Using fast or slow bcp         Copying in data with fast bcp         Bulk copying data into partitioned tables	<b>39</b> 40 41 43 43 44 44 46 47 50 50
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp.         Methods for moving data         Import and export data with bcp.         bcp requirements         bcp modes         Copy data to a file         Examples         Bulk copying encrypted data         bcp performance         Using fast or slow bcp         Copying in data with fast bcp         Bulk copying data into partitioned tables         Using narallel bulk copy to copy data into a specific partition	<b>39</b> 40 40 41 43 43 44 44 46 47 50 50
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp bcp requirements bcp modes Copy data to a file Examples Bulk copying encrypted data bcp performance Using fast or slow bcp Copying in data with fast bcp Bulk copying data into partitioned tables Using parallel bulk copy to copy data into a specific partition . Using the bcp options	<b>39</b> 40 41 43 43 44 44 46 47 50 50 53 59
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp bcp requirements bcp modes Copy data to a file Examples Bulk copying encrypted data bcp performance Using fast or slow bcp Copying in data with fast bcp Bulk copying data into partitioned tables Using parallel bulk copy to copy data into a specific partition . Using the bcp options	<b>39</b> 40 41 43 43 44 46 47 50 50 53 59 59
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data Import and export data with bcp bcp requirements bcp modes Copy data to a file Examples Bulk copying encrypted data bcp performance Using fast or slow bcp Copying in data with fast bcp Bulk copying data into partitioned tables Using parallel bulk copy to copy data into a specific partition . Using the bcp options Using the default formats	<b>39</b> 40 41 43 43 44 46 47 50 50 50 59 59 61
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data	<b>39</b> 40 40 41 43 43 44 44 46 47 50 50 50 59 61 62
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data	<b>39</b> 40 40 41 43 43 44 46 47 50 50 53 59 59 61 62 62
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp Methods for moving data	<b>39</b> 40 40 41 43 43 44 46 47 50 53 59 61 62 62 64
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp.         Methods for moving data.         Import and export data with bcp.         bcp requirements         bcp modes.         Copy data to a file         Examples.         Bulk copying encrypted data         bcp performance         Using fast or slow bcp         Copying in data with fast bcp         Bulk copying data into partitioned tables.         Using parallel bulk copy to copy data into a specific partition.         Using the bcp options.         Using the default formats         Change terminators from the command line         Change the defaults in interactive bcp         Respond to bcp prompts         File storage type.	<b>39</b> 40 40 41 43 43 44 46 47 50 50 50 59 61 62 62 64 66
CHAPTER 4	Transfer Data to and from Adaptive Server with bcp.         Methods for moving data.         Import and export data with bcp.         bcp requirements         bcp modes.         Copy data to a file         Examples.         Bulk copying encrypted data         bcp performance         Using fast or slow bcp         Copying in data with fast bcp         Bulk copying data into partitioned tables         Using parallel bulk copy to copy data into a specific partition.         Using the bcp options.         Using the default formats         Change terminators from the command line         Change the defaults in interactive bcp.         Respond to bcp prompts         File storage type.         Prefix length         Field logetth	<b>39</b> 40 40 41 43 43 44 46 47 50 53 59 61 62 62 64 66 7

	Field and row terminators	69
	Format files	
	Elements of the bcp format file	
	Examples of copying out data interactively	
	Copy out data with field lengths	
	Copy out data with delimiters	
	Examples of copying in data interactively	
	Copy in data with field lengths	
	Copy in data with delimiters	81
	Copy in data with a format file	81
	bcp and alternate languages	82
	Support for initialization strings	83
	bcp and row-level access rules	83
	Copy in and batch files	84
	Improve recoverability	84
	Batches and partitioned tables	85
	Copy out and text and image data	85
	Specify a network packet size	86
	Copy in and error files	86
	Copy out and error files	87
	Data integrity for defaults, rules, and triggers	88
	Defaults and datatypes	88
	Rules and triggers	88
	How bcp differs from other utilities	88
CHAPTER 5	Lising decn	01
CHAITER J	Cotting started with deep	
	Vorking with conver entrice	
	Adding and modifying conver entrice	
	Adding and modifying server entries	
	List and view contents of conver entries	
	List and view contents of server entries	
	Exiting dscp	
	Quick reference for dscp utility commands	
CHAPTER 6	Using dsedit	101
	Getting started with dsedit	101
	Start dsedit	101
	Open an editing session	103
	Add, view, and edit server entries	105
	Modify server entries in Windows	105
	Modify server entries in UNIX platforms	
	······································	

	Copy server entries	110
	Troubleshoot dsedit	112
CHAPTER 7	Utility Commands Reference	113
	Getting started	114
	*_r utilities	116
	Utilities quick reference	116
	Installation or configuration utilities	117
	Utilities for languages, character sets, and sort orders	117
	Utilities to start servers	118
	Database creation and manipulation utilities	118
	Utilities to gather information	119
	Tuning utility	119
	Utility to manage a cluster	119
	backupserver	120
	bcp	126
	buildmaster	142
	certauth	143
	certpk12	147
	certreq	150
	charset	154
	cobpre	155
	cpre	156
	dataserver	157
	ddlgen	165
	defncopy	190
	dscp	196
	dsedit	197
	extractjava	198
	installjava	201
	isql	205
	langinstall	217
	optdiag	220
	preupgrade	227
	pwdcrypt	232
	qptune	233
	qrmutil	240
	snowserver	246
	sqlabgr	247
	Sqlioc	252
	sqliocres	253
	sqlsrvr	254
	sqlupgrade	261
	sqlupgraderes	262

	srvbuild	
	srvbuildres	
	startserver	
	sybdiag	
	sybmigrate	276
	sybtsmpasswd	
	xpserver	282
CHAPTER 8	Using sybcluster to Manage the Cluster	285
	sybcluster	287
	add backupserver	294
	add instance	295
	connect	297
	create backupserver	299
	create cluster	301
	create xpserver	303
	deploy plugin	304
	diagnose cluster	306
	diagnose instance	308
	disconnect	309
	drop backupserver	310
	drop cluster	311
	drop instance	312
	drop xpserver	313
	exit	314
	help	315
	localize	316
	quit	318
	set backupserver	319
	set cluster	320
	set instance	321
	set xpserver port	
	show agents	323
	show backupserver config	325
	show cluster	326
	show instance	329
	show membership mode	332
	show session	333
	show xpserver	335
	shutdown cluster	336
	shutdown instance	
	start cluster	338
	start instance	339
	upgrade server	

	use	343
CHAPTER 9	Migration Utility	345
	Overview	345
	Benefits of sybmigrate	345
	What sybmigrate does	346
	What sybmigrate does not do	348
	Before you begin	349
	Dependencies	349
	Installation	350
	Permissions	350
	Platforms	351
	Environment settings	351
	Migrating proxy tables	351
	Migration process	352
	Overview of the migration process	352
	Pre-migration considerations	353
	Configuration and tuning for higher performance	355
	Possible errors to avoid	358
	Auto-select dependent objects for migration	358
	Migrating an archive database	358
	Starting sybmigrate	359
	GUI mode	363
	Resource file mode	370
	Using sybmigrate with encrypted columns	377
	Post-migration activities	378
	Migrate databases in the Replication Server domain	379
	Premigration procedures	379
	Postmigration procedures	380
	Migrating databases that support wide data	385
	Limitations	386
	Troubleshooting and error messages	388
Index		391

# Building Servers Using dataserver

Торіс	Page
Introduction	1
Building a new master device	2

Adaptive Server<sup>®</sup> does not use the buildmaster binary to build the master device. Instead, Sybase<sup>®</sup> has incorporated the buildmaster functionality in the dataserver binary. This chapter discusses how to use dataserver to build your server.

**Note** The dataserver binary in Windows is called sqlsrvr.exe. If you are using the Windows platform, substitute all reference to dataserver in this chapter with sqlsrvr.

For a detailed description of dataserver syntax, see dataserver on page 157. For a detailed description of sqlsrvr syntax, see sqlsrvr on page 254.

# Introduction

The dataserver command allows you to create master devices and databases with logical pages of size 2K, 4K, 8K, or 16K. Larger logical pages allow you to create larger rows, which can improve your performance because Adaptive Server accesses more data each time it reads a page. For example, a 16K page can hold eight times the amount of data as a 2K page, an 8K page holds four times as much data as a 2K page, and so on, for all the sizes for logical pages.

The logical page size is a server-wide setting; you cannot have databases with varying size logical pages within the same server. All tables are appropriately sized so that the row size does not exceed the current page size of the server. That is, rows cannot span multiple pages.

# Building a new master device

This section describes the process for creating a new master device using the dataserver utility. The master device is built using the **build** mode in dataserver. After the master device is built, the server shuts down. You must then manually start the server in the **start** mode. After this you can start, stop, and restart Adaptive Server whenever necessary without having to rebuild the master device

**Note** When you are building a master device you should allow an additional 8K for the config block.

Adaptive Server uses three types of page sizes:

- Logical page size these are the pages that the database objects are built with. A databases and any of its related objects must use the same logical page size. Logical page sizes come in sizes of 2K, 4K, 8K, and 16K.
- Virtual page size this is the physical page allocation at the disk level, and is always done in 2K pages. All disk I/O is done in multiples of virtual page size.
- Memory page size the memory allocated and managed within Adaptive Server. The memory page size is always in units of 2K pages.

The following syntax creates a new master device with dataserver:

```
dataserver -ddevice_name
. . .
    -b [master_device_size [k|K|m|M|g|G]
    [-z logical_page_size [k|K]
-h
```

Where:

-d *device\_name* – is the full path name of the device for the master database. The master database device must be writable by the user who starts Adaptive Server. The default master database device name is d\_master.

-b – indicates that dataserver is in build mode and creating a new master device, and indicates the size of the master device. If you do not provide a unit specifier (k, m, g) for the size of the device, dataserver assumes a size in virtual pages. The size of a virtual page is always 2K. For example:

- -b 51204 specifies a device of 51,204 virtual pages (100.0078125MB).
- -b 100M specifies a device of 100MB

-z – specifies the logical page size, which is always 2K, 4K, 8K, or 16K. This parameter is optional during the build phase and is ignored during the start mode. If you do not include the -z parameter during the build mode, the master device is built with 2K logical pages.

-h – prints the syntax for the dataserver command.

See dataserver on page 157 for a full list of dataserver parameters and their definitions.

## Environments when using dataserver

When you start an Adaptive Server with the dataserver program, Adaptive Server derives its running environment from:

- The configuration file you specify in -c configuration\_file
- The default configuration file, *servername.cfg*, if you did not specify the -c parameter
- Default values if you did not specify either -c configuration\_file or servername.cfg

For more information on these configuration parameters, see Chapter 17, "Setting Configuration Parameters," in the *System Administration Guide*.

## Examples of building a new Adaptive Server

To create a new Adaptive Server, issue dataserver using the -b and -z options. For example, to:

• Build a 100MB master device using the default logical page size (2K) and start the server:

dataserver -d /var/sybase/masterdb.dat -b100M -sMASTER2K

• Build a 100MB master device with a logical page size of size 4K:

dataserver -d /var/sybase/masterdb.dat -b100M -z4K -sMASTER4K

• Build a master device of 102,400 virtual pages of size 2K, create databases using a logical page size of 8K, and boot the server:

dataserver -d /var/sybase/masterdb.dat -b102400 -z8K -sMASTER8K

If the total requested space  $(102,400 \times 2K = 200 \text{ MB})$  is insufficient to build all the required system databases using the specified logical page size, then an error message is reported, and the process fails.

Example The following is a sample output of dataserver building a 200MB device with a 2K logical page size, called personnel2k:

dataserver -d /var/sybase/personnel2k.dat -b200M -z2k -sPERSONNEL2K

dataserver uses a default configuration file if you do not specify one:

00:00000:00000:2001/04/16 10:24:31.73 kernel Warning: Using default file '/var/sybase/PERSONNEL2K.cfg' since a configuration file was not specified. Specify a configuration file name in the RUNSERVER file to avoid this message.

To specify your own configuration file, use the dataserver -c parameter. See Chapter 11, "Setting Configuration Parameters" in the *System Administration Guide* for more information.

Adaptive Server version 15.0 treats all installations as an upgrade, regardless of whether you have an existing version of Adaptive Server or not. For this reason, you see the following output when running dataserver:

00:00000:00001:2001/04/16 10:24:32.63 server Database 'master' appears to be at an older revision than the present installation; SQL Server will assess it, and upgrade it as required.

00:00000:00001:2001/04/16 10:24:32.66 server Database 'master': beginning upgrade step [ID 1]: Initialize disk and create empty allocation units on master device.

00:00000:00001:2001/04/16 10:24:34.74 server Database 'master': beginning upgrade step [ID 2]: Bootstrap basic system catalogs in database.

dataserver continues creating the master database, including all of its tables such as systypes, sysobjects and sysusages:

00:00000:00001:2001/04/16 10:24:35.21 server Database 'master': beginning upgrade step [ID 3]: creating index (table systypes, index ncsystypes)

00:00000:00001:2001/04/16 10:24:35.36 server Database 'master': beginning upgrade step [ID 4]: creating index (table sysobjects, index ncsysobjects)

00:00000:00001:2001/04/16 10:24:35.44 server Database 'master': beginning upgrade step [ID 20]: creating table (table sysusages)

[...]

When dataserver has created the master database, it creates the model database:

#### [...]

00:00000:00001:2001/04/16 10:24:43.14 server Database 'model' appears to be at an older revision than the present installation; SQL Server will assess it, and upgrade it as required.

00:00000:00001:2001/04/16 10:24:43.14 server Database 'model': beginning upgrade step [ID 1]: Initialize disk and create empty allocation units on master device.

00:00000:00001:2001/04/16 10:24:43.83 server Database 'model': beginning upgrade step [ID 2]: Bootstrap basic system catalogs in database.

00:00000:00001:2001/04/16 10:24:43.89 server Database 'model': beginning upgrade step [ID 3]: creating index (table systypes, index ncsystypes)

00:00000:00001:2001/04/16 10:24:43.91 server Database 'model': beginning upgrade step [ID 4]: creating index (table sysobjects, index ncsysobjects)

[...]

When dataserver has created the model database, it creates the tempdb and sybsystemdb databases:

#### [...]

00:00000:00001:2001/04/16 10:24:45.23 server CREATE DATABASE: allocating 1024 logical pages (2.0 megabytes) on disk 'master'.

00:00000:00001:2001/04/16 10:24:46.79 server Database sybsystemdb successfully created.

[...]

dataserver is successful when the server changes the default sort order and shuts down:

#### [...]

00:00000:00001:2001/04/16 10:24:47.23 server Now loading SQL Server's new default sort order and character set

[...] 00:00000:00001:2001/04/16 10:24:47.31 server Default Sort Order successfully changed. 00:00000:00001:2001/04/16 10:24:47.37 server SQL Server shutdown after verifying System Indexes.

00:00000:00001:2001/04/16 10:24:47.37 kernel ueshutdown: exiting

#### Error messages

If dataserver is not successful, you cannot boot the server on that master device, and you see the following error message:

00:00000:00001:2001/04/16 19:02:39.53 kernel Use license file /var/sybase/SYSAM-1\_0/licenses/license.dat.

00:00000:00001:2001/04/16 19:02:39.54 kernel The master device's configuration area appears to be corrupt. The server needs this data to boot, and so cannot continue. The server will shut down.

If you run dataserver with a user-specified configuration file that includes options that make it impossible to allocate a shared segment and start up a server, dataserver fails with an error message, and you cannot boot the server on that master device:

00:00000:00001:2001/04/16 19:04:01.11 kernel Use license file /var/sybase/SYSAM-1\_0/licenses/license.dat.

00:00000:2001/02/09 19:04:01.25 kernel Using config area from primary master device.

00:00000:00001:2001/04/16 19:04:01.36 server The value of the 'max total\_memory' parameter (33792) defined in the configuration file is not high enough to set the other parameter values specified in the configuration file. 'max total\_memory' should be greater than the logical memory '34343'.

### Starting an existing Adaptive Server

#### Start an existing Adaptive Server

• Issue dataserver without the -b and -z options:

dataserver -d /sybase/masterdb.dat

## Upgrade to a server with larger page sizes

Adaptive Servers earlier than version 12.5 used 2K logical page sizes. You cannot change an installation's page size by upgrading. That is, if your current Adaptive Server uses 2K logical pages, you can upgrade only to an Adaptive Server that uses 2K logical pages.

However, you can migrate databases with 2K logical pages from earlier versions of Adaptive Server. For information on how to use the sybmigrate data migration tool, see Chapter 9, "Migration Utility."

## View the current server limits

To display information about Adaptive Server's limits:

• dbcc serverlimits includes the size of your server's logical page size in its output. For example, enter:

dbcc serverlimits

- Search for the string "logical page size" in the error log.
- The global variable @ @ maxpagesize displays the server's logical page size. At the isql prompt, issue:

select @@maxpage size ------8192

# Using Interactive isql from the Command Line

This chapter describes the command line SQL utility, isql.

Торіс	Page
Before you begin	9
Starting and stopping isql	9
How to use Transact-SQL in isql	10
Changing the command terminator	
Performance statistics interaction with command terminator values	14
Setting the network packet size	15
Input and output files	15

For a detailed description of isql syntax, see isql on page 205.

# Before you begin

If you are running Open Client version 11.1 or later and are using an external Sybase configuration file, you must add the following in your configuration file to enable isql:

[isql]

# Starting and stopping isql

#### Starting isql

1 Enter this command at the operating-system prompt:

isql

2 When the prompt appears, enter your password.

The password does not appear on the screen as you type. The isql prompt appears:

1>

You can now issue Transact-SQL commands.

#### Stopping isql

- Enter either of these commands on a line by itself:
  - quit exit

## How to use Transact-SQL in isql

isql sends Transact-SQL commands to Adaptive Server, formatting the results and printing them to standard output. There is no maximum size for an isql statement. For more information about using Transact-SQL, see the *Transact-SQL User's Guide*.

**Note** To use Transact-SQL directly from the operating system with the isql utility program, you must have an account, or login, on Adaptive Server.

To execute a Transact-SQL command, type the default command terminator "go" on a new line.

For example:

```
isql
Password:
1> use pubs2
2> go
1> select *
2> from authors
3> where city = "Oakland"
4> go
```

## Formatting isql output

The width for isql output is adjusted according to the character set expansion or the character width, and displays a output column of the maximum possible bytes. For example, for the UTF8 character set, each character may use at most four bytes, so the output column width is the character number multiplied by four. However, the output column width can not be larger than the column defined value, and the column width is calculated using this formula:

Min(character\_number X max\_character\_width, column\_defined\_width).

For example, if a column co11 is defined as varchar(10), then left(col1, 2) returns a width of eight, or four bytes per character. A value of left(col1,5) returns a width or 10, and cannot be larger than the defined length, even though, according to the formula, 5 X 4 equals 20).

Table 2-1 describes the options that change the format of isql output:

Option	Default	Meaning
-h headers	1	Number of rows to print between column headings
-s colseparator	Single space	Changes the column separator character
-w columnwidth	80 characters	Changes the line width
-е		Includes each command issued to isql in the output
-n		Removes numbering and prompt symbols.

Table 2-1: Format options for isql

In this example, the query's results are placed in a file called *output*:

```
isql -Uuser_name -Ppassword -Sserver -e -n -o output
use pubs2
go
select *
```

```
select *
from authors
where city = "Oakland"
go
quit
```

To view the contents of *output*, enter:

• In Windows:

type output

• In UNIX platforms:

cat output

select \*

```
from authors
where city = "Oakland"
                              address
au id
       au lname
                 au fname phone
         state country postalcode
  city
_____
----- -----
213-46-8915 Green Marjorie 415 986-7020 309 63rd St. #411
   Oakland CA USA 94618
274-80-9391 Straight Dick 415 834-2919 5420 College Av.
  Oakland CA USA 94609
724-08-9931 Stringer Dirk 415 843-2991 5420 Telegraph Av.
   Oakland CA USA 94609
724-80-9391 MacFeather Stearns 415 354-7128 44 Upland Hts.
   Oakland CA USA 94612
756-30-7391 Karsen
               Livia 415 534-9219 5720 McAuley St.
  Oakland CA USA 94609
```

**Note** The *output* file does not include the command terminator.

## **Correcting input**

If you make an error when typing a Transact-SQL command, you can:

- Press Ctrl-c or type the word "reset" on a line by itself this clears the query buffer and returns the isql prompt.
- Type the name of your text editor on a line by itself this opens a text file where you can edit the query. When you write and save the file, you are returned to isql and the corrected query appears. Type "go" to execute it.

## set options that affect output

Table 2-2 lists the set options that affect Transact-SQL output. For more information, see set in the *Reference Manual*.

set option	Default	Meaning
char_convert	Off	Turns character-set conversion off and on between Adaptive Server and a client; also starts a conversion between the server character set and a different client character set.

Table 2-2: set options that affect Transact-SQL output

set option	Default	Meaning
fipsflagger	Off	Warns when any Transact-SQL extensions to entry-level SQL92 are used. This option does not disable the SQL extensions. Processing completes when you issue the non-ANSI SQL command.
flushmessage	Off	Sends messages as they are generated.
language	us_english	Sets the language for system messages.
nocount	Off	Turns off report of number of rows affected.
noexec	Off	Compiles each query but does not execute it; often used with showplan.
parseonly	Off	Checks the syntax of queries and returns error messages without compiling or executing the queries.
showplan	Off	Generates a description of the processing plan for a query; does not print results when used inside a stored procedure or trigger.
statistics io	Off	Displays performance statistics after each execution.
statistics time		
statistics	Off	Displays the number of cache hits, misses, and rows in the subquery cache for each
subquerycache		subquery.
textsize	32K	Controls the number of bytes of text or image data returned.

# Changing the command terminator

If you include the command terminator argument (-c), you can choose your own terminator symbol; go is the default value for this option. Always enter the command terminator without blanks or tabs in front of it.

For example, to use a period as the command terminator, invoke isql as follows:

```
isql -c.
```

A sample isql session with this command terminator looks like this:

```
1> select name from sysusers
2> .
name
------
sandy
kim
leslie
(3 rows affected)
```

Using the isql command terminator option with scripts requires advance planning:

- Adaptive Server supplies scripts, such as installmaster, use "go". Do not change the command terminator for any session that uses these scripts.
- Your own scripts may already have "go" in them. Remember to update your scripts to include the terminator you plan to use.

# Performance statistics interaction with command terminator values

isql provides a performance statistics option (-p).

For example, this syntax returns the following statistics:

```
isql -p
1> select * from sysobjects
2> go
Execution Time (ms.): 1000 Clock Time (ms.): 1000
1 xact:
```

This means that a single transaction took 100 milliseconds. The clock time value reflects the entire transaction, which starts when Client-Library<sup>TM</sup> builds the query and ends when Client-Library returns the information from Adaptive Server.

You can gather performance statistics based on the execution of one or more transactions. To gather statistics on more than one transaction, specify a number after the command terminator.

For example, the following command instructs Adaptive Server to execute three select \* transactions and report the performance statistics:

```
isql -p
1> select * from sysobjects
2> go 3
Execution Time (ms.): 1000 Clock Time (ms.): 1000
Execution Time (ms.): 1000 Clock Time (ms.): 2000
Execution Time (ms.): 1000 Clock Time (ms.): 1000
Execution Time (ms.): 1000 Clock Time (ms.): 4000
3xact:
```

## Setting the network packet size

Setting the correct network packet size can greatly increase the performance of Adaptive Server.

The -A size option specifies the network packet size to use for an isql session. The default value is 2048 bytes. To set the packet size to 4096 bytes for the current isql session, enter:

isql -A 4096

To check your network packet size, type:

select \* from sysprocesses

The value for this isql session appears under the network\_pktsz heading in the sysprocesses table.

See the *System Administration Guide* for more information about setting the network packet size.

## Input and output files

You can specify input and output files on the command line with the -i and -o options.

isql does not provide formatting options for the output. However, you can use the -n option to eliminate the isql prompts and other tools to reformat the output.

If you use the -e option, isql echoes the input to output. The resulting output file contains both the queries and their results.

### **UNIX command line redirection**

The UNIX redirection symbols, "<" and ">", provide a similar mechanism to the -i and -o options, as follows:

isql -Usa < input > output

You can direct is to take input from the terminal, as shown in this example:

isql -Usa -Ppassword -Sserver\_name << EOF > output
use pubs2
go

```
select * from table
go
EOF
```

"<<EOF" instructs isql to take input from the terminal up to the string "EOF." You can replace "EOF" with any character string. Similarly, the following example signals the end of input with Ctrl-d:

```
isql -Usa << > output
```

# Using Interactive SQL in Graphics Mode

This chapter discusses how to run and use the GUI-based Interactive SQL utility.

Торіс	Page
Starting Interactive SQL	18
The main Interactive SQL window	19
The Interactive SQL toolbar	21
Open multiple windows	21
Keyboard shortcuts	21
Using Interactive SQL to display data	22
Edit table values in Interactive SQL	23
SQL statements in Interactive SQL	26
Configure Interactive SQL	30
Run command files	35
The SQL escape syntax in Interactive SQL	37
Interactive SQL commands	38

Interactive SQL allows you to execute SQL statements, build scripts, and display database data to the server. You can use it to:

- Browse the information in a database.
- Test SQL statements that you plan to include in an application.
- Load data into a database and carrying out administrative tasks.

In addition, Interactive SQL can run command files or script files. For example, you can build repeatable scripts to run against a database and then use Interactive SQL to execute these scripts as batches.

# **Starting Interactive SQL**

The menu item Open Interactive SQL opens a connection to a server. However, when you select the menu item for a server, Interactive SQL opens a connection to the default database for that server. When you select a specific database from the Open Interactive SQL menu, Interactive SQL opens to the selected database.

#### \* Starting Interactive SQL from Sybase Central

- To start Interactive SQL, either:
  - Select a database in Sybase Central and select File | Open Interactive SQL. Interactive SQL connects to the database. You can also right-click on the database and select Open Interactive SQL.
  - To start Interactive SQL without a connection to a server, select Tools | Adaptive Server Enterprise | Open Interactive SQL. The Connect dialog appears.

#### Starting Interactive SQL from the command line

How you start Interactive SQL from the command line depends on your operating system.

- If you start Interactive SQL independently, the Connect dialog appears, which lets you connect to a database just as you would in Sybase Central.
  - For UNIX, Sybase Central and Interactive SQL do not have to be installed under \$SYBASE (\$SYBASE does not even need to exist for them to start). Instead, they are installed under \$SYBROOT, an environment variable set by the installer. Move to \$SYBROOT and enter:

dbisql

On Windows, change to the %SYBROOT directory and enter:

dbisql.bat

• In the Connection dialog, enter the information to connect to a database in the Connect dialog box and click OK.

To open a new Interactive SQL window:

- 1 Choose Window | New Window. The Connect dialog appears.
- 2 In the Connect dialog, enter connection options, and click OK to connect.

The connection information (including the database name, your user ID, and the database server) appears on the title bar above the SQL Statements pane.

You can also connect to or disconnect from a database with the Connect and Disconnect commands in the SQL menu, or by executing a connect or disconnect statement in the SQL Statements pane.

# The main Interactive SQL window

The Interactive SQL window includes these panes:

- SQL Statement provides a place for you to type SQL statements.
- Results displays the results of commands that you execute. For example, if you use SQL statements to search for specific data in the database, the Results tab in this pane displays the columns and rows that match the search criteria. If the information exceeds the size of the pane, scroll bars automatically appear. You can edit the result set on the Results tab.
- Messages displays messages from the database server.
- Plan displays the query optimizer's execution plan for a SQL statement. For more information, see Plan dialog tab below.

The window title displays the connection name. For Adaptive Server, the connection name is either the server name (determined by the server's interfaces file entry) or the host name and port number the user enters at the time of connection.

## Plan dialog tab

The Plan tab displays a GUI representation of execution engine's plan for the currently running SQL text, and helps you understand the performance and statistic characteristics of the currently running query.

**Note** The Plan tab only appears if you connect to Adaptive Server version 15.0 and later.

The top half of the Plan tab shows the logical flow of the operators used in the plan in a tree-based, hierarchal structure, with each operator a separate node of the tree. The cost of each operator is based on the cost model used by the query processor. Each operator node in the tree is costed relative to other nodes, which makes it easier to identify operators based on their costs.

Each node includes tooltip text (text that appears when you move your mouse over the node) that provides details about each operator, so you do not have to select the nodes to compare details between operators.

The Plan tab includes the following tabs:

- Details shows the details of the operator statistics as two tables:
  - Node Statistics shown for all the operators, and includes statistics like row count, logical I/O, and physical I/O.
  - Subtree Statistics the aggregate sum of all the operators below, and are shown for the non-leaf operators, and include statistics on row count, logical I/O, and physical I/O.
- XML shows the result set as XML output.
- Text displays the text version of the query plan (the same as the output of showplan).
- Advanced includes the following:
  - Abstract query plan shows the abstract query plan used by the query.
  - Resource utilization describes the resources used by the plan, including number of threads and the auxiliary session descriptors (SDESs, every table scan requires one session descriptor to track the scan).
  - Cost lists costs associated with the plan, including logical I/O, Physical I/O, and CPU usage.
  - Optimizer Metrics lists the query-plan statistics, including the run time for the query, run time for the first plan, the number of plans evaluated, the number of plans that were valid, and the amount of procedure cache used.
  - Optimizer Statistics lists the last time you ran update statistics on the table, any missing histogram steps, and the density of the steps.

# The Interactive SQL toolbar

The Interactive SQL toolbar appears at the top of the Interactive SQL window. Use the buttons on this toolbar to:

- Recall the executed SQL statement immediately before your current position in the history list.
- View a list of up to 50 previously executed SQL statements.
- Recall the executed SQL statement immediately after your current position in the history list.
- Execute the SQL statement currently appearing in the SQL Statements pane.
- Interrupt the execution of the current SQL statement.

# **Open multiple windows**

You can open multiple Interactive SQL windows. Each window corresponds to a separate connection. You can connect simultaneously to two (or more) databases on different servers, or you can open concurrent connections to a single database.

# **Keyboard shortcuts**

Interactive SQL provides the following keyboard shortcuts.

Function	Description
ALT+F4	Exits Interactive SQL.
ALT+LEFT CURSOR	Displays the previous SQL statement in the history list.
ALT+RIGHT CURSOR	Displays the next SQL statement in the history list
CTRL+C	Copies the selected row(s) and column headings to the clipboard.
CTRL+END	Moves to the bottom of the current pane.
CTRL+F6	Cycles through the open Interactive SQL windows.
CTRL+H	Displays the history of your executed SQL statements during the current session.
CTRL+HOME	Moves to the top of the current pane.

#### Table 3-1: Keyboard shortcuts

#### Using Interactive SQL to display data

Function	Description
CTRL+N	Clears the contents of the Interactive SQL window.
CTRL+Q	Displays the Query Editor, which helps you build SQL queries. When you have finished
	building your query, click OK to export it back into the SQL Statements pane.
CTRL+S	Saves the contents of the SQL Statements pane.
SHIFT+F5	Refreshes the plan without executing the statement in the SQL Statements pane. This
	allows you to see the plan for a statement without altering table data.
ESC	Clears the SQL Statements pane.
F2	Allows you to edit the selected row in the result set. You can use the Tab key to move
	from column to column within the row.
F5	Executes all text in the SQL Statements pane. You can also perform this operation by
	clicking the Execute SQL Statement button on the toolbar.
F7	Displays the Lookup Table Name dialog. In this dialog, you can find and select a table
	and then press Enter to insert the table name into the SQL Statements pane at the cursor position. Or with a table selected in the list press F7 again to display the columns in
	that table. You can then select a column and press Enter to insert the column name into
	the SQL Statements pane at the cursor position.
F8	Displays the Lookup Procedure Name dialog. In this dialog, you can find and select a
	procedure, then press Enter to insert the procedure name into the SQL Statements pane
	at the cursor position.
F9	Executes the selected text in the SQL Statements pane. If no text is selected, all of the
	statements are executed.
Page down	Moves down in the current pane.
Page up	Moves up in the current pane.

# Using Interactive SQL to display data

Interactive SQL allows you to browse the information in databases.

You can display database information using the select statement in Interactive SQL. Once you enter the statement, click the Execute SQL Statement button on the toolbar.

After you execute the statement, the result set appears in the Results pane. You can use the scroll bars to see areas of the table that are outside your current view of the pane.

#### \* Listing all the columns and rows of the *authors* table

1 Start Interactive SQL and connect to the pubs2 database.

2 Enter the following in the SQL Statements pane:

select \* from authors

3 On the toolbar, click the Execute SQL Statement button.

You can add, delete, and update rows within the result set.

## Edit table values in Interactive SQL

Once you execute a query in Interactive SQL, you can edit the result set to modify the database. You can also select rows from the result set and copy them for use in other applications. Interactive SQL supports editing, inserting, and deleting rows. These actions have the same result as executing update, insert, and delete statements.

Before you can copy, edit, insert, or delete rows, you must execute a query in Interactive SQL that returns a result set on the Results tab in the Results pane. When you edit the result set directly, Interactive SQL creates and executes a SQL statement that makes your change to the database table.

To edit a row or value in the result set, you must have the proper permissions on the table or column you want to modify values from. For example, to delete a row, you must have delete permission for the table the row belongs to.

Editing the result set may fail if you:

- Attempt to edit a row or column you do not have permission on.
- Select columns from a table with a primary key, but do not select all of the primary key columns.
- Attempt to edit the result set of a join (for example, there is data from more than one table in the result set).
- Enter an invalid value (for example, a string in a numeric column or a NULL in a column that does not allow NULLs).

When editing fails, an Interactive SQL error message appears explaining the error, and the database table values remain unchanged.

Once you make changes to table values, you must enter a commit statement to make the changes permanent. To undo your changes, you must execute a rollback statement.

## Copy rows from the Interactive SQL result set

You can copy rows directly from the result set in Interactive SQL and then paste them into other applications. Copying rows also copies the column headings. Copied data is comma-delimited, which allows other applications, such as Microsoft Excel, to format the copied data correctly. By default, copied data is in ASCII format, and all strings are enclosed in single quotes. You can select only consecutive rows in the result set.

#### \* Copying rows from the Interactive SQL result set

- 1 Select the rows you want to copy. To select a row(s):
  - Press and hold the Shift key while clicking the row(s), or
  - Press and hold the Shift key while using the Up or Down arrow.
- 2 Right-click the result set and select Copy from the pop-up menu. You can also copy the selected row(s) by pressing CTRL+C.

The selected row(s), including their column headings, are copied to the clipboard. You can paste them into other applications by selecting Edit | Paste or by pressing CTRL+V.

## Edit table values from the Interactive SQL result set

The Edit command allows you to change individual values within a row. You can change any or all of the values within existing rows in database tables. You must have update permission on the columns being modified. When you edit the result set, you can make changes to the values in only 'one row at a time.

#### Editing a row in the result set

- 1 Select the row to edit
- 2 Right-click the result set and choose Edit from the pop-up menu. You can also press F2 to edit the result set.
- 3 A blinking cursor appears in the first value in the row.
- 4 Press Tab to move the cursor from column to column across the row. You can also edit a value by clicking the value in the selected row.
- 5 Enter the new value.
- 6 You cannot enter invalid datatypes into a column. For example, you cannot enter a string datatype into a column that is configured for the int datatype.

7 Execute a commit statement to make your changes to the table permanent.

## Insert rows into the database from the Interactive SQL result set

The Insert command adds a new blank row to the database table. Use the Tab key to move between columns in the result set to add values to the row. When you add values to the table, characters are stored in the same case as they are entered. You must have insert permission on the table to add new rows (for information about insert permissions, see insert in the *Adaptive Server Commands and Reference Manual*.

#### Inserting a new row into the result set

1 Right-click the result set and choose Add from the pop-up menu.

A new blank row appears in the result set with a blinking cursor in the first value in the row.

Press Tab to move the cursor from column to column across the row. You can also insert a value by clicking on the appropriate field in the selected row.

2 Enter the new value.

You cannot enter invalid datatypes into a column. For example, you cannot enter a string into a column that accepts the int datatype.

3 Execute a commit statement to make your changes to the table permanent.

### Delete rows from the database using Interactive SQL

The Delete command removes the selected rows from a database table. You must have delete permission on the table to delete rows.

#### Deleting a row from the result set

- 1 Select the row(s) you want to delete. To select a rows:
  - Press and hold the Shift key while clicking the rows.
  - Press and hold the Shift key while using the Up or Down arrow.

To delete non-consecutive rows, you must delete each row individually.

2 Right-click the result set and choose Delete from the pop-up menu. You can also delete the selected row(s) by pressing the Delete key.

The selected row(s) are removed from the database table.

3 Execute a commit statement to make your changes to the table permanent.

# SQL statements in Interactive SQL

You can enter all SQL statements as commands in the top pane of the Interactive SQL window. When you are finished typing, execute the statement to run it.

#### Executing a SQL statement

- Press the Execute SQL Statement button, or
- Select F5.

To clear the SQL Statements pane, choose Edit | Clear SQL or press ESCAPE.

**Note** If you are running a long-running query, Interactive SQL displays a splash screen that describes some diagnostic tips.

## **Canceling an Interactive SQL command**

Use the Interrupt button on the Interactive SQL toolbar to cancel a command.

A Stop operation stops current processing and prompts for the next command. If a command file was being processed, you are prompted for an action to take (Stop Command File, Continue, or Exit Interactive SQL). You can control these actions with the Interactive SQL ON\_ERROR option.

When an interruption is detected, one of three different errors is reported, depending on when the interruption is detected. If the interruption is detected:

• When Interactive SQL is processing the request (as opposed to the database server), this message appears

ISQL command terminated by user

Interactive SQL stops processing immediately and the current database transaction is not updated.

• By the database server while processing a data manipulation command (select, insert, delete, or update), this message appears:

Statement interrupted by user.

The effects of the current command are left unfinished, but the rest of the transaction is left intact.

• While the database server is processing a data definition command (create *object*, drop *object*, alter *object*, and so on.), this message appears:

Terminated by user -- transaction rolled back

Since data definition commands all perform a commit automatically before the command starts, rollback simply cancels the current command.

This message also occurs when the database server is running in bulk operations mode executing a command that modifies the database (insert, update, and delete). In this case, rollback cancels not only the current command, but everything that has been done since the last commit. In some cases, it may take a considerable amount of time for the database server to perform the automatic rollback.

## Combining multiple statements

Interactive SQL allows you to enter multiple statements at the same time. End each statement with the Transact-SQL command, go.

1 Enter multiple statements in the SQL Statements pane separated by go:

```
update titles
set price = 21.95
where pub_id = "1389"
go
update titles
set price = price + 2.05
where pub_id = "0736"
go
update titles
set price = price+2.0
where pub_id = "0877"
go
```

2 On the toolbar, click the Execute SQL Statement button (or select F9). All three statements are executed. After execution, the commands remain in the SQL Statements pane. To clear this pane, press the Esc key.

You can roll back your changes by entering rollback and executing the statement.

## Looking up tables, columns, and procedures

**Note** You must have jConnect for JDBC installed to use the functionality described in this section.

Select Tools | Lookup Table Name and Tools | Lookup Procedure Name utilities to look up the names of tables, columns, or procedures stored in the current database and insert them at your cursor position.

Enter the first characters of a table, column, or procedure in the Lookup Table Name and Lookup Procedure Name dialogs. This list narrows to display only those items that start with the text you entered.

You can use the standard SQL wildcard character % to mean "match anything". Clear the search area to display all items.

#### Looking up names of tables in the database

- 1 Choose Tools | Lookup Table Name.
- 2 Find and select the table.
- 3 Click OK to insert the table name into the SQL Statements pane.

#### Looking up column names in the database

- 1 Choose Tools | Lookup Table Name.
- 2 Find and select the table containing the column.
- 3 Click Show Columns.
- 4 Select the column and click OK to insert the column name into the SQL Statements pane.

#### Looking up procedure names in the database

- 1 Choose Tools | Lookup Procedure Name.
- 2 Find and select the procedure.
3 Click OK to insert the procedure name into the SQL Statements pane.

#### **Recall commands**

When you execute a command, Interactive SQL automatically saves it in a history list that lasts for the duration of the current session. Interactive SQL maintains a record of as many as 50 of the most recent commands. You can view the entire list of commands in the Command History dialog.

To access the Command History dialog, press Ctrl+H, or select the book icon in the toolbar.

The most recent commands appear at the bottom of the list. To recall a command, highlight it and click OK. It appears in the SQL Statements pane.

You can also recall commands without the Command History dialog. Use the arrows in the toolbar to scroll back and forward through your commands, or press Alt+Right Arrow and Alt+Left Arrow.

You can save commands in text files and use them in a subsequent Interactive SQL session.

#### Log commands

With the Interactive SQL logging feature, you can record commands as you execute them. Interactive SQL continues to record until you stop the logging process, or until you end the current session. The recorded commands are stored in a log file.

#### Beginning to log Interactive SQL commands

- 1 Choose SQL | Start Logging.
- 2 In the Save dialog, specify a location and name for the log file.
- 3 Click Save when finished.

To stop logging Interactive SQL commands, select SQL | Stop Logging.

To start logging by typing in the SQL Statements pane, enter and execute start logging "c:\file\_name.sql", where c:\file\_name.sql is the path, name, and extension of the log file. A log file must have the .sql extension. Include the single quotation marks if the path contains embedded spaces. To stop logging, enter and execute stop logging.

**Note** The commands start logging and stop logging are not Transact-SQL commands, and are not supported by Adaptive Server outside the Interactive SQL dialog box.

Once you start logging, all commands that you try to execute are logged, including ones that do not execute properly.

# **Configure Interactive SQL**

You can configure Interactive SQL in the Options dialog, which provides settings for commands, appearance, import/export features, and messages.

After you have made your selections, select either OK or Make Permanent. If you select Make Permanent, Interactive SQL starts with the configuration you selected.

You can set each option either by using the GUI, or by using the set option statement.

To access the Options dialog, choose Tools | Options.

### General dialog box

The General dialog box includes these components:

• Commit – lets you select when transactions are committed. You can commit transactions automatically after each statement is executed or only when you exit your Interactive SQL session.

You can also commit manually by entering an explicit commit command whenever appropriate. The default behavior is that transactions are committed when you exit Interactive SQL.

	<ul> <li>Command files – determine how Interactive SQL acts when an error occurs. When an error occurs:</li> </ul>
	• Continue – Interactive SQL displays the error message in the Results pane but does not exit. Correct the problem, then reissue the command.
	• Exit – Interactive SQL exits when an error occurs.
	• Notify and Continue – Interactive SQL displays the error message in a dialog box and describes the error but does not exit
	<ul> <li>Notify and Exit – Interactive SQL displays the error message in a dialog box, describes the error, and exits.</li> </ul>
	<ul> <li>Notify and stop – Interactive SQL displays the error message and describes the error.</li> </ul>
	• Prompt – the default setting. Interactive SQL displays a message box asking if you want to continue.
	• Stop – Interactive SQL displays the error message in the Results pane. Correct, then reissue the command.
	Echo Command Files to Log – when you enable logging, this option causes SQL statements executed from script files (or command files) to be copied to the log along with the SQL statements entered interactively. If you disable this option, only SQL statements entered interactively are copied to the log when you start logging.
Folders	Determines in which directory the browser should start looking for files. Select either "Last folder used" or "Current folder."

## **Result dialog box**

The Results dialog box has these components:

- Display null values lets you specify how you want nulls to appear in the table columns when you browse data. The default setting is (NULL).
- Maximum number of rows to display limits the number of rows that appear. The default setting is 500.
- Truncation length limits the number of characters that appear in each column in the Results pane in Interactive SQL. The default setting is 30.

• Show multiple result sets – enables or disables the display of multiple result sets. For example, you can use this feature when you create a procedure containing multiple select statements. If this option is enabled, you can see each result set on a separate tab in the Results pane when you call the procedure.

If you are using the jConnect driver, choosing to display multiple result sets requires Interactive SQL to wait for an entire result set to be retrieved before any rows appear. This may result in longer waits for large result sets. This option is off by default.

- Show row number check if you want the row numbers displayed in the result set.
- Automatically refetch result enables or disables the ability of Interactive SQL to automatically regenerate the most recent result set after you execute an insert, update, or delete statement. For example, if you are updating a table with the Results tab in the Results pane displaying the rows about to be affected, this option causes Interactive SQL to automatically refresh the Results tab to reflect the executed changes. This option is on by default.
- Console Mode select how you want the result sets displayed in the console; only the last result sets, all result sets, or no result sets.
- Font select which font you want to use for the result set.

## Import/Export dialog box

The Import/Export dialog box has these components:

- Default export format select the default file format for exporting. This format is automatically selected in the Files of Type field in the Save dialog, but you can still choose other formats. The default is also used when Interactive SQL interprets an output statement if no format is specified. The default setting is ASCII.
- Default import format select the default file format for importing. This format is automatically selected in the Files of Type field in the Open dialog, but you can still choose other formats. The default is also used when Interactive SQL interprets an input statement if no format is specified. The default setting is ASCII.

• ASCII options – specify the default symbols that are used for the field separator, quote string, escape character, and the default encoding datatype when you import or export data in the ASCII format. The default settings are the comma (,) for the field separator, an apostrophe (i) for the quote string, and a backslash (\) for the escape character.

By default, Interactive SQL uses the default datatype of the server.

### Messages dialog tab

The Messages dialog box has these components:

- Measure execution time for SQL statements enables or disables the ability of Interactive SQL to measure the time it takes for a statement to execute. When this option is enabled (which is the default), the time appears in the Messages pane.
- Show separate Messages pane lets you specify where information from the database server appears. By default, messages appear on the Messages tab in the Results pane. If you select this option, database server information appears in a separate Messages pane in the Interactive SQL window.
- Default number of lines in Messages pane lets you specify the initial height (in lines) of the Messages pane. The default is 7 lines.

### Editor

The Editor dialog box has these components:

- Editor Select your scrollbar style preference: vertical, horizontal, or both.
- Tabs This pane determines how tabs are used in your SQL text:
  - Tab size enter the number of spaces you want each tab to comprise.
  - Indent size Enter the number of spaces for each indent.
  - Tab radio buttons Select Insert spaces to convert tabs to spaces when you indent SQL text. Select Keep tabs to retain tabs as spaces when you indent SQL text.
  - Auto indent Select:

- None if you do not want to automatically indent SQL text
- Default to use the default tab and indent settings
- Smart if you want Interactive SQL to automatically indent SQL text. Select Indent open brace to indent open braces or Indent closing brace to indent the closing braces. Interactive SQL displays how these decisions affect the text in the window below the buttons.
- Format Determines the look of your SQL text.
  - Text Highlighting select the type of text you want to highlight from the list (keywords, comments, strings, and so on).
  - Foreground select the foreground color of the text.
  - Background select the color of the text's background field.
- Style
  - Font size select the size font.
  - Caret color determines the color of the caret.
  - Reset All returns all styles to original selections.
- Print Customizes your printed jobs:
  - Header enter the header text.
  - Footer enter the footer text.
  - Font size select the font size.

### **Query Editor**

The Query Editor dialog box has these components:

- Fully qualify table and column names select this to have Interactive SQL prefix table names with the owner (for example, dbo.authors) and prefix column names with the owner and table names (for example, dbo.titles.price).
- Quote names Select this to automatically put quotes around table and columns names to avoid conflicts with reserved words.
- Get list of tables on startup Select this to automatically get a list of tables in the database when the query editor is started.

## **Run command files**

This section describes how to process files consisting of a set of commands.

#### Write output to a file

In Interactive SQL, the output for each command remains in the Results pane until the next command is executed. To keep a record of your data, you can save the output of each statement to a separate file.

If statement1 and statement2 are two select statements, then you can output them to file1 and file2, respectively, as follows:

```
Statement1; OUTPUT TO file1
go
statement2; OUTPUT TO file2
go
```

For example, the following command saves the result of a query:

```
select * from titles
go
output to "C:\My Documents\Employees.txt"
```

#### **Execute command files**

You can execute command files by:

• Using the Interactive SQL read command to execute command files. The following statement executes the file temp.sql:

read temp.SQL

 Loading a command file into the SQL Statements pane and execute it directly from there.

You load command files back into the SQL Statements pane by choosing File | Open. Enter *transfer.sql* when prompted for the file name.

• Supplying a command file as a command-line argument for Interactive SQL.

The SQL Statements pane in Interactive SQL has a limit of 500 lines. For command files larger than this, you should use a generic editor capable of handling large files and use the read command to import it into Interactive SQL, which has no limit on the number of lines it can read.

#### Save, load, and run command files

You can save the commands currently present in the SQL Statements pane so they are available for future Interactive SQL sessions. The file in which you save them is called a command file.

Command files are text files containing SQL statements. You can use any editor you like to create command files. You can include comment lines along with the SQL statements to be executed. These command files are commonly called scripts.

When you begin a new session, you can load the contents of a command file into the SQL Statements pane, or you can run the contents immediately.

#### Saving the commands from the SQL Statements pane to a file

- 1 Choose File | Save.
- 2 In the Save dialog, specify a location, name, and format for the file. Click Save when finished.
- Loading commands from a file into the SQL Statements pane
  - 1 Choose File | Open
  - 2 In the Open dialog, find and select the file. Click Open when finished.

#### Running a command file immediately

- 1 Choose File | Run Script.
- 2 The Run Script menu item is the equivalent of a read statement. For example, in the SQL Statements pane, you can also run a command file by typing the following, where *c:\filename.sql* is the path, name, and extension of the file. Single quotation marks (as shown) are required only if the path contains spaces:

READ "c:\filename.sql"

3 In the Open dialog, find and select the file. Click Open when finished.

The Run Script menu item is the equivalent of a READ statement. For example, in the SQL Statements pane, you can also run a command file by typing the following, where *c:\filename.sql* is the path, name, and extension of the file. Single quotation marks (as shown) are required only if the path contains spaces:

READ 'c:\filename.sql'

# The SQL escape syntax in Interactive SQL

Interactive SQL supports JDBC escape syntax. This escape syntax allows you to call stored procedures from Interactive SQL regardless of the database management system you are using. The general form for the escape syntax is:

{{ keyword parameters }}

The braces must be doubled. This doubling is specific to Interactive SQL. There must not be a space between successive braces: "{{" is acceptable, but "{ {" is not. As well, you cannot use newline characters in the statement. The escape syntax cannot be used in stored procedures because they are not executed by Interactive SQL.

You can use the escape syntax to access a library of functions implemented by the JDBC driver that includes number, string, time, date, and system functions.

For example, to obtain the name of the current user in a database management system-neutral way, you would type the following:

select {{ fn user() }}

The functions that are available depend on the JDBC driver that you are using. The numeric functions that are supported by jConnect are:

abs	cos	log10	sign
acos	cot	pi	sin
asin	degrees	power	sqrt
atan	exp	radians	tan
atan2	floor	rand	
ceiling	log	round	

The string functions that are supported by jConnect are:

ascii	difference	repeat	space
char	lcase	right	substring
concat	length	soundex	ucase

The system functions that are supported by jConnect are:

database	ifnull	user	convert
aalababb	innan	acon	00111011

The system functions that are supported by jConnect are:

curdate	dayofweek	monthname	timestampadd
curtime	hour	now	timestampdiff
dayname	minute	quarter	year

dayofmonth month

A statement using the escape syntax should work in Adaptive Server Anywhere, Adaptive Server Enterprise, Oracle, SQL Server, or another database management system that you are connected to from Interactive SQL. For example, to obtain database properties with the sa\_db\_info procedure using SQL escape syntax, type the following in the SQL Statements pane in Interactive SQL:

second

((CANN sa\_db\_info(1)))

# Interactive SQL commands

Interactive SQL includes a set of commands that are entered in the top pane of the Interactive SQL display. These commands are intended only for Interactive SQL and are not sent to Adaptive Server for execution. The commands available for Interactive SQL are:

Command	Description
clear	Clears the Interactive SQL panes.
configure	Opens the Interactive SQL Options dialog.
connect	Establishes a connection to a database.
disconnect	Drops the current connection to a database.
exit	Leaves Interactive SQL.
input	Imports data into a database table from an external file or from the keyboard.
output	Imports data into a database table from an external file or from the keyboard.
parameters	Specifies parameters to an Interactive SQL command file.
read	Reads Interactive SQL statements from a file.
set connection	Changes the current database connection to another server.
set option	Use this statement to change the values of Interactive SQL options.
start logging	Use this statement to start logging executed SQL statements to a log file.
stop logging	Use this statement to stop logging of SQL statements in the current session.
system	Use this statement to launch an executable file from within Interactive SQL.

See "Using DBISQL Commands" in the Reference Manual: Commands.

# Transfer Data to and from Adaptive Server with *bcp*

This chapter explains how to use the bulk copy utility, bcp, to move data between Adaptive Server and an operating system file.

Торіс	Page	
Methods for moving data	40	
bcp requirements	41	
bcp modes	43	
Copy data to a file	43	
Bulk copying encrypted data	44	
bcp performance	46	
Using the bcp options	59	
Change the defaults in interactive bcp	62	
Format files	71	
Examples of copying out data interactively	76	
Examples of copying in data interactively	79	
bcp and alternate languages	82	
Support for initialization strings	83	
bcp and row-level access rules	83	
Copy in and batch files	84	
Copy out and text and image data	85	
Specify a network packet size		
Copy in and error files	86	
Copy out and error files	87	
Data integrity for defaults, rules, and triggers	88	
How bcp differs from other utilities	88	

bcp provides a convenient, high-speed method for transferring data between a database table or view and an operating system file. bcp can read or write files in a wide variety of formats. When copying in from a file, bcp inserts data into an existing database table; when copying out to a file, bcp overwrites any previous contents of the file.

For a detailed description of bcp syntax, see bcp on page 126.

Versions earlier than 15.0.3 did not allow you to run fast bcp on tables with non-clustered indexes or triggers. Cluster Edition version 15.0.3 and later removes this restriction.

# Methods for moving data

You can use the following methods to move data to and from your Adaptive Server databases:

- bcp as a standalone program from the operating system. This chapter provides instructions for this method.
- Client-Library, which calls bulk library routines. For more information about the Client-Library, see the *Open Client and Open Server Common Libraries Reference Manual*.

## Import and export data with bcp

Transact-SQL commands cannot transfer data in bulk. For this reason, you must use bcp for any large transfers. You can use bcp to:

• Import data that was previously associated with another program, such as the records from another database management system. This is the most common use for bcp.

Before using bcp, you must create a file of the records you want to import. The general steps are:

- a Put the data to transfer into an operating system file.
- b Run bcp from the operating system command line.
- Move tables between Adaptive Servers or between Adaptive Server and other data sources that can produce an operating-system file.
- Copy out data from a view. See bcp on page 126 for a description of the syntax for using bcp to copy out from a view.

Note You cannot use bcp to copy in data to a view.

• Transfer data for use with other programs, for example, with a spreadsheet program. The general steps to transfer data are:

- a Use bcp to move the data from Adaptive Server into an operating-system file from which the other program imports the data.
- b When you finish using your data with the other program, copy it into an operating-system file, and then use bcp to copy it into Adaptive Server.

Adaptive Server can accept data in any character or binary format, as long as the data file describes either the length of the fields or the **terminators**, the characters that separate columns.

The structures in the tables involved in the transfer need not be identical, because when bcp:

- Imports from a file, it appends data to an existing database table.
- Exports to a file, it overwrites the previous contents of the file.

When the transfer is complete, bcp informs you of the:

- Number of rows of data successfully copied
- Number of rows (if any) that it could not copy
- Total time the copy took
- Average amount of time, in milliseconds, that it took to copy one row
- Number of rows copied per second.

If bcp runs successfully, you see a return status of 0. The return status generally reflects errors from the operating system level and correspond to the ones listed in the *errno.h* file in the */usr/include/sys/* directory.

# bcp requirements

Before using bcp, you need to provide it with basic data information and prepare both the data for transfer and the command to access the data.

Basic requirements

You must supply the following information to transfer data successfully to and from Adaptive Server:

- Name of the database and table or view
- Name of the operating system file
- Direction of the transfer (in or out)

You can also use bcp to modify the storage type, storage length, and terminator for each column if you want to do so.

Permissions You must have an Adaptive Server account and the appropriate permissions on the database tables or views, as well as the operating system files to use in the transfer to use bcp.

- To copy data into a table, you must have insert and select permission on the table.
- To copy a table to an operating system file, you must have select permission on the following tables:
  - the table to copy
  - sysobjects
  - syscolumns
  - sysindexes

Pretransfer tasks Before you can use bcp in, you must prepare the command and the data for transfer:

• To use either fast or slow bcp, set select into/bulkcopy/pllsort to true. For example, to turn on this option for the pubs2 database, you would enter:

sp\_dboption pubs2, "select into/bulkcopy/pllsort", true

For more information, see "bcp modes" on page 43.

• To use fast bcp, remove indexes on the target table. For more information about this requirement, see "bcp performance" on page 46.

In addition:

• If you are running Open Client version 11.1 or later and are using an external Sybase configuration file, you must add the following to enable bcp:

[BCP]

- You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use bcp.
- To use a previous version of bcp, you must set the CS\_BEHAVIOR property in the [bcp] section of the *ocs.cfg* file:

```
[bcp]
CS_BEHAVIOR = CS_BEHAVIOR_100
```

If CS\_BEHAVIOR is not set to CS\_BEHAVIOR\_100, you can use functionality for bcp 11.1 and later.

## bcp modes

bcp in works in one of two modes:

- Slow bcp logs each row insert that it makes, used for tables that have one or more indexes.
- Fast bcp logs only page allocations, copying data into tables without indexes or at the fastest speed possible. You can use fast bcp on tables with nonclustered indexes.

To determine the bcp mode that is best for your copying task, consider the:

- Size of the table into which you are copying data
- Amount of data that you are copying in
- Number of indexes on the table
- Amount of spare database device space that you have for re-creating indexes

**Note** Fast bcp might enhance performance; however, slow bcp gives you greater data recoverability.

# Copy data to a file

You can use bcp to copy data from a table to an operating system file. You can specify a table name and one or more partitions as the source. Data can be copied:

- To a single file for all partitions
- To a single file for each partition

If you do not specify a destination file name, Adaptive Server creates file names based on the partition names.

## **Examples**

In these examples, we are copying data from bigtable, which is partitioned three ways: ptn1, ptn2, and ptn3, to various operating system files.

To copy the data in bigtable to *file1*, enter:

bcp mydb..bigtable out file1

To copy the data from ptn1, ptn2, and ptn3 to *file2*, enter:

bcp mydb..bigtable partition ptn1, ptn2, ptn3 out file2

To copy the data from ptn1 and ptn2 to data files *ptn1.dat* and *ptn2.dat*, enter:

bcp mydb..bigtable partition ptn1, ptn2 out ptn1.dat, ptn2.dat

This example also copies the data from ptn1 and ptn2 to *ptn1.dat* and *ptn2.dat*. Enter:

bcp mydb..bigtable partition ptn1, ptn2 out

See Chapter 7, "Utility Commands Reference," for complete syntax and usage information for bcp.

## Bulk copying encrypted data

bcp transfers encrypted data in and out of databases in either plain text or cipher text form. By default, bcp copies plain text data, processing them as follows:

- Data is automatically encrypted by Adaptive Server before insertion when executing bcp in. Slow bcp is used. The user must have insert and select permission on all columns.
- Data is automatically decrypted by Adaptive Server when executing bcp out. select permission is required on all columns; in addition, decrypt permission is required on the encrypted columns.

This example copies the customer table out as plain text data in native machine format:

bcp uksales.dbo.customer out uk\_customers -n -Uroy -Proy123

If the data to be copied out as plain text is encrypted by a key that uses an explicit password, you can supply that password to bep using the --c password or --colpasswd options.

For example, if the salary column in the employee table is encrypted by a key that is protected by an explicit password, you can only copy out the salary data as plain text by providing bcp with the password, as follows:

```
bcp hr.dbo.employee out -c -Upjones -PX15tgol --
colpasswd hr.dbo.employee.salary '4mIneIsonly'
```

Alternatively, if you know the name of the key that encrypts the salary column, you can use:

```
bcp hr.dbo.employee out -c -Upjones -PX15tgol --
keypasswd keydb.dbo.hr_key '4mIneIsonly'
```

bcp uses the password to issue a set encryption passwd command before selecting the data.

Use the --keypasswd and --colpasswd options in a similar way on the bcp command line when copying the data back in.

Use the -C option for bcp to copy the data as cipher text. When copying cipher text, you may copy data out and in across different operating systems. If you are copying character data as cipher text, both platforms must support the same character set.

The -C option for bcp allows administrators to run bcp when they lack decrypt permission on the data. When the -C option is used, bcp processes data as follows:

- Data is assumed to be in cipher text format during execution of bcp in, and Adaptive Server performs no encryption. Use the -C option only if the file being copied into Adaptive Server was created using the -C option on bcp out. The cipher text must have been copied from a column with exactly the same column attributes and encrypted by the same key as the column into which the data is being copied. Fast bcp is used. The user must have insert and select permission on the table.
- bcp in -C bypasses the domain rule and check constraint for encrypted columns if either exist on an encrypted column because, in this situation, Adaptive Server uses fast bcp. Domain rules and check constraints do not affect bcp out -C.
- If an access rule exists on an encrypted column, using bcp out -C results in a 2929 error. Access rules do not affect bcp in -C.
- Data is copied out of Adaptive Server without decryption on bcp out. The cipher text data is in hexadecimal format. The user must have select permission on all columns. For copying cipher text, decrypt is not required on the encrypted columns.

• Encrypted char or varchar data retains the character set used by Adaptive Server at the time of encryption. If the data is copied in cipher text format to another server, the character set used on the target server must match that of the encrypted data copied from the source. The character set associated with the data on the source server when it was encrypted is not stored with the encrypted data and is not known or converted on the target server.

You can also perform bcp without the -C option to avoid the character set issue.

You cannot use the -J option (for character set conversion) with the -C option.

The following example copies the customer table. The cc\_card column is copied out as human-readable cipher text. Other columns are copied in character format. User "roy" is not required to have decrypt permission on customer cc\_card.

bcp uksales.dbo.customer out uk\_customers -C -c -Uroy -Proy123

When copying data as cipher text, ensure that the same keys are available in the database when the data is copied back in. If necessary, use the ddlgen utility to move keys from one database to another.

## bcp performance

Keeping indexes on a table causes the bulk copy utility to use slow bcp automatically. However, slow bcp can fill the transaction log very quickly.

- When you are copying a large number of rows, the performance penalty and log space requirements for using slow bcp can be severe.
- For extremely large tables, using slow bcp is not an option because its detailed log makes it much too slow.

To improve the performance of bcp:

• Use partitioned tables. Several bcp sessions with a partitioned table can reduce dramatically the time required to copy the data. However, such performance improvements are more noticeable in fast bcp than in slow bcp.

• Use bcp in parallel to increase performance dramatically. Parallel bulk copy can provide balanced data distribution across partitions. For more information, see "Using parallel bulk copy to copy data into a specific partition" on page 53.

## Using fast or slow bcp

The existence of indexes on tables affects transfer speed. When you use bcp on such tables, bcp automatically uses its slow mode, which logs data inserts in the transaction log. These logged inserts can cause the transaction log to become very large.

To control this data excess and ensure that the database is fully recoverable in the event of a failure, you can back up the log with dump transaction.

Note bcp does not fire any trigger that exists on the target table.

Fast bcp logs only the page allocations. For copying data in, bcp is fastest if your database table has no indexes.

However, if you used fast bcp to make data inserts, which fast bcp does not log, you cannot back up (dump) the transaction log to a device. The changes are not in the log, and a restore cannot recover nonexistent backup data. The requested backup (dump transaction) produces an error message that instructs you to use dump database instead. This restriction remains in force until a dump database successfully completes. For more information about dump database and dump transaction, see the *System Administration Guide*, and the *Reference Manual*.

- sp\_dboption 'select into/bulkcopy/pllsort' is off.
- sp\_dboption 'select into/bulkcopy/pllsort' is on, but the table uses the allpages locking scheme and has a clustered index.
- sp\_dboption 'select into/bulkcopy/pllsort' is on, but the table has a unique nonclustered index.

If the option ignore\_dup\_key option is enabled on the unique index, performing fast bcp can put the table and index in an inconsistent state if rows with duplicate keys are inserted. To avoid the inconsistency, Adaptive Server performs slow bcp.

• If the table has nonclustered indexes or triggers, and the table is marked for replication or the database is used as a warm standby.

When does Adaptive Server uses slow bcp?

	Because fast bcp does not log inserts, if Adaptive Server uses fast bcp, the rows bcp copies cannot be recovered on the replication site if there is a problem. Adaptive Server uses slow bcp in these situations to maintain compatibility with applications that were written to use the old behavior.				
When does Adaptive Server use fast bcp?	These are situations in which Adaptive Server uses fast bcp (in all cases sp_dboption 'select into/bulkcopy/pllsort' is enabled and the table does not have a clustered index):				
	• When the table has a non-unique, nonclustered index. Adaptive Server logs the index updates and the page allocations only. It does not log inserts into the table.				
	• When a table has triggers. However, bcp does not fire any triggers in the target table.				
	• When a table has datarows or datapage locking scheme with a clustered index.				
	If the table includes nonclustered indexes or triggers, but sp_dboption 'select into/bulkcopy/pllsort' is not enabled, Adaptive Server uses slow bcp.				
	bcp optimization is performed by Adaptive Server and does not require that you use Open Client version 15.0 or later.				
Copying tables with indexes	The bcp program is optimized to load data into tables that do not have indexe associated with them. It loads data into tables without indexes at the fastest possible speed, with a minimum of logging. Page allocations are logged, but the insertion of rows is not.				
	When you copy data into a table that has one or more indexes, you can use fast bcp. This includes indexes implicitly created using the unique integrity constraint of a create table statement. However, bcp does not enforce the other integrity constraints defined for a table.				
	By default, the select into/bulkcopy/pllsort option is false (off) in newly created databases. To change the default setting for future databases, turn this option on in the model database.				
	<b>Note</b> The log can grow very large during slow bcp because bcp logs inserts into a table that has indexes. After the bulk copy completes, back up your database with dump database, then truncate the log with dump transaction after the bulk copy completes and after you have backed up your database with dump database.				

While the select into/bulkcopy/pllsort option is on, you cannot dump the transaction log. Issuing dump transaction produces an error message instructing you to use dump database instead.

**Warning!** Be certain that you dump your database before you turn off the select into/bulkcopy/pllsort flag. If you have inserted unlogged data into your database, and you then perform a dump transaction before performing a dump database, you will not be able to recover your data.

Fast bcp runs more slowly while a dump database is taking place.

Adaptive Server prohibits dump transaction after running fast bcp. Instead, you must use dump database. Because slow bcp is a minimally logged operation, Adaptive Server allows you to issue dump transaction after running slow bcp whether select into/bulkcopy/pllsort is set to true or false in the database.

**Note** The performance penalty for copying data into a table that has indexes in place can be severe. If you are copying in a very large number of rows, it may be faster to drop all the indexes beforehand with drop index (or alter table, for indexes created as a unique constraint); set the database option; copy the data into the table; re-create the indexes; and then dump the database. Remember to allocate disk space for the construction of indexes: about 2.2 times the amount of space needed for the data.

Configuring databases for fast <i>bcp</i>	To allow a user to copy in data using fast bcp, either a System Administrator or
	the Database Owner first must use sp_dboption to set select into/bulkcopy/pllsort
	to true on the database that contains the target table or tables. If the option is set
	to false when a user tries to use fast bcp to copy data into a table without
	indexes, Adaptive Server generates an error message.

**Note** You do not need to set the select into/bulkcopy/pllsort option to true to copy out data from, or to copy in data to a table that has indexes. Slow bcp always copies tables with indexes and logs all inserts.

By default, the select into/bulkcopy/pllsort option is set to false (off) in newly created databases. To change the default setting for future databases, turn this option on (set to true) in the model database.

# Dropping indexes If you are copying a very large number of rows, you must have 1.2 times the amount of space needed for the data and enough space for the server to reconstruct a clustered index.

- If space is available, you can use drop index to drop all the indexes beforehand.
- If you do not have enough space for the server to sort the data and build the index or indexes, use slow bcp.

## Copying in data with fast bcp

Table 4-1 summarizes the steps for copying in data to Adaptive Server using fast bcp.

Step	Who can do it
Use sp_dboption to set select into/bulkcopy/pllsort to true.	System Administrator or Database Owner
Run checkpoint in the database that was changed.	
Have enough space to re-create any indexes on the table.	Table owner
Drop the indexes on the table.	
Have insert permission on the table.	Granted by the table owner
Perform the copy with bcp.	Any user with insert permission
Re-create the indexes.	Table owner
Reset sp_dboption, if desired, and run checkpoint in the database that was changed.	System Administrator or Database Owner
Use dump database to back up the newly inserted data.	System Administrator, Operator, or Database Owner
Run stored procedures or queries to determine whether any of the newly loaded data violates rules.	Table owner or stored procedure owner

Table 4-1: Steps for copying in data using fast bcp

## Bulk copying data into partitioned tables

In certain circumstances, you can improve bcp performance dramatically by executing several bcp sessions with a partitioned table.

Partitioned tables improve insert performance by reducing lock contention and by distributing I/O over multiple devices. bcp performance with partitioned tables is improved primarily because of this distributed I/O.

When you execute a bcp session on a partitioned table, consider:

• A partitioned table improves performance when you are bulk copying **in** to the table.

- The performance of slow bcp does not improve as much with partitioned tables. Instead, drop all indexes and use fast bcp, as described in Table 4-1 on page 50, to increase performance.
- Network traffic can quickly become a bottleneck when multiple bcp sessions are being executed. If possible, use a local connection to the Adaptive Server to avoid this bottleneck.

When copying data into a partitioned table, you can:

• Copy the data randomly without regard to the partition to which data is copied. For example, to copy data from *file1* to bigtable, enter:

bcp mydb..bigtable in file1

To copy data from *file1*, *file2*, and *file3* to bigtable, enter:

bcp mydb..bigtable in file1, file2, file3

• Copy the data into a specific partition For example, to copy data from *file1* to ptn1, *file2* to ptn2, and *file3* to ptn3, enter:

```
bcp mydb..bigtable partition ptn1, ptn2, ptn3 in
file1, file2, file3
```

To copy data from *file1* to the first partition of bigtable, enter:

bcp mydb..bigtable:1 in file1

If the table has a clustered index, bcp runs in slow mode and allows the index to control the placement of rows.

See Chapter 7, "Utility Commands Reference," for complete syntax and usage information for bcp.

#### Copying data randomly into partitions

To copy data randomly into partitioned tables when using multiple bcp sessions, you must:

1 Configure the table with as many partitions and physical devices as you require for your system.

For more information, see the *Performance and Tuning Guide*, and "Using parallel bulk copy to copy data into a specific partition" on page 53 of this manual.

2 Make sure Adaptive Server is configured with enough locks to support multiple bcp sessions. For information on configuring locks, see the *System Administration Guide*. 3 Remove the indexes on the table and enable fast bcp. See "Using fast or slow bcp" on page 47 for instructions.

**Note** If you use slow bcp, performance may improve significantly after you remove the indexes.

4 Divide the bcp input file into as many files of equal size as the number of planned simultaneous bcp sessions.

You also can use the -F *first\_row* and -L *last\_row* options to specify the start and end of each "input file."

5 Execute the bcp sessions with separate files in parallel on the local Adaptive Server machine.

For example, on UNIX platforms, you can execute different sessions in different shell windows or start individual bcp sessions in the background.

Read the *Performance and Tuning Guide* for a detailed description of copying data into partitioned tables.

#### Monitoring bcp sessions with dbcc checktable and sp\_helpsegment

If you do not specify which partition the bcp sessions should use, Adaptive Server randomly assigns the multiple bcp sessions to the table's available partitions. If this random assignment occurs, be sure to monitor the partitions to ensure that the process has evenly distributed the inserts by using either of the following:

- dbcc checktable to periodically to check the total page counts for each partition
- sp\_helpsegment or sp\_helpartition to perform a similar check, but without locking the database objects

For more information about dbcc checktable, see the *System Administration Guide*. For more information about sp\_helpsegment and sp\_helpartition, see the *Reference Manual*.

For more information about table partitions, see the *Performance and Tuning Guide*.

#### Reducing logging by increasing page allocations

If you are using fast bcp, consider that each bcp in batch requires the page manager to allocate one or more extents. Each such allocation generates a single log record.

Use the number of preallocated extents configuration parameter to specify how many extents Adaptive Server is to allocate through the page manager.

- Valid values for the number of preallocated extents configuration parameter are from 0 to 31; the default value is 2.
- You must restart Adaptive Server to change the value.
- When performing large bcp operations, increase this number to prevent the page allocations from filling the log.
- Set this value to 0 to prevent large extent allocations, so that the page manager performs only single-page allocations.

Adaptive Server may allocate more pages than are actually needed, so keep the value small when space is limited. These pages are deallocated at the end of the batch.

For more information, see the System Administration Guide.

### Using parallel bulk copy to copy data into a specific partition

Use parallel bulk copy to copy data in parallel to a specific partition. Parallel bulk copy substantially increases performance during bcp sessions because it can split large bulk copy jobs into multiple sessions and run the sessions concurrently.

To use parallel bulk copy:

- The destination table must be partitioned.
  - Use sp\_helpartition to see the number of partitions on the table.
  - Use alter table ... partition to partition the table, if the table is not already partitioned.
- The destination table should not contain indexes because:
  - If the table has a clustered index, this index determines the physical placement of the data, causing the partition specification in the bcp command to be ignored.

- If any indexes exist, bcp automatically uses its slow bulk copy instead of its fast bulk copy mode.
- If nonclustered indexes exist on the tables, parallel bulk copy is likely to lead to deadlocks on index pages.
- Each partition should reside on a separate physical disk for the best performance.
- Before you copy data into your database, you must partition the table destined to contain the data.
- Parallel bulk copy can copy in to a table from multiple operating system files.

For all types of partitioned tables, use:

bcp tablename partition partition\_name in file\_name

For round-robin partitioned tables only, you can use:

bcp tablename partition\_number in file\_name

Figure 4-1 illustrates the parallel bulk copy process.

# Figure 4-1: Copying data into a round-robin partitioned table using parallel bulk copy

# Large file divided into four smaller files



See the *Performance and Tuning Guide* for information about partitioning a table.

**Note** When using parallel bulk copy to copy data out, you cannot specify a partition number. You can specify a partition name.

#### bcp in and locks

When you copy in to a table using bcp, and particularly when you copy in to a table using parallel bcp, the copy process acquires the following locks:

- An exclusive intent lock on the table
- An exclusive page lock on each data page or data row
- An exclusive lock on index pages, if any indexes exist

If you are copying in very large tables, and especially if you are using simultaneous copies into a partitioned table, this can involve a very large number of locks.

To avoid running out of locks:

- Increase the number of locks.
  - To estimate the number of locks needed, use:

```
# of simultaneous batches * (rows_per_batch / (2016/row_length))
```

• To see the row length for a table, use:

```
1> select maxlen
2> from sysindexes
3> where id = object_id("tablename") and (indid = 0 or indid = 1)
```

See the *System Administration Guide* for more information about setting the number of locks.

- Use the -b *batchsize* flag to copy smaller batches; the default batch size is 1000 rows. The smallest batch size bcp can process is 1; the largest is 2147483647L.
- Run fewer batches concurrently.

#### Parallel bulk copy methods

Use one of the following methods to copy in data using parallel bulk copy:

- Start multiple bcp sessions in the background, being sure to:
  - Specify the password at the command line.
  - Use native mode, character mode, or a format file.

You can start bcp as many times as the table is partitioned.

- Create and use a format file:
  - a Start bcp in interactive mode.
  - b Answer the prompts.
  - c Create a format file that stores your responses.
  - d Put the process in the background when the copy begins.
  - e Issue the next bcp command, and specify the format file created with the first bcp command.
- Start bcp sessions in multiple windows.
- Specify a partition to file mapping in a single bcp in command.

The client can execute independent bcp in sessions in parallel. Alternatively, the user can specify the --maxconn option to control the maximum number of parallel connections that the bcp client can open to the server.

#### Parallel bulk copy syntax

The syntax for parallel bulk copy is:

bcp table\_name[:partition\_number | partrition\_name] in file\_name
-Pmypassword

Where:

- table\_name is the name of the table into which you are copying the data
- partition\_name is the name of the partition into which you are copying
- *file\_name* is the host file that contains the data
- mypassword is your password

#### Using parallel bulk copy on round-robin partitioned tables

To copy sorted data in parallel into a specific partition:

• Specify the partition by appending a colon (:) plus the partition number to the table name. For example:

```
publishers:10
```

**Note** The partition you specify must exist before you issue the bcp command.

- Split the sorted data into separate files, or delineate the "files" by specifying the first row (-F *first\_row*) and the last row (-L *last\_row*) of the host file.
- Note the number of partitions in the table. This number limits the number of parallel bulk copy sessions that you can start.

For example, if a table has four partitions, and you start five parallel bulk copy jobs, only the first four jobs can run in parallel; the fifth job does not start until one of the first four jobs finish.

bcp copies each file or set of line numbers to a separate partition. For example, to use parallel bulk copy to copy in sorted data to mydb..bigtable from four files into four partitions, enter:

```
bcp mydb..bigtable:1 in file1 -Pmypassword -c &
bcp mydb..bigtable:2 in file2 -Pmypassword -c &
bcp mydb..bigtable:3 in file3 -Pmypassword -c &
bcp mydb..bigtable:4 in file4 -Pmypassword -c &
```

#### Parallel bulk copy and IDENTITY columns

When you are using parallel bulk copy, IDENTITY columns can cause a bottleneck. As bcp reads in the data, the utility both generates the values of the IDENTITY column and updates the IDENTITY column's maximum value for each row. This extra work may adversely affect the performance improvement that you expected to receive from using parallel bulk copy.
To avoid this bottleneck, you can explicitly specify the IDENTITY starting point for each session.

Retaining sort order If you copy sorted data into the table without explicitly specifying the IDENTITY starting point, bcp might not generate the IDENTITY column values in sorted order. Parallel bulk copy reads the information into all the partitions simultaneously and updates the values of the IDENTITY column as it reads in the data. Specifying the starting

point from the

command line

A bcp statement with no explicit starting point would produce IDENTITY column numbers similar to those shown in Figure 4-2:

Pa	rtitio	n 1	Partition 2		Partition 3		Partition 4		n 4			
ID col	umn		ID col	umn		Π	D colu	ımn		ID col	umn	
100	А		102	С		-	103	F		101	Η	
104	Α		106	С		-	105	F		110	Η	
107	В		109	С		-	111	F		113	Ι	
108	В		112	D		-	116	G		115	J	
114	В		117	E		-	119	G		118	J	

#### Figure 4-2: Producing IDENTITY columns in sorted order

The table has a maximum IDENTITY column number of 119, but the order is no longer meaningful.

If you want Adaptive Server to enforce unique IDENTITY column values, you must run bcp with either the -g or -E parameter.

Use the -g *id\_start\_value* flag to specify an IDENTITY starting point for a session in the command line.

The -g parameter instructs Adaptive Server to generate a sequence of IDENTITY column values for the bcp session without checking and updating the maximum value of the table's IDENTITY column for each row. Instead of checking, Adaptive Server updates the maximum value at the end of each batch.

**Warning!** Be cautious about creating duplicate identity values inadvertently when you specify identity value ranges that overlap.

To specify a starting IDENTITY value, enter:

```
bcp [-gid_start_value]
```

For example, to copy in four files, each of which has 100 rows, enter:

bcp mydb..bigtable in file1 -g100 bcp mydb..bigtable in file2 -g200 bcp mydb..bigtable in file3 -g300 bcp mydb..bigtable in file4 -g400

Using the -g parameter does not guarantee that the IDENTITY column values are unique. To ensure uniqueness, you must:

	• Know how many rows are in the input files and what the highest existing value is. Use this information to set the starting values with the -g parameter and generate ranges that do not overlap.
	In the example above, if any file contains more than 100 rows, the identity values overlap into the next 100 rows of data, creating duplicate identity values.
	• Make sure that no one else is inserting data that can produce conflicting IDENTITY values.
Specifying the starting point using the data file	Use the -E parameter to set the IDENTITY starting point explicitly from the data file.
	The -E parameter instructs bcp to prompt you to enter an explicit IDENTITY column value for each row. If the number of inserted rows exceeds the maximum possible IDENTITY column value, Adaptive Server returns an error.

# Using the bcp options

The information in this section clarifies some of the more complex options of the bcp syntax. For a complete description of the syntax, see bcp on page 126.

## Using the default formats

bcp provides two command line options that create files with frequently used default formats. These options provide the easiest way to copy data in and out from Adaptive Server.

- The -n option uses "native" (operating system) formats.
- The -c option uses "character" (char datatype) for all columns. This datatype supplies tabs between fields on a row and a newline terminator, such as a carriage return, at the end of each row.

When you use the native or character options, bcp operates noninteractively and only asks you for your Adaptive Server password.

#### Native format

The -n option creates files using **native** (operating system-specific) formats. Native formats usually create a more compact operating system file. For example, the following command copies the publishers table to the file called *pub\_out*, using native data format:

bcp pubs2..publishers out pub\_out -n

Here are the contents of *pub\_out*:

```
0736<sup>^</sup>MNew Age Books<sup>^</sup>FBoston<sup>^</sup>BMA0877<sup>^</sup>PBinnet & Hardley<sup>^</sup>J
Washington<sup>^</sup>BDC1389<sup>^</sup>TAlgodata Infosystems<sup>^</sup>HBerkeley<sup>^</sup>BCA
```

bcp prefixed each field, except the pub\_id, which is a char(4) datatype, with an ASCII character equivalent to the length of the data in the field. For example, "New Age Books" is 13 characters long, and ^M (Ctrl-m) is ASCII 13.

All the table data stored in the *pub\_out* file is char or varchar data, so it is human-readable. In a table with numeric data, bcp writes the information to the file in the operating system's data representation format, which may not be human-readable.

bcp can copy data out to a file either as its native (database) datatype or as any datatype for which implicit conversion is supported for the datatype in question. bcp copies user-defined datatypes as their base datatype or as any datatype for which implicit conversion is supported. For more information on datatype conversions, see dbconvert in the *Open Client DB-Library/C Reference Manual* or the *Adaptive Server Enterprise Reference Manual*.

**Note** The bcp utility does not support copying data in native format from different operating systems; for example, copying from Windows to UNIX. Use the -c flag if you need to use bcp to copy files from one operating system to another.

**Warning!** Do not use row terminator (-t) or field terminator (-r) parameters with bcp in native format. Results are unpredictable and data may be corrupted.

#### **Character format**

Character format (-c) uses the char datatype for all columns. It inserts tabs between fields in each row and a newline terminator at the end of each row.

For example, the following command copies out the data from the publishers table in character format to the file *pub\_out*:

```
bcp pubs2..publishers out pub out -c
```

The command produces the following bcp output:

0736	New Age Books	Boston	MA
0877	Binnet & Hardley	Washington	DC
1389	Algodata Infosystems	Berkeley	CA

#### Change terminators from the command line

Terminators are the characters that separate data fields (field terminators). The row terminator is the field terminator of the last field in the table or file. Use the *-tfield\_terminator* and *-rrow\_terminator* command line options with the character format option (-c) to change the terminators from the command line.

The following example uses the comma (, ) as the field terminator and return (r) as the row terminator.

In UNIX platforms:

```
bcp pubs2..publishers out pub_out -c -t , -r \\r
```

Remember to "escape" the backslash, if necessary, for your operating system command shell.

In Windows:

bcp pubs2..publishers out pub\_out -c -t , -r \r

This bcp command line produces the following information:

0736,New Age Books,Boston,MA 0877,Binnet & Hardley,Washington,DC 1389,Algodata Infosystems,Berkeley,CA

**Note** You can use the -t and -r options to change the default terminators without including the character option (-c).

# Change the defaults in interactive bcp

If you do not specify native (-n) or character (-c) format, bcp prompts you interactively for:

- The file storage type
- The prefix length
- The terminator for each column of data to be copied
- A field length for fields that are to be stored as char or binary

The default values for these prompts produce the same results as using the native format and provide a simple means for copying data out of a database for later reloading into Adaptive Server.

If you are copying data to or from Adaptive Server for use with other programs, base your answers to the prompts on the format required by the other software.

These four prompts provide an extremely flexible system that allows you either to read a file from other software or to create a file that requires little or no editing to conform to many other data formats.

The following sections discuss these prompts and the way they interact to affect the data.

## Respond to bcp prompts

When you copy data in or out using the -n (native format) or -c (character format) parameters, bcp prompts you only for your password, unless you supplied it with the -P parameter. If you do not supply either the -n, -c or -f *formatfile* parameter, bcp prompts you for information for each field in the table or view.

- Each prompt displays a default value, in brackets, which you can accept by pressing Return. The prompts include:
  - The file storage type, which can be character or any valid Adaptive Server datatype
  - The prefix length, which is an integer indicating the length in bytes of the following data
  - The storage length of the data in the file for non-NULL fields
  - The field terminator, which can be any character string

• Windows – Scale and precision for numeric and decimal data types

The row terminator is the field terminator of the last field in the table, view, or file.

- The bracketed defaults represent reasonable values for the datatypes of the field in question. For the most efficient use of space when copying out to a file:
  - Use the default prompts
  - Copy all data in the datatypes defined by their table
  - Use prefixes as indicated
  - Do not use terminators
  - Accept the default lengths

Table 4-2 shows the bcp prompts, defaults, and the possible alternate user responses:

Prompt	Default provided	Possible user response
File Storage	Use database storage type for most fields except:	char to create or read a human-readable file; any Adaptive Server datatype where implicit conversion is supported.
Туре	char for varchar	
	binary for varbinary	
Prefix Length	• 0 for fields defined with char datatype (not storage type) and all fixed-length datatypes	0 if no prefix is desired; otherwise, defaults are recommended.
	• 1 for most other datatypes	
	• 2 for binary and varbinary saved as char	
	• 4 for text and image	
Storage Length	• For char and varchar, use defined length.	Default values, or greater, are recommended.
	• For binary and varbinary saved as char, use double the defined length.	
	• For all other datatypes, use maximum length needed to avoid truncation or data overflow.	
Field or Row Terminator	None	Up to 30 characters, or one of the following:
		• \t − tab
		• $n - newline$
		• \r – carriage return
		• $\setminus 0$ – null terminator
		• \ – backslash

Table 4-2: Defaults and user responses for bcp prompts

## File storage type

The file storage type prompt offers you choices about how to store the data in the file. You can copy data into a file as:

- Its database table type,
- A character string, or
- Any datatype for which implicit conversion is supported.

Note bcp copies user-defined datatypes as their base types.

Table 4-3 shows the default storage type for each Adaptive Server datatype and the abbreviations that are acceptable to bcp.

- For the most compact storage, use the default value.
- For character files, use char.
- Keep in mind that the date storage type is the Adaptive Server internal storage format of datetime, not the host operating system format of the date.
- timestamp data is treated as binary(8).

In Table 4-3, brackets [] indicate that you can use the initial character or the beginning characters of the word. For example, for "bit" you can use "b," "bi," or "bit."
Table datatype	Storage type
char, varchar	c[har]
text	T[ext]
int	i[nt]
smallint	s[mallint]
tinyint	t[inyint]
float	f[loat]
money	m[oney]
bit	b[it]
datetime	d[atetime]
binary, varbinary, timestamp	x
image	I[mage]
smalldatetime	D
real	r
smallmoney	М
numeric	n
decimal	e

Table 4-3: File storage datatypes for bcp

To display this list while using bcp interactively, type a question mark (?) in response to the prompt "Enter the file storage type".

The suggested values that appear in the prompts are the defaults. Remember that your response determines how the data is stored in the output file; you need not indicate the column's type in the database table.

bcp fails if you enter a type that is not either implicitly convertible or char. For example, you may not be able to use smallint for int data (you may get overflow errors), but you can use int for smallint.

When storing noncharacter datatypes as their database types, bcp writes the data to the file in Adaptive Server's internal data representation format for the host operating system, rather than in human-readable form.

Before copying data that is in character format from a file into a database table, check the datatype entry rules in the *Reference Manual*. Character data copied into the database with bcp must conform to those rules. Note especially that dates in the undelimited (*yy*)*yymmdd* format may result in overflow errors if the year is not specified first.

When you send host data files to sites that use terminals different from your own, inform them of the *datafile\_charset* that you used to create the files.

## **Prefix length**

By default, bcp precedes each field that has a variable storage length with a string of one or more bytes indicating the length of the field. This prefix enables the most compact file storage.

The default values in the prompts indicate the most efficient prefix length:

- For fixed-length fields, the prefix length should be 0.
- For fields of 255 bytes or less, the default prefix length is 1.
- For text or image datatypes, the default prefix length is 4.
- For binary and varbinary datatypes that are being converted to char storage types, the default prefix length is 2, since each byte of table data requires 2 bytes of file storage.
- For binary, varbinary, and image data, use even numbers for the prefix and length. This requirement maintains consistency with Adaptive Server, which stores data as an even number of hexadecimal digits.
- For any data column that permits null values, use a prefix length, other than 0, or a terminator to denote the length of each row's data. bcp considers such columns, including columns with integer datatypes that might ordinarily be considered fixed-length columns, to be of variable length.
- For data with no prefix before its column, use a prefix length of 0.

A prefix length is a 1-, 2-, or 4-byte integer that represents the length of each data value in bytes. It immediately precedes the data value in the host file.

Unless you supply a terminator, bcp pads each stored field with spaces to the full length specified at the next prompt, "length."

Because prefix lengths consist of **native** format integers, the resulting host file contains nonprintable characters. The nature of these characters could prevent you from printing the host file or from transmitting it through a communications program that cannot handle non-human-readable characters.

For more information about prefix lengths, see Table 4-8 on page 75.

### **Field length**

In almost all cases, use the bcp default value for the storage length while copying data out.

**Note** The terms "length" and "storage length" in this section refer to the operating system file, not to Adaptive Server field lengths.

- If you are creating a file to reload into Adaptive Server, the default prefixes and length keep the storage space needed to a minimum.
- If you are creating a human-readable file, the default length prevents the truncation of data or the creation of overflow errors that cause bcp to fail.

Because you can change the default length by supplying another value, you must be familiar with the data to transfer. If you are copying character data in from other software, examine the source file carefully before choosing length values.

**Note** If the storage type is noncharacter, bcp stores the data in the operating system's native data representation and does not prompt for a length.

When bcp converts noncharacter data to character storage, it suggests a default field length that is large enough to store the data without truncating datetime data or causing an overflow of numeric data.

• The default lengths are the number of bytes needed to display the longest value for the Adaptive Server datatype. Table 4-4 lists the default field lengths for data conversion to character storage.

Table 4-4: Default field lengths for noncharacter to character datatypes

Datatype	Default size
int	12 bytes
smallint	6 bytes
tinyint	3 bytes
float	25 bytes
money	24 bytes
bit	1 byte
datetime	26 bytes
smalldatetime	26 bytes
real	25 bytes
smallmoney	24 bytes

- If you specify a field length that is too short for numeric data when copying data out, bcp prints an overflow message and does not copy the data.
- The default length for binary and varbinary fields is twice the length defined for the column, since each byte of the field requires 2 bytes of file storage.
- If you accept the default storage length, the actual amount of storage space allocated depends on whether or not you specify a prefix length and terminators.
  - If you specify a prefix length of 1, 2, or 4, bcp uses a storage space of the actual length of the data, plus the length of the prefix, plus any terminators.
  - If you specify a prefix length of 0 and no terminator, bcp allocates the maximum amount of space shown in the prompt, which is the maximum space that may be needed for the datatype in question. In other words, bcp treats the field as if it were fixed length to determine where one field ends and the next begins.

For example, if the field is defined as varchar(30), bcp uses 30 bytes for each value, even if some of the values are only 1 character long.

- Fields defined in the database as char, nchar, and binary, and those that do not permit null values, are always padded with spaces (null bytes for binary) to the full length defined in the database. timestamp data is treated as binary(8).
- If data in the varchar and varbinary fields is longer than the length specified for copy out, bcp silently truncates the data in the file at the specified length.
- bcp does not know how large any one data value will be before copying all the data, so it always pads char datatypes to their full specified length.
- The file storage type and length of a column do not have to be the same as the type and length of the column in the database table. If the types and formats copied in are incompatible with the structure of the database table, the copy fails.
- File storage length generally indicates the maximum amount of data that can be transferred for the column, excluding terminators and/or prefixes.
- When copying data into a table, bcp observes any defaults defined for columns and user-defined datatypes. However, bcp ignores rules in order to load data at the fastest possible speed.

- bcp considers any data column that can contain a null value to be variable length, so use either a length prefix or a terminator to denote the length of each row of data.
- The file storage type and length of a column need not be the same as the type and length of the column in the database table. (If types and formats copied in are incompatible with the structure of the database table, the copy fails.)

### Field and row terminators

You can use a terminator to mark the end of a column or row, separating one from the next. The default is no terminator.

- Field terminators separate table columns.
- A row terminator is a field terminator for the last field in the row of the table or file.

Terminators are very useful for dealing with character data because you can choose human-readable terminators. The bcp character option, which uses tabs between each column with a newline terminator at the end of each row, is an example of using terminators that enhance the readability of a data file.

When you prepare data for use with other programs, and when you want to use bcp to prepare tabular data, supply your own terminators. The available terminators are:

- Tabs, indicated by  $\t$
- New lines, indicated by \n
- Carriage returns, indicated by \r
- Backslash, indicated by  $\setminus$
- Null terminators (no visible terminator), indicated by  $\0$
- Any printable character, for example, \*, A, t, |
- Strings of up to 10 printable characters, including some or all of the terminators listed above (for example, \*\*\t\*\*, end, !!!!!!!!!, and \t--\n)

Note Control characters (ASCII 0-25) cannot be printed.

### **Choose terminators**

Choose terminators with patterns that do not appear in any of the data.

For example, using a tab terminator with a string of data that also contains a tab creates an ambiguity: which tab represents the end of the string? bcp always looks for the first possible terminator, which in this case would be incorrect, since the first tab it would encounter would be the one that is part of the data string.

Data in native format can also conflict with terminators. Given a column that contains a 4-byte integer in native format, if the values of these integers are not strictly limited, it will be impossible to choose a terminator that is guaranteed not to appear inside the data. Use bcp's native format option for data in native format.

**Note** "No terminator" is different from a "null terminator," which is an invisible, but real, character.

A field terminator string can be up to 30 characters long. The most common terminators are a tab (entered as \t and used for all columns except the last one), and a newline (entered as \n and used for the last field in a row). Other terminators are: \0 (the null terminator), \ (backslash), and \r (Return). When choosing a terminator, be sure that its pattern does not appear in any of your character data, because bcp always looks for the first possible terminator.

For example, if you used tab terminators with a string that contained a tab, bcp would not be able to identify which tab represents the end of the string. bcp always looks for the first possible terminator, so, in this example it would find the wrong one.

A terminator or prefix affects the actual length of data transferred:

When a terminator or prefix is present, it affects the length of data transferred. If the length of an entry being copied out to a file is less than the storage length, it is immediately followed by the terminator or the prefix for the next field. The entry is not padded to the full storage length (char, nchar, and binary data is returned from Adaptive Server already padded to the full length). When bcp is copying in from a file, data is transferred until either the number of bytes indicated in the "Length" prompt has been copied or the terminator is encountered. Once the number of bytes equal to the specified length has been transferred, the rest of the data is flushed until the terminator is encountered. When no terminator is used, the table storage length is strictly observed.

- Fields stored as char (except char, nchar, and binary fields) instead of their database datatypes take less file storage space with the default length and prefix or a terminator. bcp can use either a terminator or a prefix to determine the most efficient use of storage space. bcp suggests the maximum amount of storage space required for each field as the default. For char or varchar data, bcp accepts any length.
- Table 4-5 and Table 4-6 show the interaction of prefix lengths, terminators, and field length on the information in the file. "P" indicates the prefix in the stored table; "T" indicates the terminator; and dashes, (--) show appended spaces. An ellipsis (...) indicates that the pattern repeats for each field. The field length is 8 bytes for each column; "string" represents the 6-character field each time.

#### Table 4-5: Adaptive Server char data

	Prefix length = 0	Prefix length-1, 2, or 4
No terminator	stringstring	PstringPstring
Terminator	stringTstringT	PstringTPstringT

#### Table 4-6: Other datatypes converted to char storage

	Prefix length = 0	Prefix length-1, 2, or 4
No terminator	stringstring	PstringPstring
Terminator	stringTstringT	PstringTPstringT

# **Format files**

After gathering information about each field in the table, bcp asks if you want to save the information to a **format file** and prompts for the file name.

Using a format file created for the data to be copied with the bcp utility allows you to copy data in or out noninteractively; that is, without being prompted by bcp for information. The format file supplies the information that bcp needs. You can use this newly created format file at any other time to copy the data back into Adaptive Server or to copy data out from the table. Figure 4-3 illustrates the format of the bcp format files. It shows the publishers table from the pubs2 database, with all the host file columns in character format, with no prefix, and using the default data length, a newline terminator at the end of the final column of a row, and tabs as terminators for all other columns.



Figure 4-3: bcp format file

### Elements of the bcp format file

The following list names the various elements of a bcp format file. Use Figure 4-3 as the format file example.

- The Tabular Data Stream (TDS) version is always the first line of the file. It specifies the version of TDS that you are using, not the Adaptive Server version, and appears is a literal string without quotation marks. In Figure 4-3, the version is 10.0.
- The second line of a bcp format file is the number of columns, which refers to the number of records in the format file, not including lines 1 and 2. Each column in the host table has one line.

	• One line for each column follows the first and second lines in the database table. Each line consists of elements that are usually separated by tabs, except for the host file datatype and the prefix length which are usually separated by a space. These elements are:
	Host file column order
	• Host file datatype
	• Prefix length
	• Host file data length
	• Terminator
	Server column order
	Server column name
	Column precision
	Column scale
	The following sections describe the column elements in the format file.
Host file column order	The host file column order is the sequential number of the field in the host data file, which begins numbering at 1.
Host file datatype	The host file datatype refers to the storage format of the field in the host data file, not the datatype of the database table column.
	Table 4-7 lists the valid storage formats.

Storage format	Adaptive Server datatype
SYBCHAR	char, chavarchar (ASCII), nchar, nvarchar
SYBTEXT	text
SYBBINARY	binary, timestamp, unichar, univarchar, varbinary
SYBIMAGE	image
SYBINT1	tinyint
SYBINT2	smallint
SYBINT4	int
SYBINT8	bigint
SYBFLT8	float
SYBREAL	real
SYBBIT	bit
SYBNUMERIC	numeric
SYBDECIMAL	decimal
SYBMONEY	money
SYBMONEY4	smallmoney
SYBDATETIME	datetime
SYBDATETIME4	smalldatetime
SYBDATE	date
SYBTIME	time
SYBUINT8	unsigned bigint
SYBUINT4	unsigned int
SYBUINT2	unsigned smallint
SYBUNITEXT	unitext
SYBFLT8	double

Table 4-7: Host file datatype storage format

Data written to a host file in its native format preserves all of its precision. datetime and float values preserve all of their precision, even when they are converted to character format. Adaptive Server stores money values to a precision of one ten-thousandth of a monetary unit. However, when money values are converted to character format, their character format values are recorded only to the nearest two places.

See Chapter 1, "System and User-Defined Datatypes" in the *Reference Manual: Building Blocks* for descriptions and appropriate uses of Adaptive Server datatypes.

Prefix length	Prefix length indicates the number of bytes in the field length prefix. The prefix length is a 0-, 1-, 2-, or 4-byte unsigned integer value embedded in the host data file that specifies the actual length of data contained in the field. Some fields may have a length prefix while others do not.					
	Table 4-8 shows the allowable prefix	length values.				
	Table 4-8: Allowable prefix length values					
	Length (in bytes)	Range				
	0	No prefix				
	1	2 <sup>8</sup> -1; 0-255				
	2	2 <sup>16</sup> -1; 0-65535				
	4	2 <sup>32</sup> -1; 0-4,294,967,295				
Host file data length	Host file data length refers to the ma field. To decide how much data to co	ximum number of bytes to copy for the py in or out, bcp uses one of:				
	• The maximum field length					
	• The prefix length, if any					
	• The field terminator string, if an	у				
	If more than one method of field length specification is given, bcp chooses the one that copies the least amount of data.					
Terminator	The terminator can be up to 30 bytes of characters enclosed in quotation marks (" "). The terminator designates the end of data for the host data file field.					
Server column order	The server column order represents the colid (column ID) of the syscolumns column into which the host data file column is to be loaded. Together with the host file column order, this element maps host data file fields to the database table columns.					
Server column name	The server column name is the name of the database table column into which this field is to be loaded.					
Column precision	The column precision is the precision of the database table column into which this field is to be loaded. This element is present only if the storage format is numeric or decimal.					
Column scale	The column scale is the scale of the database table column into which this field is to be loaded. This element is present only if the storage format is numeric or decimal.					

# Examples of copying out data interactively

By changing the default values of the prompts to bcp, you can prepare data for use with other software.

To create a human-readable file, respond to the bcp prompts as follows:

- File storage type, enter 0.
- Prefix length, enter 0.
- Field length, accept the default.
- Terminator the field terminator you enter depends on the software that you plan to use.
  - Choose between delimited fields or fixed-length fields. Always use \n, the newline terminator, to terminate the last field.

For fixed-length fields, do not use a terminator. Each field has a fixed length, with spaces to pad the fields. Adjacent fields, where the data completely fills the first field seem to run together, since there are no field separators on each line of output. See the example below.

• For comma-delimited output, use a comma (, ) as the terminator for each field. To create tabular output, use the tab character  $(\t)$ .

## Copy out data with field lengths

The following example uses fixed-length fields to create output in the personal computer format called SDF (system data format). This format can be easily read or produced by other software.

Note For information about format files, see "Format files" on page 71.

bcp pubs2..sales out sal\_out

The results as stored in the *sal\_out* file are as follows:

5023	AB-123-DEF-425-173	Oct	31 1985 12:00AM
5023	AB-872-DEF-732-221	Nov	6 1985 12:00AM
5023	AX-532-FED-452-2Z7	Dec	1 1990 12:00AM
5023	BS-345-DSE-860-1F2	Dec	12 1986 12:00AM
5023	GH-542-NAD-713-9F9	Mar	15 1987 12:00AM
5023	NF-123-ADS-642-9G3	Jul	18 1987 12:00AM
5023	XS-135-DER-432-8J2	Mar	21 1991 12:00AM

5023	ZA-000-ASD-324-4D1	Jul	27	1988	12:00AM
5023	ZD-123-DFG-752-9G8	Mar	21	1991	12:00AM
5023	ZS-645-CAT-415-1B2	Mar	21	1991	12:00AM
5023	ZZ-999-ZZZ-999-0A0	Mar	21	1991	12:00AM
6380	234518	Sep	30	1987	12:00AM
6380	342157	Dec	13	1985	12:00AM
6380	356921	Feb	17	1991	12:00AM
7066	BA27618	Oct	12	1985	12:00AM
7066	BA52498	Oct	27	1987	12:00AM
7066	BA71224	Aug	5 1	988 1	2:00AM
7067	NB-1.142	Jan	2 1	987 1	2:00AM
7067	NB-3.142	Jun	13	1990	12:00AM
7131	Asoap132	Nov	16	1986	12:00AM
7131	Asoap432	Dec	20	1990	12:00AM
7131	Fsoap867	Sep	8 1	987 1	2:00AM
7896	124152	Aug	14	1986	12:00AM
7896	234518	Feb	14	1991	12:00AM
8042	12-F-9	Jul	13	1986	12:00AM
8042	13-E-7	May	23	1989	12:00AM
8042	13-J-9	Jan	13	1988	12:00AM
8042	55-V-7	Mar	20	1991	12:00AM
8042	91-A-7	Mar	20	1991	12:00AM
8042	91-V-7	Mar	20	1991	12:00AM

The contents of the *sal\_fmt* format file are as follows:

10.0 3 1 SYBCHAR 04 "" 1 stor\_id 2 SYBCHAR 020 "" 2 ord\_num 3 SYBCHAR 026 "" 3 date

For information about format files, see "Format files" on page 71.

### Copy out data with delimiters

In the following examples, bcp copies data interactively from the publishers table to a file.

Note For information about format files, see "Format files" on page 71.

### Comma-delimited, newline-delimited with format file

The first example creates an output file with commas between all fields in a row and a newline terminator at the end of each row. This example creates a format file (*pub\_fmt*) that you can use later to copy the same or similar data back into Adaptive Server.

bcp pubs2..publishers out pub\_out

The results as stored in the *pub\_out* file are:

0736,New Age Books,Boston,MA 0877,Binnet & Hardley,Washington,DC 1389,Algodata Infosystems,Berkeley,CA

The contents of the *pub\_fmt* format file are:

10.0						
4						
1	SYBCHAR	0	4	","	1	pub_id
2	SYBCHAR	0	40	","	2	pub_name
3	SYBCHAR	0	20	","	3	city
4	SYBCHAR	0	2	"\n"	4	state

### Tab-delimited with format file

Similarly, the following example creates tab-delimited output from the table pubs2..publishers in the *pub\_out* file.

bcp pubs2..publishers out pub\_out

The results as stored in the *pub\_out* file are:

0736	New Age Books	Boston	MA
0877	Binnet & Hardley	Washington	DC
1389	Algodata Infosystems	Berkeley	CA

The contents of the *pub\_fmt* format file are:

10.0 4 1 SYBCHAR 04 "\t" 1 pub\_id 2 SYBCHAR 040 "\t" 2 pub\_name 3 SYBCHAR 020 "\t" 3 city 4 SYBCHAR 02 "\n" 4 state

## Examples of copying in data interactively

To copy in data successfully to a table from a file, you must know what the terminators in the file are or what the field lengths are and specify them when you use bcp.

The following examples show how to copy data in, either with fixed field lengths or with delimiters, using bcp with or without a format file.

### Copy in data with field lengths

In this example, bcp copies data from the *salesnew* file into the pubs2..sales table.

In the *salesnew* file are three fields: the first is 4 characters long, the second is 20, and the third is 26 characters long. Each row ends with a newline terminator (n), as follows:

5023ZS-731-AAB-780-2B9	May	24	1993	12:00:00:000AM
5023XC-362-CFB-387-3Z5	May	24	1993	12:00:00:000AM
6380837206	May	24	1993	12:00:00:000AM
6380838441	May	24	1993	12:00:00:000AM

Use the following command to copy in the data interactively from *salesnew*:

bcp pubs2..sales in salesnew

The system responds to the bcp command as follows:

```
Password:
Enter the file storage type of field stor id [char]:
Enter prefix-length of field stor id [0]:
Enter length of field stor id [4]:
Enter field terminator [none]:
Enter the file storage type of field ord num [char]:
Enter prefix-length of field ord num [1]: 0
Enter length of field ord num [20]:
Enter field terminator [none]:
Enter the file storage type of field date [datetime]: char
Enter prefix-length of field date [1]: 0
Enter length of field date [26]:
Enter field terminator [none]: \n
Do you want to save this format information in a file? [Y/n] y
Host filename [bcp.fmt]: salesin fmt
Starting copy...
4 rows copied.
```

Clock Time (ms.): total = 1 Avg = 0 (116000.00 rows per sec.)

When you log in to Adaptive Server and access sales, you see the following data from *salesnew* appended to the table:

select *	from sales	
stor_id	ord_num	date
5023	AB-123-DEF-425-1Z3	Oct 31 1985 12:00AM
5023	AB-872-DEF-732-2Z1	Nov 6 1985 12:00AM
5023	AX-532-FED-452-2Z7	Dec 1 1990 12:00AM
5023	BS-345-DSE-860-1F2	Dec 12 1986 12:00AM
5023	GH-542-NAD-713-9F9	Mar 15 1987 12:00AM
5023	NF-123-ADS-642-9G3	Jul 18 1987 12:00AM
5023	XS-135-DER-432-8J2	Mar 21 1991 12:00AM
5023	ZA-000-ASD-324-4D1	Jul 27 1988 12:00AM
5023	ZD-123-DFG-752-9G8	Mar 21 1991 12:00AM
5023	ZS-645-CAT-415-1B2	Mar 21 1991 12:00AM
5023	ZZ-999-ZZZ-999-0A0	Mar 21 1991 12:00AM
6380	234518	Sep 30 1987 12:00AM
6380	342157	Dec 13 1985 12:00AM
6380	356921	Feb 17 1991 12:00AM
7066	BA27618	Oct 12 1985 12:00AM
7066	BA52498	Oct 27 1987 12:00AM
7066	BA71224	Aug 5 1988 12:00AM
7067	NB-1.142	Jan 2 1987 12:00AM
7067	NB-3.142	Jun 13 1990 12:00AM
7131	Asoap132	Nov 16 1986 12:00AM
7131	Asoap432	Dec 20 1990 12:00AM
7131	Fsoap867	Sep 8 1987 12:00AM
7896	124152	Aug 14 1986 12:00AM
7896	234518	Feb 14 1991 12:00AM
8042	12-F-9	Jul 13 1986 12:00AM
8042	13-E-7	May 23 1989 12:00AM
8042	13-J-9	Jan 13 1988 12:00AM
8042	55-V-7	Mar 20 1991 12:00AM
8042	91-A-7	Mar 20 1991 12:00AM
8042	91-V-7	Mar 20 1991 12:00AM
(34 rows	affected)	

Since there is a unique clustered index on the stor\_id and ord\_num columns of sales, the new rows were sorted in order.

A conflict or violation can affect the copy process:

• Had there been any violations of the unique index on the columns in the data being copied from the file, bcp would have discarded the entire batch in which the violating row was encountered.

A batch size of 1 evaluates each row individually, but loads more slowly and creates a separate data page for each row during a fast bcp session.

• If the types copied in are incompatible with the database types, the entire copy fails.

### Copy in data with delimiters

In the following example, bcp copies data from the file *newpubs* into the table pubs2..publishers. In the *newpubs* file, each field in a row ends with a tab character  $(\t)$  and each row ends with a newline terminator  $(\n)$ , as follows:

1111	Stone Age Books	Boston	MA
2222	Harley & Davidson	Washington	DC
3333	Infodata Algosystems	Berkeley	CA

Since *newpubs* contains all character data, you can use the character command-line flag and specify the terminators with command line options:

• In UNIX platforms:

```
bcp pubs2..publishers in newpubs -c -t/\t -r/\n
```

In Windows:

bcp pubs2..publishers in newpubs -c -t\t -r\n

### Copy in data with a format file

To copy data back into Adaptive Server using the saved *pub\_fmt* format file, run the following command:

bcp pubs2..publishers in pub\_out -fpub\_fmt

You can use the *pub\_fmt* file to copy any data with the same format into Adaptive Server. If you have a similar data file with different delimiters, you can change the delimiters in the format file.

Similarly, you can edit the format file to reflect any changes to the field lengths, as long as all fields have the same length. For example, the *moresales* file contains:

804213-L-9 Jan 21 1993 12:00AM 804255-N-8 Mar 12 1993 12:00AM 804291-T-4 Mar 23 1993 12:00AM 804291-W-9 Mar 23 1993 12:00AM

Edit the *sal\_fmt* format file to read as follows:

10.0 3 1 SYBCHAR 0 4 "" 1 stor\_id 2 SYBCHAR 0 7 "" 2 ord\_num 3 SYBCHAR 0 21 "\n" 3 date

Then enter the following command:

• In UNIX platforms:

bcp pubs2..sales in moresales -fsal fmt

• In Windows:

bcp pubs2..sales in moresale -fsal\_fmt

The system responds as follows:

```
Starting copy...
4 rows copied.
Clock Time (ms.): total = 1 Avg = 0 (116000.00 rows
per sec.)
```

## bcp and alternate languages

Adaptive Server stores data using its default character set, which is configured during installation. If your terminal does not support that default character set, it may send confusing characters to bcp when you respond to prompts either by typing or by using host file scripts.

Omitting all character-set options causes bcp to use the character set that was named as the default for the platform. This default can cause communications problems:

- The default is not necessarily the same character set that was configured for Adaptive Server.
- The default may not necessarily be the character set that the client is using.

For more information about character sets and the associated flags, see Chapter 8, "Configuring Client/Server Character Set Conversions," in the *System Administration Guide*.

## Support for initialization strings

The bcp utility supports sending Transact-SQL commands, such as set replication off, to Adaptive Server before data is transferred.

Although you can use any Transact-SQL command as an initialization string for bcp, you must reset possible permanent changes to the server configuration after running bcp. You can, for example, reset changes in a separate isql session.

## bcp and row-level access rules

If Adaptive Server is enabled for row-level access, and you bulk-copy-out data, bcp copies out only the rows of data to which you have access. To copy out the entire table, you must first drop the access rules, then bcp out. Reinstate the access rules after you are done, if applicable.

If you bulk-copy-in data to a table that has access rules enabled, Adaptive Server may issue "uniqueness violation" errors. For example, if you load data from a bcp data file that was generated before the access rules were created on the table, and the bcp data file contains rows that were previously inserted into the table, you may receive this type of error.

If this happens, the table may look to the user like it does not include the rows that failed the bcp insert because of the uniqueness violation, but the user does not have access to the "missing" rows because of the access rules.

To copy in the entire table, drop the access rules, load the data, address any errors, then reinstate the access rules.

# Copy in and batch files

Batching applies only to bulk copying in; it has no effect when copying out. By default, Adaptive Server copies all the rows in batches of 1000 lines. To specify a different batch size, use the command-line option (-b).

bcp copies each batch in a single transaction. If Adaptive Server rejects any row in the batch, the entire transaction is rolled back. By default, bcp copies all rows in a single batch; use the -b parameter to change the default batch size. Adaptive Server considers each batch a single bcp operation, writes each batch to a separate data page, and continues to the next batch, regardless of whether the previous transaction succeeded.

When data is being copied in, it can be rejected by either Adaptive Server or bcp.

- Adaptive Server treats each batch as a separate transaction. If the server rejects any row in the batch, it rolls back the entire transaction.
- When bcp rejects a batch, it then continues to the next batch. Only fatal errors roll back the transaction.
- Adaptive Server generates error messages on a batch-by-batch basis, instead of row-by-row, and rejects each batch in which it finds an error. Error messages appear on your terminal and in the error file.

### Improve recoverability

To ensure better recoverability:

• Break large input files into smaller units.

For example, if you use bcp with a batch size of 100,000 rows to bulk copy in 300,000 rows, and a fatal error occurs after row 200,000, bcp would have successfully copied in the first two batches—200,000 rows—to Adaptive Server. If you had not used batching, bcp would not have been able to copy in any rows to Adaptive Server.

• Set the trunc log on chkpt to true (on).

The log entry for the transaction is available for truncation after the batch completes. If you copy into a database that has the trunc log on chkpt database option set on (true), the next automatic checkpoint removes the log entries for completed batches. This log cleaning breaks up large bcp operations and keeps the log from filling.

• Set -b batch\_size to 10.

The batch size parameter set to 10 causes bcp to reject the batch of 10 rows, including the defective row. The error log from this setting allows you to identify exactly which row failed.

A batch size of 1 is the smallest that bcp processes.

**Note** bcp creates 1 data page per batch, and setting b *batch\_size* to 10 creates data pages with 10 rows on each page. If you set -b *batch\_size* to 1, the setting creates data pages with 1 row on each page. This setting causes the data to load slowly and takes up storage space.

### **Batches and partitioned tables**

When you bulk copy data into a partitioned table without specifying a partition number, Adaptive Server randomly assigns each batch to an available partition. Copying rows in a single batch places all those rows in a single partition, which can lead to load imbalance in the partitioned table.

To help keep partitioned tables balanced, use a small batch size when bulk copying data or specify the partition ID during the bcp session. For information about partitioning tables, see the *Performance and Tuning Guide*.

## Copy out and text and image data

When you copy out text or image data, Adaptive Server, by default, copies only the first 32K of data in a text or image field. The -T *text\_or\_image\_size* parameter allows you to specify a different value. For example, if the text field to copy out contains up to 40K of data, you can use the following command to copy out all 40K:

bcp pubs2..publishers out -T40960

**Note** If a text or image field is larger than the given value or the default, bcp does not copy out the remaining data.

## Specify a network packet size

To improve the performance of large bulk copy operations, you may want to use larger network packet sizes than the defaults. The -A *size* option specifies the network packet size to use for the bcp session that you are beginning.

The value of *size* must be:

- Between the values of the default network packet size and max network packet size configuration parameters, and
- A multiple of 512.

**Note** The new packet size remains in effect for the current bcp session only.

For example, this command specifies that Adaptive Server send 40K of text or image data using a packet size of 4096 bytes for the bcp session:

bcp pubs2..authors out -A 4096 -T40960

## Copy in and error files

When you specify the -e *error\_file* option with copy in, bcp stores the rows that it cannot copy in to Adaptive Server in the specified error file.

- The error file stores:
  - A line that indicates which row failed and the error that occurred, and
  - A line that is an exact copy of the row in the host file.
- If the file name specified after -e already exists, bcp overwrites the existing file.
- If bcp does not encounter any errors, it does not create the file.

bcp in detects two types of errors:

- Data conversion errors
- Errors in building the row; for example, attempts to insert a NULL into columns that do not accept null values or to use invalid data formats, such as a 3-byte integer

The copy in process displays error messages on your monitor.

The following example loads the *newpubs* file into the publishers database, storing any error rows in the *pub\_err* file:

bcp pubs2..publishers in newpubs -epub\_err

Keep the following in mind when working with error files generated by copy in:

- bcp stores rows in an error file only when the bcp program itself detects the error.
- bcp continues to copy rows until bcp encounters the maximum number of error rows, at which point bcp stops the copy.
- bcp sends rows to Adaptive Server in batches, so bcp cannot save copies of rows that are rejected by Adaptive Server, for example, a duplicate row for a table that has a unique index.
- Adaptive Server generates error messages on a batch-by-batch basis, instead of row-by-row, and rejects the entire batch if it finds an error.
- It is not considered an error for Adaptive Server to reject duplicate rows if either allow\_dup\_row or ignore\_dup\_key was set when a table's index was created. The copy proceeds normally, but the duplicate rows are neither stored in the table nor in the bcp error file.

## Copy out and error files

During the copy out process, as with copy in, bcp overwrites any file of the same name and does not create an error file if no errors occurred.

There are two situations that cause rows to be logged in the error file during a copy out:

- A data conversion error in one of the row's columns
- An I/O error in writing to the host file

Keep the following in mind when working with error files generated by copy out:

- bcp logs rows in the error file in the default character format.
- All data values print as characters with tabs between the columns and a newline terminator at the end of each row.

## Data integrity for defaults, rules, and triggers

To ensure integrity, bcp handles data to copy depending upon its element.

### **Defaults and datatypes**

When copying data into a table, bcp observes any defaults defined for the columns and datatypes. That is, if there is a null field in the data in a file, bcp loads the default value instead of the null value during the copy.

For example, here are two rows in a file to be loaded into authors:

```
409-56-7008,Bennet,David,415 658-9932,622 Pine
St.,Berkeley,CA,USA,94705213-46-8915,Green,Marjorie,,309 63rd St.
#411,Oakland,CA,USA,94618
```

Commas separate the fields; a newline terminator separates the rows. There is no phone number for Marjorie Green. Because the phone column of the authors table has a default of "unknown," the rows in the loaded table look like this:

409-56-7008 Bennet David 415 658-9932 622 Pine St. Berkeley CA USA 94705 213-46-8915 Green Marjorie unknown 309 63rd St. #411 Oakland CA USA 94618

### **Rules and triggers**

bcp, to enable its maximum speed for loading data, does not fire rules and triggers.

To find any rows that violate rules and triggers, copy the data into the table and run queries or stored procedures that test the rule or trigger conditions.

## How bcp differs from other utilities

The bcp utility, which copies entire tables or portions of a single table, is distinct from the other utilities that move data from one place to another.

The following list names these other utilities and their commands and describes how you can best use them to move data.

dump database, load database, dump transaction, and load transaction	Use the SQL commands dump database, load database, dump transaction, and load transaction for backup purposes only. Unlike bcp, the dump commands create a physical image of the entire database.
	You must use load database or load transaction to read data backed up with dump database or dump transaction.
	For information on using the SQL dump and load commands, see the <i>System</i> Administration Guide and the <i>Reference Manual</i> .
<i>insert, update,</i> and <i>delete</i>	Use the data modification commands insert, update, and delete, respectively, to add new rows to, change existing rows in, or remove rows from a table or view.
	• Use the insert command with a select statement to move data between tables.
	• Use the select statement with an into clause to create a new table, based on:
	• the columns named in the select statement,

- the tables named in the from clause, and
- data in the rows named in the where clause.

For details on adding, changing, and deleting data, see insert, update, and delete in the *Reference Manual*.

# Using dscp

Торіс	Page
Getting started with dscp	91
Working with server entries	93
Exiting dscp	98
Quick reference for dscp utility commands	98

dscp is a utility program that you use to view and edit server entries in the interfaces file.

Note dscp is not available for Windows.

For a detailed description of dscp syntax, see dscp on page 196.

## Getting started with dscp

#### Starting dscp

• Enter:

\$SYBASE/\$SYBASE\_OCS/bin/dscp

The dscp prompt, >>, appears.

#### Getting help with dscp

- To view the dscp help screen, enter one of the following commands:
  - help h ?

### Using a dscp session

Before you can view, add, or modify server entries, you must open a session so that you can interact with the interfaces file.

You can have multiple sessions open at one time.

### \* Opening a session with the interfaces file

• Enter:

open InterfacesDriver

When you open a session, dscp provides the session's number. For example, if you open a session using the open InterfacesDriver command, dscp displays the following message:

ok Session 1 InterfacesDriver>>

### Listing all open sessions

• Enter:

sess

### Switching to another open session

• Enter the following, where *sess* is the session number:

switch sess

For example, you are switched to session 3 if you enter:

switch 3

The switch keyword is optional. For example, entering "3" also switches you to session 3.

#### Closing a session

• Enter the following, where *sess* is the session number:

close *sess* 

For example, session 3 closes if you enter:

close 3

If you do not specify a session number, dscp closes the current session.

# Working with server entries

Use dscp to add or modify server entries.

### Adding and modifying server entries

After you open a session, you can add or modify server entries associated with that session.

**Note** When you add or modify a server entry, dscp automatically creates or modifies both master and query lines. The master line and the query line of an interfaces file entry contain identical information.

Each server entry is made up of a set of attributes. When you add or modify a server entry, dscp prompts you for information about each attribute. Table 5-2 describes each attribute.

			Can be edit or modifyin	ed when adding g a server entry
Attributes	Type of value	Default value and valid values	Adding	Modifying
Server Object Version	Integer	110	No	No
Server Name	Character string	N/A	N/A	No
Server Service	Character string	SQL SERVER	Yes	No
Server Status	Integer	4	No	No
		Valid values are:		
		1 Active		
		2 Stopped		
		3 Failed		
		4 Unknown		
Transport Type	Character string	tcp. Valid values are: decnet, spx, tcp, tli, spx, tli tcp	Yes	Yes
Transport Address	Character string	None. Valid values are character strings recognized by the specified transport type	Yes	Yes

#### Table 5-1: Server attributes

			Can be edited when adding or modifying a server entry	
Attributes	Type of value	Default value and valid values	Adding	Modifying
Security Mechanism	Character string Note You can add up to 20 security mechanism strings for each server entry	None Valid values are character strings associated with object identifiers defined in the user's <i>objectid.dat</i> .	Yes	Yes

### Adding a server entry

1

1 Enter:

add servername

You are now in add mode. You can continue to add server entries, but you cannot execute any other dscp commands until you exit this mode. While in add mode, dscp prompts you for information about *servername*.

1

- 2 Do one of the following:
  - Enter a value for each attribute, or
  - Press Return to accept the default value, which is shown in brackets
     [ ]

For example, dscp prompts for the following information when you enter:

```
add myserver
Service: [SQL Server]
Transport Type: [tcp] tcp
Transport Address: victory 8001
Security Mechanism []:
```

A server entry can have up to 20 transport type/address combinations associated with it.

For a description of the server attributes, see Table 5-1 on page 93.

3 To exit add mode, enter:

#done

#### Modifying a server entry

You cannot use dscp to modify the Version, Service, and Status entries in the *interfaces* file.

1 Enter:

```
mod servername
```

You are now in modify mode. You can continue to modify server entries, but you cannot execute any other dscp commands until you exit this mode. In modify mode, dscp prompts you for information about *servername*.

- 2 Do one of the following:
  - Enter a value for each attribute, or
  - Press Return to accept the default value, which is shown in brackets
     [ ]

For example, dscp prompts for the following information when you enter:

```
mod myserver
Version: [1]
Service: [SQL Server] Open Server
Status: [4]
Address:
Transport Type: [tcp]
Transport Address: [victory 1824] victory 1826
Transport Type: [tcp]
Transport Address: [victory 1828]
Transport Type: []
Security Mechanism []:
```

For a description of the server attributes, see Table 5-1 on page 93.

3 To delete an address, enter:

#del

4 To exit modify mode, enter:

#done

### Copy server entries

dscp allows you to copy server entries within a session and between two sessions. You have four options when copying a server entry.

You can copy:

- A server entry to a new name in the current session
- A server entry to a different session
- A server entry to a new name in a different session

• All entries in the current session to a different session

#### Creating a new server entry within a session by copying

• Enter:

copy name1 to name2

For example, if you enter the following, dscp creates a new entry, "my\_server," that is identical to "myserver":

copy myserver to my\_server

You can then modify the new entry and leave the original intact.

#### Copying a server entry without changing the name

• Enter:

copy name1 to sess

For example, dscp copies the "myserver" entry in the current session to session 2 when you enter:

copy myserver to 2

#### Copying a server entry and rename it

• Enter:

copy name1 to sess name2

For example, dscp copies the "myserver" entry in the current session to session 2 and renames it "my\_server" when you enter:

copy myserver to 2 my\_server

- Copying all entries in the current session to a different session
  - Enter:

copyall sess

For example, dscp copies all entries in the current session to session 2 when you enter:

copyall 2

### List and view contents of server entries

You can list names and attributes associated with a session.

#### Listing names of server entries

• Enter:

list

- Listing the attributes of server entries
  - Enter:

```
list all
```

For a description of server attributes, see Table 5-1 on page 93.

#### Viewing the contents of a server entry

• Enter:

read servername

For example, the following information is displayed when you enter:

read myserver

```
DIT base for object: interfaces
Distinguish name: myserver
Server Version: 1
Server Name: myserver
Server Service: SQL Server
Server Status: 4 (Unknown)
Server Address:
Transport Type: tcp
Transport Addr: victory 1824
Transport Type: tcp
Transport Addr: victory 1828
```

For a description of the server attributes, see Table 5-1 on page 93.

### **Delete server entries**

You can delete one entry or all entries associated with a session.

#### Deleting entries associated with a session

• Enter:

del servername

For example, dscp deletes the entry for "myserver" when you enter:

del myserver

- Deleting all entries associated with a session
  - Enter:

delete-all

## **Exiting dscp**

To exit dscp, enter one of the following commands:

```
exit
quit
```

# Quick reference for dscp utility commands

dscp allows you to perform functions by entering commands at the dscp prompt. Table 5-2 provides a quick reference to these commands.

Command	Description
add servername	Adds server entry <i>servername</i> in the current session. dscp prompts you for information about <i>servername</i> . Press Return to accept the default value, which is shown in square brackets []. Enter "#done" to exit add mode.
addattr servername	Adds an attribute to the server entry servername in the current session.
close [sess]	Closes a session identified by the <i>sess</i> number. If you do not specify <i>sess</i> , closes the current session.
config	Displays configuration information related to your Sybase environment.
copy name1 to {name2   sess   sess name2}	<ul> <li>Copies server entry <i>name1</i> in the current session to:</li> <li>Server entry <i>name2</i> in the current session,</li> <li>Session <i>sess</i>, or</li> <li>Server entry <i>name2 in session sess</i>.</li> </ul>
copyall to sess	Copies all server entries in the current session to session sess.
del servername	Deletes server entry <i>servername</i> in the current session.
delete-all	Deletes all server entries in the current session.
exit	Exits dscp.
help, ?, h	Displays the online help.

Table 5-2: dscp commands

Command	Description
list [all]	Lists the server entries for the current session. To list the names of the entries, use the list command. To list the attributes for each entry, use the list all command.
mod servername	Modifies server entry <i>servername</i> in the current session. dscp prompts you for information about <i>servername</i> . Press Return to accept the default value, which is shown in square brackets []. Enter "#done" to exit modify mode.
open [ <i>dsname</i> ]	Opens a session for the specified directory service, where dsname is the directory service name. If you do not specify a value for <i>dsname</i> , this command opens a session for the default directory service. To open a session, specify the value "InterfacesDriver" for <i>dsname</i> .
quit	Exits dscp.
read servername	Displays the contents of server entry servername.
sess	Lists all open sessions.
[switch] sess	Makes session number sess the current session.
# CHAPTER 6 Using dsedit

This chapter explains how to use the dsedit utility to edit the Adaptive Server interfaces file.

Торіс	Page
Getting started with dsedit	101
Add, view, and edit server entries	105
Troubleshoot dsedit	112

## Getting started with dsedit

dsedit is a graphical utility that lets you view and edit server entries in the interfaces file (*sql.ini* in Windows). For a detailed description of dsedit syntax, see dsedit on page 197.

**Note** UNIX users: If your system does not have X-Windows, use dscp to configure server entries in the interfaces file. See Chapter 5, "Using dscp" for more information.

## Start dsedit

Windows

You can start dsedit from the command prompt, the Windows Explorer, or the Sybase for Windows program group.

## \* Starting dsedit from the command prompt

• Enter:

dsedit

You can specify the following command-line arguments:

- -ddsname Specifies which directory service to connect to. dsname is the local name of the directory service, as listed in the *libtcl.cfg* file. If you do not specify the -ddsname argument, dsedit presents a list of directory service options in the first dialog box.
- -*lpath* Specifies the path to the *libtcl.cfg* file, if other than *SYBASE\_home*\*INI*. Use this argument only if you want to use a *libtcl.cfg* file other than the one located in *SYBASE\_home*\*INI*.

## Starting dsedit through the Windows Explorer

- 1 Go to the %SYBASE%\bin\ directory.
- 2 Double-click on the *DSEDIT.exe* file.

## Starting dsedit from the Sybase for Windows program group

- 1 Choose Sybase for Windows from the Start menu.
- 2 Choose dsedit from the Sybase for Windows menu. The Select Directory Service dialog box appears.

UNIX platforms Before starting dsedit, make sure that you have write permission on the interfaces file.

If you are running dsedit from a remote machine, make sure that the DISPLAY environment variable is set so the dsedit screens will show on your machine instead of on the remote machine.

## Setting the DISPLAY environment variable

- 1 Log in to the remote machine.
- 2 Enter:

setenv DISPLAY your\_machine\_name:0.0

## Starting dsedit

• Enter:

\$SYBASE/bin/dsedit

The Select a Directory Service window appears. This window lets you open editing sessions for the interfaces file. The full path name of the default interfaces file is shown in the Interfaces File to Edit box. The full path name of the configuration file is shown below it.

## Open an editing session

Windows

The Select Directory Service dialog box allows you to open a session with a directory service. You can open a session with:

- Any directory service that has a driver listed in the *libtcl.cfg* file
- The sql.ini file

## Opening a session in Windows

- 1 Double-click on the local name of the directory service you want to connect to, as listed in the DS Name box, or
- 2 Click on the local name of the directory service you want to connect to, as listed in the DS Name box, and click the OK button.

**Note** dsedit uses the SYBASE environment variable to locate the *libtcl.cfg* file. If the SYBASE environment variable is not set correctly, dsedit cannot locate the *libtcl.cfg* file.

The session number and local name of the directory service appear in the header bar.

## Opening additional sessions

dsedit allows you to have multiple sessions open at one time.

1 Choose Open Directory Service from the File menu.

The Select Directory Service box appears.

2 Double-click the local name of the directory service to which you want to be connected (or click on the directory service name and click OK).

Opening multiple sessions allows you to copy entries between directory services. See "Copy server entries" on page 110 for more information.

## Switching between sessions

If you have multiple sessions open at one time, you need to activate a session before you can work in it.

- Activate a session by either:
  - Clicking in the session window
  - Choosing the session from the Windows menu

The dsedit title bar shows which session is active.

UNIX platforms

## \* Opening the default interfaces file for editing

- 1 Select Sybase Interfaces File.
- 2 Click OK.

## \* Opening a file other than the default interfaces file

- 1 Select Sybase Interfaces File.
- 2 Edit the displayed file name.
- 3 Click OK.

The Directory Service Session window appears.

You can open multiple interfaces file sessions with different files.

The Directory Service Session screen displays the full path name of the interfaces file and lists the server entries contained within it.

- Add new server entry displays the Server Entry Editor window, where you specify the name and network addresses for a new server entry.
- **Modify server entry** lets you view and modify the network addresses for a selected server entry. To view or modify a server entry, select the server in the list, then click Modify server entry to display the server's attributes in the Server Entry Editor window.
- **Copy server entry** lets you copy one or more entries to another interfaces file.
- **Close Session** closes the session window and writes changes to the interfaces file.

For procedures on using these buttons, see "Modify server entries in Windows" on page 105.

Clicking the Add new server entry or Modify server entry button in the Session screen displays the Server Entry Editor window.

You use the Server Entry Editor window to view or edit server entries in an interfaces file:

• Server name – if you are adding a server entry, type the name of the new server. If you are editing a server entry, you can edit the name field to rename the server. The new name cannot already exist in the interfaces file.

- Available network transports a list of the network addresses where the server accepts client connections.
  - To create a new address, click Add network transport. See "Modify server entries in Windows" on page 105.
  - To edit an existing address, click Modify network transport. See ٠ "Modify server entries in Windows" on page 105.
  - To remove a selected network address, click Delete network transport. ٠
  - To rearrange the order of addresses in the list, click Move network transport up or Move network transport down.
- OK commits your changes and closes the window. Changes to the ٠ interfaces file are not applied until you close the session using the Close Session button in the Directory Service Session screen.
- Cancel closes the window and discards any edits.

## Add, view, and edit server entries

Once you are in an open session, you can add, modify, rename and delete server entries associated with that session, as well as copy server entries within a session and between sessions.

## Modify server entries in Windows

The server entries associated with the session appear in the Server box. Click on a server entry to select it.

Each server entry is made up of a set of attributes. The attributes are described in Table 6-1.

Attribute name	Type of value	Description	Default value
Server Version	Integer	Version level of the server object definition. Sybase provides this attribute to identify future changes to the object definition.	150
Server Name	Character string	Server name.	N/A
Server Service	Character string	A description of the service provided by the server. This value can be any meaningful description.	Adaptive Server

## Table 6-1: Server attributes

Attribute name	Type of value	Description	Default value
Server Status	Integer	The operating status of the server. Values are:	4
		• Active	
		• Stopped	
		• Failed	
		• Unknown	
Security Mechanism	Character string	Object identifier strings (OID) that specify the security mechanisms supported by the server. This attribute is optional. If it is omitted, Open Server allows clients to connect with any security mechanism for which Open Server has a corresponding security driver.	N/A
Server	Character string	One or more addresses for the server.	N/A
Address		The format of the address varies by protocol, and some protocols allow more than one format. The options are:	
		• TCP/IP – two formats:	
		computer name, port number	
		• ip-address,portnumber	
		<ul> <li>Named Pipe – <i>pipe name</i>: "\pipe" is a required prefix to all pipe names. Server pipes can be only local.</li> </ul>	
		• Local – \pipe\sql\query	
		• <b>Remote</b> – \\computer_name\pipe\sql\query	
		• IPX/SPX – three formats:	
		• server name	
		• net number, node number, socket number	
		• server name, socket number	
		• DECnet – four formats:	
		<ul> <li>area number.node number,object name</li> </ul>	
		• area number.node number,object number	
		<ul> <li>node name,object name</li> </ul>	
		<ul> <li>node name,object number</li> </ul>	
	♦ Add	ing a server entry	
	1	Choose Server Object   Add.	
	2	Type a server name in the Server Name box.	
	3	Click OK.	

The server entry appears in the Server box. To specify an address for the server, you must modify the entry.

## Modifying a server attribute

You can modify any attribute of a server entry.

- 1 Click on a server entry in the Server box.
- 2 Choose Server Object | Modify Attribute.
- 3 Click on the attribute you want to modify in the Attributes box.

A dialog box appears that shows the current value of the attribute.

4 Type a new value for the attribute, or select a value from the drop-down list.

See Table 6-1 on page 105 for a description of each attribute.

5 Click OK.

## Renaming a server entry

- 1 Click on a server entry in the Server box.
- 2 Choose Server Object | Rename.
- 3 Type a new name for the server entry in the Server Name box.
- 4 Click OK.

## Deleting a server entry

- 1 Click on a server entry in the Server box.
- 2 Choose Server Object | Delete.

## Copying server entries within the current session

1 Click on one or more server entries in the Server box.

Use the Shift key to select multiple entries.

- 2 Click the Copy button (below the menu bar), or choose Edit | Copy.
- 3 Click the Paste button (below the menu bar), or choose Edit | Paste.

dsedit appends the copied server entries with a version number of \_n. You can rename the copied server entries Server Object | Rename option on. See "Renaming a server entry" on page 107 for more information.

## Copying server entries between sessions

1 Open a session with the directory service or *sql.ini* file that you want the entries copied to.

- 2 To open a session, choose File | Open Directory Service. See "Opening additional sessions" on page 103 for more information.
- 3 Click on one or more server entries in the Server box of the session that you want the entries copied from.

Use the Shift key to select multiple entries.

4 To copy the server entries, click the Copy button (below the menu bar), or choose Edit | Copy.

To cut the server entries, click the Cut button (below the menu bar), or choose Edit | Cut.

5 Activate the session where you want to paste the server entries.

See "Switching between sessions" on page 103 for instructions for activating a session.

6 Click the Paste button (below the menu bar), or choose Edit | Paste.

You can rename the copied server entries using Server Object | Rename. See "Switching between sessions" on page 103 for more information.

## Modify server entries in UNIX platforms

To perform the procedures in this section, open the interfaces session window using the instructions in "Open an editing session" on page 103.

**Note** After performing each procedure in this section, you must click on Close Session to apply your edits to the interfaces file. Clicking this button also closes the interfaces session window.

## Adding a new server entry

- 1 Click on Add new server entry.
- 2 Specify the name and network addresses for a new server entry.

## Viewing or modifying a server entry

- 1 Click on Modify server entry.
- 2 Modify the attributes as desired.

## Copying a server entry to another interfaces file

1 Use one of the following methods to select the entries to copy:

- To copy a single entry, click it once.
- To copy a range of consecutive entries, click the first entry in the range, press and hold down Shift, and click the last entry in the range. You can also select "backwards" by clicking the last entry, holding down Shift, and clicking the first entry.
- To select multiple, nonconsecutive entries, press and hold down the Ctrl key while you click each entry.
- 2 Click Copy server entry.
- 3 Select the Sybase interfaces file from the list.
- 4 Edit the displayed file name.
- 5 Click OK.

## Add or edit network transport addresses

The Network Transport Editor window allows you to view, edit, or create the transport addresses at which a server accepts client connections. This window displays the name of the server entry for the address and allows you to configure the following items:

- Transport type specifies the protocol and interface for the address. For all platforms except Digital UNIX, values are tcp, tli tcp, tli spx, and spx. For Digital UNIX, values are decnet, tcp, and tli tcp.
- Address information depending on the transport type, different address components are required. The following sections discuss address formats in detail.

# TCP/IP addresses The address information for a TCP/IP entry consists of a host name (or IP address) and a port number (entered as a decimal number). For tli tcp-formatted interfaces entries, the host's IP address and the port number are converted to the 16-byte hexadecimal representation required for tli tcp-formatted interfaces entries.

In interfaces entries, use tli tcp for:

- All pre-10.0 clients on platforms that use tli-formatted interfaces entries
- Adaptive Server or Replication Server version 11.0.x or earlier on platforms that use tli- formatted interfaces entries

Use tcp for other clients and servers.

To indicate a TCP/IP address, choose tcp or tli tcp from the Transport Type menu.

## **SPX/IPX** addresses

SPX/IPX addresses allow Adaptive Server to listen for connections from client applications running on a Novell network. SPX/IPX addresses consist of the following information:

- Host address an eight digit hexadecimal value representing the IP address of the computer on which the server runs. Each component of the dot-separated decimal IP address format maps to one byte in the hex address format. For example, if your host's IP address is 128.15.15.14, enter "800F0F0E" as the SPX/IPX host address value.
- Port number the port number, expressed as a four-digit hexadecimal number.
- Endpoint the path for the device file that points to the SPX device driver. Defaults to /dev/mspx on Solaris and /dev/nspx on any other platform. If necessary, adjust the path so that it is correct for the machine on which the server runs. The default path is based on the platform on which you are running dsedit.

To indicate an SPX/IPX address, choose tli spx or spx from the Transport Type menu.

## **Copy server entries**

dsedit allows you to copy server entries within a session and between sessions. This includes copying entries from a *sql.ini* file to a directory service.

Windows

## \* Copying server entries within the current session

1 Click on one or more server entries in the Server box.

Use the Shift key to select multiple entries.

- 2 Click the Copy button (below the menu bar), or choose Edit | Copy.
- 3 Click the Paste button (below the menu bar), or choose Edit | Paste.

dsedit appends the copied server entries with a version number of \_n. You can rename the copied server entries using Server Object | Rename. See "Renaming a server entry" on page 107 for more information.

## Copying server entries between sessions

- 1 Open a session with the directory service or *sql.ini* file that you want the entries copied to.
- 2 To open a session, choose File | Open Directory Service. See "Opening additional sessions" on page 103 for more information.
- 3 Click on one or more server entries in the Server box of the session that you want the entries copied from.

Use the Shift key to select multiple entries.

4 To copy the server entries, click the Copy button (below the menu bar), or choose Edit | Copy.

To cut the server entries, click the Cut button (below the menu bar), or choose Edit | Cut.

5 Activate the session where you want to paste the server entries.

See "Switching to another open session" on page 92 for instructions for activating a session.

6 Click the Paste button (below the menu bar), or choose Edit | Paste.

You can rename the copied server entries using the Rename command in the Server Object menu. See "Renaming a server entry" on page 107 for more information.

## UNIX platforms

## \* Copying a server entry to another interfaces file

- 1 Use one of the following methods to select the entries to copy:
  - To copy a single entry click it once.
  - To copy a range of consecutive entries click the first entry in the range, press and hold down Shift, and click the last entry in the range. You can also select "backwards" by clicking the last entry, holding down Shift, and clicking the first entry.
  - To select multiple, nonconsecutive entries press and hold down the Ctrl key while you click each entry.
- 2 Click Copy server entry.
- 3 Select the Sybase interfaces file from the list.
- 4 Edit the displayed file name.
- 5 Click OK.

# **Troubleshoot dsedit**

This section lists some common dsedit problems and describes how to correct them.

Problem	Solution
The dsedit utility does not	Check for the following:
start	• The SYBASE environment variable is not set or points to the wrong directory.
	• UNIX platforms X-Windows is not configured correctly. If you are running dsedit on a remote host, make sure that X-Windows clients on the remote host can connect to the X-Windows server on your own machine. See your X-Windows documentation for more troubleshooting information. If X-Windows is not available, use dscp instead of dsedit.
Error message: "Unable to open X display"	(UNIX platforms) dsedit might not work if the display machine is set up to reject X-Windows connections from remote hosts. If this is the problem, you see a message similar to the following:
	Unable to open X display. Check the value of your \$DISPLAY variable. If it is set correctly, use the 'xhost +' command on the display machine to authorize use of the X display. If no X display is available, run dscp instead of dsedit.
	This error may be caused by either of the following situations:
	• The value for the DISPLAY environment variable is not entered correctly or is not set.
	Solution: Enter the DISPLAY environment variable correctly.
	• You are not authorized to open windows on the machine to which DISPLAY refers.
	Solution: Run the command 'xhost +' on the display machine.
Cannot add, modify, or delete server entries	Check for permissions problems with the interfaces file. To edit interfaces entries, you must have write permission on both the interfaces file and the Sybase installation directory.

# CHAPTER 7 Utility Commands Reference

This chapter contains reference pages for the Adaptive Server utility program commands.

Торіс	Page
Getting started	114
Utilities quick reference	116
backupserver	120
ЬСР	126
buildmaster	142
certauth	143
certpk12	147
certreq	150
charset	154
cobpre	155
cpre	156
dataserver	157
ddlgen	165
defncopy	190
dscp	196
dsedit	197
extractjava	198
installjava	201
isql	205
langinstall	217
optdiag	220
preupgrade	227
pwdcrypt	232
qptune	233
showserver	246
sqldbgr	247
sqlloc	252
sqllocres	253
sqlsrvr	254

Торіс	Page
sqlupgrade	261
sqlupgraderes	262
srvbuild	263
srvbuildres	265
startserver	266
sybdiag	269
sybmigrate	276
xpserver	282

# **Getting started**

 UNIX
 You enter a utility program command at the system prompt in a UNIX shell.

 Windows
 If a utility:

- Has an icon in the Sybase for Windows or Sybase for the Windows program group, double-click the icon to launch the utility program.
- Does not have an icon in the program group, enter the utility program command at the Windows command prompt to launch the utility program.

Place characters with special meaning to the shell (the command prompt in Windows), such as the backslash (\), asterisk (\*), slash (/), and spaces, in quotes. You can precede some special characters with the backslash (\) to "escape" them. This prevents the shell (command prompt) from interpreting the special characters.

Table 7-1 describes the utility programs available with Adaptive Server.

**Note** The utility programs described in Table 7-1 may allow you to use a -P parameter to enter your password. If security is an issue, do not use this parameter to specify your password. Another user may have an opportunity to see it. Instead, log in as usual without the -P parameter, and let Adaptive Server prompt you for your password.

## Table 7-1: Utility programs

Utility	Description
backupserver	Executable form of the Backup Server <sup>™</sup> program.
bcp	Copies rows in a database table to or from an operating system file in a user-specified format.

Utility	Description
certauth	Converts a server-certificate request into a certificate authority-signed certificate.
certpk12	Export or import a PKCS#12 file.
certreq	Creates a server certificate request and corresponding private key in two ways:
charset	Loads the character sets and sort order files.
cobpre	Precompiler for COBOL.
cpre	Precompiler for C.
dataserver	Executable form of the Adaptive Server program.
ddlgen	Generates data definition language for server- and database-level objects in ASE.
defncopy	Copies definitions for specified views, rules, defaults, triggers, procedures, or reports from a database to an operating system file or from an operating system file to a database.
dscp	Allows you to view and edit server entries in the interfaces file in command-line mode.
dsedit	Allows you to view and edit server entries in the interfaces file using a graphical user interface based on X11/Motif.
extractjava	Copies a retained JAR from an Adaptive Server to a client file.
installjava	Installs a JAR from a client file into an Adaptive Server.
isql	Interactive SQL parser to Adaptive Server.
langinstall	Installs a new language on the Adaptive Server.
optdiag	Displays optimizer statistics or loads updated statistics into system tables.
preupgrade	Performs tests on an installation or database to determine its readiness for upgrade.
pwdcrypt	Creates and prints an encrypted LDAP password in the libtcl.cfg file.
qptune	Enables you to fix missing statistics and identify the best query plan, optimization goal, or other configuration settings, and apply them at the query or server level.
showserver	Shows Adaptive Servers and Backup Servers that are currently running on the local machine.
sqldbgr	Debugs stored procedures and triggers.
sqlloc	Installs and modifies languages, character sets, and sort order defaults for Adaptive Server in GUI mode.
sqllocres	Installs and modifies languages, character sets, and sort order defaults for Adaptive Server in command-line mode.
sqlsrvr	Executable form of the Adaptive Server program.
sqlupgrade	Upgrades your currently installed release of Adaptive Server to the newest release in GUI mode.
sqlupgraderes	Upgrades your currently installed release of Adaptive Server to the newest release in command-line mode.
srvbuild	Creates a new Adaptive Server, Backup Server, or XP Server in GUI mode with default or user-specified values for key configuration attributes.
srvbuildres	Creates a new Adaptive Server, Backup Server, or XP Server in command-line mode with default or user-specified values for key configuration attributes.
startserver	Starts an Adaptive Server or a Backup Server.
srvmgr	Starts Adaptive Server and Backup Server as Windows services.

Utility	Description
sybcluster	Manages a shared-disk cluster. See Chapter 8, "Using sybcluster to Manage the Cluster."
sybdiag	Collects comprehensive configuration and environment data for Adaptive Server.
sybload	Uploads Sybase products from the distribution media and builds the Sybase installation directory from the command line.
sybmigrate	Enables you to migrate database from a server using 2K logical pages to a server using 4, 8, or 16K logical pages.
sybsetup	Installs and configures Adaptive Server from a single location using a GUI interface.
xpserver	Starts XP Server manually.

## \*\_r utilities

Sybase provides you with the \_r versions of some of the utilities for use with threaded drivers.

The utilities in this manual that have \_r versions are:

- bcp
- cobpre
- cpre
- defncopy
- dscp
- isql

## **Utilities quick reference**

This section provides a quick reference for the utilities, divided into the following categories:

- "Installation or configuration utilities" on page 117
- "Utilities for languages, character sets, and sort orders" on page 117
- "Utilities to start servers" on page 118
- "Database creation and manipulation utilities" on page 118
- "Utilities to gather information" on page 119

- "Tuning utility" on page 119
- "Utility to manage a cluster" on page 119

## Installation or configuration utilities

	Use the following to install or configure databases:
dataserver	Allows you to build a new Adaptive Server.
dscp	Allows you to view and edit server entries in the interfaces file from the command line.
dsedit	Allows you to view and edit server entries in the interfaces file using a GUI based on X11/Motif in UNIX platforms.
	In Windows, allows you to create and modify network connection information in the interfaces file.
preupgrade	Performs tests on an installation or database to determine its readiness for upgrade, and reports problems found.
sqlupgrade	Upgrades your currently installed release of Adaptive Server to the newest release using a GUI based on X11/Motif in UNIX platforms.
sqlupgraderes	Upgrades your currently installed release of Adaptive Server to the newest release using resource files in UNIX platforms.
srvbuild	Creates a new Adaptive Server, Backup Server, or XP Server with default or user-specified values for key configuration attributes using a graphical user interface based on X11/Motif in UNIX platforms.
srvbuildres	Creates a new Adaptive Server, Backup Server, or XP Server, using resource files to specify values for key configuration attributes in UNIX platforms.

## Utilities for languages, character sets, and sort orders

	Use the following utilities to set languages, character sets and sort orders:
charset	Loads the character sets and sort order files in Windows.
langinstall	Installs a new language on an Adaptive Server.
sqlloc	Installs and modifies languages, character sets, and sort order defaults for Adaptive Server, using a GUI based on X11/Motif in UNIX platforms.

sqllocresInstalls and modifies languages, character sets, and sort order defaults for<br/>Adaptive Server, using a resource file in UNIX platforms.

## Utilities to start servers

	Use the following utilities to start servers manually:
backupserver	Starts the Backup Server executable. Use the startserver command instead of this utility to start Backup Server manually. In Windows, you can use the srvmgr utility instead to start Backup Server manually.
dataserver	Starts the Adaptive Server executable. Use the startserver command instead of this utility to start Adaptive Server manually.
sqlsrvr	Starts the Adaptive Server executable in Windows . Use the services manager utility instead of this utility to start Adaptive Server manually.
srvmgr	Starts, pauses, and stops Adaptive Server, Backup Server, and Adaptive Server Monitor <sup>TM</sup> as Windows services.
startserver	Starts an Adaptive Server and a Backup Server in UNIX platforms.

## Database creation and manipulation utilities

	Use the following utilities to create and manipulate databases:
bcp	Copies a database table to or from an operating system file in a user-specified format.
ddlgen	Generates data definition language for server- and database-level objects in ASE.
defncopy	Copies definitions for specified views, rules, defaults, triggers, or procedures from a database to an operating system file or from an operating system file to a database.
extractjava	Copies a retained JAR and the classes it contains from an Adaptive Server to a client file.
installjava	Installs a JAR from a client file into an Adaptive Server database.
isql	Interactive SQL parser to Adaptive Server.
optdiag	Displays optimizer statistics or loads updated statistics into system table.

## Utilities to gather information

	Use the following utilities to gather information:
showserver	Shows the Adaptive Servers and Backup Servers that are currently running on the local machine in UNIX platforms.
sybdiag	Collects comprehensive Adaptive Server configuration and environment data to help Sybase Technical Support diagnose server issues.
wdllvers	Provides information about the Sybase DLLs (dynamic link libraries) that are loaded into memory in Windows.

## **Tuning utility**

	Use the following utility to tune the Adaptive Server:
qptune	Enables you to fix missing statistics and identify the best query plan,
	optimization goal, or other configuration settings, and apply them at the query
	or server level.

## Utility to manage a cluster

(Cluster Edition only) Use the following utility to manage an Adaptive Server shared-disk cluster:

sybclusterProvides a set of interactive, command line options for creating and managing<br/>a cluster. See Chapter 8, "Using sybcluster to Manage the Cluster."

# backupserver

Description	The executable form of the Backup Server program, located in <i>\$SYBASE/\$SYBASE_ASE/bin</i> .
	(Windows) The utility is bcksrvr.exe, located in %SYBASE%\%SYBASE_ASE%\bin.
Syntax	backupserver [-C server_connections] [-S b_servername] [-I interfaces_file] [-e error_log_file] [-M sybmultbuf_binary] [-M network_connections] [-T trace_value] [-T trace_value] [-L Sybase_character_set_name] [-Sybase_character_set_name] [-C tape_config_file] [-D n] [-A pathname] [-P active_service_threads] [-V level_number] [-p n] [-m max_shared_memory]
	backupserver -v
Parameters	<ul> <li>-C server_connections specifies the number of server connections for the Backup Server. The Backup Server requires:</li> <li>Two connections for each dump session</li> <li>One connection for each load session</li> <li>One connection for volume change messages</li> <li>Allow a maximum of three times the number of expected concurrent dump and load sessions. The default value is 30 server connections.</li> <li>-S <i>b_servername</i> specifies the name of the Backup Server to start. The default is SYB_BACKUP. This entry must specify the name of a Backup Server in the interfaces file.</li> </ul>

## -l interfaces\_file

specifies the name and location of the interfaces file to search when connecting to Backup Server. If -I is omitted, backupserver looks for a file named *interfaces* in the directory pointed to by your SYBASE environment variable.

-v

prints the version number and copyright message of the backupserver software and then exits.

-e error\_log\_file

specifies the name and location of the Backup Server error log file used to report Open Server internal errors, sybmultbuf errors, errors that halt the Backup Server, and errors for disconnected sessions. All other errors are sent to the notify destination specified in the dump database, dump transaction, load database, and load transaction commands.

-M sybmultbuf\_binary

specifies the full path name of the sybmultbuf executable. Use this parameter only when starting Backup Server from a directory other than the *bin* directory of the Sybase installation directory, or when using a diagnostic version of sybmultbuf.

-N network\_connections

specifies the number of total network connections (DBPROCESSes) that the master Backup Server can originate. The default value is 25.

-T trace\_value

interprets *trace\_value* as a bitmask (base-2 number). The 1 bits in *trace\_value* correspond to Open Server Trace flags to turn on. If you specify more than one -T parameter on the command line, the final -T value overrides the values from earlier -T parameters. The *trace\_value* must be a positive integer.

-L Sybase\_language\_name

specifies the default language for Backup Server. If not specified, Backup Server uses the locale specified by the LC\_ALL or LANG environment variables. If these variables are not set, Backup Server searches for the "default" entry in *locales.dat*.

**Note** The -L parameter does not override the value set in the LANG environment variable.

-J Sybase\_character\_set\_name

specifies the default character set for Backup Server.

## -c tape\_config\_file

specifies the name and location of the tape configuration file to search for tape device configuration information before doing a dump database or a dump transaction. If you do not specify -c, the default path name for the tape configuration file is *\$SYBASE/backup\_tape.cfg*.

## -D n

specifies the bitmap (base 10 number) of the diagnostic flags used within Backup Server.

## -A pathname

specifies the pathname to the directory of the Archive API dynamically loadable library.

## -P active\_service\_threads

allows you to increase the number of stripes during multiple dump/load operations (with a maximum of 12286 stripes per single operation).

## -V level\_number

limits the messages that are printed to the Backup Server error log. The *level\_number* variable determines the degree of error verbosity (-V) for Backup Server:

- -V4 displays all -V0 messages except "Connection from Server" messages printed for each connection event.
- -V3 displays only completion messages from a normal dump or load command and the following types of messages:
  - Error messages from Backup Server and sybmultbuf
  - Other sybmultbuf messages
  - Volume change messages
  - Open Server<sup>TM</sup> messages
  - Trace print messages
  - Informational messages from the System & Tape Auto Config modules
- -V2 displays:
  - All -V3 messages plus
  - File creation and file mount messages
- -V1 displays:
  - All -V2 messages plus
  - Phase messages
- -V0 (default) displays all messages, including backup progress

This limitation does not involve the messages that are sent to the client or console as determined by the NOTIFY= parameter in a dump or load command.

This option also does not affect logging for the following message types:

- Open Server messages
- Trace printing messages from bs\_traceprint
- sybmultbuf messages

	-p <i>n</i> specifies the TDS packet size in bytes that the <b>local</b> Backup Server requests from the <b>remote</b> Backup Server during network dumps. The actual packet size used is limited to the -p parameter value of the remote Backup Server. If you do not specify -p, the default is 2048 bytes. The packet size should be an integer greater than, or equal to 256.
	-m max_shared_memory specifies the maximum amount of shared memory in megabytes that Backup Server can use for all of its dump or load sessions.
Usage	• Make sure that you use Backup Server 15.5 with Adaptive Server 15.5, both the clustered and nonclustered versions. Backup Server versions 15.0.3 and earlier do not work with Adaptive Server 15.5.
	• Start Backup Server with the startserver command rather than by directly executing the backupserver program.
	• To change default values in UNIX, edit the <i>RUN_servername</i> file in your Sybase installation directory. See the startserver reference page for details.
	• To change default values in Windows, use Server Config to change the command-line parameters of the Backup Server. See the <i>Configuration Guide</i> for details.
	• Make sure that the device driver options you include with the dump command are accurate. Backupserver does not verify any device driver options you include during a dump command. For example, if you include a option that forces Backupserver to rewind a tape before use, it will always rewind the tape to the beginning instead of reading the tape from the point of the dump.
	• If you do not specify a Backup Server name with the -S parameter, and you have not set the environment variable DSLISTEN, backupserver uses the default Backup Server name SYB_BACKUP in UNIX.
	(Windows) bcksrvr uses the default Backup Server name <i>server_name_BS</i> . The value of the DSLISTEN environment variable overrides this default value, and the -S parameter overrides both the default and the value specified in DSLISTEN.
	• Whenever possible, the Backup Server and any Adaptive Servers that dump or load directly through the Backup Server should share the same interfaces file ( <i>sql.ini</i> in UNIX). The interfaces file that Backup Server uses must contain entries for:
	Backup Server

•	Any other Backup Servers with which this Backup Server
	communicates

Trace flags cause the Backup Server to print information regarding its operation while it is running, for debugging problems in the Backup Server. See the *Open Server Server-Library/C Reference Manual* for more details on trace flags. Backup Server does not support use of the Open Server-defined SRV\_TR symbols for -T.

- If Backup Server cannot find the *locales* and *charsets* directories specified by the -L and -J parameters, or if these parameters specify an incorrect language and character set combination, Backup Server issues an error message and uses the default language and character set.
- Backup Server cannot perform loads or dumps between servers that use different logical page sizes. For example, you can load a 4K logical page sized database dump into another server using a 4K logical page size. But Backup Server does not support dumping a 4K logical page sized database and loading it into a database that uses 16K logical page size.
- Permissions Anyone with execute permission on the binary, and who has read/write access to all the files.

See also Utilities startserver

# bcp

Description	Copies a database table to or from an operating system file in a user-specified format. bcp is located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> .
	(Windows) The utility is bcp.exe, and is located in %SYBASE%\%SYBASE_OCS%\bin.
Syntax	<pre>bcp [[database_name.].wwner.]table_name [: [ partition_id   slice_number ]       partition_partition_name] {in   out} datafile     [-f formatfile]     [-e errifie]     [-d discardfileprefix]     [-F firstrow]     [-L lastrow]     [-b batchsize]     [-m maxerrors]     [-n]     [-c]     [-f field_terminator]     [-r row_terminator]     [-r tield_terminator]     [-Y password]     [-J username]     [-P password]     [-J display_charsef]     [-z language]     [-A packet_size]     [-T text_or_image_size]     [-T text_or_image_size]     [-E]     [-g id_start_value]     [-N]     [-X]     [-M LabelName LabelValue]     [-labeled]     [-K keytab_file]     [-Z security_options]]     [-Z]     [-Y]     [-y sybase directory]     [-x trusted.txt_file]     [-maxconn maximum_connections     [-show-fi]     [-hide-vcc]     [-colpasswd [[[database_name.[owner].table_name.]column_name     [-woldstart_value]     [-woldsta</pre>
	password

[--keypasswd [[database\_name.[owner].]key\_name [password]]] [--initstring 'Transact-SQL\_command']

## Or

#### Parameters

#### maxconn maximum\_connections

is the maximum number of parallel connections permitted for each bulk copy operation. The default is 10.

#### database\_name

bcp -v

is optional if the table being copied is in your default database or in master. Otherwise, you must specify a database name.

#### owner

is optional if you or the Database Owner owns the table being copied. If you do not specify an owner, bcp looks first for a table of that name that you own, and then looks for one owned by the Database Owner. If another user owns the table, you must specify the owner name or the command fails.

#### table\_name

is the name of the database table to copy. The table name cannot be a Transact-SQL reserved word.

#### partition\_id

specifies the partition number into which data is to be copied. It is supported only for bcp in. It is the equivalent of slice\_number in Adaptive Server 12.5.x.

#### slice\_number

specifies the partition slice into which data is to be copied. It is supported only for bcp in and only for round-robin partitioned tables in Adaptive Server 15.0 and later.

#### partition partition\_name

specifies a set of one or more partitions, separated by commas.

in | out

is the direction of the copy. in indicates a copy from a file into the database table; out indicates a copy to a file from the database table or view.

#### datafile

specifies a set of one or more unique data files, separated by commas. It is supported for both bcp in and bcp out. The path name can be from 1 to 255 characters in length.

## -f formatfile

is the full path name of a file with stored responses from a previous use of bcp on the same table. After you answer bcp's format questions, it prompts you to save your answers in a format file. Creation of the format file is optional. The default file name is *bcp.fmt*. The bcp program can refer to a format file when you are copying data so that you do not have to duplicate your previous format responses interactively. Use the -f parameter only if you previously created a format file that you want to use now for a copy in or copy out. If you do not specify this parameter, bcp interactively queries you for format information.

#### -e errfile

is the full path name of an error file where bcp stores any rows that it was unable to transfer from the file to the database. Error messages from bcp appear on your terminal. bcp creates an error file only when you specify this parameter.

## -d discardfileprefix

Logs the rejected rows into a dedicated discard file. The discard file has the same format as the host file and is created by appending the input file name to the discard file prefix supplied. You can correct the rows in this file and use the file to reload the corrected rows.

Sybase recommends that you use the -d *discardfileprefix* option in conjunction with -e *errorfile* to help identify and diagnose the problem rows logged in the discard file.

## -F firstrow

is the number of the first row to copy from an input file (default is the first row).

Avoid using the -F option when performing heavy-duty, multi-process copying, as it causes bcp to generally spend more effort to run, and does not provide you with a faster process. Instead, use -F for single-process, ad-hoc copying.

-L lastrow

is the number of the last row to copy from an input file (default is the last row). if multiple files are used, this option applies to each file.

## -b batchsize

is the number of rows per batch of data copied. By default, bcp in copies n rows in one batch, where n is equal to the batch size. Batching applies only when you are bulk copying in; it has no effect on bulk copying out. The smallest number bcp accepts for *batchsize* is 1. The largest number bcp accepts for *batchsize* is 2147483647L.

**Note** Setting the batch size to 1 causes Adaptive Server to allocate one data page to one row copied in. This option only applies to fast bcp, and is only useful in locating corrupt rows of data. Use -b1 with care—doing so causes a new page to be allocated for each row, and is a poor use of space.

## -m maxerrors

is the maximum number of nonfatal errors permitted before bcp aborts the copy. bcp discards each row that it cannot insert (due to a data conversion error, or an attempt to insert a null value into a column that does not allow them), counting each rejected row as one error. If you do not include this parameter, bcp uses a default value of 10.

-n

performs the copy operation using native (operating system) formats. Specifying the -n parameter means bcp will not prompt for each field. Files in native data format are not human-readable.

## Warning! Do not use:

- bcp in native format for data recovery or salvage or to resolve an emergency situation.
- bcp in native format to transport data between different hardware platforms, different operating systems, or different major releases of Adaptive Server.
- field terminators (-t) or row terminators (-r) with bcp in native format.

Results are unpredictable and data may become corrupted.

Using bcp in native format can create flat files that cannot be reloaded into Adaptive Server and it may be impossible to recover the data. If you cannot rerun bcp in character format (for example, a table was truncated or dropped, hardware damage occurred, a database was dropped, and so on) the data is unrecoverable. -C

performs the copy operation with char datatype as the default storage type of all columns in the data file. Use this format if you are sharing data between platforms. This parameter does not prompt for each field; it uses char as the default storage type, no prefixes,  $\t$  (tab) as the default field terminator, and  $\n$  (new line) as the default row terminator.

-t field\_terminator

specifies the default field terminator.

-r row\_terminator

specifies the row terminator.

**Warning!** Do not use -t or -r parameters with bcp in native format. Results are unpredictable and data may become corrupted.

When specifying terminators from the command line with the -t or -r parameter, you must escape characters that have special significance to the UNIX operating system (or the command prompt shell for Windows). See the examples for bcp for more information. Either place a backslash in front of the special character or enclose it in quotes. This is not necessary when bcp prompts you (interactive mode).

-U username

specifies an Adaptive Server login name.

-P password

specifies an Adaptive Server password. If you do not specify -P*password*, bcp prompts for a password. You can leave out the -P flag if your password is NULL.

-l interfaces\_file

specifies the name and location of the interfaces file to search when connecting to Adaptive Server. If you do not specify -I, bcp looks for an interfaces file (*sql.ini* in Windows) located in the directory specified by the SYBASE environment variable (*ini* directory in Windows).

-S server

specifies the name of the Adaptive Server to which to connect. If you specify -S with no argument, bcp uses the server specified by the DSQUERY environment variable.

-a display\_charset

allows you to run bcp from a terminal where the character set differs from that of the machine on which bcp is running. Use -a in conjunction with -J to specify the character set translation file (*.xlt* file) required for the conversion. Use -a without -J only if the client character set is the same as the default character set.

The following error message appears if the character translation file(s) named with the -a parameter is missing, or you mistype the name(s):

```
Error in attempting to determine the size of a pair of translation tables.:'stat' utility failed.
```

-z language

is the official name of an alternate language the server uses to display bcp prompts and messages. Without the -z flag, bcp uses the server's default language.

You can add languages to an Adaptive Server during installation or afterwards, using either the langinstall utility (or langinst in Windows) or the sp\_addlanguage stored procedure.

The following error message appears if an incorrect or unrecognized language is named with the -z parameter:

```
Unrecognized localization object. Using default value
'us_english'.
Starting copy...
=> warning.
```

-v

displays the version number of bcp and a copyright message and returns to the operating system.

-A packet\_size

specifies the network packet size to use for this bcp session. For example, the following sets the packet size to 4096 bytes for this bcp session:

bcp pubs2..titles out table\_out -A 4096

*packet\_size* must be between the values of the default network packet size and maximum network packet size configuration variables, and it must be a multiple of 512.

Use network packet sizes larger than the default to improve the performance of large bulk-copy operations.

-J client\_charset

specifies the character set to use on the client. bcp uses a filter to convert input between *client\_charset* and the Adaptive Server character set.

-J *client\_charset* requests that Adaptive Server convert to and from *client\_charset*, the character set used on the client.

-J with no argument sets character set conversion to NULL. No conversion takes place. Use this if the client and server use the same character set.

Omitting -J sets the character set to a default for the platform, which may not necessarily be the character set that the client is using.

This error message appears if an incorrect or unrecognized character set is named with the -J parameter:

```
Unrecognized localization object. Using default value
'iso_1'.
Starting copy...
=> warning.
```

For more information about character sets and associated flags, see the *System Administration Guide*.

-T text\_or\_image\_size

allows you to specify, in bytes, the maximum length of text or image data that Adaptive Server sends. The default is 32K. If a text or an image field is larger than the value of -T or the default, bcp does not send the overflow.

## -E

explicitly specifies the value of a table's IDENTITY column.

By default, when you bulk copy data into a table with an IDENTITY column, bcp assigns each row a temporary IDENTITY column value of 0. This is effective only when copying data into a table. bcp reads the value of the ID column from the data file, but does not send it to the server. Instead, as bcp inserts each row into the table, the server assigns the row a unique, sequential, IDENTITY column value, beginning with the value 1. If you specify the -E flag when copying data into a table, bcp reads the value from the data file and sends it to the server which inserts the value into the table. If the number of rows inserted exceeds the maximum possible IDENTITY column value, Adaptive Server returns an error.

The -E parameter has no effect when you are bulk copying data out. Adaptive Server copies the ID column to the data file, unless you use the -N parameter.

You cannot use the -E and -g flags together.

## -g id\_start\_value

specifies the value of the IDENTITY column to use as a starting point for copying data in.

You cannot use the -g and -E flags together.

## -N

skips the IDENTITY column. Use this parameter when copying data in if your host data file does not include a placeholder for the IDENTITY column values, or when copying data out, if you do not want to include the IDENTITY column information in the host file.

You cannot use both -N and -E parameters when copying data in.

## -W

specifies that if the server to which bcp is attempting to connect supports neither normal password encryption nor extended password encryption, plain text password retires are disabled. If this option is used, the CS\_SEC\_NON\_ENCRYPTION\_RETRY connection property will be set to CS\_FALSE, and plain text (unencrypted) passwords will not be used in retrying the connection.

## -X

specifies that, in this connection to the server, the application initiates the login with client-side password encryption. bcp (the client) specifies to the server that password encryption is desired. The server sends back an encryption key, which bcp uses to encrypt your password, and the server uses the key to authenticate your password when it arrives.

If bcp crashes, the system creates a core file that contains your password. If you did not use the encryption option, the password appears in plain text in the file. If you used the encryption option, your password is not readable.

## -M LabelName LabelValue

(secure Adaptive Server only) enables multilevel users to set the session labels for the bulk copy. Value values for *LabelName* are:

- curread (current reading level) is the initial level of data that you can read during this session, curread must dominate curwrite.
- curwrite (current write level) is the initial sensitivity level that will be applied to any data that you write during this session.
- maxread (maximum read level) is the maximum level at which you can read data. This is the upper bound to which you as a multilevel user can set your curread during the session. maxread must dominate maxwrite.
- maxwrite (maximum write level) is the maximum level at which you can write data. This is the upper bound to which you as a multilevel user can set your curwrite during a session. maxwrite must dominate minwrite and curwrite.
- minwrite (minimum write level) is the minimum level at which you can write data. This is the lower bound to which you as a multilevel user can set curwrite during a session. minwrite must be dominated by maxwrite and curwrite.

*LabelValue* is the actual value of the label, expressed in the human-readable format used on your system (for example, "Company Confidential Personnel").

## -labeled

(secure Adaptive Server only) indicates that the data you are importing already has labels in the first field of every record.

For exporting data, this option indicates that you want the sensitivity label of every row to be copied out as the first field.

## -K keytab\_file

specifies the path to the keytab file used for authentication in DCE.

## -R remote\_server\_principal

specifies the principal name for the server as defined to the security mechanism. By default, a server's principal name matches the server's network name (which is specified with the -S parameter or the DSQUERY environment variable). Use the -R parameter when the server's principal name and network name are not the same.

-C

supports bulk copy of encrypted columns if Adaptive Server supports encrypted columns. -C enables the ciphertext option before initiating the bulk copy operation.

-V security\_options

specifies network-based user authentication. With this option, the user must log in to the network's security system before running the utility. In this case, users must supply their network user name with the -U option; any password supplied with the -P option is ignored.

You can follow -V with a *security\_options* string of key-letter options to enable additional security services. These key letters are:

- c enables data confidentiality service
- i enables data integrity service
- m enables mutual authentication for connection establishment
- o enables data origin stamping service
- r enables data replay detection
- q enables out-of-sequence detection
- -i input\_file

specifies the name of the input file. The Standard Input is used as the default.

-o output\_file

specifies the name of the output file. The Standard Output is used as the default.

-Z security\_mechanism

specifies the name of a security mechanism to use on the connection.

Security mechanism names are defined in the *\$SYBASE/install/libtcl.cfg* configuration file. If no *security\_mechanism* name is supplied, the default mechanism is used. For more information on security mechanism names, see the description of the *libtcl.cfg* file in the *Open Client and Open Server Configuration Guide*.

-Q

provides backward compatibility with bcp version 10.0.4 for copying operations involving nullable columns.

#### -Y

specifies that character-set conversion is disabled in the server, and is instead performed by bcp on the client side when using bcp in.

**Note** A client-side Unicode conversion is supported only for Adaptive Server 15.0 and later.

All character-set conversion is done in the server during bcp out.

```
-y sybase_directory
```

sets an alternate Sybase home directory.

```
-x trusted.txt_file
```

specifies an alternate trusted.txt file.

#### --maxconn maximum\_connections

is the maximum number of parallel connections that the bcp client can open to the server. If --maxconn is not specified, bcp determines the number of connections to use.

--show-fi

instructs bcp to copy functional indexes, while using either bcp in or bcp out.

Using this option sends the data from a functional index to or from the server.

#### --hide-vcc

instructs bcp not to copy virtual computed columns either to or from a datafile. When you use this option in bcp OUT, the data file contains no data for virtual computed columns. When you use it in bcp IN, the data file may contain no data for a virtual computed column.

If you use this option, Adaptive Server does not calculate or send virtual computed column data.

--colpasswd [[database\_name [owner].]table\_name.]column\_name [password]]] sets the passwords for encrypted columns by sending set encryption passwd password for column column\_name to Adaptive Server. This does not automatically apply passwords to other encrypted columns, even if the second column is encrypted with the same key. The password must be supplied a second time to access the second column.

## --keypasswd [[database\_name.[owner].]key\_name [password]]] sets passwords for all columns accessed by a key by sending set encryption passwd **password** for key **key\_name** to Adaptive Server.
--initstring ["Transact-SQL\_command"]

sets any Transact-SQL command as an initialization string for the current isql session only. Result sets issued by the initialization string are silently ignored, unless an error occurs.

Examples Example 1 Copies data from the publishers table to a file named *pub\_out* with char datatype as the default storage type of all columns in the data file, specifying the default field terminator and row terminator.

In UNIX, the first backslash before the final "r" escapes the second so that only one backslash is printed:

```
bcp pubs2..publishers out pub_out -c -t , -r \\r
```

In Windows:

bcp pubs2..publishers out pub\_out -c -t , -r \r

**Example 2** Copies data from the publishers table to a file named *pub\_out* for later reloading into Adaptive Server. Press Return to accept the defaults specified by the prompts. The same prompts appear when you copy data into the publishers table:

```
bcp pubs2..publishers out pub_out
Password:
Enter the file storage type of field pub id [char]:
Enter prefix length of field pub id [0]:
Enter length of field pub id [4]:
Enter field terminator [none]:
Enter the file storage type of field pub name [char]:
Enter prefix length of field pub name [1]:
Enter length of field pub name [40]:
Enter field terminator [none]:
Enter the file storage type of field city [char]:
Enter prefix length of field city [1]:
Enter length of field city [20]:
Enter field terminator [none]:
Enter the file storage type of field state [char]:
Enter prefix length of field state [1]:
Enter length of field state [2]:
Enter field terminator [none]:
```

In UNIX, you are then asked:

Do you want to save this format information in a file? [Y-n] y Host filename [bcp.fmt]: pub\_form Starting copy... 3 rows copied. Clock Time (ms.): total = 1 Avg = 0 (3000.00 rows per sec.)

**Example 3** Copies data back into Adaptive Server using the saved format file, *pub\_form*:

bcp pubs2..publishers in pub out -f pub form

**Example 4** Enter the single letter exactly as it appears below:

```
To see examples of datatypes, enter "?" at the prompt:
Enter the file storage type of field 'pub id'
    ['char']:?
Invalid column type. Valid types are:
<cr>: same type as Adaptive Server column.
   c : char
   T : text
    i : int
    s : smallint
    t : tinyint
   f : float
   m : money
   b : bit
    d : datetime
   x : binary
    I : image
   D : smalldatetime
   r : real
   M : smallmoney
   n : numeric
    e : decimal
```

**Example 5** Copies a data file created with a character set used on a VT200 terminal into the pubs2..publishers table. The -z flag displays bcp messages in French:

```
bcp pubs2..publishers in vt200 data -J iso 1 -z french
```

**Example 6** (UNIX) Specifies that you are using a Macintosh, running bcp on a workstation that is using roman8:

bcp pubs2..publishers in -a mac -J roman8

**Example 7** Specifies that Adaptive Server send 40K of text or image data using a packet size of 4096 bytes:

bcp pubs2..publishers out -T 40960 -A 4096

**Example 8** Sets 2 as the maximum number of parallel connections permitted for each operation.

bcp r --maxconn 2

**Example 9** Copies the *mypart.dat* file of the current directory to partition p1 of table t1.

bcp t1 partition p1 in mypart.dat

**Example 10** Copies partition p1, p2, and p3 to files *a*, *b*, and *c* respectively, into the |work2| data directory.

bcp t1 partition p1, p2, p3 out \work2\data\1, \work2\data\b, \work2\data\c

**Example 11** Limits this to the current session, disabling replication for the bcp connection during the transfer of data from *titles.txt* data into pubs2..titles.

bcp pubs2..titles in titles.txt --initstring 'set replication off'

You need not explicitly reset the configuration option after bcp is finished. If Adaptive Server returns an error, bcp stops the data transfer and displays an error message.

**Example 12** Copies out database db\_1, which includes table t1 with materialized computed column c1:

bcp db 1..t1 out db 1.dat -Usa -P -S big db -I./interfaces -f ./bcp.fmt

**Example 13** Copies in the data file (*db\_1.dat*) created in Example 12, containing table t1 with materialized computed column c1:

bcp db 1..t1 in db 1.dat -Usa -P -S big db -I./interfaces -f ./bcp.fmt

Usage

- Use this syntax for bcp if you are using threaded drivers.
- You cannot use named pipes to copy files in or out.
- You can use bcp to copy encrypted data in and out of the server. See "Bulk copying encrypted data" on page 44.
- Error message format is different than earlier versions of bcp. If you have scripts that perform routines based on the values of these messages you may need to rewrite them, for example:

The display message that indicates the number of rows transferred has been changed. During a session, this version of bcp periodically reports a running total of rows transferred. This message replaces the "1000 rows transferred" message displayed by the previous bcp.

• Using --hide-vcc improves performance because Adaptive Server does not transfer and calculate data from virtual computed columns.

- *slice\_number* is included for backward compatibility with Adaptive Server 12.5.x and earlier, and can be used only with round-robin partitioned tables.
- You can specify either *partition\_id* or *partition\_name*, but not both.
- You can specify multiple partitions and data files. Separate each partition name or data file name with commas.
- If you provide no partition name, bcp copies to the entire table.
- When using bcp out:
  - If *partition\_name* and *datafile* are both specified, then either *datafile* must specify a single data file, or you must specify a one-to-one mapping between partition names and data files.
  - If *datafile* is not specified, data from each partition is copied to a file named for the named partition with a *.dat* extension. For example, if the partition name is ptn1, the data file is *ptn1.dat*.
- You can use initstring to run any Transact-SQL command, but you must reset any permanent changes to the server initstring causes after bcp finishes. For instance, as in Example 11 above, if the Adaptive Server account doesn't have the appropriate permissions, Adaptive Server returns an error message for the initialization string. bcp displays the server error message and stops before any data is transferred.

Result sets issued by the initialization string are silently ignored unless an error occurs.

• When using bcp in, if *partition\_name* is specified, *datafile* must specify a corresponding number of data files

Using bcp with compressed data

Pages in a compressed table may have a combination of row-, page- or uncompressed rows. Tables and partitions listed as not compressed may contain a mixture of rows in different states of compression because you created them at times when the table's compression level was different.

- bcp out
  - Decompresses compressed rows and returns them to the client, either in native or character form.
  - Supports IDENTITY, encrypted columns, and so on.
  - Returns text data as uncompressed.

• bcp in compresses uncompressed data received from the client according to the table or partition's compression level.

Using bcp to copy data out and then bcp it back in to a table configured for compression results in compressed data, even if the data was originally uncompressed.

Permissions You must have an Adaptive Server account and the appropriate permissions on the database tables or views, as well as the operating system files to use in the transfer to use bcp.

- To copy data into a table, you must have insert permission on the table.
- To copy a table to an operating system file, you must have select permission on the following tables:
  - The table to copy
  - sysobjects
  - syscolumns
  - sysindexes

Auditing

Values in event and extrainfo columns are:

Event	Audit option	Command or access audited	Information in extrainfo
4	bcp	bcp in	• <i>Roles</i> – Current active roles
			• <i>Keywords or options</i> – NULL
			Previous value – NULL
			<i>Current value</i> – NULL
			• Other information – NULL
			<ul> <li>Proxy information – Original login name, if set proxy in effect</li> </ul>

Tables used	sysaudits_01 – sysaudits_08
See also	Commands insert
	<b>Documentation</b> Chapter 4, "Transfer Data to and from Adaptive Server with bcp" for an in-depth discussion of bcp, and the <i>Performance and Tuning Guide</i> for more information on how changing certain parameters can affect bcp for large batches.

Sytem procedures sp\_audit, sp\_dboption, sp\_displayaudit

# buildmaster

Description	Adaptive Server version 12.5 and later no longer uses the buildmaster binary to build the master device. Instead, Sybase has incorporated the buildmaster functionality in the dataserver binary. See Chapter 1, "Building Servers Using
	dataserver" for more information, and dataserver on page 157 for syntax.
Syntax	None.

## certauth

Description	Converts a server certificate request to a CA- (certificate authority) signed certificate. Located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> .
	(Windows) The utility is certauth.exe, and is located in %SYBASE%\%SYBASE_OCS%\bin.
Syntax	certauth [-r] [-C caCert_file] [-Q request_filename] [-K caKey_filename] [-N serial_number [-O SignedCert_filename] [-P caPassword] [-s start_time] [-T valid_time]
	Or
	certauth -v
Parameters	-r when specified, creates a self-signed root certificate for the test environment.
	-C caCert_file specifies the name of the CA's certificate request file when -r is specified, or specifies the name of the CA's root certificate.
	-Q request_filename specifies the name of certificate request file.
	-K caKey_filename specifies the name of the CA's private key.
	-N serial_number specifies the serial number in the signed certificate. If -N is not specified, certauth generates a pseudo-random serial number.
	-O SignedCert_filename specifies the name to use for the output when creating a signed certificate file. If -r is specified, SignedCert_filename is the self-signed root certificate. If -r option is not used, SignedCert_filename is the certificate signed by the caCert_file.
	-P caPassword specifies the CA's password that is used to decrypt its private key.

	-s start_time specifies the start of the valid time range, measured in days from the current time. The default is the current time.
	-T <i>valid_time</i> specifies the length of the valid time range for a signed certificate. The valid time range is in units of days.
	-v prints the version number and copyright message of the certauth tool, then exits.
Examples	<b>Example 1</b> Converts the CA's certificate request ( <i>ca_req.txt</i> ) to a certificate, using the private key ( <i>ca_pkey.txt</i> ). The private key is protected using <i>password</i> . This example sets the valid time range to 365 days, self-signs the certificate, and outputs it as a root certificate ( <i>trusted.txt</i> ):
	certauth -r -C ca_req.txt -Q ca_req.txt -K ca_pkey.txt -P password -T 365 -O trusted.txt
	The utility returns this message:
	Sybase Test Certificate Authority Certificate Validity: startDate = Tue Sep 5 10:34:43 2000 endDate = Wed Sep 5 10:34:43 2001 CA sign certificate SUCCEED (0)

**Note** You need to create a trusted root certificate for the test CA only once. After you have created the trusted root certificate, you can use it to sign many server certificates in your test environment.

**Example 2** Converts a server certificate request (*srv5\_req.txt*) to a certificate, and sets the valid time range to 180 days. It signs the certificate with a CA's certificate and private key (*trusted.txt* and *ca\_pkey.txt*), uses password protection, and outputs the signed certificate as *sybase\_srv5.crt*:

```
certauth -C trusted.txt -Q srv5_req.txt
    -K ca_pkey.txt -P password -T 180 -O sybase_srv5.crt
```

**Note** If you do not set valid time, the default is 365 days.

The utility returns this message:

```
-- Sybase Test Certificate Authority -- Certificate Validity:
```

startDate = Tue Sep 5 10:38:32 2000
endDate = Sun Mar 4 09:38:32 2001
CA sign certificate SUCCEED (0)

The following is a sample certificate. See the certauth Usage section for additional steps to take to create a server certificate that the server can use.

```
----BEGIN CERTIFICATE-----
```

MIICSTCCAgUCAVAwCwYHKoZIzjgEAwUAMG8xCzAJBgNVBAYTAlVTMRMwEQYDVQQI EwpDYWxpZm9ybmlhMRMwEQYDVQQHEwpFbWVyeXZpbGxlMQ8wDQYDVQQKFAZTeWh c2UxDDAKBgNVBAsUA0RTVDEXMBUGA1UEAxQOc3liYXNlX3Rlc3RfY2EwHhcNMDAw ODE4MTkxMzM0WhcNMDEwODE4MTkxMzM0WjBvMQswCQYDVQQGEwJVUzETMBEGAUE CBMKQ2FsaWZvcm5pYTETMBEGA1UEBxMKRW1lcnl2aWxsZTEPMA0GA1UEChQGU3li YXNlMQwwCgYDVQQLFANEU1QxFzAVBgNVBAMUDnN5YmFzZV90ZXN0X2NhMIHwMIo BgcqhkjOOAQBMIGCAkEA+6xG7XCxiklxbP96nHBnQrTLTCjHlcy8QhIekwv90lqG EMG9AjJLxj6VCkPOD75vqVMEkaPPjoIbXEJEe/aYXQIVAPyvY1+B9phC2e2YFcf7 cReCcSNxAkBHt7rn0JZ1Dnd8iLQGt0wd1w4lo/Xx20eZS4CJW0KVKkGId1hNGz8r GrQTspWcwTh2rNGbXx1NXhAV5g4OCgrYA0MAAkA70uNE190Kmhdt3RISiceCMgOf 1J8dgtWF15mcHeS80mF9s/vqPAR5NkaVk7LJK6kk7QvXUBY+8LMOugpJf/TYMASG ByqGSM44BAMFAAMxADAuAhUAhM21cn1pSavQtXFzXJUCoOmNLpkCFQDtE8RUGuo8

ZdxnQtPu9uJDmoBiUQ==

----END CERTIFICATE----

Usage

- Adaptive Server includes the openssl open source utility in \$SYBASE/\$SYBASE\_OCS/bin (%SYBASE%\%SYBASE\_OCS%\bin in Windows). Use openssl to accomplish all certificate management tasks implemented by certreq, certauth and certpk12. Sybase includes this binary as a convenience, and is not responsible for any issues incurred using the binary. See the OpenSSL Web site at http://www.openssl.org for details.
- The maximum length of the serial number in the -N option is 20 hexadecimal characters. If the specified serial number is longer, certauth truncates the serial number to the maximum length.
- Running certauth requires that you place the entry for \$SYBASE/\$SYBASE\_OCS/lib3p before the entry for \$SYBASE/\$SYBASE\_OCS/libp364 in the dynamic library search path
- To create a server certificate file that Adaptive Server understands, append the certificate requestor's private key to the end of the signed certificate file. Using example 2 above, you would cut and paste *srv5\_pkey.txt* to the end of the signed certificate file, *sybase\_srv5.crt*.

	• To create a trusted roots file that the server can load upon start-up, rename <i>trusted.txt</i> to <i>sybase_srv5.txt</i> where <i>sybase_srv5.txt</i> is the common name of the server.
	• Then copy the <i>sybase_srv5.txt</i> file into the Adaptive Server installation directory, for example, <i>\$SYBASE/\$SYBASE_ASE/certificates</i> .
	• The options -s and -T together specify the time range for the certificate.
	The file, which is required for an SSL-based session, is used to start the SSL-enabled Adaptive Server.
	After the CA's root certificate is created, you can use it to sign multiple server certificates.
See also	Utilities certpk12, certreq

certpk12	
Description	Export or import a PKCS #12 file into a certificates file and a private key. Located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> .
	(Windows) The utility is certpk12.exe, and is located in %SYBASE%\%SYBASE_OCS%\bin.
Syntax	certpk12 {-O Pkcs12_file   -I Pkcs12_file} [-C Cert_file] [-K Key_file] [-P key_password] [-E Pkcs12_password]
	Or
	certpk12 -v
Parameters	-O <i>Pkcs12_file</i> specifies the name of a PKCS #12 file to be exported. The file can contain a certificate plus a private key, a single certificate, or a single private key. Either -O or -I needs to be on.
	-I <i>Pkcs12_file</i> specifies the name of a PKCS #12 file to be imported. The file can contain a certificate plus a private key, a single certificate, or a single private key. Either -I or -O needs to be on.
	-C Cert_file specifies the name of certificate file to be exported to a PKCS #12 file if -O is on; or the name of certificate file to be imported from a PKCS #12 file if -I is on.
	-K Key_file specifies the name of private key file to be exported to a PKCS #12 file if -O is on; or the name of private key file to be imported from a PKCS #12 file if -I is on.
	-P <i>Key_password</i> specifies the password which is used to protect the private key specified by -K. If -O is on, the password is required to export the private key to a PKCS #12 file; if -I is on, the password is required to output the private key to a text file after it is imported from a PKCS #12 file.

```
-E Pkcs12_password
                            specifies the password used to protect the PKCS #12 file. If -O is on, the
                            password is used to encrypt the PKCS #12 file to be exported; if -I is on, the
                            password is used to decrypt the PKCS #12 file to be imported. The password
                            is also called "transport password."
                         -v/
                            prints the version number and copyright message of the certpk12 tool and
                           exits.
Examples
                         Example 1 Exports caRSA.crt, the certificate file and caRSApkey.txt, the
                         private key file, to a PKCS#12 file (caRSA.p12). password is the password
                         used to decrypt caRSApkey.txt. pk12password is the password used to encrypt
                         the final caRSA.p12:
    certpk12 -O caRSA.p12 -C caRSA.crt -K caRSApkey.txt
         -P password -E pk12password
    -- Sybase PKCS#12 Conversion Utility certpk12 Thu Nov 9 16:55:51 2000--
                         Example 2 Imports caRSA.p12, a PKCS #12 file that contains a certificate and
```

a private key. Output the embedded certificate to a text file (*caRSA\_new.crt*) and the embedded private key to a text file (*caRSA\_pkey\_new.txt*):

```
certpk12 -I caRSA.p12 -C caRSA_new.crt -K caRSApkey_new.txt
    -P new_password -E pk12password
```

-- Sybase PKCS#12 Conversion Utility certpk12 Thu Nov 9 16:55:51 2000--

*new\_password* is used to protect *caRSApkey\_new.txt*, and *pk12password* is required to decrypt *caRSA.p12* file.

**Note** After you run examples 1 and 2, *caRSA.crt* and *caRSA\_new.crt* are identical. *caRSApkey.txt* and *caRSApkey\_new.txt* are different because they are encrypted randomly.

**Example 3** Exports the certificate file (*caRSA.crt*) to a PKCS#12 file (*caRSAcert.p12*). *pkcs12password* is used to encrypt *caRSAcert.p12*.

```
certpk12 -O caRSAcert.p12 -C caRSA.crt -E pk12password
```

-- Sybase PKCS#12 Conversion Utility certpk12 Thu Nov 9 16:55:51 2000--

**Example 4** Imports a PKCS#12 file (*caRSAcert.p12*) that contains a certificate. Output the embedded certificate to a text file (*caRSAcert.txt*).

certpk12 -I caRSAcert.p12 -C caRSAcert.txt -E pk12password

```
-- Sybase PKCS#12 Conversion Utility certpk12 Thu Nov 9 16:55:51 2000--
```

pk12password is required to decrypt caRSAcert.p12 file.

**Note** After you run Examples 3 and 4, the *caRSA.crt* and *caRSA.crt*.txt, are identical.

 Adaptive Server includes the openssl open source utility in \$SYBASE/\$SYBASE\_OCS/bin (%SYBASE%)%SYBASE\_OCS%\bin in Windows). Use openssl to accomplish all certificate management tasks implemented by certreq, certauth and certpk12. Sybase includes this binary as a convenience, and is not responsible for any issues incurred using the binary. See the OpenSSL Web site at http://www.openssl.org for details.

- certpk12 only supports triple-DES encrypted PKCS #12 file.
- Running certpk12 requires that you place the entry for \$SYBASE/\$SYBASE\_OCS/lib3p before the entry for \$SYBASE/\$SYBASE\_OCS/libp364 in the dynamic library search path
- Append certificate requestor's private key to the end of its signed certificate file.
- Name the file *servername.crt*, where *servername* is the name of the server. Place it in the certificates directory under *\$SYBASE/\$SYBASE\_ASE* (%SYBASE%\%SYBASE\_ASE% on Windows).

This file is needed to start the SSL-enabled Adaptive Server.

See also

Usage

Utilities certauth, certreq

## certreq

Description	Creates a server certificate request and corresponding private key. This utility can be used in interactive mode, or you can provide all optional parameters on the command line. Located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> .
	(Windows) The utility is certreq.exe, and is located in %SYBASE%\%SYBASE_OCS%\bin.
Syntax	certreq [-F <i>input_file</i> ] [-R <i>request_filename</i> ] [-K <i>PK_filename</i> ] [-P <i>password</i> ]
	Or
	certreq -v
Parameters	-F <i>input_file</i> specifies the file name that contains attribute information to build a certificate request. If you do not specify an <i>input_file</i> name, the required information must be interactively entered by a user.
	The <i>input_file</i> needs an entry for each of the following:
	<pre>req_certtype={Server, Client} req_keytype={RSA, DSA} req_keylength={for RSA: 512-4096;</pre>

Note The common name must be the same as the server name.

See the Examples section for a sample file called *input\_file*.

```
-R request_filename
```

specifies the name for the certificate-request file.

-K PK\_filename

specifies the name for the private-key file.

-P password

specifies the password used to protect the private key.

-V

displays the version number and copyright message, then exits.

Examples

**Example 1** This example does not use the -F *input\_file* parameter, and is therefore in interactive mode. To create a server certificate request (*server\_req.txt*) and its private key (*server\_pkey.txt*), enter:

```
certreq
   Choose certificate request type:
       S - Server certificate request
       C - Client certificate request (not supported)
       Q - Quit
   Enter your request [Q] : s
   Choose key type:
       R - RSA key pair
       D - DSA/DHE key pair
       Q - Quit
   Enter your request [Q] : r
   Enter key length (512, 768, 1024 for DSA; 512-2048 for
   RSA) : 512
   Country: US
   State: california
   Locality: dublin
   Organization: sybase
   Organizational Unit: dst
   Common Name: server
The utility returns the message:
   Generating key pair (please wait) . . .
After the key pair is generated, the certreq utility prompts you for more
information.
   Enter password for private key : password
   Enter file path to save request: server_req.txt
```

Enter file path to save private key : server\_pkey.txt

**Example 2** In this sample text file, the format, *tag=value*, is used for noninteractive entry for a certificate request. You can use the -F option for noninteractive mode. When you use the -F option, be sure to use valid values and follow the format described above. Failure to do so prevents the certificate from being built correctly.

```
certreq -F input_file
req_certtype=server
req_keytype=RSA
req_keylength=512
req_country=us
req_state=california
req_locality=dublin
req_organization=sybase
req_orgunit=dst
req_commonname=server
```

After you create and save this file, enter on the command line, where *path\_and\_file* is the location of the text file:

```
certreq -F path_and_file -R server_req.txt -K server_pkey.txt -P password
```

This file creates a server certificate request, *server\_req.txt*, and its private key, *server\_pkey.txt* which is protected by *password*.

You can edit the server certificate file with any standard ASCII text editor.

Usage

- Adaptive Server includes the openssl open source utility in \$SYBASE/\$SYBASE\_OCS/bin (%SYBASE%\%SYBASE\_OCS%\bin in Windows). Use openssl to accomplish all certificate management tasks implemented by certreq, certauth and certpk12. Sybase includes this binary as a convenience, and is not responsible for any issues incurred using the binary. See the OpenSSL Web site at http://www.openssl.org for details.
  - The input file uses the format of *tag=value*. *tag* is case-sensitive and should be the same as described above.
  - Running certreq requires that you place the entry for \$SYBASE/\$SYBASE\_OCS/lib3p before the entry for \$SYBASE/\$SYBASE\_OCS/libp364 in the dynamic library search path
  - The "=" is required. Valid *value* should start with a letter or digit, must be a single word, and there should not be any spaces within *value*.
  - *value* is required for *req\_certtype*, *req\_keytype*, *req\_keylength* and *req\_commonname*.

- The space or tab around <*tag*>, = and *value* is allowed. Blank lines are also allowed.
- Each comment line should start with #.
- The certificate request file is in PKCS #10 format and used as acceptable input for the certauth tool to convert the request to a CA-signed certificate.

See also Utilities certauth, certpk12

## charset

Description	(UNIX only) Loads the character sets and sort order files in Adaptive Server. Located in <i>\$SYBASE/\$SYBASE_ASE/bin</i> .
Syntax	charset [-Ppassword] [-Sserver] [-linterface] sort_order [ charset ]
	Or
	charset -v
Parameters	-P password specifies your password. If you do not specify -P, charset prompts for your password.
	-S server specifies the name of the server on which to change the character set and sort order.
	-l interface specifies the network interface used by the server.
	sort_order specifies the name of the sort order file Adaptive Server will use.
	charset specifies the character set Adaptive Server will use.
	-v displays the version number and copyright message for charset.
Usage	• Before using charset, you must set your SYBASE environment variable to point to the current release directory.
Permissions	You must be a System Administrator to use charset.
See also	Commands set
	Utilities langinstall

# cobpre

Description	Precompiler for COBOL, located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> (% <i>SYBASE%\%SYBASE_OCS%\bin</i> in Windows). For a full description of cpre, see Appendix A of the <i>Open Client and Open Server Programmer's Supplement</i> .
Syntax	See above.

## cpre

Description	Precompiler for C, located in <i>\$SYBASE_\$SYBASE_OCS/bin</i> ( <i>%SYBASE%\%SYBASE_OCS%\bin</i> in Windows). For a full description of cpre, see Appendix A of the <i>Open Client and Open Server Programmer's Supplement</i> .
Syntax	See above.

## dataserver

Description	(UNIX only) The executable form of the Adaptive Server program, located in <i>\$SYBASE/\$SYBASE_ASE/bin</i> .
Syntax	dataserver [-f] [-g] [-G] [-h] [-H] [-m] [-q] [-v] [-X] [-a path_to_CAPs_directive_file] [-b master_device_size [k   K   m   M   g   G   t   T] ] [-c config_file_for_server] [-d device_name] [-e path_to_error_log] [-i interfaces_file_directory] [-K keytab_file] [-L config_file_name_for_connectivity] [-M shared_memory_repository_directory] [-N licinstant] [-n sa_login_name [-p sa_login_name] [-r mirror_disk_name] [-s server_name] [-T trace_flag] [-u sa/sso_name] [-w master   model database] [-y [password] ] [-z page_size [ k   K ] ] Syntax for the Cluster Edition:
	dataserver -u,admin-name=sa/sso_name buildquorum=[force] -a,caps-file=filename -F,cluster-input=filename cluster-takeover -L,conn-config-file=[filename] create-cluster-id [=quorum] -D,default-db-size=size_spec -e,error-log=[filename] -G,event-log-server=logserv_name -f,forcebuild -H,ha-server -h,help=[{0 1 2 3}[,display_width]] instance=instance_name -y,key-password=[key_password] -K,keytab-file=filename -N,license-prop-file=filename -Z,logical-page-size=size_spec -d,master-db-size=size_spec] master_dev-size=[size_spec] master_key_password [=password]

Parameters

- -r, --master-mirror=filename
- -m, --masterrecover
- -g, --no-event-logging
- -Q, --quorum-dev=quorum\_dev
- -q, --recover-quiesced
- -w, --rewrite-db=database\_name
- -p, --sa-name={SSO\_login\_account | sso\_role | sa\_role}
- -k, --server-principal=s\_principal
- -M, --shared-mem-dir=directory\_name
- -X, --sybmon
- -T, --trace=trace\_flag
- -v, --version

#### Or

dataserver -v

- -a path\_to\_CAPs\_directive\_file specifies the path to the CAPs directive file.
  - -b master\_device\_size [k | K | m | M | g | G | t | T ] specifies the size of the master device or database you want to build. The server calculates the sizes, so you can use "K", "M", "G", and "T" instead of exact byte numbers.
  - -c config\_file\_for\_server

specifies the full path name of an Adaptive Server configuration file. Use this parameter to start Adaptive Server with the configuration values in the specified configuration file.

If you specify a configuration file with the dataserver -c parameter, make sure all the parameters in this configuration file are compatible before you boot the server. If some of the configuration parameters are incompatible, the server may not boot. To avoid this, do not specify a configuration file when you build the master device. The build phase uses all default settings when you do not specify a configuration file.

For more information, see the System Administration Guide.

-d device\_name

is the full path name of the device for the master database. The master database device must be writable by the user who starts Adaptive Server. If you do not use the -d parameter, the default master database device name is d\_master.

-e errorlogfile

is the full path name of the error log file for Adaptive Server system-level error messages.

-f

forces initialization of a device or database. -f is valid only when used with -b and/or -w. The server fails to boot if you use -f without either -b or -w. -f forces the server in different ways, depending whether -w is present. See "Potential issues of using -f and -w options together" on page 163 and "Dependencies and conditions of -b and -w options" on page 163 for more information.

-G logserv\_name

specifies the name of the event log server.

-g

turns off event-logging.

-H

starts the High Availability (HA) server, if you have the HA feature installed on your Adaptive Server.

-h

prints this help message, then exists.

-i interfaces\_file\_directory

specifies the directory location of the interfaces file to search when connecting Adaptive Server. If -I is omitted, dataserver looks for a file named *interfaces* in the directory pointed to by your SYBASE environment variable.

-K keytab\_file

specifies the path to the keytab file used for authentication in DCE.

- -k, --server-principal=s\_principal specifies the server principal name.
- -L config\_file\_name\_for\_connectivity specifies the name the configuration file for connectivity.
- -M sharedmem\_directory

places shared memory files in the specified directory instead of in the default location, *\$SYBASE*. If *sharedmem\_directory* starts with "/", the directory name is assumed to be absolute. Otherwise, the directory name is interpreted relative to *\$SYBASE*.

#### --master\_key\_password [=password]

specifies the master key password when you provide the *password* on the command line or prompts for a master key password during Adaptive Server startup. The password characters are not displayed, and the password is not validated until later in the Adaptive Server startup sequence.

If you include the password on the command line, it is visible until the memory is read and used.

-m

starts Adaptive Server in single-user mode.

-N licinstant

specifies a nondefault directory location for the license cache file. The default location is \$SYBASE/\$SYBASE ASE/sysam/server name.properties.

-p sso\_login\_name

specifies the login name of a System Security Officer when starting Adaptive Server, for the purposes of getting a new password for that account. Adaptive Server generates a random password, displays it, encrypts it, and saves it in master..syslogins as that account's new password.

#### -q

treats quiesced databases as "in recovery."

-r mastermirror

starts the mirror of the master device. Use this parameter to start Adaptive Server if the master device has been damaged.

-s servername

specifies the name of the Adaptive Server to start. If -s is omitted, a server named SYBASE is started.

-T trace\_flag

#### -u sa/sso\_name

specifies the System Administrator or System Security Officer's name you want to unlock.

-v

prints the version number and copyright message for dataserver, then exits.

-w [master | model]

specifies whether you want to write a master or model database.

-X

starts this server as sybmon, not dataserver.

-y [password]

allows you to assign a password for the encrypted private key, so that the server prompts the user for a password. This password should match the password you used to encrypt the private key when it was created. You cannot use this parameter when you are running the server in the background.

**Note** Although you can set a password with -y, for security reasons Sybase strongly discourages you from doing so.

A private key is included with your server's digital certificate. By default, the certificate file located at /usr/local/sybase/certificates/<servername>.crt.

The location of the certificate file changes if you invoke the sp\_ssladmin addcert command.

-Z [size\_spec]

specifies the size of the initial master database.

-z page\_size [ k | K ]

specifies the page size of the server. You must use -b and -w to use this flag, and name an even power of two between 2K and 16K, or else the server does not boot.

**Example 1** Creates a new installation with a 100MB master device and a 4K page:

dataserver -d my master device -z 4k -b 100.02M

The spaces between options and their following arguments are optional and acceptable. This example specifies "100.02M" for a 100MB master device because the server requires 16K of overhead for its configuration area.

**Example 2** Rewrites a corrupt model database:

dataserver -d d\_master -w model -s server\_name

**Example 3** Specifies the "aseprincipal@MYREALM.COM" principal name:

\$SYBASE/\$SYBASE\_ASE/bin/dataserver -dmaster.dat
-s secure ase -k aseprincipal@MYREALM.COM

**Example 4** Rewrites a corrupt master database, specifying device size:

dataserver -d my\_master\_device -w master -z 4k

Examples

**Example 5** Rewrites a corrupt master database, specifying device and page sizes, forcing the server to accept these values in preference to what it may find in the config block:

```
dataserver -d my_master_device -w master -z 4k -b
100.02M -f
```

**Example 6** Rewrites a corrupt master database, specifying a page size that does not match what the server finds in its config block. This produces a failure:

```
dataserver -d my_master_device -w master -z 8k
00:00000:00000:2001/01/19 12:01:26.94 server The
configured server page size does not match that
specified on the command line. To use the configured
size, omit the command line size; to use the command
line size, specify 'force' (-f).
```

**Example 7** Rewrites a corrupt master database, specifying an incorrect page size, even in a normal restart. This produces a failure:

dataserver -d my master device -z4000

dataserver: the 'z' flag may not be used without 'b' or 'w'. dataserver: server will ignore the 'z' flag. dataserver: the 'z' flag contained an invalid page size. dataserver: the page size must be an even power of two between 2048 and 16384 bytes, inclusive.

**Example 8** Prompts for a master key password:

dataserver --master\_key\_passwd -dd\_master -eerrorlog

- dataserver allows you to create devices and databases that are up to 32Gb in size, depending on the limitation of your operating system. For more information on size limits, see the installation guide for your platform.
- Start Adaptive Server with the startserver command rather than by directly executing the dataserver program. If you need to change any of the default values, edit the *RUN\_servername* file in your Sybase installation directory. See the startserver reference page for details.
- Because Adaptive Server passwords are encrypted, you cannot recover forgotten passwords. If all System Security Officers lose their passwords, the -p parameter generates a new password for a System Security Officer account. Start Adaptive Server with -p, immediately log in to Adaptive Server with the new random password, and execute sp\_password to reset your password to a more secure one.

Usage

- When you use the -w parameter, dataserver uses the ascii-8 character set instead of the iso\_1 character set. If you require the iso\_8 character set for master, you can load a dump of the master database or change the character set with sqlloc (sqlloc requires the sybsystemprocs database.)
- After you have finished running the Adaptive Server installation program, set the file permissions on the dataserver executable to limit who can execute it.
- If you do not specify an Adaptive Server name with the -s parameter, and you have not set the DSLISTEN environment variable, dataserver uses the default Adaptive Server name SYBASE. The value of the DSLISTEN environment variable overrides this default value, and the -s parameter overrides both the default and the DSLISTEN environment variable.
- Automatic login lockouts can cause a site to end up in a situation in which all accounts capable of unlocking logins (System Administrators and System Security Officers) are locked. If this occurs, use the dataserver utility with the -u parameter to check the specified login for System Administrator or System Security Officer authorization, unlock the account, and reset the value of the current failed logins counter to zero.

Potential issues of using -f and -w options together

Be particularly careful when using the -f and -w options together. When rewriting master database using the -w option, the server requires that the configuration block page size and device size are correct. If you do not provide them on the command line they must agree. The server refits the master device, and puts master and all other included databases back in their proper places.

When you use the -f option force initialization, your page size and master device size overrides those in the configuration block. In addition, -f assigns all other unknown space—allocation blocks that are either unused or are corrupted—to the master database.

Dependencies and conditions of -b and -w options

The effect of -b changes depending on whether -w is present:

- -b without -w creates a new master device as named by -d (the default is d\_master) and with the page size as specified by -z (the default is 2048):
  - If the named device already exists as an OS file, the attempt fails, and you see a message such as:

File already exists. You must remove the existing file before attempting to create a new one using the server's -b option. Unable to create master device.

	• If the named device names an existing raw partition, the attempt fails unless you include the -f flag. This reinitializes the raw partition as a server master device.
	• -b with -w master tells dataserver to use the size specified in -z for the master device when recreating the master database. It implies nothing about creating a new device.
	-w may or may not require additional flags if you use:
	• -w model – the -z and -b flags are accepted but ignored.
	• -w master for <b>new</b> installations – -z and -b are not required because the device size information is stored in the <i>config_block</i> .
	• -w master to <b>upgrade</b> older installations:
	• The server requires -b and/or -z if the <i>config_block</i> does not contain a valid entry for the associated size(s). The command fails if it cannot get valid data for the page size or device size.
	• You can provide -b and/or -z when the <i>config_block</i> contains valid entries for the size(s) they represent. However if the sizes do not match what is in the <i>config_block</i> , you must add -f to force your new size preferences.
Permissions	Anyone with execute permission on the binary, and who has read/write access to all the files.
See also	Commands disk mirror, disk remirror, disk unmirror
	System procedures sp_ssladmin addcert
	Utilities startserver

# ddlgen

Description A Java-based tool that generates definitions for server- and database-level objects in Adaptive Server. Adaptive Server version 11.9.2 and later supports ddlgen. You must have either an sa\_role or sso\_role to generate DDL for: Encryption keys Logins Roles For all other objects, users do not need any specific permissions or roles to generate DDL. The command-line version of ddlgen is located in *\$SYBASE/ASEP/bin* for UNIX, and %SYBASE%\ASEP\bin for Windows. Syntax ddlgen -Ulogin -Ppassword -S[[ssl:]server | host\_name : port\_number] [-l interfaces\_file] [-Tobject\_type] [-Nobject\_name] [-Ddbname] [-Xextended\_object\_type] [-Ooutput\_file] [-Eerror file] [-Lprogress\_log\_file] [-Jclient\_charset] [-LC -N logical\_cluster\_name -F[ % | SGM | GRP | USR | R | D | UDD | U | V | P | XP | I | RI | KC | TR | PC ] Or ddlgen -v Parameters -U login specifies a login name, and is case-sensitive. -P password specifies your password. If you do not include the -P parameter in your ddlgen statement, ddlgen prompts you to specify a password. For instructions on how to hide passwords, see "Hiding passwords in ddlgen" on page 184.

### -S [[ssl:] server | host\_name : port\_number]

specifies the name of the Adaptive Server. ddlgen looks this name up in the interfaces file or LDAP configuration file. If you specify:

- [ssl:] allows you to generate DDL for objects in SSL-enabled servers. This parameter is optional.
- -S [host\_name:port\_number] ddlgen uses the host\_name and port\_number provided, and neither interfaces nor LDAP configuration files are read or parsed.
- -S[*server*] -I ddlgen parses the interfaces file specified at the user location for the server name (see the -I parameter description for more information).
- -S[*server*] without specifying an interfaces file, ddlgen does the following:
  - a ddlgen first tries to read the LDAP configuration file from the standard location
  - b If the LDAP file does not exist, or exists but does not contain an Adaptive Server entry, then the interfaces file is parsed at its standard location for the server name
  - c If the LDAP file exists, then ddlgen uses it to search the server name. The interfaces file is not parsed, and the LDAP configuration file is parsed.

**Note** You must use the -S option because ddlgen does not connect to a default server.

#### -1

specifies the interfaces file name, and corresponds to *\$SYBASE/interfaces* for UNIX, and *%SYBASE%\ini\sql.ini* for Windows. Use this optional parameter with -S.

#### -Tobject\_type

specifies the type of object you are creating. If you do not use -T, ddlgen generates DDL for the default database of login. The object types for -T are:

Object type	Description
С	cache
D	default
DB	database
DBD	database device

Object type	Description
DPD	dump device
EC	execution class
EG	engine group
EK	encrypted keys
GRP	group
I	index
КС	key constraints
L	login
LK	logical key
Р	stored procedure
R	rule
RI	referential integrity
RO	role
RS	remote server
SGM	segment
TR	trigger
U	table
UDD	user-defined datatype
USR	user
V	view
WS	user-defined Web service
WSC	Web service consumer
XOD	Local caches
XOU	Global caches
XP	extended stored procedure

### -Nobject\_name

specifies the fully qualified name of the object you are creating, such as -Ndb\_name.owner\_name.table\_name.object\_name. The -N option:

- Is required if you specify any *object\_type* other than DB (database) in the -T parameter.
- Accepts wildcards with the use of %.
- Generates DDL for a trigger for a table, using the -Ndb\_name.table\_owner.table\_name.trigger\_name format.

To generate **all** triggers for a table, substitute *trigger\_name* with % using the -N*db\_name.table\_owner.table\_name.*% format.

- Generates DDL for an encrypted key with -Ndb\_name.owner.key\_name.
- Generates DDL for all items of a specific object type on your server.
- Enforces strict order in which it parses the names in the -Ndb\_name.owner\_name.table\_name.object\_name format. If you only provide three arguments, ddlgen assumes they are owner\_name, table\_name, and object\_name, in that order. Alternatively, you can also use -Nowner\_name.table\_name -Ddb\_name. ddlgen does not impose this restriction if object\_name is an index (I).

#### -Ddbname

specifies the name of the database for the object you specify in the -N option. The default is the user's default database.

You cannot use the -D parameter when generating DDL for all triggers of a table.

### -Xextended\_object\_type

differentiates the following:

- User tables (OU) from proxy tables (OD) when you specify a table as your object type (-TU)
- Temporary databases (OD) from normal databases (OU) or archive databases (OA) when you specify database as your object type (-TDB)
- SQLJ procedures (OD) from stored procedures (OU) when you specify procedure as your object type (-TP).

If *object\_type* (-T) is U (table) and -X is not specified, ddlgen generates DDL for both user tables and proxy tables. To generate DDL only for:

- **user tables** use the OU extended object type with the -X option.
- **proxy tables** use the OD extended object type with the -X option.
- **in-memory databases, caches, and devices** use the OI extended object type with the -X option.
- **in-memory temporary databases** use the OIT extended object type with the -X option.

Note ddlgen does not support schema generation for system tables.

-Ooutput\_file

specifies an output file for the generated DDL. If you do not specify -O, the DDL you create appears in a console window.

-Eerror\_file

specifies a log file for recording errors. If you do not specify -E, the generated errors appear in a console window.

-Lprogress\_log\_file

specifies a log file for recording the progress of ddlgen. If you do not specify -L, the progress is not recorded.

### -Jclient\_charset

specifies the character set to use on the client. -Jclient\_charset requests that Adaptive Server convert to and from *client\_charset*, the character set used on the client. A filter converts input between *client\_charset* and the Adaptive Server character set.

Omitting -J sets the character set to a default for the platform. The default may not necessarily be the character set that the client is using.

**Note** For HP platforms – you **must** use -Jiso\_1 to specify the correct character set.

### -LC

generate DDL for one or all logical clusters on a server.

-F

filters out indexes, triggers, and constraints out of table and database definitions in the DDL of table- and database-level objects. The valid filters are:

- For tables [ % | I | RI | KC | TR | PC ]
- For databases [ % | SGM | GRP | USR | R | D | UDD | U | V | P | XP | I | RI | KC | TR]

The filter options are:

Option	Filters out
%	Everything. Retrieves the schema-only definition of a database or table.
SGM	Segments
GRP	Groups
USR	Users
R	Rules
D	Defaults
UDD	Uer-defined datatypes
U	User tables
V	Views
Р	Stored procedures
PC	Partition condition
XP	Extended stored procedures
I	Indexes
RI	Referential integrity constraints
KC	Primary- and unique-key constraints
TR	Triggers

If you use an invalid filter parameter, ddlgen generates a warning, ignores that parameter, and continues with the rest of the valid parameters you specify.

If you specify % along with other filter parameters, ddlgen ignores all other filterable parameters, and only shows schema-only definitions. ddlgen then continues to evaluate the dependencies within the subset of the applied as the filterable parameters for the database.

-v

displays the version and copyright message of ddlgen and returns to the operating system.

Examples	<b>Example 1</b> (Caches) Generates DDL for a cache called <i>default data cache</i> on a machine named HARBOR using port 1955:
ddlgen	-Uroy -Proy123 -SHARBOR:1955 -TC -N"default data cache"
	To generate DDL for all caches:
ddlgen	-Ulogin -Ppassword -Sserver:port -TC -N%
	<b>Example 2</b> (Defaults) Generates DDL for a default called "phondflt" owned by jones in the pubs2 database on a machine named HARBOR using port 1955:
ddlgen	-Uroy -Proy123 -SHARBOR:1955 -TD -Njones.phonedflt -Dpubs2
	Alternatively, because ddlgen allows you to use a fully qualified name in the -N flag, you can omit the -D <i>dbname</i> and include the database name in the -N option:
ddlgen	-Ulogin -Ppassword -Sserver:port -TD -Ndbname.owner.defaultname
	To generate DDL for all defaults in a database owned by "owner":
ddlgen	-Ulogin -Ppassword -Sserver:port -TD -Nowner.% -Ddbname
	<b>Example 3</b> (Databases) Generates DDL for a database called pubs2 on a machine named HARBOR using port 1955:
	ddlgen -Uroy -Proy123 -SHARBOR:1955 -TDB -Npubs2
	If you do not specify a <i>dbname</i> , ddlgen generates DDL for the default database of <i>login</i> :
	ddlgen -Ulogin -Ppassword -Sserver:port
	If you do not use the -T parameter, ddlgen generates DDL for a default-type database:
	ddlgen -Ulogin -Ppassword -Sserver:port -Ndbname
	To generate DDL for all databases:
	ddlgen -U <i>login</i> -Ppassword -Sserver:port -TDB -N%
	<b>Example 4</b> (Database device) Generates DDL for a database device called master running on a machine named HARBOR using port 1955:
	ddlgen -Uroy -Proy123 -SHARBOR:1955 -TDBD -Nmaster
	To generate DDL for all database devices:

```
ddlgen -Ulogin -Ppassword -Sserver:port -TDBD -N%
```

**Example 5** (Temporary databases) Generates DDL for all databases, including tempdb:
ddlgen -Ulogin -Ppassword -Sserver:port -TDB -N%

To generate DDL for all temporary databases, use the OD extended database type:

```
ddlgen -Ulogin -Ppassword -Sserver:port -TDB -XOD -N%
```

Although you can use the OD extended type in Adaptive Server versions 12.5.0.3 and later, versions earlier than 12.5.0.3 issue warning messages. You can safely ignore this message; ddlgen continues processing the command.

To generate DDL for all databases except temporary databases, use the OU extended type:

```
ddlgen -Ulogin -Ppassword -Sserver:port -TDB -XOU -N%
```

The following generates DDL for a temporary database named tempdb1:

```
ddlgen -Ulogin -Ppassword -Sserver:port -TDB -Ntempdb1
```

The output includes the following:

A create temporary database statement

```
create temporary database tempdbl on master = 4,
    asdas = 2
go
```

• An sp\_tempdb bind statement where the isql application is bound to tempdb1:

```
sp_tempdb 'bind','ap', 'isql', 'DB', 'tempdb1'
go
```

**Note** DDL for objects such as views, stored procedures, and tables is not generated along with DDL for a temporary database because these objects are temporary, and are re-created when the server restarts.

When you use the -F parameter to filter a table while generating DDL for a database object, then indexes, referential integrity, key constraints and triggers automatically get filtered, as they are a subset of the table object.

**Example 6** (In-memory databases) Generates DDL for an in-memory database:

```
ddlgen -Uroy -Proy123 -SHARBOR:1955 -TDB -Nimdb_1
```

**Example 7** Generates DDL for an in-memory temporary database:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TDB -Nimdb\_temp1

**Example 8** (Archive database) To generate DDL for all archive databases, use the extended filter option "OA."

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TDB -N% -XOA

To generate DDL for a single archive database, use the syntax for normal databases. This example creates DDL for the archive database adb1.

```
ddlgen -Uroy -Proy123 -SHARBOR:1955 -TDB -Nadb1
```

**Example 9** (Dump device) Generates DDL for a dump device called tapedump1 running on a machine named HARBOR using port 1955:

```
ddlgen -Uroy -Proy123 -SHARBOR:1955 -TDPD -Ntapedump1
```

To generate DDL for all dump devices:

ddlgen -Ulogin -Ppassword -Sserver:port -TDPD -N%

**Example 10** (Encrypted keys) Generates system encryption passwords along with DDLs for encryption keys when you include the extended option -XOD. The output generates the sp\_encryption statement followed by DDL statements for all encrypted keys. This generates DDL for the login "george" on a machine named HARBOR using port 1955:

```
ddlgen - Uroy - Proy123 - SHARBOR: 1955 - TEK - Ngeorge - XOD
```

To generate DDL for all the encrypted keys in the authors database on a machine named HARBOR using port 1955:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TEK -Nauthors.dbo.%

**Example 11** Generates DDL for all encryption keys in the accounts database on a machine named "HARBOR" using port 1955:

```
ddlgen -Uroy -Proy123 -SHARBOR:1955 -TEK -Naccounts.dbo.%
```

Alternatively, you use the -D option to specify the database name.

**Example 12** Generate DDL for an encryption key "ssn\_key" in a the SampleKeysDB database:

ddlgen -Usa -P -Sserver -TEK -NSampleKeysDB.dbo.ssn\_key

**Example 13** This example uses -FEKC to avoid creating DDL for key copies when generating DDL for the "ssn\_key" encryption key:

```
ddlgen -Usa -P -Sserver -TEK -NSampleKeysDB.dbo.ssn_key -FEKC
```

**Example 14** Generates DDL for "ssn\_key" and its key copies:

ddlgen -Usa -P -Sserver -TEK -NSampleKeysDB.dbo.ssn key

**Example 15** This example issues a ddlgen command on a table called employee, which has an "ssn" column that is encrypted with encryption key "ssn\_key," and a decrypt default value that is set to 100:

ddlgen -Usa -P -Sserver -TU -N db1.db0.employee

**Example 16** (Engine groups ) Generates DDL for an engine group called LASTONLINE running on a machine named HARBOR using port 1955:

```
ddlgen - Uroy - Proy123 - SHARBOR: 1955 - TEG - NLASTONLINE
```

To generate DDL for all engine groups:

ddlgen -Ulogin -Ppassword -Sserver:port -TEG -N%

**Example 17** (Execution class) Generates DDL for an execution class called EC2 running on a machine named HARBOR using port 1955:

```
ddlgen - Uroy - Proy123 - SHARBOR: 1955 - TEC - NEC2
```

To generate DDL for all execution classes:

ddlgen -Ulogin -Ppassword -Sserver:port -TEC -N%

**Example 18** (Extended stored procedures) Generates DDL for the xp\_cmdshell extended stored procedure in the pubs2 database, owned by Jones and running on a machine named HARBOR using port 1955, by using the fully qualified *dbname.owner.extendedstoredprocedure* format with the -N option:

```
ddlgen -Uroy -Proy123 -SHARBOR:1955 -TXP -Npubs2.jones.xp cmdshell
```

Alternatively, you can use the -D option instead of using the fully qualified name:

ddlgen -Ulogin -Ppassword -Sserver:port -TXP -Nowner.extendedstoredprocedure -Ddbname

To generate DDL for all extended stored procedures:

ddlgen -Ulogin -Ppassword -Sserver:port -TXP -Ndbname.owner.%

**Example 19** (Filters) Generates DDL for the authors table in the pubs2 database, filtering for all indexes (I), and referential integrity constraints (RI), primary and unique key constraints (KC), triggers (TR), and partition condition (PC) from the DDL of a table:

```
ddlgen - Uroy - Proy123 - TU - Nauthors - Dpubs2 - F%
```

Alternatively, you can specify each of the filters individually:

ddlgen -Ulogin -Ppassword -TU -Ndbname.owner.table -FI,RI,KC,TR The following generates the definition of *table\_name* while filtering out foreign keys and primary-unique keys:

```
ddlgen -Ulogin -Ppassword -TU -Ntable_name -Ddbname
-FRI,KC
```

Both of these generate foreign keys for a specified user in the entire database:

```
ddlgen -Ulogin -Ppassword -TRI -N%.%.% -Ddbname
```

Or:

ddlgen -Ulogin -Ppassword -TRI -Ndbname%.%.%

Both of these generate DDL for the primary and unique keys of all the tables in a database that begin with "PK":

```
ddlgen -Ulogin -Ppassword -TKC -Ndbname.%.%.PK%
```

Or:

```
ddlgen -Ulogin -Ppassword -TKC -N%.%.PK% -Ddbname
```

The following generates schema-only definition of a database:

```
ddlgen -Ulogin -Ppassword -Sserver:port -TF -Ndbname -F%
```

Alternatively, you can specify each of the filters individually:

```
ddlgen -Ulogin -Ppassword -Sserver:port -TDB -Ndbname
-FSGM,GRP,USR,R,D,UDD,V,P,XP,I,RI,KC,TR
```

The following generates the database DDL skipping the compiled object:

```
ddlgen -Ulogin -Ppassword -Sserver:port -TDB -Ndbname -FTR,D,XP,V,R
```

The following generates database definition without a table definition:

ddlgen -Ulogin -Ppassword -Sserver:port -TDB -Ndbname -FU

**Example 20** (Groups) Generates DDL for a group called "public" in the pubs2 database, running on a machine named HARBOR using port 1955, by using the fully qualified *dbname.groupname* format in the -N option:

```
ddlgen -Uroy -Proy123 -SHARBOR:1955 -TGRP -Npubs2.public
```

Alternatively, you can use the -D option to specify the *dbname*:

```
ddlgen -Ulogin -Ppassword -Sserver:port -TGRP -Ngroupname -Ddbname
```

To generate DDL for all groups:

ddlgen -Ulogin -Ppassword -Sserver:port -TGRP -Ndbname.%

**Example 21** (Indexes) Generates DDL for an index called au\_Iname for the table authors owned by dbo, in the pubs2 database:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TI -Ndbo.authors.au lname -Dpubs2

Alternatively, because ddlgen allows you to use a fully qualified name in the -N flag, you can omit the -D*dbname* and include the database name in the -N option:

```
ddlgen -Ulogin -Ppassword -Sserver:port
-TI -Ndbname.owner.tablename.indexname
```

If you use a fully qualified name, you may omit the -D option.

To generate DDL for all indexes for a single table:

ddlgen -Ulogin -Ppassword -Sserver:port -TI -Ndbname.owner.tablename.%

To generate DDL for all indexes of all tables in a database:

For example, this generates DDL for all indexes for all tables in the pubs2 database:

ddlgen -Usa -P -SHARBOR:1955 -TI -Npubs2.%.%.%

**Example 22** (Keys) Both of these generate DDL for the primary and unique keys of all the tables in a database that begin with "PK":

ddlgen -Usa -P -TKC -Ndbname.%.%.PK%

Or:

ddlgen -Usa -P -TKC -N%.%.PK% -Ddbname

**Example 23** (Logical keys) LK generates logical keys of table defined by sp\_primarykey, sp\_commonkey, sp\_foreignkey statements. Since these keys do not have a name, the name of the object in this case would be the name of the table. This example generate a DDL for logical keys of table authors in database pubs2 running on a machine named HARBOR using port 1955:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TLK -Npubs2.dbo.authors

To generate DDL for all logical keys in database pub2 use:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TLK -Npubs2.%.%

To filter out logical keys definition from DDL of table authors use LK in -F argument, use:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TLK -Npubs2.dbo.authors -FLK

**Example 24** (Logins) TL generates DDL for one or all logins. This example generates DDL for all logins on a machine named HARBOR using port 1955:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TL -N%

**Note** The password in the DDL generated for all logins is "password".

Alternatively, you can specify an individual login by using -Nusername instead of -N%:

ddlgen -Ulogin -Ppassword -Sserver:port -TL -Nusername

If server-wide password complexity options have been specified for the login or logins, all sp\_addlogin and sp\_loglogin DDL statements are generated first, followed by DDL statements for the password options. This example generates DDL for the login "george" on a machine named HARBOR using port 1955:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TL -Ngeorge

**Example 25** (Remote servers) Generates DDL for a remote server called ORANGE on a machine named HARBOR using port 1955:

ddlgen - Uroy - Proy123 - SHARBOR: 1955 - TRS - NORANGE

To generate DDL for all remote servers:

ddlgen -Ulogin -Ppassword -Sserver:port -TRS -N%

**Example 26** (Roles) Generates DDL for the sa\_role on a machine named HARBOR using port 1955:

ddlgen - Uroy - Proy123 - SHARBOR: 1955 - TRO - Nsa\_role

To generate DDL for all roles:

ddlgen -Ulogin -Ppassword -Sserver:port -TRO -N%

**Note** The password in the DDL generated for all roles is "password".

**Example 27** (Rules) Generates DDL for all rules associated with authors on a machine named HARBOR using port 1955:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TR -Nauthors.dbo.% The % symbol tells ddlgen to create DDLs for all rules that exist on the server. You can also give the fully qualified name of the rule: ddlgen -Ulogin -Ppassword -Sserver:port -TR -Ndbname.owner.rulename

Alternatively, you can also use the -D parameter:

ddlgen -Ulogin -Ppassword -Sserver:port -TR -Nowner.rulename -Ddbname

**Example 28** (Segments) Generates DDL using the fully qualified *dbname.segmentname* format in the -N option for a segment called logsegment for the pubs2 database, on a machine named HARBOR using port 1955:

ddlgen - Uroy - Proy123 - SHARBOR: 1955 - TSGM - Npubs2.logsegment

Alternatively, you can use specify the *dbname* using the -D option:

ddlgen -Ulogin -Ppassword -Sserver:port -TSGM -Nsegmentname -Ddbname To generate DDL for all segments:

ddlgen -Ulogin -Ppassword -Sserver:port -TSGM -Ndbname.%

**Example 29** (SQLJ functions) Generates DDL for a SQLJ function named region\_of owned by dbo in database master:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TF -Nmaster.dbo.region\_of

Alternatively you can also use the -D parameter:

ddlgen -Ulogin -Ppassword -Sserver:port -TF -Ndbo.region\_of -Dmaster

To generate DDL for all SQLJ functions in a database, use object type F:

ddlgen -Ulogin -Ppassword -Sserver:port -TF -Ndbname.owner.%

**Example 30** (SQLJ procedures) Are a kind of stored procedure. You generate DDL for SQL procedures along with DDL for stored procedures. The following generates DDL for all stored procedures—including SQLJ procedures—owned by dbo in the master database:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TP -Nmaster.dbo.%

To generate DDL for all SQLJ procedures that are only owned by dbo in the master database, use the following, where the extended type OD refers to SQLJ procedures:

```
ddlgen -Ulogin -Ppassword-Sserver:port -TP -Nmaster.dbo.% -XOD
```

To generate DDL for all procedures except SQLJ procedures owned by dbo in the master database, use the following, where the extended type OU refers to all stored procedures except SQLJ procedures:

ddlgen -Ulogin -Ppassword-Sserver:port -TP -Nmaster.dbo.% -XOU

**Example 31** (Stored procedures) Generates DDL for the sp\_monitor stored procedure for the pubs2 database on a machine named HARBOR using port 1955, using the fully qualified *dbname.owner.procedure\_name* format for the -N option:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TP -Npubs2.dbo.sp\_monitor

Alternatively, you can use specify the *dbname* using the -D option:

ddlgen -Ulogin -Ppassword -Sserver:port -TP -Nowner.procedurename -Ddbname

To generate DDL for all stored procedures:

ddlgen -Ulogin -Ppassword -Sserver:port -TP -Ndbname.owner.%

**Example 32** (SSL-enabled servers) Generates DDL for objects in the pubs2 database for an SSL-enabled Adaptive Server running on a machine named HARBOR using port 1955:

ddlgen -Uroy -Proy123 -Sssl:HARBOR:1955 -TDB -Npubs2

**Example 33** (Tables) Generates DDL for all user tables in the pubs2 database owned by "dbo" and running on a machine named HARBOR using port 1955:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TU -Ndbo.% -Dpubs2

You can also use the -N parameter to give the fully qualified name of the table:

ddlgen -Ulogin -Ppassword -Sserver:port -TU -Ndbname.tableowner.tablename

Alternatively, you can also use the -D parameter to specify the database:

ddlgen -Ulogin -Ppassword -Sserver:port -TU -Ntableowner.tablename -Ddbname

To generate DDL for all proxy tables, which uses the value OD, use -XOD instead, where X is the extended type, and OD denotes proxy tables:

ddlgen -Ulogin -Ppassword -Sserver:port -TU -Ntableowner.% -Ddbname -XOD

To generate DDL for all user tables, which uses the value OU, use -XOU instead, where X is the extended type, and OU denotes user tables:

ddlgen -Ulogin -Ppassword -Sserver:port -TU -Ntableowner.% -Ddbname -XOU

To generate DDL for all tables, including user tables and proxy tables:

ddlgen -Ulogin -Ppassword -Sserver:port -TU -Ndbname.tableowner.%

**Example 34** (Triggers) Generates DDL for the trigger checksum for the pubs2 database on a machine named HARBOR using port 1955, using the fully qualified *dbname.owner.trigger\_name* format for the -N option:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TTR -Npubs2.dbo.checksum

Alternatively, you can use specify the *database\_name* using the -D option:

ddlgen -Ulogin -Ppassword -Sserver:port -TTR -Nowner.triggername -Ddbname

You can also generate DDL for a trigger for a table, using:

-Ndb\_name.table\_owner.table\_name.trigger\_name

To generate DDL for all triggers of a database:

ddlgen -Ulogin -Ppassword -Sserver:port -TTR -Ndbname.owner.%

You can also use the following format to generate DDL for all triggers of a table:

-Ndb\_name.table\_owner.table\_name.%

**Note** You cannot use the -D parameter when generating DDL for all triggers of a table.

**Example 35** (User-defined datatypes) Generates DDL for the user-defined datatype "Identype" for the pubs2 database on a machine named HARBOR using port 1955 using the fully qualified *dbname.userdefined\_datatype* format for the -N option:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TUDD -Npubs2.Identype

Alternatively, you can use the -D option to specify the *dbname*:

ddlgen -Ulogin -Ppassword -Sserver:port -TUDD -Nuserdefined datatype -Ddbname

To generate DDL for all user-defined datatypes:

ddlgen -Ulogin -Ppassword -Sserver:port -TUDD -Nbname.%

**Example 36** (Views) Generates DDL for a view named retail owned by Miller in the pubs2 database running on a machine named HARBOR using port 1955, by using the fully qualified *dbname.owner.viewname* format with the -N option:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TV -Npubs2.miller.retail

Alternatively, you can use the -D option instead of using the fully qualified name:

ddlgen -Ulogin -Ppassword -Sserver:port -TV -Nowner.viewname -Ddbname

To generate DDL for all views:

ddlgen -Ulogin -Ppassword -Sserver:port -TV -Ndbname.owner.%

**Example 37** (Users) Generates DDL for a user named Smith in the pubs2 database running on a machine named HARBOR using port 1955, by using a fully qualified *dbname.username* format with the -N option:

ddlgen -Uroy -Proy123 -SHARBOR:1955 -TUSR -Npubs2.smith

Alternatively, you can use both the -N and -D options instead of using a fully qualified name in -N:

ddlgen -Ulogin -Ppassword -Shost name:port -TUSR -Nusername -Ddbname

To generate DDL for all users:

ddlgen -Ulogin -Ppassword -Sserver:port -TUSR -Ndbname.%

**Example 38** (Logical cluster) Generates DDL for "my\_lcluster" on server "ase1", enter:

ddlgen -Usa -P -Sase1 -TLC -Nmy\_lcluster

**Example 39** (Logical cluster) Generates DDL for all logical clusters on server "ase1", enter:

ddlgen -Usa -P -Sase1 -TLC -N%

**Example 40** (User-defined Web services) Generates DDL for a named user-defined Web service, sp\_who\_service, in the pubs2 database running on a machine named HARBOR using port 1995, by using a fully qualified *dbname.username.webservice\_name* format with the -N and -T options:

ddlgen -Uroy -Proy123 -SHARBOR:1995 -TWS -Npubs2.dbo.sp\_who\_service

The syntax for generating DDL for a named user-defined Web service is as follows:

```
ddlgen -Ulogin -Ppassword -Shost_name:port -TWS -Ndbname.owner.webservice name
```

To generate DDL for all user-defined Web services owned by all users in database *dbname*:

ddlgen -Ulogin -Ppassword -Shost name:port -TWS -Ndbname.%.%

**Note** An sp\_webservices 'addalias' statement is only generated if the DDL is to be generated for all user-defined web services or for a database.

Usage
 ddlgen does not identify existing sequences within views, stored procedures or triggers. For this reason, when generating DDL for a database, you must first run ddlgen on those views, stored procedures and triggers that are independent, before running ddlgen on those with dependencies. For example, if view B depends on view A, you must first run ddlgen on view A, before running it on view B.

• The default information for ddlgen is:

Option	Parameter	Required	Default
-U	username	Yes	None
-P	password	Yes	None
-S	host_name:port_number	Yes	None
-T	object_type	No	Database
	See the -T parameter description for a list of valid object types		
-N	object_name	Yes, if <i>object_type</i> for -T is not DB (database)	Default database name of username, if -Tobject_type is db or if -T is not specified
-D	database_name	No	Default database of username
-X	<ul> <li>extended_object_type</li> <li>Options are:</li> <li>OU – for user tables, user databases (excluding temporary databases), and stored procedures (excluding SQLJ procedures).</li> <li>OD – for proxy tables, temporary databases, and SQLJ procedures.</li> </ul>	<ul> <li>No; use only when the <i>object_type</i> for -T is:</li> <li>U (user table)</li> <li>P (procedure)</li> <li>DB (database)</li> </ul>	None
-0	output_file_name	No	Standard out
-E	error_file_name	No	Standard out
-L	log_file_name	No	None
-V	version_number of ddlgen	No	None

• At the command line, invoke ddlgen using the *ddlgen* shell script file (*ddlgen.bat* for Windows), included in your Adaptive Server installation. The main class in *DDLGen.jar* is *com.sybase.ddlgen.DDLGenerator*.

- To start ddlgen in the Sybase Central plug-in for Adaptive Server:
  - a Right-click on the object for which you want to generate DDL.
  - b Select Generate DDL.
- In the output DDL of create table, bind statements are generated as independent DLL instead of dependent DLL.

The following section provides more details about:

- "Hiding passwords in ddlgen" on page 184
- "Using ddlgen for encrypted columns" on page 185

## Hiding passwords in *ddlgen*

When you issue the ddlgen utility in a UNIX command-line environment, other users on that UNIX machine can see your ddlgen command—including its password—if they issue the ps process management command, which shows the status of processes that are running on that machine.

The ddlgen -P password parameter option lets you to invoke ddlgen from a script so that the password is hidden from other users.

To achieve this, set the *\$PSWD* environment variable to point to your Adaptive Server login password, and include the string "ext" in the -P parameter. ext acts as a pseudo password, allowing you to supply the actual password in the next line. Set *\$PSWD* at the command line or a Bourne shell script, but not from the C-shell.

To run ddlgen using \$PSWD:

1 Set the *\$PSWD* environment variable:

setenv PSWD pass\_word

2 Run ddlgen:

```
ddlgen -Ulogin -Pext -Sserver:port -Ttype -Nname << END
$PSWD
END
```

If you prefer to keep your password in a file, replace *\$PSWD* with 'cat *filename*', where *filename* is the location of your password file. For example:

```
ddlgen -Ulogin -Pext -Sserver:port -Ttype -Nname << END
'cat filename'
END</pre>
```

Using ddlgen for encrypted columns

• The ddlgen utility supports pre-15.0.2 encryption. Pre-15.0.2 ddlgen support includes generating DDL for an encryption key in a database, and generating DDL to synchronize encryption keys across servers.

If you use ddlgen to generate DDL for encryption keys on Adaptive Server version 15.0.2 or later, the DDL may cause errors on a pre-15.0.2 version Adaptive Server, specifically if an encryption key is encrypted by a user specified-password or has key copies.

- The type EK, used for encryption key, generates the DDL to create an encryption key and to grant permissions on it. ddlgen generates encrypted column information and a grant decrypt statement, along with the table definition.
- If you do not specify the -XOD option, and the key to be migrated has been created in the source database using the with passwd clause, ddlgen generates a create encryption key command with password as its explicit password. This is similar to what ddlgen does for roles and login passwords.
- The -XOD generates the create encryption key that specifies the key's encrypted value as represented in sysencryptkeys. Use the -XOD to synchronize encryption keys across servers for data movement.

ddlgen -XOD generates DDL that includes a system encryption password (if it was set and DDL is generated for a key encrypted with a system encryption password) and DDL for keys.

#### Generating DDL without specifying the -XOD flag

--a password was specified when this key was created.

- Two things can happen if users do not specify the -XOD flag in ddlgen:
  - If users **did not** specify a password when the encryption key was created, ddlgen generates DDL with no password.
  - If users specified a password when the encryption key was first created, ddlgen generates the default password of 'password'. This is similar to what ddlgen does for roles and login passwords, and its output looks similar to the following:

-- DDL for EncryptedKey 'ssn\_key' print 'ssn\_key' --The DDL is generated with a default password - 'password' as

```
create encryption key SampleKeysDB.dbo.ssn_key for AES
with keylength 128
passwd 'password'
init_vector random
go
```

## Generating DDL with the -XOD flag

 When a user specifies "-XOD" in the ddlgen command, ddlgen generates DDL that includes a system encryption password (if it has been set and DDL is generated for a key encrypted with a system encryption password) and DDL for keys.

The following syntax generates a system encryption password:

```
ddlgen -Usa -P -Sserver -TEK -NsampleKeysdb.dbo.ek1 -XOD
```

The output for the command is:

```
-- System Encryption Password
use SampleKeysDB
go
sp encryption 'system encr passwd',
'0x8e050e3bb607225c60c7cb9f59124e99866ca22e677b2cdc9a4d09775850f4721',
NULL, 2, 0
qo
_____
- - -
-- DDL for EncryptedKey 'ek1'
                      -----
- - -
print '<<<< CREATING EncryptedKey - "ek1" >>>>>'
qo
create encryption key SampleKeysDB.dbo.ek1 for AES
with keylength 128
passwd 0x0000C7BC28C3020AC21401
init vector NULL
keyvalue
0xCE74DB1E028FF15D908CD066D380AB4AD3AA88284D6F7742DFFCADCAABE4100D01
keystatus 32
```

**Note** When migrating keys from a source to a target server using ddlgen, set the system encryption password to NULL (if it exists) in the target server if you want to run the ddlgen output (from the source server) for encryption keys generated using "-XOD" parameter. Failure to do this results in errors when you try to execute the ddlgen output against the target server.

**Key copy support** The ddlgen utility also generates DDL for key copies along with the DDL for base key. For example, the following syntax would generate DDL for "ssn\_key" and its key copies:

ddlgen -Usa -P -Sserver -TEK -NSampleKeysDB.dbo.ssn\_key

The output from ddlgen would look like:

-- DDL for EncryptedKey 'ssn key' ---------print 'ssn\_key' --The DDL is generated with a default password - 'password' as --a password was specified when this key was created. create encryption key SampleKeysDB.dbo.ssn key for AES with keylength 128 passwd 'password' init vector random qo print 'Key Copies for ssn key' -- Generating DDL for Key Copies for 'ssn key' alter encryption key 'ssn\_key' with passwd 'password' add encryption with passwd 'passwd' for user 'dbo'. If you include the -XOD flag, the DDL for key copy would look like: alter encryption key SampleKeysDB.dbo.ssn key add encryption with keyvalue 0x84A7360AA0B28801D6D4CBF2F8219F634EE641E1082F221A2C58C9BBEC9F49B501 passwd 0x000062DF4B8DA5709E5E01 keystatus 257

go

```
for user 'user1'
qo
EKC encryption key
                      With Adaptive Server 15.0.2, ddlgen supports the EKC (encryption key copy)
copy filter
                      extended type for its -F filter argument, to suppress the generation of key copies
                      for encryption keys.
                      This example uses -FEKC to avoid creating DDL for key copies when
                      generating DDL for the "ssn_key" encryption key:
                         ddlgen -Usa -P -Sserver -TEK -NSampleKeysDB.dbo.ssn_key -FEKC
                      The output from ddlgen would look like:
                                                -- DDL for EncryptedKey 'ssn key'
   -----
                                              print 'ssn key'
   --The DDL is generated with a default password - 'password' as
   --a password was specified when this key was created.
   create encryption key SampleKeysDB.dbo.ssn key for AES
   with keylength 128
   passwd 'password'
   init vector random
   qo
Create table DDL
                      ddlgen can generate decrypt_default statements (if set for an encrypted column)
                      along with DDL of a table.
                      The following example issues a ddlgen command on a table called employee
                      which has an "ssn" column that is encrypted with encryption key "ssn key,"
                      and a decrypt default value that is set to "100":
                         ddlgen -Usa -P -Sserver -TU -Nemployee
                      The DDL output from the command is:
   create table employee (
                      int
                                not null encrypt with ssn key decrypt default
     ssn
   100 ,
     last name
                     int
                               not null ,
     first name
                      int
                                not null
   )
   lock allpages
    on 'default'
   go
Permissions
                      Users must have either sa_role or sso_role to generate DDL for:
```

- Encryption keys
- Logins
- Roles

For all other objects, users do not need any specific permissions or roles to generate DDL.

## defncopy

Description	Copies definitions for specified views, rules, defaults, triggers, or procedures from a database to an operating-system file or from an operating-system file to a database. Located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> .	
	(Windows) The utility is defncopy.exe and is located in %SYBASE%\%SYBASE_OCS%\bin.	
Syntax	<pre>defncopy     [-X]     [-a display_charset]     [-1 interfaces_file]     [-J [client_charset]]     [-J [client_charset]]     [-Y password]     [-P password]     [-R remote_server_principal]     [-S [server_name]]     [-U username]     [-V security_options]     [-Z security_mechanism]     [-Z security_mechanism]     [-z language]     { in file_name database_name           out file_name database_name [owner.]object_name     [[owner.]object_name] } Or </pre>	
Parameters	-X	

initiates the login with client-side password encryption in this connection to the server. defncopy (the client) specifies to the server that password encryption is desired. The server sends back an encryption key, which defncopy uses to encrypt your password, and the server uses to authenticate your password when it arrives.

If defncopy crashes, the system creates a core file which contains your password. If you did not use the encryption option, the password appears in plain text in the file. If you used the encryption option, your password is not readable.

## -a display\_charset

runs defncopy from a terminal whose character set differs from that of the machine on which defncopy is running. Use -a in conjunction with -J to specify the character set translation file (*.xlt* file) required for the conversion. Use -a without -J only if the client character set is the same as the default character set.

**Note** The ascii\_7 character set is compatible with all character sets. If either the Adaptive Server character set or the client character set is set to ascii\_7, any 7-bit ASCII character can pass unaltered between client and server. Other characters produce conversion errors. See the *System Administration Guide* for more information on character set conversion.

### -l interfaces\_file

specifies the name and location of the interfaces file to search when connecting to Adaptive Server. If you do not specify -I, defncopy looks for a file named *interfaces* in the directory specified by the SYBASE environment variable in UNIX platforms, and *sql.ini* in the *ini* subdirectory for your Sybase release directory in Windows.

-J client\_charset

specifies the character set to use on the client. A filter converts input between *client\_charset* and the Adaptive Server character set.

-J *client\_charset* requests that Adaptive Server convert to and from *client\_charset*, the client's character set.

-J with no argument sets character set conversion to NULL. No conversion takes place. Use this if the client and server are using the same character set.

Omitting -J sets the character set to a default for the platform. The default may not be the character set that the client is using. For more information about character sets and their associated flags, see the *System Administration Guide* and *Configuration Guide* for your platform.

-K keytab\_file

specifies the path to the keytab file used for authentication in DCE.

-P password

specifies your password. If you do not specify -P, defncopy prompts for your password.

### -R remote\_server\_principal

specifies the principal name for the server. By default, a server's principal name matches the server's network name (which is specified with the -S parameter or the DSQUERY environment variable). Use the -R parameter when the server's principal name and network name are not the same.

## -S server\_name

specifies the name of the Adaptive Server to which to connect. If you specify -S with no argument, defncopy looks for a server named SYBASE. If you do not specify -S, defncopy uses the server specified by your DSQUERY environment variable.

### -U username

specifies a login name. Login names are case sensitive. If you do not specify *username*, defncopy uses the current user's operating system login name.

## -V security\_options

specifies network-based user authentication. With this option, the user must log in to the network's security system before running the utility. In this case, users must supply their network user name with the -U option; any password supplied with the -P option is ignored.

-V can be followed by a *security\_options* string of key-letter options to enable additional security services. These key letters are:

- c Enable data confidentiality service
- i Enable data integrity service
- m Enable mutual authentication for connection establishment
- o Enable data origin stamping service
- r Enable data replay detection
- q Enable out-of-sequence detection

### -Z security\_mechanism

specifies the name of a security mechanism to use on the connection.

Security mechanism names are defined in the *\$SYBASE/install/libtcl.cfg* configuration file. If no *security\_mechanism* name is supplied, the default mechanism is used. For more information on security mechanism names, see the description of the *libtcl.cfg* file in the *Open Client and Open Server Configuration Guide*.

٠Z	language
----	----------

is the official name of an alternate language that the server uses to display defncopy prompts and messages. Without the -z flag, defncopy uses the server's default language.

Add languages to an Adaptive Server at installation, or afterwards with the utility langinstall (langinst in Windows) or the stored procedure sp\_addlanguage.

```
in | out
```

specifies the direction of definition copy.

#### file\_name

specifies the name of the operating system file destination or source for the definition copy. The copy out overwrites any existing file.

#### database\_name

specifies the name of the database to copy the definitions from or to.

#### owner

is optional if you or the Database Owner own the table being copied. If you do not specify an owner, defncopy first looks for a table of that name that you own, and then looks for one owned by the Database Owner. If another user owns the table, you must specify the owner name or the command fails.

#### object\_name

specifies name(s) of database object(s) for defncopy to copy out. Do not use *objectname* when copying definitions in.

#### -V

displays the version and copyright message of defncopy and returns to the operating system.

Examples Example 1 Copies definitions from the file *new\_proc* into the database stagedb on server MERCURY. The connection with MERCURY is established with a user of name "sa" and a NULL password:

defncopy -Usa -P -SMERCURY in new proc stagedb

**Example 2** Copies definitions for objects sp\_calccomp and sp\_vacation from the employees database on the SYBASE server to the file *dc.out*. Messages and prompts display in french. The user is prompted for a password:

defncopy -S -z french out dc.out employees sp\_calccomp sp\_vacation

Usage

- Use this syntax for defncopy\_r if you are using threaded drivers.
- Use this syntax for defncopy you are using threaded drivers in the IBM platform.

- You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use defncopy.
- Invoke the defncopy program directly from the operating system. defncopy provides a noninteractive way to copy out definitions (create statements) for views, rules, defaults, triggers, or procedures from a database to an operating system file. Alternatively, it copies in all the definitions from a specified file.
- The in *filename* or out *filename* and the database name are required and must be stated unambiguously. For copying out, use file names that reflect both the object's name and its owner.
- defncopy ends each definition that it copies out with the comment:

/\* ### DEFNCOPY: END OF DEFINITION \*/

Definitions created as text must end with this comment so that defncopy can copy them in successfully.

• Enclose values specified to defncopy in quotation marks, if they contain characters that could be significant to the shell.

**Warning!** Long comments of more than 100 characters that are placed before a create statement may cause defncopy to fail.

```
Permissions
```

• You must have select permission on the sysobjects and syscomments tables to copy out definitions; you do not need permission on the object itself.

	• You may not have select permission on the text column of the syscomments table if the System Security Officer has reset the allow select on syscomments.text column parameter with the system procedure sp_configure. This reset restricts select permission to the object owner and the System Administrator. This restriction is required in order to run Adaptive Server in the <b>evaluated configuration</b> , as described in the installation and configuration documentation for your platform. In this case, the object owner or a System Administrator must execute defncopy to copy out definitions.
	<b>Note</b> If the text has been encrypted, it may be hidden from you even if you have all the required permissions. See "Verifying and Encrypting Source Text" in the <i>Transact-SQL User's Guide</i> for more information.
	• You must have the appropriate create permission for the type of object you are copying in. Objects copied in belong to the copier. A System Administrator copying in definitions on behalf of a user must log in as that user to give the user proper access to the reconstructed database objects.
Tables used	syscomments, sysobjects
See also	Commands create, select
	<b>System procedures</b> sp_addlanguage, sp_checkreswords, sp_configure, sp_procqmode, sp_remap

Utilities langinstall

## dscp

Description	(UNIX only) Allows you to view and edit server entries in the interfaces file from the command line in UNIX platforms. Located in <i>\$SYBASE_OCS/bin</i> .
Syntax	dscp [-p]
	or
	dscp -v
	To exit from dscp:
	quit
	or
	exit
Parameters	-p suppresses command-line prompts.
	<ul> <li>-v displays the version and copyright message of dscp and returns to the operating system.</li> </ul>
Examples	Opens the default interfaces file for editing and suppresses the command-line prompt:
	dscp -p
Usage	• You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use dscp.
	• The dscp utility program is a text-based utility.
	• See Chapter 5, "Using dscp" for more information about the dscp utility program.
See also	Utilities dsedit

## dsedit

Description	The dsedit utility allows you to view and edit server entries in the interfaces file using a GUI based on X11/Motif in UNIX platforms. The utility is located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> .
	(Windows) The dsedit.exe utility creates and modifies network connection information in the interfaces file. The utility is located in %SYBASE%\%SYBASE_OCS%\bin.
Syntax	dsedit
	or
	dsedit -v
Parameters	-v displays the version and copyright message of dsedit.
Usage	• You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use dsedit.
	• You must set the DISPLAY environment variable before invoking dsedit, unless you are only using the -v parameter to display the version number.
	• For more information about the dsedit utility program, see Chapter 6, "Using dsedit" Also see the installation guide, and the configuration guide for your platform.
See also	Utilities dscp

## extractjava

Description	Copies a retained JAR and the classes it contains from an Adaptive Server into a client file. Located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> .	
	(Windows) The utility is extrjava.exe, and is located in %SYBASE%\%SYBASE_OCS%\bin.	
Syntax	extractjava (extrjava in Windows) -j jar_name -f file_name [-S server_name] [-U user_name] [-P password] [-D database_name] [-I interfaces_file] [-a display_charset] [-J client_charset] [-J client_charset] [-z language] [-t timeout] [-v]	
	Or	
	extractjava -v	
Parameters	-j jar_name specifies the name assigned to the retained JAR in the database that is the source of the transfer.	
	-f file_name specifies the name of the client file that is the target of the transfer.	
	-S server_name specifies the name of the server.	
	-U user_name specifies an Adaptive Server login name. If you omit the -U flag and parameter, or if you specify the -U flag with no parameter, Adaptive Server uses the current user's operating system login name.	
	-P password specifies an Adaptive Server password. If you omit the -P flag and parameter, extractjava prompts for a password. If you specify the -P flag with no password, the null password is used.	
	-D database_name specifies the name of the database in which to install the JAR. If you omit the -D flag, or if you specify the -D flag with no parameter, the user's default database is used.	

## -l interfaces\_file

specifies the name and location of the interfaces file to search when connecting to Adaptive Server. If you omit the -I flag and parameter, or if you specify the -I flag with no parameter, the interfaces file in the directory designated by your SYBASE environment variable is used.

-a display\_charset

allows you to use extractjava from a machine where the character set differs that of the server. Use -a in conjunction with -J to specify the character set translation file (*.xlt* file) required for the conversion. Use -a without -J only if the client character set is the same as the default character set.

-J client\_charset

specifies the character set to use on the client. extractjava uses a filter to convert input between *client\_charset* and the Adaptive Server character set.

-J *client\_charset* requests that Adaptive Server convert to and from *client\_charset*, the character set used on the client.

-J with no argument disables character set conversion. Use this if the client and server use the same character set.

Omitting -J sets the character set to a default for the platform, which may not necessarily be the character set that the client is using. See the *System Administration Guide* for more information about character sets and associated flags.

-z language

specifies the name of an alternate language for displaying extractjava prompts and messages. Without the -z flag, extractjava uses the server's default language. You can add languages to an Adaptive Server during installation or afterward, using the langinstall utility or the sp\_addlanguage stored procedure.

-t timeout

specifies the number of seconds before a SQL command times out. If you do not specify a timeout, the command runs indefinitely. This affects commands issued from within extractjava, not the connection time. The default timeout for logging into extractjava is 60 seconds.

	٦	
-	1	L
		•

prints the version number and copyright message for extractjava and then exits.

Downloads the classes associated with the employees JAR to the client file *newaddr.jar*.

• On UNIX:

Examples

extractjava	-j employees -t '/home/usera/jars/addr.jar' -new
	On Windows:
extrjava -j	employees -f '\home\usera\jars\addr.jar' -new
Usage	• You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use extractjava.
	• If the target client file already exists, extractjava overwrites its contents.
	• The parameter flags -f, -j, -S, -U, -P, -D, and -I can be written with or without a space between the flag letter and the following parameter.
	• When you execute extractjava, an exclusive lock is placed on sysxtypes.
	• If -jar is specified, an exclusive table lock is placed on sysjars.
Permissions	You need to be a System Administrator or Database Owner to use extractjava.
Tables used	sysjars, sysxtypes
See also	Commands remove java
	<b>Documentation</b> Java in Adaptive Server Enterprise for more information about how this utility is used when Java is enabled in the database.
	System procedures sp_helpjava
	Utilities installjava

# installjava

Description	Installs a JAR from a client file into an Adaptive Server. The utility is located in <i>\$SYBASE_\$SYBASE_OCS/bin</i> .	
	(Windows) The utility is instjava.exe, located in %SYBASE%\%SYBASE_OCS%\bin.	
Syntax	installjava -f file_name [-new   -update ] [-j jar_name] [-S server_name] [-U user_name] [-P password] [-D database_name] [-1 interfaces_file] [-a display_charset] [-J client_charset] [-z language] [-t timeout] [-v]	
	Or	
	installjava -v	
Parameters	-f file_name is the name of the source file containing the classes to be installed in the database.	
	-new   -update specifies whether the classes in the file already exist in the database. If you specify:	
	• -new – you cannot install a class with the same name as an existing class	
	• -update – you can install a class with the same name as an existing class, and the newly installed class replaces the existing class	
	-j jar_name is the name of the JAR containing the classes to be installed in the database. Indicates that the JAR file should be saved in the database and associated with the classes it contains.	
	-S server_name is the name of the server.	

#### -U user\_name

is an Adaptive Server login name. If you omit the -U flag and parameter, or if you specify the -U flag with no parameter, Adaptive Server uses the current user's operating system login name.

#### -P password

is an Adaptive Server password. If you omit the -P flag and parameter, installjava prompts for a password. If you specify the -P flag with no password, the null password is used.

#### -D database\_name

is the name of the database in which to install the JAR. If you omit the -D flag, or if you specify the -D flag with no parameter, the user's default database is used.

## -l interfaces\_file

is the name and location of the interfaces file to search when connecting to Adaptive Server. If you omit the -I flag and parameter, or if you specify the -I flag with no parameter, the interfaces file in the directory designated by your SYBASE environment variable is used.

## -a display\_charset

allows you to use installjava from a machine where the character set differs that of the server. Use -a in conjunction with -J to specify the character set translation file (*.xlt* file) required for the conversion. Use -a without -J only if the client character set is the same as the default character set.

#### -J client\_charset

specifies the character set to use on the client. installjava uses a filter to convert input between *client\_charset* and the Adaptive Server character set.

-J *client\_charset* requests that Adaptive Server convert to and from *client\_charset*, the character set used on the client.

-J with no argument disables character set conversion. Use this if the client and server use the same character set.

Omitting -J sets the character set to a default for the platform, which may not necessarily be the character set that the client is using. See the *System Administration Guide* for more information about character sets and associated flags.

	<ul> <li>-z language</li> <li>is the name of an alternate language for displaying installjava prompts and messages. Without the -z flag, installjava uses the server's default language. You can add languages to an Adaptive Server during installation or afterward, using the langinstall utility or the sp_addlanguage stored procedure.</li> </ul>
	-t <i>timeout</i> specifies the number of seconds before a SQL command times out. If you do not specify a timeout, the command runs indefinitely. This affects commands issued from within installjava, not the connection time. The default timeout for logging into installjava is 60 seconds.
	<ul> <li>v prints the version number and copyright message for installjava and then exits.</li> </ul>
Examples	<b>Example 1</b> Installs <i>addr.jar</i> and its classes, but does not retain the association between the JAR and classes:
	installjava -f '/home/usera/jars/addr.jar' -new
	In Windows:
	instjava -f '\home\usera\jars\addr.jar' -new
	<b>Example 2</b> Reinstalls <i>addr.jar</i> and associates its classes with the employees JAR name:
installjava -f	'/home/usera/jars/addr.jar' -update -j employees
	In Windows:
instjava -f '\h	ome\usera\jars\addr.jar' -update -j employees
Usage	• You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use installjava.
	• Any user can reference installed classes.
	• The parameter flags -f, -j, -S, -U, -P, -D, and -I can be written with or without a space between the flag letter and the following parameter.
	Adding new JARs
	• If you use new with the -jar option and a JAR of that name already exists in the database, an exception is raised.
	• If any classes of the same name as those in the source JAR already exist in the database, an exception is raised.

Updating JARs and classes

**Warning!** If you alter a class used as a column datatype by reinstalling a modified version of the class, you must make sure that the modified class can read and use existing objects (rows) in tables using that class as a datatype. Otherwise, you may be unable to access those objects without reinstalling the class.

- If you use -update with the -jar option:
  - All classes in the database associated with the target JAR are deleted from the database and the classes in the source JAR file installed in their place.
  - If a class in the source JAR file is already installed in the database but is not attached to a JAR, the class in the source JAR is installed in the database and the unattached class is deleted.
- If you use -update without the -jar option:
  - Classes in the source JAR file replace unattached classes of the same name.
  - Classes in the source JAR that do not correspond to an installed class are installed as unattached classes in the database.
- If you install a new JAR with a replacement for an installed class that is referenced by a SQLJ procedure or function, make sure that the newly installed class has a valid signature for the SQLJ routine. If the signature is invalid, an exception is raised when the SQLJ routine is invoked.

### Locks

- When you execute installjava, an exclusive lock is placed on sysxtypes.
- If -jar is specified, an exclusive table lock is placed on sysjars.

You need to be a System Administrator or Database Owner to use installjava.

Tables used	sysjars, sysxty	pes

Commands remove java

**Documentation** Java in Adaptive Server Enterprise for more information about how this utility is used when Java is enabled in the database.

System procedures sp\_helpjava

Utilities extractjava

Permissions

See also

# isql

Description	Interactive SQL parser to Adaptive Server. Located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> .
	(Windows) The utility is isql.exe, located in %SYBASE%\%SYBASE_OCS%\bin.
Syntax	<pre>isql [-b] [-e] [-F] [-n] [-v] [-W] [-X] [-Y] [-Q] [-a display_charsef] [-A packet_size] [-c cmdend] [-D database] [-E editor] [-H header] [-H hostname] [-i inputfile] [-I interfaces_file] [-J client_charsef] [-K keytab_file] [-I login_timeout] [-m errorlevef] [-o outputfile] [-P password] [-R remote_server_principal] [-S server_name] [-t timeout] -U username [-V [security_options]] [-w columnwidth] [-Z security_mechanism] [-conceal]</pre>
	Note See Table 7-2 for a list and description of commands that can be executed
	from within isql.
Parameters	-b disables the display of the table headers output. -e echoes input.

#### -F

enables the FIPS flagger. When you specify the -F parameter, the server returns a message when it encounters a non-standard SQL command. This option does not disable SQL extensions. Processing completes when you issue the non-ANSI SQL command.

#### -p

prints performance statistics.

-n

removes numbering and the prompt symbol (>) from the echoed input lines in the output file when used in conjunction with -e.

-V

prints the version number and copyright message for isql and then exits.

## -X

initiates the login connection to the server with client-side password encryption. -X enables both extended password encrypted connections and password encrypted connections without plain text password reconnection. isql (the client) specifies to the server that password encryption is desired. The server sends back an encryption key, which isql uses to encrypt your password, and the server uses the key to authenticate your password when it arrives.

If isql crashes, the system creates a core file that contains your password. If you did not use the encryption option, the password appears in plain text in the file. If you used the encryption option, your password is not readable.

### -W

disables both extended password and password encrypted negotiations

-Y

tells the Adaptive Server to use chained transactions.

## -Q

provides clients with failover property. See Using Sybase Failover in a High Availability System for more information.

-a display\_charset

runs isql from a terminal whose character set differs from that of the machine on which isql is running. Use -a in conjunction with -J to specify the character set translation file (*.xlt* file) required for the conversion. Use -a without -J only if the client character set is the same as the default character set.

**Note** The ascii\_7 character set is compatible with all character sets. If either the Adaptive Server character set or the client character set is set to ascii\_7, any 7-bit ASCII character can pass unaltered between client and server. Other characters produce conversion errors. For more information on character set conversion, see the *System Administration Guide*.

### -A packet\_size

specifies the network packet size to use for this isql session. For example, the following sets the packet size to 4096 bytes for this isql session:

isql -A 4096

To check your network packet size, enter:

select \* from sysprocesses

- The value is displayed under the network\_pktsz heading.
- *size* must be between the values of the default network packet size and maximum network packet size configuration parameters, and must be a multiple of 512.
- Use larger-than-default packet sizes to perform I/O-intensive operations, such as readtext or writetext operations.
- Setting or changing Adaptive Server's packet size does not affect the packet size of remote procedure calls.
- -c cmdend

changes the command terminator. By default, you terminate commands and send them to by typing "go" on a line by itself. When you change the command terminator, do not use SQL reserved words or control characters.

-D database

selects the database in which the isql session begins.

-E editor

specifies an editor other than the default editor vi. To invoke the editor, enter its name as the first word of a line in isql.

-h headers

specifies the number of rows to print between column headings. The default prints headings only once for each set of query results.

-H hostname

sets the client host name.

-i inputfile

specifies the name of the operating system file to use for input to isql. The file must contain command terminators ("go" is the default).

Specifying the parameter as follows is equivalent to < inputfile:</li>

-i inputfile

- If you use -i and do not specify your password on the command line, isql prompts you for it.
- If you use < inputfile and do not specify your password on the command line, you must specify your password as the first line of the input file.
- -l interfaces\_file

specifies the name and location of the interfaces file to search when connecting to Adaptive Server. If you do not specify -I, isql looks for a file named *interfaces* in the directory specified by your SYBASE environment variable.

-J client\_charset

specifies the character set to use on the client. -J *client\_charset* requests that Adaptive Server convert to and from *client\_charset*, the character set used on the client. A filter converts input between *client\_charset* and the Adaptive Server character set.

-J with no argument sets character set conversion to NULL. No conversion takes place. Use this if the client and server use the same character set.

Omitting -J sets the character set to a default for the platform. The default may not necessarily be the character set that the client is using. For more information about character sets and the associated flags, see "Configuring Client/Server Character Set Conversions," in the *System Administration Guide, Volume One.* 

-K keytab\_file

specifies the path to the keytab file used for authentication in DCE.
#### -l login\_timeout

specifies the maximum timeout value allowed when connecting to Adaptive Server. The default is 60 seconds. This value affects only the time that isql waits for the server to respond to a login attempt. To specify a timeout period for command processing, use the -t *timeout* parameter.

#### -m errorlevel

customizes the error message display. For errors of the severity level specified or higher, only the message number, state, and error level are displayed; no error text appears. For error levels lower than the specified level, nothing appears.

-o outputfile

specifies the name of an operating system file to store the output from isql. Specifying the parameter as -o *outputfile* is similar to > *outputfile* 

-P password

specifies your Adaptive Server password. If you do not specify the -P flag, isql prompts for a password. If your password is NULL, use the -P flag without any password.

-R remote\_server\_principal

specifies the principal name for the server as defined to the security mechanism. By default, a server's principal name matches the server's network name (which is specified with the -S parameter or the DSQUERY environment variable). Use the -R parameter when the server's principal name and network name are not the same.

-s colseparator

resets the column separator character, which is blank by default. To use characters that have special meaning to the operating system (for example, "|", ";", "&", "<", ">"), enclose them in quotes or precede them with a backslash.

The column separator appears at the beginning and the end of each column of each row.

-S server\_name

specifies the name of the Adaptive Server to which to connect. isql looks this name up in the interfaces file. If you specify -S with no argument, isql looks for a server named SYBASE. If you do not specify -S, isql looks for the server specified by your DSQUERY environment variable.

#### -t timeout

specifies the number of seconds before a SQL command times out. If you do not specify a timeout, the command runs indefinitely. This affects commands issued from within isql, not the connection time. The default timeout for logging into isql is 60 seconds.

#### -U username

specifies a login name. Login names are case sensitive.

-V security\_options

specifies network-based user authentication. With this option, the user must log in to the network's security system before running the utility. In this case, users must supply their network user name with the -U option; any password supplied with the -P option is ignored.

You can follow -V with a *security\_options* string of key-letter options to enable additional security services. These key letters are:

- c Enable data confidentiality service
- i Enable data integrity service
- m Enable mutual authentication for connection establishment
- o Enable data origin stamping service
- q Enable out-of-sequence detection
- r Enable data replay detection

#### -w columnwidth

sets the screen width for output. The default is 80 characters. When an output line reaches its maximum screen width, it breaks into multiple lines.

-z locale\_name

specifies the official name of an alternate language to display isql prompts and messages. Without -z, isql uses the server's default language. You can add languages to an Adaptive Server during installation or afterward, using the langinstall utility (langinst in Windows) or the sp\_addlanguage stored procedure.

-Z security\_mechanism

specifies the name of a security mechanism to use on the connection.

Security mechanism names are defined in the *libtcl.cfg* configuration file located in the *ini* subdirectory below the Sybase installation directory. If no *security\_mechanism* name is supplied, the default mechanism is used. For more information on security mechanism names, see the description of the *libtcl.cfg* file in the *Open Client and Open Server Configuration Guide*.

--conceal

Hides your input during an isql session. The --conceal option is useful when entering sensitive information, such as passwords. The syntax for the --conceal option is:

isql --conceal [':?' | 'wildcard']

The maximum length of wildcard, a 32-byte variable, is 80 characters.

**Note** --conceal is silently ignored in batch mode.

Examples

**Example 1** Puts you in a text file where you can edit the query. When you write and save the file, you are returned to isql. The query appears; type "go" on a line by itself to execute it:

```
isql -Ujoe -Pabracadabra
1> select *
2> from authors
3> where city = "Oakland"
4> vi
```

**Example 2** reset clears the query buffer. quit returns you to the operating system:

```
isql -Ualma
Password:
1> select *
2> from authors
3> where city = "Oakland"
4> reset
1> quit
```

**Example 3** Specifies that you are running isql from a Macintosh against a server that is using the roman8 character set:

isql -a mac -J roman8

**Example 4** Creates column separators using the "#" character in the output in the pubs2 database for store ID 7896:

```
isql -Usa -P -s#
1> use pubs2
2> go
1> select * from sales where stor_id = "7896"
#stor_id#ord_num #date #
#-----#
#7896 #124152 # Aug 14 1986 12:00AM#
#7896 #234518 # Feb 14 1991 12:00AM#
```

isql

#### (2 rows affected)

**Example 5** Changes password without displaying the password entered. This example uses "old" and "new" as prompt labels:

```
$ isql -Uguest -Pguest -Smyase --conceal
sp_password
;? old
,
:?:? new
------
old
new
Confirm new
Password correctly set.
(Return status 0)
```

**Example 6** Activates a role for the current user. This example uses a custom wildcard and the prompt labels "role" and "password:"

```
$ isql -UmyAccount --conceal '*'
Password:
set role
* role
with passwd
** password
on
go
role
password
Confirm password
```

Usage

- Use this syntax for isql\_r if you are using threaded drivers.
- Use this syntax for isql if you are using threaded drivers in the IBM platform.
- You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use isql.
- Table 7-2 describes the commands you can execute from within interactive isql.

Command	Description		
:r filename	Reads an operating system file into the command buffer.		
	Do not include the command terminator in the file; once you have finished editing, enter the terminator interactively on a line by itself.		
:R filename	Reads an operating system file into the command buffer and then displays it.		
	Do not include the command terminator in the file; once you have finished editing, enter the terminator interactively on a line by itself.		
use database_name	Changes the current database.		
<pre>!! os_command</pre>	Executes an operating system command. Place at the start of a line.		
>file_name	Redirects the output of the T-SQL command to <i>file_name</i> .		
	The following example inserts the server version into <i>file_name</i> :		
	select @@version		
	go > file_name		
>> file_name	Appends the output of the T-SQL command to <i>file_name</i>		
	The following example appends the server version to <i>file_name</i> :		
	select @@version		
	go >> file_name		
command	Pipes the output of the T-SQL command to an external command		
	The following example finds all instances of "sa" in the listing produced by sp_who:		
	sp_who		
	go   grep sa		
vi (UNIX	Calls the default editor.		
edit (Windows)			
reset	Clears the query buffer.		
quit or exit	Exits isql.		

	Table 7-2:	Commands	available	within	isql
--	------------	----------	-----------	--------	------

- The 5701 ("changed database") server message is no longer displayed after login or issuing a use database command.
- Error message format differs from earlier versions of isql. If you have scripts that perform routines based on the values of these messages you may need to rewrite them.
- When you include the -X parameter, the password-enabled connection proceeds according to server capabilities:
  - If the server can handle both extended password and password encryption, extended password encryption negotiations are used.
  - If the server can handle password encryption only, password encryption negotiations are used.

- If the server cannot handle password encryption or extended password encryption, the first connection attempt fails and the client attempts to reconnect using a plain text password.
- To use isql interactively, give the command isql (and any of the optional parameters) at your operating system prompt. The isql program accepts SQL commands and sends them to Adaptive Server. The results are formatted and printed on standard output. Exit isql with quit or exit.
- Terminate a command by typing a line beginning with the default command terminator go or another command terminator, if the -c parameter is used. You can follow the command terminator with an integer to specify how many times to run the command. For example, to execute this command 100 times, type:

```
select x = 1 go 100
```

The results display once at the end of execution.

• If you enter an option more than once on the command line, isql uses the last value. For example, if you enter the following command, "send", the second value for -c, overrides ".", the first value:

isql -c"." -csend

This enables you to override any aliases you set up.

• To call an editor on the current query buffer, enter its name as the first word on a line. Define your preferred callable editor by specifying it with the EDITOR environment variable. If EDITOR is not defined, the default is vi on UNIX and edit on Windows.

For example, if your EDITOR environment variable is set to "emacs," then you must invoke it from within isql with "emacs" as the first word on the line.

- To clear the existing query buffer, type reset on a line by itself. isql discards any pending input. You can also press Ctrl-c anywhere on a line to cancel the current query and return to the isql prompt.
- Read in an operating system file containing a query for execution by isql as follows:

isql -U alma -Ppassword < input\_file</pre>

The file must include a command terminator. The results appear on your terminal. Read in an operating system file containing a query and direct the results to another file as follows:

isql -U alma -Ppassword < input\_file > output\_file

- Case is significant for the isql flags.
- isql displays only six digits of float or real data after the decimal point, rounding off the remainder.
- You can include comments in a Transact-SQL statement submitted to Adaptive Server by isql. Open a comment with "/\*". Close it with "\*/", as shown in the following example:

```
select au_lname, au_fname
/*retrieve authors' last and first names*/
from authors, titles, titleauthor
where authors.au_id = titleauthor.au_id
and titles.title_id = titleauthor.title_id
/*this is a three-way join that links authors
**to the books they have written.*/
```

If you want to comment out a go command, it should not be at the beginning of a line. For example, use the following to comment out the go command:

```
/*
**go
*/
```

Do not use the following:

- /\* go \*/
- isql defines the order of the date format as month, date, and year (mm dd yyyy hh:mmAM (or PM)) regardless of the locale environment. To change this default order, use the convert function.
- In an isql session, the default prompt label is either the default wildcard :? or the value of *wildcard*. You can customize the prompt label by providing a one-word character string, with a maximum length of 80 characters after a wildcard. If you specify a prompt label that is more than one word, the characters after the first word are ignored.

**Note** In an isql session, isql recognizes :?, or the value of *wildcard*, as wildcards only when these characters are placed at the beginning of an isql line.

Commands create schema, set

See also

Datatype exact numeric datatypes

**Documentation** Chapter 2, "Using Interactive isql from the Command Line" for details on isql, and the *Reference Manual* for more information regarding default network packet size and maximum network packet size configuration parameters.

Functions convert

System ESP xp\_sendmail

**System procedures** sp\_addlanguage, sp\_addlogin, sp\_addremotelogin, sp\_add\_resource\_limit, sp\_bindexeclass, sp\_configure, sp\_defaultlanguage, sp\_droplanguage, sp\_helplanguage, sp\_processmail, sp\_remoteoption, sp\_serveroption, sp\_showcontrolinfo, sp\_unbindexeclass, sp\_volchanged

# langinstall

Description	Installs a new language in an Adaptive Server. Located in <i>\$SYBASE/\$SYBASE_ASE/bin</i> .
	(Windows) The utility is langinst.exe, located in %SYBASE%\%SYBASE_ASE%\bin.
Syntax	langinstall [-S server] [-U user] [-P password] [-R release_number] [-I path] language character_set
	Or
	langinstall -v
Parameters	-S server specifies the name of the Adaptive Server to which to connect. If you do not specify -S, langinstall uses the server specified by your DSQUERY environment variable. If DSQUERY is not set, langinstall attempts to connect to a server named SYBASE.
	-U user specifies a login name. Login names are case sensitive.
	-P <i>password</i> specifies the System Administrator's ("sa" account) password. If you omit -P, langinstall prompts for the "sa" account password.
	-R <i>release_number</i> specifies the release number, in the format <i>n.n.n</i> , to use to upgrade messages in mastersysmessages. Use -R only in failure conditions, such as if langinstall (langinst in Windows) fails, in case of user error, or when you think that messages in sysmessages are out of date.
	The -R parameter forces langinstall to collect messages from a release previous to the current one. langinstall compares the existing messages with the ones to be installed and replaces any that have changed.
	For example, if the current version is 15.0, and the previous version was 12.5, and you think sysmessages may not be correct, include the messages from the earlier version in the syslanguages.upgrade column (12.5 in this case) by specifying -R 12.5. langinstall then installs all messages from Adaptive Server 12.5.

-l patl	ŀ
---------	---

specifies the name and location of the interfaces file (*sql.ini* file in Windows) that langinstall searches when connecting to Adaptive Server. If you do not specify -I, langinstall uses the interfaces file in the directory specified by the SYBASE environment variable. If SYBASE is not set, langinstall looks for the default *SYBASE* directory.

#### language

is the official name of the language to be installed. You must specify a language.

#### character\_set

is the name of Adaptive Server's default character set. *character\_set* indicates the directory name of the localization files for the language. The *common.loc* and *server.loc* localization files for an official language reside in the character set directory *\$SYBASE/locales/language/character\_set* in UNIX platforms, or *%SYBASE%\locales\language\character\_set* in Windows. You must specify a character set.

-v

prints the version number and copyright message for langinstall and then exits.

- The Adaptive Server installation program runs langinstall automatically for a new installation as well as for customers who are upgrading from an earlier version.
- langinstall does the following:
  - Adds the specified language-specific information to master..syslanguages using sp\_addlanguage. If the language already exists, langinstall updates the appropriate row in syslanguages.
  - Adds to, updates, and deletes error messages as necessary from master..sysmessages.
  - Updates syslanguages.update, inserting the new release number.
- langinstall validates the entries in the localization file sections that it uses. If anything is missing, langinstall prints an error message and does not add the language to syslanguages.
- langinstall compares the version numbers of each localization file it uses, *common.loc* and *server.loc*. If they are not the same, it prints a warning message. syslanguages.upgrade is always set according to the version number in *server.loc*.

Permissions

Only a System Administrator using the "sa" account can run langinstall.

Usage

 Tables used
 master.dbo.syslanguages, master.dbo.sysmessages

 See also
 System procedures sp\_addlanguage, sp\_addlogin, sp\_configure, sp\_defaultlanguage, sp\_droplanguage, sp\_helplanguage

 Utilities
 defncopy, srvbuild

# optdiag

Description	Displays optimizer statistics or loads updated statistics into system tables. optdiag is located in <i>\$SYBASE/\$SYBASE_ASE/bin</i> .
	(Windows) The utility is optdiag.exe, located in %SYBASE%\%SYBASE_ASE%\bin.
Syntax	optdiag [binary] [simulate] statistics { -i input_file   database[.owner[.[table[.column] ] ] ] [-o output_file] } [-U user_name] [-P password] [-T trace_value] [-I interfaces_file] [-S server] [-v] [-h] [-s] [-z language] [-J client_character_sef] [-a display_charsef]
Parameters	<pre>binary   extracts statistics in human-readable form and in binary form. When used   with an input file (-i input_file), loads binary statistics into system tables.</pre>
	simulate specifies that optdiag display or load simulated statistics. See the <i>Performance and Tuning Guide</i> .
	<ul> <li>-i input_file specifies the name of the operating system file to use for optdiag input. Specifying an input file causes optdiag to update optimizer statistics for the table or column by using the values in the specified file (also called "input mode").</li> </ul>
	database is the name of the database whose statistics you want displayed. In input mode, optdiag uses the database name as specified in the file, and does not accept a database name from the command line.
	<i>owner</i> is the name of a table owner.
	• In display mode, if you do not specify an owner, but do specify a table name, optdiag displays output for all of the owners of a table.
	• In input mode, optdiag ignores the table owner specified on the command line and uses the value in the input file.

#### table

is the name of the table to survey for statistics.

- If the command does not include an owner name or a table name, optdiag displays statistics for all tables in the database.
- If the command includes an owner name, but no table name, optdiag displays all of the tables that belong to the specified owner.
- In input mode, optdiag ignores the table name specified on the command line and uses the value from the input file.

#### column

is the name of the colum to survey.

- If the command does not include a column name, optdiag displays all statistics for a table.
- In input mode, optdiag ignores the column name on the command line and uses the values from the input file.

#### -o output\_file

specifies the name of an operating system file to store the output from optdiag. If a file with the same name already exists, optdiag overwrites that file without warning.

#### -U user\_name

specifies an Adaptive Server login name.

-P password

specifies your Adaptive Server password. If you do not specify the -P flag, optdiag prompts for a password.

-T trace\_value

sets trace flags for the optdiag session. The optdiag trace flags are:

Flag value	Meaning
1	Do not stop with a warning if the optdiag version of Adaptive Server in use does not match the
	Adaptive Server version in the input file.
2	Display status message "Next table is <i>table_name</i> " when in input mode.
4	Skip consistency checking for step numbers while loading histograms in input mode.
6	Display lines of input file during input mode. This flag has no effect in display mode.
7	Do not stop with a warning if the optdiag input file does not include sampling percent information.

#### -l interfaces\_file

specifies the name and location of the interfaces file to use when connecting to Adaptive Server.

If you do not use -I and specify an interfaces file name, optdiag looks for the interfaces file (*interfaces* in UNIX), in the directory specified by the SYBASE environment variable. In Windows, optdiag looks for a file named *sql.ini* in the *ini* subdirectory in the Sybase installation directory (*d:\sybase*). Then, if SYBASE is not set, optdiag looks for the file in the default \$*SYBASE* directory (%*SYBASE*% in Windows).

#### -S server

specifies the name of the Adaptive Server to which to connect. optdiag looks for this name in the *interfaces* file (*sql.ini* in Windows).

- If you use -S without specifying a server name, optdiag looks for a server named SYBASE.
- When you do not use -S, optdiag looks for the server that your DSQUERY environment variable specifies.

#### -v

displays the version number of and a copyright message for optdiag and exits.

#### -h

displays the optdiag syntax help.

#### -S

includes system tables in optdiag output. By default, only user tables are included.

#### -z language

is the official name of an alternate language that the server uses both for date formats and to display optdiag prompts and messages. Without the -z flag, optdiag uses the server's default language.

You can add languages to Adaptive Server either during or after installation, After Adaptive Server installation, use either the langinstall utility or the sp\_addlanguage stored procedure to add a language.

#### -J client\_charset

specifies the character set to use on the client. A filter converts input between *client\_charset* and the Adaptive Server character set.

By using -J *client\_charset*, you request that Adaptive Server convert data to and from *client\_charset*, the client's character set.

By using -J without a character set name, you specify character set conversion as NULL; no conversion takes place. Use this -J alone when the client and server are using the same character set.

By omitting -J, you set the character set to the default set for the platform. A filter converts input between the default set and the Adaptive Server character set. Keep in mind that the default may not necessarily be the character set that the client is using.

For more information about character sets and their associated flags, see the *System Administration Guide*.

-a	displ	lay_	charset
----	-------	------	---------

runs optdiag from a terminal with a character set that differs from that of the machine on which optdiag is running.

- Use -a in conjunction with -J to specify the character set translation (*.xlt*) file required for the conversion.
- Use -a without -J only if the client character set is the same as the default character set.

**Note** The ascii\_7 character set is compatible with all character sets. If either the Adaptive Server character set or the client character set is set to ascii\_7, any 7-bit ASCII character can pass unaltered between client and server. Any other characters produce conversion errors. For more information on character-set conversion, see the *System Administration Guide*.

On some Linux platforms, the LANG environment variable might be set by default to "en\_US.UTF-8," which can cause unnecessary LONGCHAR conversion between the client and server. If your server and client have different charsets, Sybase recommends that you bypass the conversion using one of these methods:

- unsetenv LANG
- setenv LANG C
- optdiag -J
- optdiag -Jiso-1 (if your server uses iso-1)

Examples Example 1 Displays statistics for all user tables in the pubs2 database and places the output in the *pubs2.opt* file:

optdiag statistics pubs2 -Usa -Ppasswd -o pubs2.opt

**Example 2** Displays statistics for the titles table:

optdiag statistics pubs2..titles -Usa -Ppasswd -o titles.opt

**Example 3** Displays statistics using the roman8 character set and row labels and error messages in French:

optdiag statistics pubs2..titles -Usa -Ppasswd -o titles.opt -J roman8 -z french

**Example 4** Displays binary statistics for the price column in the titles table:

optdiag binary statistics pubs2..titles.price -Usa -Ppasswd -o price.opt

**Example 5** Loads edited statistics from the *price.opt* file:

optdiag statistics -i price.opt -Usa -Ppasswd

Usage

- You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use optdiag.
- By default, optdiag does not include the system tables when you display statistics for a database. To include the system tables in the output, use the -s flag.
- You cannot specify a particular partition on the optdiag command line; optdiag displays statistics for all partitions of a specified table.
- When you use binary mode, optdiag displays the human-readable values with comment marks (#s) at the beginning of the lines, as shown in this example:

```
Statistics for column:
                                 "price"
Last update of column statistics: Jan 20
1998
       7:16PM
Statistics loaded from Optdiag.
    Range cell density: 0x3f8b9cfefece26bf
#
   Range cell density:
                               0.013483040000000
   Total density:
                               0x3f8b9cfefece26bf
#
   Total density:
                                0.013483040000000
   Range selectivity:default used (0.33)Range selectivity:default used (0.33)
#
    In between selectivity:
                              default used (0.25)
#
    In between selectivity:
                                default used (0.25)
```

- When you use optdiag with an input file to change statistics, it ignores all characters after the "#" in a line.
- Converting floating-point values may lead to rounding errors when you use files for input.

When you are loading statistics on the same hardware platform, edit the statistics using the binary values to provide greater precision.

- optdiag displays the statistic, sampling percent last used, which indicates that statistics are gathered with a user-specified sampling percent.
- optdiag displays statistics for each partition of a multi-partitioned table or index.
- optdiag displays global- and partition-level statistics for each column in a table with multiple partitions.

Byte ordering and binary optdiag files

- Do not use the binary mode option to move statistics between Adaptive Servers on machines that use different byte ordering.
  - On an incompatible architecture server, always comment out binary statistics and load the human-readable statistics.
  - On a compatible architecture server, you can load either binary statistics or human-readable statistics.

#### Input mode

- When you use the -i *input\_file* syntax, optdiag reads the file as named and updates statistics in sysstatistics.
- optdiag input mode changes the allow update to system tables configuration parameter by setting the parameter to 1 at the beginning of the session, and then to 0 at the end of the session.
- During histogram input, the process checks the following rules and displays error messages for any violated rules:
  - The step numbers must increase monotonically, unless the command includes the -T4 trace flag.
  - The column values for the steps must increase monotonically.
  - The weight for each cell must be between 0.0 and 1.0.
  - The total of weights for a column must be close to 1.0.
  - The first cell represents null values, and it must be present, even in columns that do not allow null values. There must be only one cell to represent the null value.
  - Two adjacent cells must not both use the < (less than) operator.

See also Commands create index, delete statistics, set, update statistics

**Documentation** *Performance and Tuning Guide* for more information about the optdiag command and an explanation of the optdiag output, and *Performance and Tuning Guide* for more information on changing statistics using optdiag.

**System procedures** sp\_addlogin, sp\_configure, sp\_defaultlanguage, sp\_droplanguage, sp\_flushstats, sp\_helplanguage

## preupgrade

Description	Performs tests on an installation or database to determine its readiness for upgrade, and reports found problems. preupgrade is located in <i>\$SYBASE_ASE/upgrade</i> .
	(Windows) The utility is preupgrd.exe, located in %SYBASE%\%SYBASE_ASE%\upgrade.
Syntax	preupgrade [-v] [-h] [-N] [-p [ <i>skip_sybprocs</i> ] [-D <i>database_name</i> ] [-I <i>interfaces_file</i> ] [-P <i>password</i> ] [-S <i>server_name</i> ] [-U <i>user_name</i> ] [-X <i>option</i> [, <i>option</i> ]]
Parameters	-D database_name limits checking to the named database and a subset of possible checks. Use this parameter to check newly loaded databases before bringing them online.
	-h prints help text and then exits.
	-l interfaces_file specifies an interfaces file for the server. The default is <i>\$SYBASE/interfaces</i> .
	-N specifies preupgrade is to run in noninteractive mode. Thus, if preupgrade determines that any database is too small, the utility exits immediately.
	-p [skip_sybprocs] specifies whether you want to skip the parsing validity test on stored procedures.
	During the upgrade process, stored procedures are automatically re-created internally from the text source, requiring that they be parsed correctly. The valid options for preupgrade -p are:
	• -p – skips the parsing in all databases
	• -p skip_procs – skips parsing in sybsystemprocs while parsing the other databases
	• Not using -p – parses text everywhere. This is the default.

#### -P password

specifies the password for connecting to the server. Sybase recommends that you do not use this option on the command line as the password is then visible to other users when they view displays of system information. Rather, wait until Adaptive Server prompts for a password, and enter the information then.

#### -S server\_name

specifies the name of the server to which you want to connect. This server must be listed in the interfaces file specified by the -I parameter. The default is **\$DSQUERY**.

-U user\_name

specifies the user name to use when connecting to the server. The default is "sa." *user\_name* must have "sa\_role" privileges on the server being checked.

**Note** If you use the -D option, which limits checking to a named database, and that database is offline, you must enter "sa" or accept the default as the user name.

-v

prints version information and exits.

-X option[, option...]

specifies a list of checks to be made. The default is all checks, except when using the -D option, which uses only a subset of available checks. If you specify the -X option more than once on the command line, preupgrade performs only those checks in the last entered -X parameter.

When using the -X parameter with an options list, you must either:

- List options without a space between the comma and the next option, or
- Surround the options list with quotes.

Valid check options are described in Table 7-3. Sybase may occasionally change valid options for the -X parameter; use the -h parameter to view the current set of valid options

Table 7-3: Check options with the -X parameter

Check options	Options used with the -D parameter	Description
all		Performs all permitted checks. When used with the -D option, only checks subset of options. Otherwise, all options are checked

Check options	Options used with the -D parameter	Description
cache		Checks the definition of default cache size. If the definition is DEFAULT, enter its current value in the configuration file as its actual value. This ensures that its size does not change because the new server's default value is different from the current server's default value.
config		Checks the server's configuration parameters to see if they are consistent with new requirements, and reports discrepancies.
		Discrepancies can cause errors or warnings for certain parameters:
		• Errors – occur when the current value of a parameter is outside the new server's range, or when its value is too low for upgrade.
		• Warnings – occur when the current value of a parameter is between the maximum and minimum values, but less than the default value
data_mods		Performs updates to system tables, including clearing certain system table columns that are non-zero. Applies primarily to older Adaptive Servers, and will make no changes to newer systems.
datatype	Х	Checks the systypes table to make sure that if existing datatypes use a system-defined name, type, or user type, they match what the new server expects. Reports discrepancies and suggests remedies.
db_size		Checks that certain system databases meet the minimum size requirements for installation.
free_space	Х	Checks for free space in the named database or in all databases. Makes sure that there is sufficient free data and log space to perform the necessary upgrade steps.
object_id	Х	Checks that object IDs of user-defined objects are not reserved for system objects.
		• Adaptive Server 15.0 and later reserves objects IDs 1 – 255.
		• Adaptive Server 12.5.x and earlier reserves object IDs 1 – 99.
		Does not issue an error. If you receive a warning that a user object ID is reserved, contact Sybase Technical support for directions for changing the user object ID after upgrade.
required_dbs		Checks that required system databases exist. Some versions of Adaptive Server may require specialized databases such as sybsystemdb.
sproc_text	X	Checks for the existence of stored procedure text in the named database or in all databases. After upgrade, Adaptive Server must recompile stored procedures from their source text. This check makes sure that all of the source text is both available and valid.
srvclass		Checks for servers classed as "generic" in master.dbo.sysservers. This class is deprecated by Adaptive Server 12.0 and later.

Check options	Options used with the -D parameter	Description
statistics		Checks for duplicate rows in sysstatistics. Duplicate rows may occur when upgrading from Adaptive Server 12.0 to Adaptive Server 15.0 and later due to schema changes in the sysstatistics table.
Examples	<b>Examp</b> l cache si installat	<b>e 1</b> This example runs preupgrade and specifies checks for the default ze, minimum database size, and duplicate rows in sysstatistics for the ion.
	pre	eupgrade -X cache,db_size,statistics
	<b>Examp</b> l database procedu	<b>e 2</b> This example runs preupgrade to check a newly loaded, offline e. preupgrade checks datatypes, free space, object IDs, and stored re text.
	pre	eupgrade -Dmy_db -Usa
	<b>Examp</b> l When u and exit	<b>e 3</b> This example shows how the sqlupgrade utility uses preupgrade. sed in this way, preupgrade checks all databases, runs noninteractively, s with a failing status if any database is too small.
	pre	eupgrade -N
Usage	• Wh	en preupgrade finds no errors, it exits with status $0$ (zero).
	<ul> <li>pre pro data pro bro</li> </ul>	upgrade is primarily used before upgrading an installation to ensure the cedure will run smoothly. You can also run preupgrade after loading a abase created by a previous version of Adaptive Server to check for blems that might prevent that database from upgrading while being ught online.
	• sqlu	upgrade calls preupgrade as part of its normal procedure.
	• Uni sys	less the -D parameter is included, preupgrade checks all databases in the tem, and runs only on previous server versions.
	• If t	he -D parameter is included, preupgrade:
	•	Checks only the named database.
	•	Can run be run against server of the same version number as the preupgrade utility.
	•	Limits checking to a subset of possible checks. See Table 7-3 for a list of checks that are valid when used in conjunction with this parameter.

	• The -D parameter is used primarily to check newly loaded databases before bringing them online. To do so, preupgrade must force access to offline databases, which requires that preupgrade log in as user "sa" The "sa_role" privilege alone is insufficient. The default is -Usa.
	When run as part of a normal upgrade, the -D parameter is optional, and you can choose a System Administrator login other than "sa."
	• When running preupgrade after upgrade to check a newly loaded but offline database, you must use the -D parameter and either specify the "sa" login or omit the -U parameter.
	• When you specify the -D option, or specify a partial list of options with the -X parameter, preupgrade performs the specified checks and, if there are no errors, displays a list of checks performed in the exit message.
	• You may want to use the -D and the -X parameters as part of the normal upgrade if preupgrade reports warnings or errors for a particular database or area. Using these parameters allows you to focus on problem areas without repeating unnecessary checks.
	sqlupgrade always runs the full set of preupgrade checks. You can correct problems and run preupgrade to ensure that the problems are indeed corrected before letting sqlupgrade repeat the full preupgrade procedure.
Permissions	The user login specified by the -U parameter must have System Administrator privileges to run preupgrade on the server specified by the -S parameter.
	When using the -D parameter to check an offline database, preupgrade must log in as user "sa." The "sa_role" privilege is insufficient
See also	Utilities sqlupgrade, sqlupgraderes

# pwdcrypt

Description	Creates and prints an encrypted LDAP password in the <i>libtcl.cfg</i> file. pwdcrypt is located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> .
	(Windows) The utility is located in %SYBASE%\%SYBASE_OCS%\bin.
Syntax	pwdcrypt
Parameters	None
Examples	Typing pwdcrypt at the prompt returns a request to enter your password twice, after which pwdcrypt returns the LDAP password:
pwdcrypt Enter passwor Enter passwor	rd please: <i>password</i> rd again : <i>password</i>
The encrypted 0x01312a775ab	1 password: 59d5c71f99f05f7712d2cded288d0ae1ce79268d0e8669313d1bc4c706
	Replace the last part of the LDAP URL in <i>libtcl.cfg</i> with this encrypted password:
ldap=libsybd ldap://dolly 0x01312a775ał	ldap.so :389/dc=sybase,dc=com????bindname=cn=Manager,dc=sybase,dc=com? o9d5c71f99f05f7712d2cded288d0ae1ce79268d0e8669313d1bc4c706
	An unencrypted password looks like this:
ldap=libsybd] ldap://dolly	Ldap.so :389/dc=sybase,dc=com????bindname=cn=Manager,dc=sybase,dc=com?

secret

Usage	You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use pwdcrypt.
Permissions	You must use file system permissions to prevent unauthorized access to this encrypted password in your <i>libtcl.cfg</i> file.

### qptune

Description	QPTune is an Adaptive Server utility written in Java/XML. It enables users to fix missing statistics and identify the best query plan, optimization goals, or other configuration settings, and apply them at the query or server level. This results in optimal performance of subsequent query executions.
Syntax	<pre>qptune [-U username] [-P password] [-S hostname:port/database] [-A action] [-M mode] [-T appTime] [-i inputFile] [-o outputFile] [-o outputFile] [-f fileList(,)] [-c configFile] [-l limit] [-e evalField] [-d <diff%(,diff_abs)>] [-m missingCount] [-n login] [-J charset&gt;] [-N (noexec)] [-g (applyOptgoal)] [-v (verbose)] [-s (sort)] [-h (help)]</diff%(,diff_abs)></pre>
Parameters	-U username specifies the database user name.
	-P password specifies the database password.
	-S server specifies the database server. The database server is denoted by <i>host:port/database</i> .
	<b>Note</b> You must specify the -S option while using any QPTune action.

#### -A action

specifies the action to be taken. Valid actions are:

- start
- collect
- collect\_full
- compare
- fix
- start\_stats
- collect\_stats
- fix\_stats
- undo\_fix\_stats

#### -J charset

specifies the character set used to connect to Adaptive Server. If this option is not specified, the Adaptive Server uses the server's default character set.

**Note** If the installed JRE does not support the server's default charset encoding, you see an error message during the login process. Use the -J option to specify a more generic character set, such as -J utf8.

#### -M mode

specifies the optimization goal or custom mode for an application. One of: allrows\_oltp, allrows\_dss, allrows\_mix. You may also define custom modes; \_basic\_ is a system reserved custom mode.

-T appTime

specifies the application running time, in minutes.

-o outputFile

specifies the output file.

-i inputFile

specifies the input file for the fix, fix\_stats, and undo\_fix\_stats actions. You can also use -i to apply special rules to the specified queries for start for custom modes.

-f fileList

compares a list of files to get the best plans; use commas to separate filenames.

-c configFile

specifies the configuration file.

-l *limit* 

specifies a limit on the number of queries that should be analyzed and applied with special rules.

-e evalField

is the evaluation field used for performance comparison.

-d difference

specifies the percentage and absolute value difference for performance improvement to be considered outstanding.

-N

used along with fix\_stats and undo\_fix\_stats, -N generates a SQL script with update statistics or delete statistics statements. The update or delete statements are not executed through QPTune. The statements are written into a SQL script that is specified by the -o option.

-n *login* 

specifies the user's login whose query executions are collected and analyzed.

-m missingCount

specifies the threshold value for missing statistics. The default value is 5.

-v

specifies verbose mode.

-g

when used along with the fix action, applies the default goal. The default goal is the best optgoal setting that most queries used as the best plan using QPTune's fix action. This option only generates plans for queries that do not currently use the server's default optimization goal.

**Example 1** Fixes missing statistics, start the utility with the start\_stats action:

```
QPTune -A start_stats -S my_host:4816/my_database -v
```

Executing : QPTune -U sa -P [unshown] -S jdbc:sybase:Tds:my\_host:4816/my\_database -A start\_stats -M allrows\_dss -T 0 -i null -o metrics.xml -f null -c config.xml -l 5 -e elap\_avg -d 5,5 -m 5 -n null -v You are now connected to database: my\_database [INFO] Config: sp\_configure 'capture missing statistics', 1 [INFO] Config: sp\_configure 'system table', 1 [INFO] Config: delete systatistics where formatid =110

Examples

**Example 2** Uses collect\_stats to retrieve missing statistics information from the sysstatistics table for statistics that exceed a specified threshold for count of missing statistics: QPTune -A collect stats -m 1 -o missingstats.xml -v -S my host:4816/my database Executing : QPTune -U sa -P [unshown] -S jdbc:sybase:Tds:my host:4816/my database -A collect stats -M allrows dss -T 0 -i null -o missingstats.xml -f null -c config.xml -l 5 -e elap avg -d 5,5 -m 1 -n null -v You are now connected to database: my database Now collecting missing statistics information from sysstatistics on "Fri Sep 26 10:08:06 PDT 2008". <?xml version="1.0" encoding="UTF-8"?> <server url="jdbc:sybase:Tds:my host:4816/my database"</pre> file="missingstats.xml" type="missing stats" datetime="Fri Sep 26 10:08:06 PDT 2008" > <missingStat id="1"> <id>1068527809</id> <stats>Y(y4,y2)</stats> <count>2</count> </missingStat> <missingStat id="2"> <id>1068527809</id> <stats>Y(y3)</stats> <count>1</count> </missingStat> <missingStat id="3"> <id>1068527809</id> <stats>Y(y2,y1)</stats> <count>1</count> </missingStat> <missingStat id="4"> <id>1068527809</id> <stats>Y(y1)</stats> <count>1</count> </missingStat> </server> The missing statistics information is written into XML file: missingstats.xml [INFO] End config: sp configure 'enable metrics capture', 0 [INFO] End config: sp configure 'abstract plan dump', 0 [INFO] End config: sp configure 'system table', 0 [INFO] End config: sp configure 'capture missing statistics', 0 Program has restored the data source for metrics collection. ----- QPTune finished executing. ------

**Example 3** After collecting missing statistics information into an XML file called *missingstats.xml*, updates the statistics using the fix\_stats action:

QPTune -A fix stats -m 1 -i missingstats.xml -v -S my host:4816/my database Executing : QPTune -U sa -P [unshown] -S jdbc:sybase:Tds:my host:4816/my database -A fix stats -M allrows dss -T 0 i missingstats.xml -o metrics.xml -f null -c config.xml -l 5 -e elap\_avg d 5,5 -m 1 -n null -v You are now connected to database: my database Fix statistics on "Fri Sep 26 10:14:59 PDT 2008" Details of statements(s) fixed: Fixed statistics: [Update] Y(y4,y2) [INFO] Fix Statement = update statistics Y(y4,y2) Fixed statistics: [Update] Y(y3) [INFO] Fix Statement = update statistics Y(y3) Fixed statistics: [Update] Y(y2,y1) [INFO] Fix Statement = update statistics Y(y2,y1) Fixed statistics: [Update] Y(y1) [INFO] Fix Statement = update statistics Y(y1) ----- QPTune finished executing. ------

Generates a SQL script for updating statistics, without executing the actual updates, by using the -N option to indicate "noexec", and the -o option to indicate the output script file:

QPTune -U sa -P -S my\_host:5000/my\_database -A fix\_stats -m 5 -i missingstats.xml -N -o missingstats.sql

**Example 4** Starts QPTune to apply standard optimization goal settings to queries:

```
QPTune -S host:port/database -A start
    [-M {allrows_oltp, allrows_dss, allrows_mix}]
```

Start QPTune to apply custom rules to specified queries:

**Example 5** Runs your application and collect metrics into an XML file named *a2.xml*:

QPTune -S host:port/database -A collect -T 0

**Example 6** Once metrics are collected, compares different XML files to get the best query optimization goal or criteria for each of the queries:

QPTune -A compare -f a1.xml,a2.xml -d 51,10 -o best.xml -S my\_host:5000/my\_database

This result shows a comparison between two XML metrics files: *a1.xml* has six queries, and *a2.xml* has seven queries. Comparisons can only be made between the queries that are common to both files. There are three queries that ran faster in *a2.xml*:

```
Compare all the files: | a1.xml, a2.xml|
Report generated on "Tue Aug 19 21:13:04 PST 2008"
           _ _ _ _ _ _ _ _ _ _ _ _ _ _ _ _ _ _ _
                            _____
File #1: [name= a1.xml : mode=allrows mix]
File #2: [name= a2.xml : mode=custom 1]
Query count in File #1 : [mode=allrows mix]
                                          6
Query count in File #2 : [mode=custom 1]
                                           7
_____
Query count improved in File #2: [mode=allrows mix] 3
Total performance improved [from 422 to 129]: 69 %
Following queries run better in File #2:
[mode=allrows mix]
_____
Group 1: improved by no more than 25% [0 gueries]
Group 2: improved by 25% to 50% [1 queries]
Query: select count (T.title id) from authors A, titleauthors T where A.au id
= T.au id
Average elapsed time (ms): File #1=100 File #2=50 Improvement=50.0%
```

Outstanding=No
Group 3: improved by 50% to 75% [0 queries]
Group 4: improved by 75% to 100% [2 queries]
Query: select count(\*) from titlles T, titleauthors TA where T.title\_id =
TA.title\_id
Average elapsed time (ms): File #1=34 File #2=7 Improvement=79.0%
Outstanding=Yes
Query: select au\_lname, au\_fname from authors where state in ("CA", "AZ")
Average elapsed time (ms): File #1=9 File #2=0 Improvement=100.0%
Outstanding=No

Usage

If specific values are not indicated for the parameters, the following defaults are used:

- -A : collect
- -M : allrows\_dss
- -T:0
- -o : metrics.xml
- -c : config.xml
- -e : elap\_avg
- -d : 5,5. If percentage is specified but not the absolute value, then absolute value defaults to 0.
- - I limit
- -m 5

Permissions QPtune's compare action may be run by any user. All other actions of QPTune may only be run by users with sa\_role and sso\_role.

See also For more information about the QPTune utility or the QPTune GUI, see the *Migration Technology Guide*.

### qrmutil

Description	(Cluster Edition only) qrmutil is a command line utility that allows you to back up, restore, and reconfigure the quorum device. qrmutil is located in <i>\$SYBASE_\$SYBASE_ASE/bin</i> .
Syntax	<ul> <li>-additional-run-parameters=parameter_list</li> <li>-ase-config-extract=file_name</li> <li>-ase-config-info</li> <li>-ase-config-info</li> <li>-ase-config-store=file_name</li> <li>-ase-config-version=version_number</li> <li>-buildquorum=[force]cluster-take-over</li> <li>-config-file=file_name</li> <li>-diag={all   boot   toc   nodes   locks   config   cms}</li> <li>-display={boot   nodes   heartbeat   master   cluster  </li></ul>
Parameters	additional-run-parameters= <i>parameter_list</i> parameters that Unified Agent uses to start the data server. Unlike other settings, dataserver does not read the additional run parameters. They are read by the unified agent and passed to the dataserver command line. If you include theinstance parameter, the additional run parameters apply to the specified instance. Otherwise, the additional run parameters apply to all instances in the cluster.

--ase-config-extract=file\_name

extracts the Adaptive Server configuration file stored on the quorum device to the named file.

--ase-config-info

displays information about the Adaptive Server configuration file stored on the quorum device.

--ase-config-store=file\_name

stores the named file in the quorum device as the Adaptive Server configuration file.

--ase-config-version=[version\_number]

displays or sets the version of the master Adaptive Server configuration file stored on the quorum device.

--buildquorum[=force]

builds a new quorum device. Use =force to overwrite an exiting file or an existing quorum device on a raw partition. You must include the --cluster-input parameter with --buildquorum.

--config-file=config\_file\_name

if used with -instance, sets this path to the Adaptive Server configuration file for the specified instance. If you do not include -instance, sets the path to the cluster-wide configuration file.

--diag={all | boot | toc | nodes | locks | config | cms} for internal use only.

--display={boot | nodes | heartbeat | master | cluster | instance | config | state} displays the current state of cluster or instance:

- boot displays start-up information for the cluster, including the version of the quorum device, any trace flags issued at start-up, the boot ID of the cluster, and any messages displayed at start-up.
- nodes displays the registered management nodes.
- heartbeat displays heartbeat information for all nodes in the cluster.
- master displays master device information.
- cluster displays the cluster configuration.
- instance displays the instance configuration. You must include --instance=*instance\_name* with this parameter.
- config displays configuration for the cluster and for all instances in the cluster.
- state displays the current state for the cluster and for all instances in the cluster.

#### --drop-cluster=[force]

drops a cluster and removes the quorum device. Use =force to force the drop if the quorum indicates the cluster is running.

Warning! -- drop-cluster removes the cluster.

```
--drop-instance=instance_name
Sybase internal use only.
```

Warning! Use the sybcluster utility to drop an instance from the cluster.

--errorlog=log\_file\_name

full path to the error log for the specified instance. You must include the - instance-name parameter. Takes effect at next restart of the instance.

#### --extract-config=file\_name

extracts the configuration area of the quorum device to the specified file.

-h | --help

displays the full syntax of qrmutil.

-F | cluster-input=file\_name

loads the cluster configuration from the specified cluster input file.

--fence-capable=device\_path

tests if specified device can be used for I/O fencing. Returns either "Device is fence capable" or "Device is not fence capable".

--installation=installation\_mode

changes the installation mode for the cluster. Values are:

- shared (default)
- private

```
-instance=instance_name
```

applies qrmutil parameters to a specified instance.

--interfaces-dir=interfaces\_path

the path to a directory that contains a file named interfaces. If this parameter is used with --instance, it sets the path to the interfaces file for the specified instance. If --instance is not included, sets the path to the cluster-wide interfaces file.

--max-instances=number\_of \_instances

sets the maximum number of instances for the cluster configuration.

--master-dev=master\_device\_name

changes the master device the cluster uses.

--membership-mode=*membership\_mode* sets the membership mode. Values are:

- native (default)
- vcs

--primary-address=*interconnect\_address* 

changes the primary interconnect address for a given instance.

- --primary-port=*port\_number* changes the starting port number for the primary interconnect for a given instance.
- --primary-protocol=*protocol* changes the protocol used for the primary cluster interconnect.
- -Q | --quorum-dev=quoum\_path specifies the full path to the quorum device.
- --register-node=node\_name registers a node for quorum management.

	secondary-address=inteconnect_address changes the secondary interconnect address for a given instance.
	secondary-port= <i>port_number</i> changes the starting port number for the secondary interconnect for a given instance.
	secondary-protocol= <i>protocol</i> changes the protocol used for the secondary cluster interconnect.
	traceflags= <i>trace_flag</i> , <i>trace_flag</i> changes the cluster-wide or the instance-specific trace flags for start-up. If you do not include a list of trace flags, qrmutil clears the trace flags for the cluster instance.
	unregister-node=node_name unregisters a node from quorum management.
	verify-node=node_name indicates that the specified node is registered on the quorum device.
	-v  version displays the version information for the qrmutil utility.
Examples	<b>Example 1</b> Changes the path to the error log to <i>/sybase/opt/cluster/ASE-15_0/ase1.log</i> :
qrmutilquorum errorlog=/syba	_dev=/dev/raw/raw101instance=ase1 se/cluster/ASE-15_0/ASE-15_0/ase1.log
	<b>Example 2</b> Registers the node "blade5" for mycluster:
qrmutilquorum	_dev=/dev/raw/raw101register-node=blade5
	<b>Example 3</b> Creates a new quorum device for the cluster "mycluster":
qrmutilquorum input=/sybase/cl	-dev=/dev/raw/raw101cluster- uster/ase1.inp -buildquorum
	<b>Example 4</b> Vacks up the quorum device to <i>/sybase/cluster_bak/quorum.bak</i> :

qrmutil --quorum-dev=/dev/raw/raw101
--extract-config=/sybase/cluster\_bak/quorum.bak

**Example 5** Restores the quorum device from the backup created in */sybase/cluster\_bak/quorum.bak*:

qrmutil --quorum-dev=/dev/raw/raw101 --clusterinput=/sybase/cluster\_bak/quorum.bak --buildquorum=force

**Example 6** Displays the cluster configuration stored on the quorum device:
qrmutil --quorum-dev=/dev/raw/raw101 --display=config

**Example 7** Rests whether the named device can be fenced:

```
grmutil --quorum-dev=/dev/raw/raw101 --fence-capable=/dev/raw/raw106
```

Usage

- qrmutil is primarily a diagnostic utility. Sybase recommends that you use sybcluster to make configuration changes to the cluster.
- You can pass as many as 20 commands to qrmutil. However, you can specify the --instance= parameter only once.
- If you specify --buildquorum, the quorum is built and qrmutil exits without running any commands other than --cluster-input.
- qrmutil exits after it executes the --drop-cluster parameter.
- This is an example of using multiple commands:

```
qrmutil --quorum-dev=/dev/raw/raw101 --display=cluster
--register-node=blade1 --unregister-node=blade2 --verify-node=blade3
```

Permissions

To run qrmutil, you must be the same sybase user that started the instance, with execute priveledges on the qrmutil binary, have direct access to the quorum device, and at least read permissions on the quorum file.

## showserver

Description	(UNIX only) Shows the Adaptive Servers and Backup Servers that are currently running on the local machine, available only in UNIX platforms. showserver is located in <i>\$SYBASE/\$SYBASE_ASE/install</i> .
Syntax	showserver
Parameters	None
Examples	Shows the Adaptive Servers and Backup Servers that are currently running on the local machine:
showserver	
USER PID user114276 0.0 -d greensrv.dat sybase 1071 /usr/local/sybas user128493 0.0 -e/install/backu	<pre>%CPU %MEM SZ RSS TT STAT START TIME COMMAND 1.7 712 1000 ? S Apr 5514:05 dataserver -sgreensrv -einstall/greensrv+_errorlog 0.0 1.4 408 820 ? S Mar 28895:38 e/bin/dataserver -d/dev/rsd1f -e/install/errorlog 0.0 3692 0 ? IW Apr 1 0:10 backupserver -SSYB_BACKUP p.log -Iinterfaces -Mbin/sybmultbuf -Lus_english -Jiso_1</pre>
Usage	showserver displays process information about Adaptive Server or Backup Server. If no servers are running, only the header appears.
See also	Commands dataserver, startserver
	Function host_name
	Utilities langinstall

## sqldbgr

Description sqldbgr is a command line utility that debugs stored procedures and triggers. As with many source-level debuggers, you can: Attach sqldbgr to a task ٠ Set, enable, and disable breakpoints . . Step through a task one line at a time Step into and out of procedures Detach sqldbgr from stored procedures or triggers once the debugging is complete. (UNIX) sqldbgr is located in \$SYBASE/\$SYBASE ASE/bin. ٠ (Windows) sqldbgr is located in %SYBASE%\%SYBASE ASE%\bin. **Note** You do not have the ability to view sqldbgr version strings. Syntax saldbar -U username -P password -S host.port Parameters -U username specifies the user name. You must insert a space between -U and username. -P password specifies the user password. You must insert a space between -P and password. -S host.port specifies the machine name and the port number. You must insert a space between -S and host:port. Examples **Example 1** Shows sqldbgr debugging stored procedures and triggers on host **MERCURY:** \$SYBASE/\$SYBASE ASE/bin/sqldbgr -U sa -P -S MERCURY:16896 (sqldbg) stop in sp who Breakpoint moved to line 20 (sqldbg) run sp who (sp who::20)if @@trancount = 0 (sqldbg) next set chained off (sp who::22)

(sqldbg) cont

```
fid spid status loginame origname hostname blk spid dbname cmd block xloid
   2
        sleeping NULL
                                               NETWORK HANDLER
0
                       NULL
                                0
                                        master
                                                                     0
0
   3
        sleeping NULL
                       NULL
                                0
                                                 NETWORK HANDLER
                                                                     0
                                        master
0
   4
        sleeping NULL
                       NULL
                                0
                                        master DEADLOCK TUNE
                                                                     0
0
   5
       sleeping NULL
                       NULL
                                0
                                        master MIRROR HANDLER
                                                                     0
                                        master ASTC HANDLER
0
   6
       sleeping NULL
                       NULL
                                0
                                                                     0
0
  7
       sleeping NULL
                       NULL
                               0
                                        master ASTC HANDLER
                                                                     0
                                        master CHECKPOINT SLEEP
0
  8
       sleeping NULL
                       NULL
                               0
                                                                     0
                                        master HOUSEKEEPER
0
  9
       sleeping NULL NULL
                               0
                                                                     0
0
  10
      running sa
                               0
                                        master SELECT
                                                                     0
                       sa
0
   11
        sleeping sa
                       sa
(sqldbg) show breakpoints
1 stop in sp who
(sqldbq)
```

**Example 2** In this example, the System Administrator first logs in to Adaptive Server using isql, then starts sqldbgr from the command line to debug a stored procedure that is running in another task:

```
$SYBASE/$SYBASE OCS/bin/isql -U sa -P
1> select @@spid
2> qo
_ _ _ _ _ _
12
1>
$SYBASE/$SYBASE ASE/bin/sqldbgr -U sa -P -S MERCURY:16896
(sqldbg) attach 13
The spid is invalid
(sqldbg) attach 12
(sqldbg) show breakpoints
(sqldbq) stop in sp who
Breakpoint moved to line 20
(sqldbg) /* at this point run the sp who procedure from spid 12 */
(sqldbq) where
(sp who::20::@loginname = <NULL>)
(ADHOC::1::null)
(sqldbq) next
(sp who::22)
               set chained off
(sqldbq) next
(sp who::25)set transaction isolation level 1
(sqldbg) cont
(sqldbq) /* at this point the sp who result will show up in the isql screen */
(sqldbq) detach 12
(sqldbg)
```

Usage	• The sql command is executed in the context of debugged task, while the mysql command is executed in the context of debugger task. Setting session-specific information, such as for set quoted_identifier on through sql does not work.
	• By default, the Sybase jConnect JDBC driver uses set quoted_identifier on. Since the sqldbgr utility is built using jConnect arguments that need quotes, use single quotes instead of double quotes when entering options. For example, use sp_configure 'allow update' instead of sp_configure "allow update".
	• Before you can run sqldbgr, you must set either the SYBASE_JRE or JAVA_HOME environments to the location containing the Java run environment.
	• When you invoke sqldbgr at the command prompt, the utility starts and the prompt changes to a sqldbgr prompt:
	(sqldbgr)
	Once you see the (sqldbgr) prompt, you can enter the following sqldbgr commands to perform your tasks:
	Table 7-4: sqldbgr commands and their descriptions
Command	Description
attach spid	Attaches a task to sqldbgr when you are already logged in to Adaptive Server.
	<b>Note</b> Do not use attach <i>spid</i> to attach to a procedure that is not running.
	sqldbgr cannot debug multiple tasks in the same session. If you try to attach the utility to multiple tasks, the first <i>spid</i> continues to be marked as attached. Since you cannot attach to a <i>spid</i> that is already attached, you must use the detach command, and then attach to another <i>spid</i> .

	Cannot run a procedure while debugging another task
stop in <i>procname</i> [at line #]	Sets a breakpoint to stop the stored procedure or trigger being debugged at the beginning of the specified procedure name.
	stop in <i>procname</i> at line # sets a breakpoint to stop the stored procedure or trigger being debugged at a designated line within the specified procedure.
	If you enter an invalid line number, sqldbgr moves the breakpoint to the next valid line number, and displays:

with attach spid, run procname fails and you see the following:

Debugs stored procedures and triggers without attaching sqldbgr to an existing task.

If you attempt to use run procname while you are already debugging an existing task

Invalid line number

You can also use this command to set multiple breakpoints.

run procname

Command	Description
show breakpoints	Displays the breakpoint handle in the form of a unique number, as well as the breakpoint statements given by the user during the sqldbgr session.
	If you specify a breakpoint line number that does not contain a valid SQL statement, Adaptive Server moves the breakpoint to the next valid line number. However, Adaptive Server does not change the command you entered. This is why show breakpoints can return a breakpoint handle and a breakpoint statement given during the sqldbgr session that can be different.
	An asterisk (*) in the breakpoint line indicates that the breakpoint is set, but currently disabled.
use dbname	Tells sqldbgr what database to use in order to debug that database's stored procedures or triggers.
show variables [at level #] show @ <i>varname</i> [at level #]	show variables displays all the variables and their values in the current SQL stored procedure or trigger.
	show variables at level # displays the variables and their values in the current SQL stored procedure or trigger at the specified level.
	show @ varname displays the indicated variable and its value in the current SQL stored procedure or trigger.
	show @varname at level # displays the indicated variable and its value in the current SQL stored procedure or trigger at the specified level.
	Note sqldbgr does not support Java variables.
show where	Displays the call stack of the stored procedures and triggers that exist in the task being debugged.
step or next	step or next instructs sqldbgr to move to the next statement in the current stored procedure or trigger.
step into	Instructs sqldbgr to move into a procedure if the current statement is an execute statement. If the current statement is an update, delete, or insert statement, and if there are triggers in it, step into instructs sqldbgr to move into the update, delete, or insert triggers.
step out	Instructs sqldbgr to move out of the current stored procedure or trigger, and to stop at the next line in the calling procedure.
set @varname = VALUE	Sets the value of the indicated variable to the variable value declared in the command in the current stored procedure or trigger. The values for the variables set using set @varname = VALUE are valid only for the current session sqldbgr.
cont[inue]	Instructs sqldbgr to continue debugging, and to stop at the next breakpoint (if any).
delete #	Deletes the indicated breakpoint set in the current instance of sqldbgr.
enable # and disable #	Enables the indicated breakpoints. disable # does the opposite.
sql any_sql_statement	Executes ad hoc SQL statements. You can use this command to select and analyze data from temp tables created by the task being debugged.
	sql any_sql_statement returns a result set and any errors that occurred.

Command	Description
detach spid	Detaches sqldbgr from the indicated <i>spid</i> , and releases the task being debugged.
	It deletes the breakpoints that were set for the task being debugged during the current sqldbgr session.
help [all]	Display sqldbgr commands.

Table 7-5 lists all sqldbgr error messages:

Error message	Description
Cannot allocate resource	Indicates that Adaptive Server does not have sufficient memory resources to
in ASE	execute sqldbgr. Increase procedure cache size and restart sqldbgr.
Cannot create Debugger	Indicates that Adaptive Server does not have sufficient memory resources to
handle in ASE	create a debugger handle. Increase procedure cache size and restart sqldbgr.
The spid is invalid	Displays when you attempt to attach sqldbgr to an invalid spid. Double check
	the <i>spid</i> and try again.
You cannot debug a task	Displays when you try to debug a task that you do not own. You must log in
that is not owned by you	to the server as the owner of the task to be debugged.
Spid is already being	Displays when you execute attach spid and attempt to attach to a spid that is
debugged	already being debugged.
Spid is not debugged	Displays when you execute detach spid and attempt to detach from a spid
currently	that is not attached to sqldbgr.
Invalid command	Displays when you enter an invalid command.
Invalid procedure name	Displays when you enter an invalid procedure name in stop in procname.
Invalid line number	Displays when you enter an invalid line number in stop in procname at line #.
Variable not found	Displays when you enter an invalid variable in show @varname, show
	@varname at level #, or set @varname = VALUE.
Illegal conversion	Displays when you execute set @varname = VALUE and attempt to convert
attempted	the variable to an invalid value.
Conversion from text to	Displays when set @varname = VALUE is unsuccessful.
datatype failed	
Cannot run a procedure	Displays if you use run procname while already debugging an existing task
while debugging another	with attach spid.
task	

#### Table 7-5: sqldbgr error messages and their meaning

# sqlloc

Description	(UNIX only) Installs and modifies languages, character sets, and sort order defaults for Adaptive Server using a GUI based on X11/Motif. sqlloc is located in <i>\$SYBASE/\$SYBASE_ASE/bin</i> .
Syntax	sqlloc [-S server] [-U user] [-P password] [-s sybase dir] [-I interfaces file] [-r resource file]
	Or
	sqlloc -v
Parameters	-S server specifies the name of the Adaptive Server to which to connect.
	-U user specifies a login name. Logins are case sensitive.
	-P password specifies the "sa" account password.
	-s sybase dir specifies the value to use for the SYBASE environment variable.
	-I <i>interfaces file</i> specifies the name and location of the interfaces file to search when connecting to Adaptive Server.
	-r resource file executes the specified resource file.
	-v prints the version number and copyright message for sqlloc and then exits.
Usage	• You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use sqlloc.
	• You must set the DISPLAY environment variable before invoking sqlloc, unless you are only using the -v parameter to display the version number.
Permissions	You must be a Sybase System Administrator to use sqlloc.
See also	<b>Documentation</b> <i>Installation Guide for UNIX Platforms</i> for more information about sqlloc.
	Utilities langinstall, sqllocres

# sqllocres

Description	(UNIX only) Installs and modifies languages, character sets, and sort order defaults for Adaptive Server, using a resource file. sqllocres is located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> .
Syntax	sqllocres [-S server] [-U user] [-P password] [-s sybase dir] [-I interfaces file] [-r resource file]
	Or
	sqllocres -v
Parameters	-S server specifies the name of the Adaptive Server to which to connect.
	-U user specifies a login name.
	-P password specifies the "sa" account password.
	-s sybase dir specifies the value to use for the SYBASE environment variable.
	-l <i>interfaces file</i> specifies the name and location of the interfaces file to search when connecting to Adaptive Server.
	-r resource file executes the specified resource file.
	-V
	prints the version number and copyright message for sqllocres, then exits.
Usage	You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use sqllocres.
Permissions	You must be a Sybase System Administrator to use the sqllocres utility.
See also	For more information about the sqllocres utility program, see the <i>Installation Guide for UNIX Platforms</i> .
	Utilities langinstall, sqlloc

# sqlsrvr

Description	(Windows only) The executable form of the Adaptive Server program, this utility is located in <i>%SYBASE%\%SYBASE_ASE%\bin</i> .
Syntax	sqlserver [-f] [-g] [-G] [-h] [-H] [-m] [-P] [-q] [-v] [-X] [-a path_to_CAPs_directive_file] [-b master_device_size] [k   K   m   M   g   G   t   T ] [-c config_file_for_server] [-d device_name] [-e path_to_error_log] [-i interfaces_file_directory] [-K keytab_file] [-L config_file_name_for_connectivity] [master_key_password [=password] [-M shared_memory_repository_directory] [-p sa_login_name] [-r mirror_disk_name] [-s server_name] [-T trace_flag] [-u sa/sso_name] [-w master   model database] [-y [password] ] [-z page_size [ k   K ] ]
Parameters	-f forces initialization of a device or database. You must use both -b and -w to use -f.
	-g turns off event-logging.
	-G specifies the name of the event log server.
	-h prints this help message, then exists.
	-H starts the High Availability (HA) server, if you have the HA feature installed on your Adaptive Server.
	-m starts Adaptive Server in single-user mode.
	-q treats quiesced databases as "in recovery."
	-v prints the version number and copyright message for sqlsrvr and then exits.

-X

starts this server as sybmon, not dataserver.

- -a path\_to\_CAPs\_directive\_file specifies the path to the CAPs directive file.
- -b master\_device\_size [k | K | m | M | g | G | t | T] specifies the size of the master device.
- -c config\_file\_for\_server

specifies the full path name of an Adaptive Server configuration file. Use this parameter to start Adaptive Server with the configuration values in the specified configuration file.

If you specify a configuration file with the sqlsrvr -c parameter, make sure all the parameters in this configuration file are compatible before you boot the server. If some of the configuration parameters are incompatible, the server may not start. To avoid this, do not specify a configuration file when you build the master device. The build phase uses all default settings when you do not specify a configuration file.

For more information, see the System Administration Guide: Volume 1.

-d device\_name

is the full path name of the device for the master database. The master database device must be writable by the user who starts Adaptive Server. The default master database device name is d\_master.

-e errorlogfile

is the full path name of the error log file for Adaptive Server system-level error messages.

-i interfaces\_file\_directory

specifies the directory location of the interfaces file to search when connecting Adaptive Server. If -l is omitted, sqlsrvr looks for a file named *interfaces* in the directory pointed to by your SYBASE environment variable.

-K keytab\_file

specifies the path to the keytab file used for authentication in DCE.

-L config\_file\_name\_for\_connectivity specifies the name the configuration file for connectivity.

#### --master\_key\_password [=password]

specifies the master key password when you provide the *password* on the command line or prompts for a master key password during Adaptive Server startup. The password characters are not displayed, and the password is not validated until later in the Adaptive Server startup sequence.

If you include the password on the command line, it is visible until the memory is read and used.

#### -M sharedmem\_directory

places shared memory files in the specified directory instead of in the default location, *%SYBASE%*. If *sharedmem\_directory* starts with "\", the directory name is assumed to be absolute. Otherwise, the directory name is interpreted relative to *%SYBASE%*.

#### -p sso\_login\_name

specifies the login name of a System Security Officer when starting Adaptive Server, for the purposes of getting a new password for that account. Adaptive Server generates a random password, displays it, encrypts it, and saves it in master..syslogins as that account's new password.

#### -r mastermirror

starts the mirror of the master device. Use this parameter to start Adaptive Server if the master device has been damaged.

#### -s servername

specifies the name of the Adaptive Server to start. If -s is omitted, a server named SYBASE is started.

-T trace\_flag

#### -u sa/sso\_name

specifies the System Administrator or System Security Officer's name you want to unlock.

#### -w master | model\_database

specifies whether you want to write a master or model database.

	-y [ <i>password</i> ] allows you to assign a password for the encrypted private key, so that the server prompt the user for a password. This password should match the password you used to encrypt the private key when it was created. You cannot use this parameter when you are running the server in the background.
	<b>Note</b> Although you can a password with -y, for security reasons Sybase strongly discourages you from doing so.
	A private key is included with your server's digital certificate. By default, the certificate file located:
	%SYBASE%\%SYBASE_ASE%\certificates\ <i>servername</i> .crt
	The location of the certificate file changes if you invoke the sp_ssladmin addcert command.
	-z page_size specifies the page size of the server. You must use -b and -w to use this flag, and name an even power of two between 2k and 16k, or else the server does not boot.
Examples	<b>Example 1</b> Creates a new installation with a 100MB master device and a 4k page:
	sqlsrvr -d d_master -z 4k -b 100.02M
	The spaces between options and their following arguments are optional and acceptable. This example specifies "100.02M" for a 100MB master device because the server requires 16KB of overhead for its configuration area.
	<b>Example 2</b> Rewrites a corrupt model database:
	sqlsrvr -d d_master -w model
	<b>Example 3</b> Rewrites a corrupt master database, specifying device size:
	sqlsrvr -d d_master -w master -z 4k
	<b>Example 4</b> Rewrites a corrupt master database, specifying device and page sizes, forcing the server to accept these values in preference to what it may find in the config block:
	sqlsrvr -d d_master -w master -z 4k -b 100.02M -f
	<b>Example 5</b> Rewrites a corrupt master database, specifying a page size that does not match what the server finds in its config block. This produces a

failure:

```
sqlsrvr -d d_master -w master -z 8k
```

```
00:00000:00000:2001/01/19 12:01:26.94 server The configured server page size does not match that specified on the command line. To use the configured size, omit the command line size; to use the command line size, specify 'force' (-f).
```

**Example 6** Rewrites a corrupt master database, specifying an incorrect page size, even in a normal boot. This produces a failure:

sqlsrvr -d d master -z4000

sqlsrvr: the 'z' flag may not be used without 'b' or 'w'. sqlsrvr: server will ignore the 'z' flag. sqlsrvr: the 'z' flag contained an invalid page size. sqlsrvr: the page size must be an even power of two between 2048 and 16384 bytes, inclusive.

- The sqlsrvr utility is referred to as dataserver in other Sybase documents.
- Start Adaptive Server using the services manager utility rather than by executing the sqlsrvr program directly. If you need to change any of the default parameters, edit the Adaptive Server's Registry keys. See the configuration guide for your platform for details.
- Adaptive Server derives its running environment from values in the sysconfigures system table. Run sp\_configure to see the configuration values; use sp\_configure and reconfigure to change the configuration.
- Because Adaptive Server passwords are encrypted, you cannot recover forgotten passwords. If all System Security Officers lose their passwords, the -p parameter generates a new password for a System Security Officer's account. Start Adaptive Server with -p, immediately log in to Adaptive Server with the new random password, and execute sp\_password to reset your password to a more secure one.
- By default, Adaptive Server logs error messages in both the local error log file and the local Windows event log. You can disable Windows event logging by including the -g parameter and specifying a different event-logging machine with -G *machine\_name*. Use standard Windows conventions when entering the *machine\_name*. For example, to designate a PC named "LOGSITE", substitute "\\LOGSITE" for the *machine\_name*. See the configuration guide for your platform for details on logging error messages.
- After you have finished running the installer, set the file permissions on the sqlsrvr executable to limit who can execute it.

Usage

- If you do not specify an Adaptive Server name with the -s parameter, and you have not set the DSLISTEN environment variable, sqlsrvr uses the default Adaptive Server name SYBASE. The value of the DSLISTEN environment variable overrides this default value, and the -s parameter overrides both the default and the DSLISTEN environment variable.
- Automatic login lockouts can cause a site to end up in a situation in which all accounts capable of unlocking logins (System Administrators and System Security Officers) are locked. If this occurs, use the sqlsrvr utility with the -u parameter to check the specified login for System Administrator or System Security Officer authorization, unlock the account, and reset the value of the current failed logins counter to zero.
- -f is only valid when used with -b and/or -w. The server fails to boot if you use -f without either -b or -w. -f forces the server in different ways, depending whether -w is present. See -b and -w below.

#### Starting Adaptive Server

Use either of the following methods to start Adaptive Server with a specified configuration file:

• Use Server Config to configure the server to have the -c parameter. In the Configure Adaptive Server window, select the Command Line option, and in the Command Line Parameters window, enter:

-Cconfiguration\_file\_pathname

For example, entering "-chaze.cfg " starts the server using the *haze.cfg* configuration file.

• Start Adaptive Server from the command line and provide the -c parameter.

Dependencies and conditions with -b and -w

The effect of -b changes depending on whether -w is present:

- -b without -w creates a new master device as named by -d (the default is d\_master) and with the page size as specified by -z (the default is 2048):
  - If the named device already exists as an OS file, the attempt fails, and you must remove the existing file and try again.
  - If the named device names an existing raw partition, the attempt fails unless you include the -f flag. This reinitializes the raw partition as a server master device.

•	-b with -w master tells dataserver to use the size specified in -z for the
	master device when recreating the master database. It implies nothing
	about creating a new device.

-w may or may not require additional flags:

- If you use -w model, the -z and -b flags are accepted but ignored.
- If you use -w master for **new** installations, -z and -b are not required because the device size information is stored in the *config\_block*.
- If you use -w master to **upgrade** older installations:
  - The server requires -b and/or -z if the *config\_block* does not contain a valid entry for the associated size(s). The command fails if it can't get valid data for the page size or device size.
  - You may provide -b and/or -z when the *config\_block* contains valid entries for the size(s) they represent. However if the sizes do not match what is in the *config\_block*, you must add -f to force your new size preferences.
  - -f may appear without either -b or -z, because -f also instructs the server to accept damaged allocation pages as belonging to the master database. This is useful for restoring badly corrupted databases. If you specify -w master -f, the server assigns to the master database every allocation page on the named master device that does not belong to some other database than master.
- Permissions Anyone with execute permission on the binary, and who has read/write access to all the files.

 Tables used
 sysconfigures

 See also
 Commands
 disk mirror, disk remirror, reconfigure

 System procedures
 sp\_configure, sp\_password

 Utilities
 startserver

# sqlupgrade

Description	(UNIX only) Upgrades your currently installed version of Adaptive Server to the newest release using a GUI based on X11/Motif. sqlupgrade is located in <i>\$SYBASE/\$SYBASE_ASE/bin</i> .
Syntax	sqlupgrade [-s <i>sybase dir</i> ] [-r <i>resource file</i> ]
	Or
	sqlupgrade -v
Parameters	-s sybase dir specifies the value to use for the SYBASE environment variable.
	-r resource file executes the specified resource file.
	-v prints the version number and copyright message for sqlupgrade and then exits.
Usage	• You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use sqlupgrade.
	• You must set the DISPLAY environment variable before invoking sqlupgrade, unless you are only using the -v parameter to display the version number.
Permissions	You must be a Sybase System Administrator to use sqlupgrade.
See also	<b>Documentation</b> <i>Installation Guide for UNIX Platforms</i> for more information about sqlupgrade.
	Utilities preupgrade, sqlupgraderes

# sqlupgraderes

Description	(UNIX only) Upgrades your currently installed release of Adaptive Server to the newest release using resource files. sqlupgraderes is located in <i>\$SYBASE/\$SYBASE_OCS/bin</i> .
Syntax	sqlupgraderes [-s sybase dir] [-r resource file]
	Or
	sqlupgraderes -v
Parameters	-s Sybase Dir specifies the value to use for the SYBASE environment variable.
	-r Resource File executes the specified resource file.
	-v prints the version number and copyright message for sqlupgraderes and then exits.
Usage	You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use sqlupgraderes.
Permissions	You must be a Sybase System Administrator to use sqlupgraderes.
See also	<b>Documentation</b> <i>Installation Guide for UNIX Platforms</i> for more information about sqlupgraderes.
	Utilities sqlupgrade

## srvbuild

Description	(UNIX only) Creates a new Adaptive Server, Backup Server, or XP Server with default or user-specified values for key configuration attributes. You can use srvbuild in either GUI mode based on X11/Motif, or non-GUI mode. srvbuild is located in <i>\$SYBASE/\$SYBASE_ASE/bin</i> .
Syntax	srvbuild [-s sybase_dir] [-l interfaces_file] [-r resource_file]
	Or
	srvbuild -v
Parameters	-s sybase_dir specifies the value to use for the SYBASE environment variable.
	-I <i>interfaces_file</i> specifies the name and location of the interfaces file to search when connecting to Adaptive Server.
	-r resource_file executes the specified resource file.
	-v prints the version number and copyright message for srvbuild and then exits.
Usage	You must set the SYBASE environment variable:
	• To the location of the current version of Adaptive Server before you can use srvbuild.
	• Before invoking srvbuild, unless you are only using the -v parameter to display the version number.
	Using LDAP with srvbuild in a 64-bit environment
	When you use srvbuild to build a new server using a Lightweight Directory Access Protocol (LDAP) service in a 64-bit environment, you must edit the LDAP server entry.
	srvbuild is a 32-bit application and uses the LDAP server entry from the <i>\$SYBASE_OCS/config/libtcl.cfg</i> file. Adaptive Server is a 64-bit application and uses the LDAP server information from the <i>\$SYBASE_OCS/config/libtcl64.cfg</i> file.
	Do not include any blank spaces after the LDAP server entry in the <i>libtcl.cfg</i> or <i>libtcl64.cfg</i> files; these prevent srvbuild from connecting to the LDAP server.

Permissions	You must be a Sybase System Administrator to use srvbuild.
See also	<b>Documentation</b> <i>Installation Guide for UNIX Platforms</i> for more information about srvbuild, and Chapter 11, "Managing Adaptive Server Logins, Database Users, and Client Connections," in the <i>System Administration Guide</i> for more information on configuring a server using LDAP.
	Utilities srvbuildres

## srvbuildres

Description	(UNIX only) Creates, using resource files, a new Adaptive Server, Backup Server, or XP Server with default or user-specified values for key configuration attributes. srvbuildres is located in <i>\$SYBASE/\$SYBASE_ASE/bin</i> .
Syntax	srvbuildres [-s sybase_dir] [-l interfaces_file] [-r resource_file]
	Or
	srvbuildres -v
Parameters	-s sybase_dir specifies the value to use for the SYBASE environment variable.
	-l interfaces_file specifies the name and location of the interfaces file to search when connecting to Adaptive Server.
	-r resource_file executes the specified resource file.
	-v prints the version number and copyright message for srvbuildres and then exits.
Usage	You must set the SYBASE environment variable to the location of the current version of Adaptive Server before you can use srvbuildres.
Permissions	You must be a Sybase System Administrator to use srvbuildres.
See also	<b>Documentation</b> <i>Installation Guide for UNIX Platforms</i> for more information about srvbuildres.
	Utilities srvbuild

## startserver

Description	(UNIX only) tarts an Adaptive Server or a Backup Server. startserver is located in <i>\$SYBASE/\$SYBASE_ASE/bin</i> .
Syntax	startserver [[-f runserverfile] [-m]]
Parameters	-f runserverfile specifies the relative path name of a runserver file, which is used as a reference each time you start an Adaptive Server or Backup Server. By default, the runserver file is in the current directory and is named <i>RUN_servername</i> . If you start a second Adaptive Server on the same machine, startserver creates a new runserver file named <i>RUN_servername</i> .
	-m starts Adaptive Server in single-user mode, allowing only one System Administrator to log in, and turns the allow updates to system tables configuration parameter on. Use this mode to restore the master database. The System Administrator can use the dbo use only parameter of sp_dboption for system administration activities that require more than one process, such as bulk copying or using the data dictionary. startserver normally starts up only one server per node.
	The -m parameter creates an <i>m_RUNSERVER</i> file and overwrites any existing <i>m_RUNSERVER</i> file.
Examples	<b>Example 1</b> Starts an Adaptive Server named SYBASE from the runserver file named <i>RUN_servername</i> in the current directory:
	startserver
	<b>Example 2</b> Starts an Adaptive Server named MYSERVER and a Backup Server named SYB_BACKUP:
	startserver -f RUN_MYSERVER -f RUN_SYB_BACKUP
	<b>Example 3</b> Starts only the Backup Server SYB_BACKUP:
	startserver -f RUN_SYB_BACKUP
Usage	• startserver uses the information in the runserver file to start an Adaptive Server or Backup Server. The master device must be writable by the user who starts Adaptive Server.

The startserver command creates the Adaptive Server error log file (named *errorlog*) in the directory where the server is started, and adds this information as part of the -e parameter in the Adaptive Server executable line in the runserver file. If a second Adaptive Server is started on the same machine, a new error log named *errorlog\_servername* is created; this information is added to that server's runserver file. The user must have execute permission on the specified runserver file.

- You can start multiple servers by specifying more than one runserver file, as shown in example 2. You can specify -m after each -f *runserverfile*.
- Adaptive Server derives its running environment from values in the *config* file. Run sp\_configure or edit the *config* file to see or change configuration parameters.
- To ensure the integrity of your Adaptive Server, it is important that you apply appropriate operating-system protections to the startserver executable and the runserver file.

#### The runserver file

• The runserver file, which is created by srvbuild during installation, contains the dataserver command to start Adaptive Server or the backupserver command to start Backup Server. By default, the runserver file is in the current directory and is named *RUN\_servername*. You can edit the runserver file to correct the options and parameters for the commands. The following example shows two sample runserver files.

Runserver file for server MYSERVER:

```
#!/bin/sh
#
# Adaptive Server Information:
# name:
                                  /MYSERVER
# master device:
                                  /remote/Masters/myserver dat
# master device size:
                                  10752
# errorlog:
                                  /remote/serverdev/install/errorlog
# interfaces:
                                  /remote/serverdev/interfaces
#
#
/$SYBASE/$SYBASE ASE/bin/dataserver -d/remote/Masters/myserver dat \
-sMYSERVER -e/remote/serverdev/install/MYSERVER errorlog \
-i/remote/serverdev &
```

Runserver file for backup server SYB\_BACKUP:

```
#!/bin/sh
#
# Backup Server Information:
```

```
# name:
                                         SYB BACKUP
      # errorlog:
                                         /remote/serverdev/install/backup.log
      # interfaces:
                                         /remote/serverdev/interfaces
      # location of multibuf:
                                         /remote/serverdev/bin/sybmultbuf
                                         us_english
      # language:
      # character set:
                                         iso_1
      # tape configuration file:
                                         /remote/serverdev/backup tape.cfg
      #
      #
      /remote/serverdev/bin/backupserver -SSYB BACKUP \
      -e/remote/serverdev/install/backup.log \
      -I/remote/serverdev/interfaces \
      -M/remote/serverdev/bin/sybmultbuf -Lus english -Jiso 1 \
      -c/remote/serverdev/backup tape.cfg
See also
                    Commands disk mirror, disk remirror, disk unmirror
```

Utilities backupserver, dataserver

sybdiag	
Description	sybdiag is a Java-based tool that collects comprehensive Adaptive Server configuration and environment data. Sybase Technical Support uses this information to diagnose server issues, thus expediting customer cases.
	<b>Note</b> You must run sybdiag on the same machine as the monitored Adaptive Server.
Syntax	sybdiag -U username [-P password] -S [server_name   host.port] [-I interfaces_file] [-L log_file] [-N num_threads] [-O output_directory] [-R resource_file] [-T feature_list] [-h] [-m message_level] [-V]
Parameters	<ul> <li>-1 <i>interfaces_file</i></li> <li>(optional) specifies the name of the interfaces file. If -1 is specified, sybdiag uses the <i>interfaces_file</i> specified and displays an error if that file is not found. If -1 is not specified, sybdiag first checks the LDAP server for the server entry, and if the entry is not found, sybdiag uses the default <i>interfaces</i> file in the directory specified by the SYBASE environment variable.</li> </ul>
	-L <i>log_file</i> (optional) specifies the name of the log file that sybdiag creates. If <i>log_file</i> is not an absolute path, the log file is created in the directory where sybdiag is executed.
	Whether you specify this parameter or not, sybdiag creates a default log file called <i>sybdiag.log</i> in the <i>.zip</i> output file.
	-N <i>num_threads</i> (optional) specifies the maximum number of parallel threads that sybdiag executes in parallel. The default value is 5. Do not change the default value unless you cannot execute parallel collections.
	-O <i>output_directory</i> (optional) specifies the name of a local directory in which to store sybdiag output. If not specified, sybdiag creates the output <i>.zip</i> file in the directory where the command was executed. The output file is named "sybdiag-< <i>server name&gt;-<datetime stamp="">.zip</datetime></i> ".

-R resource\_file

(optional) specifies the resource file that sybdiag uses on start-up. Use this option only at the direction of Sybase Technical Support.

-P password

specifies your Adaptive Server password. If you do not specify the -P flag, sybdiag prompts for a password. If your password is NULL, use the -P flag without any password.

-S server\_name | host.port

*server\_name* specifies the name of the Adaptive Server to which sybdiag connects. sybdiag looks for this name in the interfaces file or the LDAP directory.

If you specify -S with no argument, sybdiag looks for a server named SYBASE. If you do not specify -S, sybdiag looks for the server specified by your DSQUERY environment variable.

*host:port* specifies the machine name and the port number.

-T feature\_list

(optional) specifies the type of diagnostic data that sybdiag gathers, based on these *feature\_list* values:

- osdata operating system data.
- asecore Adaptive Server configuration data.
- aseadd Adaptive Server monitoring data.
- keyfile information about Adaptive Server and operating system files.

All diagnostic data is collected if you do not specify -T. See "Viewing sybdiag output" on page 273.

-U username

specifies a case-sensitive login name.

-h

(optional) displays all help options.

-m message\_level

(optional) displays different levels of error messages depending on the value of *message\_level*:

- 0 no messages.
- 1 fatal errors only.
- 2 all errors.
- 3 warnings and all errors.
- 4 informational messages, warnings, and all errors.
- 5 debug and informational messages, warnings, and all errors.

By default, the error message display level is set to 4.

-V

(optional) displays version information.

**Example 1** Collects all Adaptive Server diagnostics from /work/ASEInstall/ASE-15\_0/bin, and creates an output file called sybdiag-testserver-20110312024652.zip in the same directory:

sybdiag -Usa -P -Stestserver

**Note** For readability, some lines have been omitted from this sample output.

```
Collecting data for "Adaptive Server Version" (ase_version) ...
Completed data collection for "Adaptive Server Version" (ase version).
Collecting data for "Server License" (ase license) ...
Completed data collection for "Server License" (ase license).
Collecting data for "Adaptive Server Configuration" (ase cfg) ...
Completed data collection for "Adaptive Server Configuration" (ase cfg).
Collecting data for "Adaptive Server Non-default Configuration"
(ase nondefault cfg) ...
Completed data collection for "Adaptive Server Non-default
Configuration" (ase nondefault cfg).
...Lines deleted...
Collecting data for "Adaptive Server LDAP Configuration File" (ase libtcl) ...
Completed data collection for "Adaptive Server LDAP Configuration File"
(ase libtcl).
Collecting data for "Adaptive Server LDAP Configuration File (64bit)"
(ase libtcl64) ...
Completed data collection for "Adaptive Server LDAP Configuration File
(64bit)" (ase libtcl64).
Collecting data for "Virtual Memory Statistics" (os_vmstat) ...
Collecting data for "Adaptive Server General Performance Information"
(ase sysmon) ...
Collecting data for "I/O Statistics" (os_iostat) ...
```

Examples

Collecting data for "CPU Statistics" (os\_mpstat) ... Completed data collection for "Virtual Memory Statistics" (os\_vmstat). Completed data collection for "I/O Statistics" (os\_iostat). Completed data collection for "CPU Statistics" (os\_mpstat). Completed data collection for "Adaptive Server General Performance Information" (ase\_sysmon). Data collection statistics: 43 task(s) succeeded, 0 task(s) skipped, and 0 task(s) failed. The collected data is stored as /work/ASEInstall/ASE-15\_0/bin/sybdiag-testserver-20110312024652.zip Data collection completed.

**Example 2** Collects basic Adaptive Server configuration data from /work/ASEInstall/ASE-15\_0/bin, and creates an output file called sybdiag-smmdi\_9966-20110502202909.zip in the same directory:

```
sybdiag -Usa -P -Ssmmdi:9966 -Tasecore
Collecting data for "Adaptive Server Version" (ase version) ...
Completed data collection for "Adaptive Server Version" (ase version).
Collecting data for "Server License" (ase_license) ...
Completed data collection for "Server License" (ase license).
Collecting data for "Adaptive Server Configuration" (ase cfg) ...
Completed data collection for "Adaptive Server Configuration" (ase cfg).
Collecting data for "Adaptive Server Non-default Configuration"
(ase nondefault cfg) ...
Completed data collection for "Adaptive Server Non-default Configuration"
(ase nondefault_cfg).
Collecting data for "Remote Server Configuration" (ase remote server)...
Completed data collection for "Remote Server Configuration" (ase remote server).
Collecting data for "Adaptive Server Script Version" (ase_script_version) ...
Completed data collection for "Adaptive Server Script Version" (ase script version).
Collecting data for "Adaptive Server Configuration Monitor" (ase mon cfg) ...
Completed data collection for "Adaptive Server Configuration Monitor" (ase mon cfg).
Collecting data for "Adaptive Server Cache Configuration" (ase cache cfg) ...
Completed data collection for "Adaptive Server Cache Configuration" (ase cache cfg).
Collecting data for "Adaptive Server Pool Configuration" (ase pool cfg) ...
Completed data collection for "Adaptive Server Pool Configuration" (ase pool cfg).
Collecting data for "Adaptive Server Shared Memory Dump Configuration"
(ase shmdumpconfig) ...
Completed data collection for "Adaptive Server Shared Memory Dump
Configuration" (ase_shmdumpconfig).
Collecting data for "Adaptive Server Traceflags and Switches" (ase switches) ...
Completed data collection for "Adaptive Server Traceflags and Switches"
(ase switches).
Data collection statistics: 11 task(s) succeeded, 0 task(s) skipped, and
0 task(s) failed.
The collected data is stored as /work/ASEInstall/ASE-15 0/bin/sybdiag
smmdi 9966-20110502202909.zip
Data collection completed.
```

# Usage sybdiag connects to an Adaptive Server and executes stored procedures such as sp\_configure, and queries to tables like monLicense. It collects operating system and platform diagnostic information by executing commands such as ps, vmstat, and netstat.

The output of sybdiag is a compressed ZIP file containing HTML and data files that can be uncompressed and viewed in a Web browser. The information collected includes operating system and environment data, Adaptive Server configuration and monitoring data, and Adaptive Server files and scripts.

sybdiag does not collect Adaptive Server or operating system data for logins, passwords, or user lists, and does not collect information from application database tables.

Configuring options for sybdiag

To generate certain reports, you must enable corresponding configuration options using sp\_configure, or by editing the server configuration file. If configuration options are set incorrectly, sybdiag skips the related reports.

Option	Value	sybdiag Reports
enable monitoring	1	Adaptive Server Wait Events
		Adaptive Server Locks
		Adaptive Server Deadlock History
wait event timing	1	Adaptive Server Wait Events
deadlock pipe active	1	Adaptive Server Deadlock History
deadlock pipe max	Nonzero value; must be large enough to capture all	Adaptive Server Deadlock History
messages	relevant deadlock rows	

Viewing sybdiag output

The sybdiag output is in a compressed file in this format: *sybdiag-servername-datetime\_stamp.zip*. To generate individual output files, uncompress the zip file.

The ZIP file contains these HTML, data, and log files:

*sybdiag\_start.html* – an HTML file with links to diagnostic data files in the output directory. To view sybdiag output, open this file in any Web browser.

sybdiag displays information in these categories:

• Operating system information, including process status, physical and virtual memory, interprocess communication, disk usage, I/O, and network information.

Adaptive Server configuration data, including server version, platform and license information, configuration values, remote server configuration data, and so on. For the Cluster Edition, this also includes the cluster overview, cluster instances, and logical cluster information. Adaptive Server monitoring data about processes, databases, devices, locks, and so on. For the Cluster Edition, this also includes cluster interprocess communication protocol information, cluster lock usage, and cluster quorum device dump information. Adaptive Server files such as *errorlog*, *interfaces*, configuration file, SySAM properties file, and environment configuration scripts. For the Cluster Edition, a single report may contain information from many external files for several cluster instances. Diagnostic data files - collected Adaptive Server and environment information organized under different directories. These are the files that sybdiag\_start.html accesses. ٠ Log file – by default, the ZIP file includes a log file called *sybdiag.log* that provides a log of the activities sybdiag performed. Permissions To gather all Adaptive Server data, you must have permission to access all datasources used by sybdiag. In a default Adaptive Server configuration, you must have sa\_role and mon\_role to collect Adaptive Server configuration and monitoring data. Use sp\_role to grant sa\_role and mon\_role to the sybdiag user: sp role "grant", sa role, sybdiag user qo sp\_role "grant", mon\_role, sybdiag user qo You may need other permissions to access database objects if your system administrator has changed the default access restrictions. If you have insufficient permission to access certain database objects, you see an error message that lists the database objects that you cannot access. To gather all environment data, you must have authorized access to operating system and device files. **Note** On Linux, you must have read permission to access operating system messages in /var/log/messages. You must have read permissions on these files:

- Adaptive Server error log
- Adaptive Server configuration file
- Environment scripts such as SYBASE.csh, SYBASE.sh or SYBASE.bat
- You must have write permissions on an output directory specified by the -O parameter.

**Note** If you do not have the required permissions on a file, sybdiag displays an error message does not process that file.

# sybmigrate

Description sybmigrate allows you to convert an Adaptive Server from one page si another page size, and to migrate between platforms. The executable f located in the following directory: • (UNIX platforms) \$\$YBASE/\$\$YBASE_ASE/bin/sybmigrate • (Windows) %\$YBASE%\%\$YBASE_ASE/bin/sybmigrate.bat \$ybmigrate [-v] [-h] [-f] [-D 1 ] 2 ] 3 ] 4] [-I interfaces_file] [-r input_resource_file] [-r msatus [space_est] repl   diff [password] [-T aset race_filags] [-T trace_filags] [-T trac		
<ul> <li>(UNIX platforms) \$\$YBASE/\$\$YBASE_ASE/bin/sybmigrate</li> <li>(Windows) %\$YBASE/\$\$YBASE_ASE%\bin/sybmigrate.bat</li> <li>(Windows) %\$YBASE/\$\$YBASE_ASE%\bin/sybmigrate.bat</li> <li>(Windows) %\$YBASE/\$\$YBASE_ASE%\bin/sybmigrate.bat</li> <li>sybmigrate [-v] [-h] [-f]</li> <li>[-D 1 ] 2 [ 3 ] 4 ]</li> <li>[-D 1 ] [-1 ] [-4]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] [-2 ] 3 [ 4 ]</li> <li>[-D 1 ] [-2 ] [-2 ] 3 [ 4 ]</li> <li>[-1 ] [-1 [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-2 ] [-</li></ul>	n one pa e executa	age size to able file is
<ul> <li>(Windows) %SYBASE%\%SYBASE_ASE%\bin\sybmigrate.bat</li> <li>Syntax</li> <li>sybmigrate [-v] [-h] [-f]</li></ul>	migrate	<b>)</b>
Syntax sybmigrate [-v ] [-h ] [-f ] [-D 1   2   3   4] [-i interfaces_file] [-r iput_resource_file] [-r status   space_est   repl   diff   password ] [-r status   space_est   repl   diff   password ] [-r iduftut_template_resource_file] [-J client_charset] [-z language] [-T trace_filags] [-T trace_filags] [-Tase trace_filags] [-Tase trace_filags] [-f] Parameters -v prints the version string and exits. -h prints the help information and syntax usage and exits. -f overrides the locking session. -D sets the debug level for sybmigrate. The default debug level is 2. -1 identifies a specific interfaces file to find server names. If no interfact location is designated, sybmigrate uses: • For UNIX - \$SYBASE/interfaces • For Windows - %SYBASE%/ini\sql.ini -r specifies that the resource file mode is to be used in the migration p	igrate.l	bat
<ul> <li>Parameters</li> <li>v prints the version string and exits.</li> <li>h prints the help information and syntax usage and exits.</li> <li>f overrides the locking session.</li> <li>D sets the debug level for sybmigrate. The default debug level is 2.</li> <li>l identifies a specific <i>interfaces</i> file to find server names. If no <i>interfa</i> location is designated, sybmigrate uses: <ul> <li>For UNIX – \$SYBASE/interfaces</li> <li>For Windows – %SYBASE%/ini\sql.ini</li> </ul> </li> </ul>		
<ul> <li>-h prints the help information and syntax usage and exits.</li> <li>-f overrides the locking session.</li> <li>-D sets the debug level for sybmigrate. The default debug level is 2.</li> <li>-I identifies a specific <i>interfaces</i> file to find server names. If no <i>interfa</i> location is designated, sybmigrate uses:</li> <li>For UNIX - \$SYBASE/interfaces</li> <li>For Windows - %SYBASE%\ini\sql.ini</li> <li>-r specifies that the resource file mode is to be used in the migration provide the server of the mode is to be used in the migration provide the server of the ser</li></ul>		
<ul> <li>-f overrides the locking session.</li> <li>-D sets the debug level for sybmigrate. The default debug level is 2.</li> <li>-1 identifies a specific <i>interfaces</i> file to find server names. If no <i>interfa</i> location is designated, sybmigrate uses:</li> <li>For UNIX - \$SYBASE/interfaces</li> <li>For Windows - %SYBASE%\ini\sql.ini</li> <li>-r specifies that the resource file mode is to be used in the migration provide the set of the</li></ul>		
<ul> <li>-D sets the debug level for sybmigrate. The default debug level is 2.</li> <li>-I identifies a specific <i>interfaces</i> file to find server names. If no <i>interfa</i> location is designated, sybmigrate uses:</li> <li>For UNIX - \$SYBASE/interfaces</li> <li>For Windows - %SYBASE%\ini\sql.ini</li> <li>-r specifies that the resource file mode is to be used in the migration provide the second s</li></ul>		
<ul> <li>-I identifies a specific <i>interfaces</i> file to find server names. If no <i>interfa</i> location is designated, sybmigrate uses:</li> <li>For UNIX - \$SYBASE/interfaces</li> <li>For Windows - %SYBASE%\ini\sql.ini</li> <li>-r specifies that the resource file mode is to be used in the migration provide the second sec</li></ul>	level is	2.
<ul> <li>For UNIX - \$SYBASE/interfaces</li> <li>For Windows - %SYBASE%\ini\sql.ini</li> <li>-r</li> <li>specifies that the resource file mode is to be used in the migration provide the statement of the statement</li></ul>	s. If no <i>ii</i>	<i>nterfaces</i> file
<ul> <li>For Windows – %SYBASE%\ini\sql.ini</li> <li>-r specifies that the resource file mode is to be used in the migration provide the statement of t</li></ul>		
-r specifies that the resource file mode is to be used in the migration p		
If the input resource file is not specified by using the -r parameter, syk operates in GUI mode.	e migrat paramete	tion process. er, sybmigrate

-m

designates the types of operations that are performed:

- setup to set up the repository and migration working database, and to migrate the server-wide data.
- migrate to perform data and object migration.
- validate to validate the migrated objects.
- report to run any of the five reports. The reports can be run in the GUI and resource file mode. The available reports are:
  - status the migrate object status report gives information about objects that have been migrated.
  - space\_est use the target database space estimation report to verify that you have sufficient resources allocated to your target database.
  - repl use the replication report to check any explicitly replicated objects that have been migrated, determine the type of replication system, and to produce SQL commands for users to execute on the target Adaptive Server and the Replication Server.
  - diff checks the objects between the source and target databases. The diff report provides the following information for the following object types:
    - Server information
    - Database information
    - DDL objects
    - User table data
- password creates a file for the changed passwords.

#### -rn

indicates what type of report to generate. If -rn is not specified, all five reports are run.

-1

indicates a user-defined log file where the output of the migration process is stored. If -l is not used, the logs are stored in \$SYBASE\_\$SYBASE\_ASE/init/logs or the working directory.

	-t directs sybmigrate to generate an output template resource file, to be used for subsequent migrations in the resource file mode.
	-J specifies the character set to be used for the Adaptive Server connection.
	-z specifies the language to be used for the Adaptive Server connection.
	-T sets command line trace flags.
	-Tase is used to run Adaptive Server trace flags (turned on using dbcc traceon) for all Adaptive Server connections opened by sybmigrate. The trace flags should be specified in a comma-separated list.
Examples	<b>Example 1</b> Runs the status report:
	sybmigrate -r resource file -m report -rn status
	<b>Example 2</b> Runs the space_est report in the resource file mode:
	sybmigrate -r resource file -m report -rn space_est
	<b>Example 3</b> Runs the repl report, issue:
	sybmigrate -r resource file -m report -rn repl
Usage	• Make sure the allow resource limits configuration parameter is set to 0 before running sybmigrate.
	• You cannot migrate server data if metadata already exists on the target Adaptive Server.
	• If sybmigrate exited a session inappropriately, use -f to override the source and target database binding that is created so that only one session of sybmigrate can run on a source and target database path.
	• If you use the -r parameter, then you also need to use the -m argument to specify the type of operation to perform: setup, migrate, validate, or report. You can run the entire migration process in the resource file mode, or you can choose to run only parts of in this fashion.
	• You can use -t only in the resource file mode.
	-t requires that you start sybmigrate using the -r argument specifying the login information. This argument also requires -m to specify what type of resource file is to be generated.

- Adaptive Server versions 12.5.3 and later allow you to specify the size and location of a work database on your target server. When migrating a database or server from a source server with Adaptive Server Enterprise versions 12.0 and later but earlier than 12.5.0.1, you must specify the size and location of a work database on the target server.
- You can override sybmigrate, and use the *interfaces* file by providing the -I argument if the LDAP entry is defined in:
  - UNIX \$SYBASE/\$SYBASE\_OCS/config/libtcl.cfg
  - Windows %SYBASE%\%SYBASE\_OCS%\ini\libtcl.cfg
- sybmigrate automatically migrates predicated privileges when:
  - ddlgen is called to generate the scheme definitions, including grants, denies, and revokes
  - Data is migrated using CIS and proxy tables.

#### Reports

- status the migrate object status report gives information about objects that have been migrated.
- space\_est use the target database space estimation report to verify that you have sufficient resources allocated to your target database.
- repl use the replication report to check any explicitly replicated objects that have been migrated, determine the type of replication system, and to produce SQL commands for users to execute on the target Adaptive Server and the Replication Server.
- diff checks the objects between the source and target databases. Users can run the report on individual objects, or the entire database, except for server and database information or metadata. You can run the diff report at any time. You do not need to run a setup session to run the diff report. The source and target database name do not need to be the same when running the diff report.

The diff report provides the following information for the following object types:

- Server information compares the master database system catalogs row count between the source and target Adaptive Server. This task is similar to the validation session.
- Database information compares the user database system catalogs row count between the source and target Adaptive Server. This task is similar to the validation session.

	<ul> <li>DDL objects – the report displays whether the objects exist on the source or the target Adaptive Servers. If the objects exists in both databases, that object is not displayed in the report.</li> </ul>
	• User table data – compares the row count of the user tables in the source and target Adaptive Server. If the table only exists in the source or target databases, the table is not displayed in the report.
Permissions	You must be a Sybase System Administrator or log in with the sa_role to use sybmigrate.
See also	<b>Documentation</b> Chapter 9, "Migration Utility" for detailed information on sybmigrate.
# sybtsmpasswd

Description	Records or changes the user password and creates the Tivoli Storage Manager (TSM) encrypted password file, <i>TSM.PWD</i> , on the TSM client machine. The location of the file is the directory specified by the PASSWORDDIR configuration parameter in the TSM configuration file.		
	<b>Note</b> sybtsmpasswd is supported when the IBM Tivoli Storage Manager is licensed at your site.		
Syntax	sybtsmpasswd		
Examples	sybtsmpasswd prompts for password information.		
	sybtsmpasswd		
	Enter your current password: Enter your new password: Enter your new password again:		
	Your new password has been accepted and updated.		
Usage	• Execute sybtsmpasswd when you record or change the user password. Make sure the same user name and password are present in the <i>TSM.PWD</i> file on the TSM client node.		
Permissions	Only the operating system "root" user can execute systempasswd.		

#### xpserver

Description	Starts XP Server manually.
Syntax	xpserver -S XP_Server
	xpserver -SXP_Server [-linterfaces_file] [-ppriority] [-sstack_size] [-u] [-v] [-x]
Parameters	-S XP_Server specifies the name of the XP Server to start. The format of the XP server name is SQLSERVERNAME_XP, where SQLSERVERNAME is the name of the Adaptive Server to which the XP Server is dedicated. For example, the XP Server for an Adaptive Server named SMOKE would be named SMOKE_XP. The XP Server name must be in uppercase.
	-l <i>interfaces_file</i> specifies the name and location of the directory containing the interfaces file ( <i>sql.ini</i> ) that Adaptive Server searches when connecting to XP Server. If you do not specify -l, xpserver uses the <i>ini</i> subdirectory of the %SYBASE% release directory.
	-p <i>priority</i> specifies the priority of the Open Server process. Values between 0 (lowest) and 15 (highest) are valid. Overrides the esp execution priority configuration parameter. The default is 8.
	-s stack_size specifies (in bytes) the stack size of the process used to execute an extended stored procedure (ESP). Overrides the esp execution stacksize configuration parameter if it is set. The default is 34816 bytes.
	-u specifies that the functions be automatically unloaded from XP Server memory after the ESP request terminates. Overrides the esp unload dll configuration parameter if it is set. The default is not to unload the function.
	-v prints the version number and copyright message for XP Server and then exits.

	-X
	specifies that the client security context be used to execute operating system commands using the system ESP, xp_cmdshell. Overrides the xp_cmdshell context configuration parameter if it is set. The default is to use the security context of the operating system account of the Adaptive Server session.
Usage	• XP Server is normally started automatically by Adaptive Server. Use the manual command to start XP Server <b>only</b> when instructed to do so in an "XP Server Failed to Start" error message.
	• There can be only one XP Server per Adaptive Server. An Adaptive Server running ESPs communicates with a single XP Server, and the ESPs execute synchronously.
	• The -p parameter affects the priority used by the Open Server scheduler. If -p is set to a high number, the scheduler can run XP Server before running the other threads in its run queue. If -p is set to a low number, the scheduler can run XP Server only when there are no other Open Server threads in its run queue. This parameter is unrelated to the application queue priorities within Adaptive Server, which are set by sp_bindexeclass.
	See the discussion of multithread programming in the <i>Open Server Server Library/C Reference Manual</i> for information about scheduling Open Server threads.
	• If automatic unloading of ESP functions is not set by the -u parameter or by the esp unload dll configuration parameter, you can unload them at runtime using sp_freedll.
	• Unlike Adaptive Server and Backup Server, XP Server does not have a runserver file.
	• When configuring an XP Server, the directory service entry name must end with "_XP" in upper case, such as "abcdef_XP" or "ABCDEF_XP."
Permissions	No special permissions are required to run xpserver.
See also	System ESP xp_cmdshell
	System procedures sp_configure, sp_freedll

xpserver

# Using *sybcluster* to Manage the Cluster

This chapter describes sybcluster, which is the command line utility that you can use to create, start, and manage a shared-disk cluster, and manage instances in the cluster. It describes the parameters and options available in sybcluster.

sybcluster is only available in a shared-disk cluster environment. For information about how to use sybcluster, see the *Clusters Users Guide*.

Торіс	Page
sybcluster	287
sybcluster interactive commands	290
add backupserver	294
add instance	295
connect	297
create backupserver	299
create cluster	301
create xpserver	303
deploy plugin	304
diagnose cluster	306
diagnose instance	308
disconnect	309
drop backupserver	310
drop cluster	311
drop instance	312
drop xpserver	313
exit	314
help	315
localize	316
quit	318
set backupserver	319
set cluster	320
set instance	321

Торіс	Page
set xpserver port	322
show agents	323
show backupserver config	325
show cluster	326
show instance	329
show membership mode	332
show session	333
show xpserver	335
shutdown cluster	336
shutdown instance	337
start cluster	338
start instance	339
upgrade server	340
use	343

#### sybcluster

Description	Manages a Sybase shared-disk cluster. sybcluster lets you create, start, stop, and manage a cluster or any instance in a cluster.	
Syntax	sybcluster	
	[-C cluster_name] [-d discovery_list] [-F agent_connection] [-h] [-l instance_name] [-i input_file_path] [-L] [-L] [-m message_level] [-P [ password]] [-U user_name] (the default value is "uafadmin") [-V]	
Parameters	<ul> <li>-Ccluster_name is the unique name of the Sybase shared-disk cluster to be managed. sybcluster looks up the name in the cluster directory or uses agent discov services.</li> </ul>	
	-d <i>discovery_list</i> specifies the discovery services to be used to discover a shared-disk cluster agent and the discovery order. Discovery services supported for the Cluster Edition are listed in Table 8-1. The format is:	
	"method[(method_specification][,)"]]	
	For example:	
	-d "udp(),jini(jinihost1;jinihost2)"	
	Table 8-1: Discovery methods	
Discovery method	Description	
UDP()	Performs a UDP broadcast and listens for a response from listening Unified Agents. UDP discovery does not cross subnet boundaries.	
JINI( <i>JINI_spec</i> )	Specifies the JINI servers used to look up the locations of nodes in the cluster. The specification form is: <i>host-name</i> [: <i>port_num</i> ].	
	Indicate multiple JINI servers by placing a semicolon between each specification. By	

The JINI server must be running, and the management agents (UAF) must be registered with the JINI server. The locations of the nodes, and status of the instances are stored on the JINI server.

default, sybcluster uses port number 4160 to attach to a JINI server.

Discovery method	Description
LDAP( <i>LDAP_spec</i> )	Specifies an LDAP server that will be used to look up the locations of the nodes in the cluster. The specification form is: <i>host_name</i> [:port_num][?registry].
	Indicate multiple LDAP servers by placing a semicolon between each specification. By default, sybcluster uses port number 389 to attach to an LDAP server and the LDAP directory at "cn=ua-registry,ou=ua,dc=sybase,dc=com".
	-F agent_connection specifies the agent to be used to access the cluster. The format is:
	<pre>host_name[:port_num] [, host_name[:port_num ]]</pre>
	For example:
	-F "node1, node2, node3, node4:9999"
	The default port number is 9999.
	-h displays sybcluster syntax and lists supported interactive commands.
	-l <i>instance_name</i> specifies the instance to be accessed. If you do not specify the -l option when you execute sybcluster, you may need to specify it when entering certain interactive commands. sybcluster uses this name to discover the remote host, and as a default when executing interactive commands. If an interactive command affects multiple instances, the instance identified by -l, if available, is used as the priority connection.
	To override the instance specified by -I, execute the use command in interactive mode.
	-i specifies an operating system file for input to sybcluster. This file contains sybcluster commands, one command per line. The final command in the file

-L

should be quit.

creates a *sybcluster.log* file. sybcluster writes all messages to this file irrespective of the message level set by the -m option.

#### -m message\_level

specifies which sybcluster and unified agent messages are displayed on the client console. Message levels are:

- 0 off (no messages to log file or console)
- 1 fatal
- 2 error
- 3 warning
- 4 information
- 5 debug

sybcluster displays all messages of the level you choose and all messages of greater severity (with lower numbers). That is, if you select message level 3, sybcluster displays messages of level 3, 2, and 1. The default level is 4.

-P [password]

is the management agent password for the Sybase Common Security Infrastructure in the Unified Agent framework. The default user name after installation is "uafadmin" with no password. This is the Simple Login Module in the Agent configuration. The user and password can be configured to use several different mechanisms for authentication and authorization, including using the running instance and the operating system logins.

If you do not specify the -P option, sybcluster prompts for a password. For a blank or null password, use the -P option without a value or enter a set of quotation marks without content.

You can encrypt the password using the Sybase passencrypt utility. See the *Clusters Users Guide*.

-U user\_name

is the management agent login name. The default login after installation is "uafadmin." See the -P description for more information.

	٠			
•	1	L	1	

displays the sybcluster version number and other information.

Examples	<b>Example 1</b> Starts sybcluster using direct connect and default port numbers.
	sybcluster -U uafadmin -P -C mycluster
	-F "blade1,blade2,blade3"

**Example 2** Starts sybcluster using direct connect and port numbers.

Usage

```
sybcluster -U uafadmin -P -C mycluster
-F "blade1:9100,blade2:9292,blade3:9393"
```

**Example 3** You can also start sybcluster using discovery. See "Discovery methods" on page 287.

```
sybcluster -U uafadmin -P -C mycluster
-d "JINI(myjiniserver:4564)"
```

Starting sybcluster

The recommended method for starting sybcluster and connecting to a cluster is:

```
sybcluster -U login_name -P password -C cluster_name
-F agent_spec
```

The -C *cluster\_name*, -P *password*, -I *instance\_name*, -F *agent\_connection*, and -d *discovery\_list* parameters are default values that can be changed using subsequent sybcluster interactive commands. If you do not specify these values on the sybcluster command line, sybcluster prompts for them as they are required.

You can also start sybcluster and then use the interactive connect command to connect to the cluster. For example:

```
sybcluster
> connect to mycluster login uafadmin password " "
agent "blade1,blade2,blade3"
```

**Note** See "sybcluster interactive commands" on page 65 for syntax and usage descriptions of the sybcluster interactive commands.

#### sybcluster interactive commands

This section describes the sybcluster interactive commands. Some commands are active before you connect to a cluster (see "Commands active before connecting to a cluster" on page 291); others are active only after you connect to a cluster (see "Commands active after connecting to a cluster" on page 291).

The sybcluster command prompt includes the current cluster and the default instance when these values have been set. The prompt is:

- > when sybcluster is not connected to a cluster.
- cluster\_name> when sybcluster is connected to a cluster.
- cluster\_name instance\_name> when sybcluster is connected to a cluster and a default instance has been set.

Commands active before connecting to a cluster

These commands are active before you connect to a cluster. They are not available after you connect to a cluster.

Connect

[ to *cluster\_name* ] [ Login *login\_name* ] [ Password [*password* ]] [ Agent *agent\_spec* ] [ Discovery *discovery\_spec* ]

Create Cluster [cluster\_name] [Login login\_name] [Password password] [Agent agent\_spec] [Discovery discovery\_spec] [File input\_file]

Deploy Plugin

[Login login\_name] [Password password] [Agent agent\_spec] [Discovery discovery\_spec]

Exit

Help

Quit

Show agents [ login login\_name ] [ password password ] [ agent "agent\_spec[, agent\_spec[,...]]" ] [ discovery "discovery\_spec[, discovery\_spec[,...]]" ]

Upgrade server server\_name [login login\_name] [password password] [agent agent\_spec] [discovery discovery\_spec] [file input\_file\_name] [checkonly]

Commands active after connecting to a cluster

These commands are active only after you connect to a cluster:

Add

Instance *instance\_name* file *file\_name* Backupserver

#### Create

Backupserver

```
Monitorserver
    Xpserver
Disconnect
Diagnose
    Cluster
    Instance instance_name
Drop
    Backupserver
    Cluster
    Instance instance_name
    Monitorserver
    Xpserver
Localize
Set
    Cluster
        MaxInst max_num_instances
        Login [ login_name ] [ Password password ]
        TraceFlags trace_flag
        Primary Protocol protocol
        Secondary Protocol protocol
    Instance [ instance_name ]
        LogPath log_file_path
        Primarv
            Address ip_address
            Port port_range_start port_range_end
        Secondary
            Address ip_address
            Port port_range_start port_range_end
        StartArgs startup_arguments
    BackupServer
    MonitorServer
    XPServer
        Port
Show
    Cluster
        Config
             Template
        Log
            [Errors]
             [ MinSeverity severity_level ]
             [ StartDate [date_string ]]
            [EndDate [date_string]]
            [Last num_of_lines]
        Status
```

```
Instance [instance_name]
```

Config Log [Errors] [ MinSeverity severity\_level ] [StartDate [date\_string]] [EndDate [date\_string ]] [Last num\_of\_lines] Status BackupServer Config Membership mode MonitorServer Config Session XPServer Config Shutdown Cluster Instance [ instance\_name ] Start Cluster Instance instance\_name [Unlock] Use [ instance\_name ] Help Add Diagnose Disconnect Drop Set Show Shutdown Start

#### add backupserver

Description	Configures  Backup  Server  for  nodes  not  already  configured  for  Backup  Server.
Syntax	add backupserver
Examples	Adds a Backup Server to "mycluster" on nodes "blade3" and "blade4".
add backupserver	
Finding nodes fo Do you want to c Please enter the Do you want to c	r which Backup Server is not configured onfigure Backup Server for node "blade3"? [Y] Backup Server port number for node "blade3": 5001 onfigure Backup Server for node "blade4"? [Y]

Please enter the Backup Server port number for node "blade4": 50011

Usage

- You can configure Backup Server for one or more nodes in the cluster.
- add backupserver lets you add additional nodes when configuring for single Backup Servers. You cannot use this command to add multiple Backup Servers.

### add instance

Description	Adds one new instance to the cluster. The instance can be added interactively, with sybcluster prompting for necessary configuration information, or through an input file. add instance also creates a local system temporary database for the new instance. add instance prompts vary depending on whether configuration for the cluster is shared or private.
Syntax	add instance instance_name [ file "input_file" ]
Parameters	<i>instance_name</i> is the name of the instance.
	file " <i>input_file</i> " specifies a file name that contains the configuration information for adding an instance.
Usage	• add instance creates a local system temporary database for the new instance. Before executing add instance, make sure that a device with sufficient space for the local system database exists.
	• The input file for add instance has the same format as the cluster input file. However, the add instance input file may limit the instance definitions to the new instance in the node section.
	add instance may prompt for this information:
	• The instance name, if you did not enter an instance name in the command statement.
	• The node hosting the instance
	• The port number of the UAF agent on the node
	• The query port number
	• The primary and secondary address of the node
	• The primary and secondary port specification
	• If you have configured single Backup Servers for the cluster, add instance asks whether Backup Server is already configured for the new instance node. If no, add instance asks if Backup Server should be configured. If yes, it prompts for the Backup Server port for the node.
	If you have configured multiple Backup Servers for the cluster, add instance prompts for:
	• The name of the Backup Server
	• The Backup Server log file path

• The Backup Server port for the new instance

add instance also prompts for XP Server port number information for the new instance.

- If the installation mode is private, add instance prompts for additional information for the new instance:
  - The *\$SYBASE* home directory
  - The environment shell script path
  - The Adaptive Server home directory
  - The server configuration file path
  - The interfaces file path, if LDAP is not configured

#### connect

Description	Connects to an existing cluster.	
Syntax	connect [ to <i>cluster_name</i> ] [ login <i>login_name</i> ] [ password [ <i>password</i> ]] [ agent "agent_spec [, agent_spec [,]]" ] [ discovery " <i>discovery_spec</i> [, <i>discovery_spec</i> [,]]" ]	
Parameters	<i>cluster_name</i> is the name of the cluster to which you are connecting.	
	login <i>login_name</i> is the management agent login for the Sybase Common Security Infrastructure in the Unified Agent framework. The default user name after installation is "uafadmin" with no password; this is the Simple Login Module in the Agent configuration. The user name and password can be configured to use several different mechanisms for authentication and authorization, including operating system logins.	
	For information about Sybase Common Security, see Unified Agent and Agent Management Console Version 2.0 for Windows and UNIX.	
	password <i>password</i> is the management agent password for the Sybase Common Security Infrastructure in the Unified Agent framework. The default user name after installation is "uafadmin" with no password; this is the Simple Login Module in the Agent configuration. The user name and password can be configured to use several different mechanisms for authentication and authorization, including operating system logins.	
	agent <i>agent_spec</i> is the agent specification that identifies the nodes in the cluster running a Unified Agent, and the port number that sybcluster uses to connect to the Unified Agent. The format is <i>node_name:port_number</i> [, <i>node_name:port_number</i> ][,]. The default port number is 9999.	
	This is the preferred method for connecting to a cluster.	
	discovery <i>discovery_spec</i> is the discovery method used to identify the agents responsible for the requested cluster. The format is method[( <i>method_specification</i> )][, ( <i>method_specification</i> )[,]]. See Table 8-1 on page 287.	
Examples	<b>Example 1</b> Connects to "mycluster," when "mycluster" is the default cluster specified in the sybcluster command statement.	
	connect	

Usage

**Example 2** In this example, you connect to "mycluster" using the agent specification and default port numbers.

connect to mycluster agent "blade1,blade2,blade3"

- A direct connection is one in which the user identifies the cluster nodes and, optionally, the port numbers for the UAF agents. Sample agent specifications are:
  - myhost identifies the host node and assumes the default listening port of 9999.
  - myhost.mydomain.com includes the host domain name.
  - myhost:9999 identifies the host node and listening port number.

#### create backupserver

Description Creates a Backup Server for the cluster, or, if the cluster has been configured for multiple Backup Servers, creates a Backup Server for each instance in the cluster.

Syntax create backupserver

Example **Example 1** Creates the Backup Server "mycluster\_BS" for "mycluster":

create backupserver

Do you want to create multiple Backup Servers? [Y] N Enter the Backup Server name: [mycluster\_BS] Enter the Backup Server log file path: [\$SYBASE/ASE-15\_0/ install/mycluster\_BS.log] Do you want to create a Backup Server for node "blade1"? [Y] Enter the Backup Server port number for node "blade1": The Backup Server "mycluster BS" was successfully defined.

**Example 2** Creates multiple Backup Servers for "mycluster" running on "ase1" on "blade1" and "ase2" on "blade2."

#### create backupserver

Do you want to create multiple Backup Servers? [Y] Y The "dump/load" commands would be routed to appropriate Backup Server based on following policies: 1. Dedicated - Each instance associated with exactly one Backup Server. 2. Round Robin - Choose the Backup Server with least number of requests in round robin fashion starting from global cluster level counter. Enter the number corresponding to the policy to be used: [1] 1

Enter the Backup Server name for instance ase1: [ase1\_BS] Enter Backup Server log file path: [/remote/var/sybase/install/ase1\_BS\_log] Enter the Backup Server port for node "blade1": 23001

Enter the Backup Server name for instance ase2: [ase2\_BS] Enter Backup Server log file path: [/remote/var/sybase/install/ase2\_BS\_log] Enter the Backup Server port for node "blade2": 23002

Backup Servers successfully defined.

Usage

- create backupserver prompts for the Backup Server listening port on each node. It copies other necessary configuration information from the cluster configuration file. create backupserver:
  - Creates directory service entries for Backup Server on each node.

- Creates the Backup Server configuration and log files, and the RUN\_<*backup\_server>* script.
- Adds the Backup Server name to the cluster's *sysservers* table.
- Enables Backup Server HA.

#### create cluster

Description	Creates an Adaptive Server shared-disk cluster. Enter the necessary configuration information interactively, as responses to a series of prompts, or use an input file.
Syntax	create cluster [ <i>cluster_name</i> ] [ login <i>login_name</i> ] [ password <i>password</i> ] [ agent "agent_spec [, agent_spec [,]]"] [ discovery " <i>discovery_spec</i> [, <i>discovery_spec</i> [,]]"] [ file " <i>input_file</i> "]
Parameters	<i>cluster_name</i> is the name of the cluster.
	login <i>login_name</i> is the management agent login for the Sybase Common Security Infrastructure in the Unified Agent framework. The default user name after installation is "uafadmin" with no password; this is the simple login module in the agent configuration. You can configure the user name and password to use several different mechanisms for authentication and authorization, including operating system logins.
	password <i>password</i> is the management agent password for the Sybase Common Security Infrastructure in the Unified Agent framework. The default user name after installation is "uafadmin" with no password; this is the Simple Login Module in the Agent configuration. You can configure the user name and password to use several different mechanisms for authentication and authorization, including operating system logins.
	agent agent_spec is the agent specification that identifies the nodes in the cluster running a Unified Agent, and the port number that sybcluster uses to connect to the Unified Agent. The format is <i>node_name:port_number</i> [, <i>node_name:port_number</i> ] [,]. The default port number is "9999."
	discovery <i>discovery_spec</i> is the discovery method used to identify the agents responsible for the requested cluster. The format is method[( <i>method_specification</i> )] [, ( <i>method_specification</i> ) [,]]. See Table 8-1 on page 287.
	file " <i>input_file</i> " is the operating system input file for creating the cluster.
Examples	<b>Example 1</b> Creates a new cluster called "mycluster"; sybcluster prompts you for the information necessary to create the cluster.

Usage

```
create cluster mycluster
```

**Example 2** Creates a new cluster called "mycluster1" using configuration information supplied in the mycluster1.xml file.

create cluster mycluster1 file mycluster1.xml

• When you create a cluster, sybcluster prompts for the:

- Cluster name, if one has not been provided
- Number of instances
- Installation mode for the cluster (private or shared)
- Complete path to the master, quorum, PCI, systemdb, sybsysprocs, and temporary database devices
- Path to the interfaces file, if LDAP is not configured and this is a shared install
- Trace flags (optional)
- Complete path to the dataserver configuration file, if this is a shared install
- Primary and secondary interconnection protocols
- Instance host name, port number, private address, log file location, and start-up arguments.

If this is a private install, sybcluster also prompts for the *\$SYBASE* installation directory, Adaptive Server home directory, dataserver configuration file location, and interfaces file location (if LDAP is not configured).

- If sybcluster detects the Veritas Cluster Server (VCS) on the system, sybcluster asks if it should check whether device is managed by VCS.
- After you create and confirm the cluster, create cluster prompts for an I/O fencing check, which checks whether or not each device has I/O fencing capability (see the Installation Guide for a description of I/O fencing).

#### create xpserver

Description	Creates an XP Server for each instance in the cluster.
Syntax	create xpserver
Examples	Creates an XP Server for each instance in "mycluster".
	create xpserver
Enter the Enter the Enter the The XP Se	XP Server port number for instance "ase1": XP Server port number for instance "ase2": XP Server port number for instance "ase3": rver was successfully defined for each instance.
Usage	create xpserver prompts for the XP Server listening port for each node in the cluster. Other information necessary to create the XP Server is read from the cluster configuration file.

# deploy plugin

Description	Adds the configuration information for a single instance of the cluster to the Unified Agent. Can be used to configure the Unified Agent to manage a cluster if you created the cluster without using the Adaptive Server plug-in or sybcluster utility, or if you need to recreate the Unified Agent configuration for a cluster. The configuration of a cluster instance is performed by deploying a Unified Agent plug-in.
Syntax	deploy plugin [login login_name] [password password] [agent agent_spec] [discovery discovery_spec]
Parameters	login <i>login_name</i> is the management agent login for the Sybase Common Security Infrastructure in the Unified Agent framework. The default user name after installation is "uafadmin" with no password; this is the Simple Login Module in the Agent configuration. The user name and password can be configured to use several different mechanisms for authentication and authorization, including operating system logins.
	password <i>password</i> is the management agent password for the Sybase Common Security Infrastructure in the Unified Agent framework. The default user name after installation is "uafadmin" with no password; this is the Simple Login Module in the Agent configuration. The user name and password can be configured to use several different mechanisms for authentication and authorization, including operating system logins.
	agent agent_spec is the agent specification that identifies the nodes in the cluster running a Unified Agent, and the port number that sybcluster uses to connect to the Unified Agent. The format is "node_name:port_number [, node_name:port_number ] [,]]". The default port number is "9999".
	discovery <i>discovery_spec</i> is the discovery method used to identify the agents responsible for the requested cluster. The format is <i>"method[(method_specification)]</i> [, ( <i>method_specification</i> ) [,]]". See Table 8-1 for more information about discovery methods.
Examples	<b>Example 1</b> Deploys the plug-in using the uaf agent on host "system1501".
	deploy plugin agent system1501

sybcluster prompts for the cluster name, cluster node number, installation mode, full path to the quorum device, the environment shell script path, and the Adaptive Server home directory.

**Example 2** Deploys the plug-in and uses discovery to identify the agent:

deploy plugin discovery udp

#### • After you execute deploy plugin, sybcluster prompts you for the:

- Path to the quorum device.
- Path to the Sybase home directory.
- Installation mode (private or shared). The default is shared.
- The location of your Sybase environment script. This must be a shell script that can be loaded using the "*file\_name*" syntax such as "sh" or "bash". An example is *SYBASE.sh*.
- The location of your Adaptive Server software directory. The default is <*sybase\_home\_directory*>/*ASE-15\_0*. When entering the location of the Adaptive Server software directory, include the full path. Do not use \$SYBASE.
- The dataserver login and password are configured using the login command, which updates all Adaptive Server plug-ins managing the cluster.

Usage

#### diagnose cluster

Description Performs a set of checks to ensure that the cluster is working correctly.

Syntax diagnose cluster

Examples Checks that "mycluster" is working correctly.

diagnose cluster

Cluster namemycluster
Maximum instances4
Cluster node count1
Instances defined4
Is cluster lockedYes
JDBC connection available1 ase1 Yes
JDBC connection available2 ase2 Yes
JDBC connection available3 ase3 Yes
JDBC connection available4 ase4 Yes
Instance Public Network1 ase1 on blade1 (10.22.79.39) Reachable: Yes
Instance Public Network2 ase2 on blade1 (10.22.79.39) Reachable: Yes
Instance Public Network3 ase3 on blade1 (10.22.79.39) Reachable: Yes
Instance Public Network4 ase4 on blade1 (10.22.79.39) Reachable: Yes
Has private Primary network No
Has private Secondary network No
Network ports required/instance 20
Minimum port allowed 1025
Maximum port allowed65535

Current port strategy..... Public primary and secondary unique. ...The ports are sequenced primary followed by the next instance primary. ...When the primaries are are completed the secondary ports follow the same pattern.

Recommended port strategy..... Public primary and secondary unique. ...The ports are sequenced primary followed by the next instance primary. ...When the primaries are are completed the secondary ports follow the same pattern.

Usage

diagnose cluster checks that:

- A Unified Agent is running on each instance in the cluster.
- The number of instances in the cluster does not exceed the value set for maximum number of instances.
- The quorum file exists.
- All instances are defined in the interfaces file and that port numbers do not conflict.

- The primary and secondary protocol specifications do not overlap.
- Each of the *\$SYBASE* directories are shared.

# diagnose instance

Description	Performs a set of checks to ensure that the instance is configured correctly.
Syntax	diagnose instance [instance_name]
Parameters	<i>instance_name</i> is the name of an instance. If no instance name is entered, sybcluster uses the default value.
Examples	Displays and verifies configuration information for "ase1" on "mycluster".
diagnose instance	e asel
Cluster name Instance id Instance name Node name Query port JDBC connection a Instance Public I Reachable:Ye	<pre></pre>
Minimum port allo Maximum port allo	owed 1025 owed 65535
Instance port ran Instance port ran	nge 1 Primary asel 17100 to 17115 (16) Okay nge 1 Secondary asel 17165 to 17180 (16) Okay

Usage

Use diagnose cluster to ensure the cluster is configured correctly.

### disconnect

Description	Closes all connections to the current cluster and returns sybcluster to an unconnected state.
Syntax	disconnect
Usage	Use connect to reconnect to an existing cluster.

#### drop backupserver

Description Drops Backup Server from a node or from the cluster. If the cluster has been configured for multiple Backup Servers, drops all Backup Servers.

Syntax drop backupserver

Examples

**Example 1** Drops a single Backup Server.

drop backupserver

Do you want to drop the Backup Server from: 1. Selected nodes 2. Cluster Enter choice: 1 Do you want to drop Backup Server from node "blade1"? [N] y Do you want to drop Backup Server from node "blade2"? [N] The Backup Server has been dropped from selected nodes.

**Example 2** Drops the Backup Server from the cluster.

drop backupserver

Do you want to drop the Backup Server from: 1. Selected nodes 2. Cluster Enter choice: 2 Are you sure you want to drop Backup Server mycluster\_BS from cluster mycluster? (Y or N): [N] y The Backup Server has been dropped.

**Example 3** Drops all Backup Servers when multiple Backup Servers have been configured for the cluster:

drop backupserver

Multiple Backup Server are defined for the cluster. This command will drop all of them. Are you sure you want to continue? (Y/N): [N] y The Backup Server has been dropped.

Usage Use drop backupserver to drop a Backup Server from the cluster.

# drop cluster

Description	Removes each instance from a cluster and then removes the cluster definition from the cluster configuration file. Also, removes regular files associated with the cluster and the cluster agent plug-ins that manage the cluster. The cluster must be Down to use drop cluster.
Syntax	drop cluster
Examples	Drops all instances from the current cluster and deletes the cluster.
	drop cluster
Usage	• sybcluster prompts for confirmation before dropping the cluster.
	drop cluster:
	• Removes cluster and instance entries from the interfaces file, configuration files, and specified data devices.
	• Marks the quorum device as unused.
	• Shuts down and removes the cluster's UAF agent plug-ins.
	• Due to certain file system locking, the UAF plug-ins may not be deleted after you use drop cluster. Verify that the \$SYBASE_UA/nodes/*/plugins/ <cluster_name> directory has been deleted. If the directory still exists, delete it.</cluster_name>

# drop instance

Description	Removes an instance from the cluster configuration file and updates the Unified Agent Framework (UAF) and discovery services. Also, notifies the cluster that an instance is to be dropped, and removes the instance and interfaces file entries.
Syntax	drop instance [ <i>instance_name</i> ]
Parameters	<i>instance_name</i> identifies an instance in a cluster. If an instance name is not specified, sybcluster uses the default specified in the sybcluster command line.
Examples	Removes the "ase3" instance from the current cluster.
	drop instance ase3
Usage	• Before you use drop instance:
	• Start at least one instance in the cluster other than the instance to be dropped.
	• Shut down the instance to be dropped.
	• Manually remove instance-specific information. drop instance automatically removes the local system temporary database.
	• sybcluster prompts for confirmation before removing the instance.
	• You cannot drop the last instance in the cluster. You must use drop cluster.
	• drop instance removes references to the instance in the interfaces file, the instance entry in the quorum device, and notifies the cluster that the instance has been dropped.
	• drop instance removes entries for multiple and single Backup Servers if they were configured for the instance you are dropping.
	• drop instance drops XP Server and single or multiple Backup Servers if they have been configured for that instance.

### drop xpserver

Description	Drops the XP Server for each instance in the cluster.
Syntax	drop xpserver
Examples	Drops the XP Servers for "mycluster".
drop xpserver	
Are you sure you mycluster"? {Y o The XP Servers h	want to drop the XP Servers from cluster r N): [N] y ave been dropped for all instances.
Usage	Use drop xpserver to drop an XP Server from the cluster.

### exit

Description

Syntax

Usage

Exits the sybcluster utility.

exit

- exit and quit perform the same task: they exit the sybcluster utility.
- If some agents have been shut down while connected to sybcluster, error messages describing the connections may display. You can ignore these messages.

# help

Description	Lists the currently available sybcluster interactive commands.
Syntax	help
Usage	The list of currently available interactive commands changes depending on whether or not sybcluster is connected to a cluster.

# localize

Description	Displays the current values for default language, charset, and sort order. Allows modification of default values, and addition or removal of languages.
Syntax	localize
Examples	This example displays default localization values, and then prompts for changes. The default language changes to Chinese, the default charset to eucgb, and the default sort order to bin_eucgb.
localize	
Current default Default Language Default Charset Default SortOrde set(mac).	locale properties are: - portuguese - mac er - Binary ordering, for use with the Macintosh charcter
Options for defa 1. spanish 2. portuguese 3. german 4. us_english 5. thai 6. french 7. japanese 8. chinese 9. korean 10. polish Enter the number	ult Language are: • representing the language to be set as defaults: [2] 8
Options for defa 1. gb18030 2. eucgb 3. uttf8 Enter the number	wult charsets are:
Options for sort	orders are:
1. Binary orderi Enter the number	ng, for the EUC GB2312-80 character set (eucgb). representing the sort order to be set as default [1]
Do you want to i Do you want to r The cluster mycl chinese, charset	nstall any language? [Y] n emove any language? [N ] uster was successfully localized with default language eucqb, sortorder bin eucqb
• The current default localization value displays after each prompt. To accept the current value, enter a carriage return instead of a number.

- The options for default languages include all languages present in *\$SYBASE\_ASE*. If the selected default language is not configured, use localize to configure it or remove it.
- To ensure that new values are consistent for all instances in the cluster, restart the cluster after changing localization values.

# quit

Description	Exits the sybcluster utility.
Syntax	quit
Usage	exit and quit both exit the sybcluster utility.

### set backupserver

Description	Changes the listening port number for Backup Server on specified nodes in a cluster.			
Syntax	set backupserver			
Examples	<b>Example 1</b> Changes the listening port number for Backup Server on "blade1" of "mycluster".			
set backupserver				
Backup Server is 1. blade1: 30 2. blade2: 30	configured on the following nodes: 001 002			

3. blade3: 3003

Do you want to change the Backup Server port on any node? {Y} Enter the number representing the node whose port you want to change: 1 Enter the Backup Server port number for node "blade1":4001 Backup Server was successfully modified as per new properties.

**Example 2** When "mycluster" has been configured for multiple Backup Servers, changes the listening port number for one or more Backup Servers.

set backupserver

```
Multiple Backup Servers are configured for the cluster. Their configuration is as follows:
```

Backup Server Policy: Dedicated

- Backup Server name: ase1\_BS Configured for blade1:23001 Log file location: /remote/sybase/ASE-15\_0/install/ase1\_BS.log
   Backup Server name: ase2 BS
- Configured for blade2:23002 Log file location: /remote/sybase/ASE-15\_0/install/ase2\_BS.log
- 3. Backup Server name: ase3\_BS Configured for blade3:23003 Log file location: /remote/sybase/ASE-15\_0/install/ase3\_BS.log

Do you want to edit any Backup Server (y/n)? [Y] Enter the number representing the Backup Server you want to edit: [1] Enter the new port for Backup Server "ase1\_BS":24001 Do you want to edit any more Backup Servers? [N]

Backup Server "ase1 BS" successfully updated.

Usage When you set a new listening port number, Adaptive Server first checks to see if that port number is already in use.

## set cluster

Description	Changes configuration values for the cluster. The cluster must be down to execute all set cluster commands except set cluster login.				
Syntax	set cluster { maxinst <i>max_num_instances</i>   traceflags <i>trace_flag</i> [, <i>trace_flag</i> [,]]   { primary   secondary } protocol udp   login <i>login_name</i> [ password <i>password</i> ] }				
Parameters	maxinst max_instances specifies the maximum number of instances that can run in the cluster.				
	traceflags trace_flag[, trace_flag[,] specifies trace flags to be set when the cluster starts.				
	login <i>login_name</i> [password <i>password</i> ] specifies a user name and password that the Unified Agent uses to log in to the cluster and perform shutdown and certain other tasks. This login must have sa_role. By default, the Unified Agent uses the "sa" login with no password. To change this password, use set cluster login. See the <i>Clusters</i> <i>Users Guide</i> .				
	<b>Note</b> set cluster login can only be used to change the login or password that the Unified Agent uses to log in to the cluster. To change the login or password sybcluster uses to log in to the Unified Agent, use the Agent Management Console Sybase Central plug-in.				
	{ primary   secondary } protocol udp sets the protocol for the private network for the primary or secondary interface.				
Examples	<b>Example 1</b> Changes the maximum number of instances to 4 for "mycluster".				
	set cluster maxinst 4				
	<b>Example 2</b> Adds the trace flag 15506.				
	set cluster traceflags 15506				
	<b>Example 3</b> Changes the password for the "sa" user name.				
	set cluster login sa password abcde				
Usage	To check that the cluster is Down, enter show cluster status.				

## set instance

Description	Sets properties of the instance. The instance must be Down.
Syntax	set instance instance_name logpath path
	set instance instance_name startargs values
	set instance instance_name {primary   secondary} port port_range
	set instance instance_name {primary   secondary} address ip_address
Parameters	logpath <i>logfile_path</i> specifies the path for the instance log file.
	instance_name specifies an instance.
	startargs startup_args specifies arguments for starting the instance.
	{ primary   secondary } address <i>ip_address</i> specifies the primary or secondary IP address for the instance.
	{ primary   secondary } port <i>port_range</i> specifies the primary or secondary port range for the instance. The format for <i>port_range</i> is : <i>start_num end_num</i> .
Examples	Changes the port range for the primary interface listening port.
	set instance primary port 7777
Usage	To check that the instance is Down, enter show cluster status.

## set xpserver port

Description	Changes the listening port number for XP Server on specified nodes of the cluster.								
Syntax		set >	xpserv	er port					
Examples		Cha of "i	nges th myclus	ne listenir ster" with	ng por out cl	t for the XP nanging the	Server fo listening p	r instance ' oorts for "a	"ase1" on "blade1" se2" and "ase3".
set xpserv	er por	t							
Enter the Enter the Enter the	XP Ser XP Ser XP Ser	ver ver ver	port port port	number number number	for for for	instance instance instance	"ase1" "ase2" "ase3"	[3002]: [3002]: [3002]:	4002 <cr> <cr></cr></cr>

Usage

You can change the XP Server listening port number on one or more instances.

# show agents

Description	Displays information about available UAF agents.
Syntax	Show agents [login login_name] [password password] [agent "agent_spec[, agent_spec[,]]"] [discovery "discovery_spec[, discovery_spec[,]]"]
Parameters	login <i>login_name</i> is the management agent login for the Sybase Common Security Infrastructure in the Unified Agent framework. The default user name after installation is "uafadmin" with no password; this is the Simple Login Module in the Agent configuration. The user name and password can be configured to use several different mechanisms for authentication and authorization, including operating system logins.
	password <i>password</i> is the management agent password for the Sybase Common Security Infrastructure in the Unified Agent framework. The default user name after installation is "uafadmin" with no password; this is the Simple Login Module in the Agent configuration. The user name and password can be configured to use several different mechanisms for authentication and authorization, including operating system logins.
	agent agent_spec is the agent specification that identifies the nodes in the cluster running a Unified Agent, and the port number that sybcluster uses to connect to the Unified Agent. The format is "node_name:port_number [, node_name:port_number] [,]]". The default port number is "9999."
	discovery <i>discovery_spec</i> is the discovery method used to identify the agents responsible for the requested cluster. The format is " <i>method</i> [( <i>method_specification</i> )] [, ( <i>method_specification</i> ) [,]]". See Table 8-1 for more information about discovery methods.
Examples	Displays UAF agent information:
show agents	
Agent Information:	service:jmx:rmi:///jndi/rmi://bladel:9985/agent
Node Name: b. Agent Port: 99 Agent Version: 2 Agent Build: 99	lade1 985 .5.0 77

OS Name: Linux OS Version: 2.6.9-42.ELsmp OS Architecture: amd64

Agent Service Info:

Agent Service (Agent) Build: 977 Status: running BootstrapService (BootstrapService) Build: <unavailable> Status: running Configuration Service (ConfigService) Build: 977 Status: running Deployment Service (DeploymentService) Build: <unavailable> Status: running Environment Service (EnvironmentDiscoveryService) Build: 977 Status: running File Transfer Service (FileTransferService) Build: 977 Status: running Plugin Registration Service (PluginRegisterService) Build: 977 Status: running RMI Service (RMIService) Build: 977 Status: running Remote Shell Service (RemoteShellService) Build: 977 Status: running Service (SecurityService) Build: 977 Status: running Service (SelfDiscoveryService) Build: 977 Status: running Service (ServiceRegistrationService) Build: 977 Status: running Service (ServiceRegistrationService) Build: 977 Status: running Service (SessionService) Build: 977 Status: running Sybase Home Service (SybaseHomeService) Build: 14 Status: running

Agent Plugin Info:

ASE Cluster Agent Plugin (com.sybase.ase.cluster) Version: 15.1.0 Build: 85 Instance: 1 Status: running Cluster Name: marion Env Shell: /job1/miso/betaR1/SYBASE.sh Shell Type: sh Sybase Home: /job1/miso/betaR1 ASE Home: /job1/miso/betaR1/ASE-15\_0 ASE Version: Adaptive Server Enterprise/15.0.1/EBF 14721 Cluster Edition/B/x86\_64/Enterprise Linux/asecluster3/2360/64-bit/FBO/Fri Jul 20 10:04:16 2007 ASE Login: sa Update Time: 60 seconds Last Update: 2007-09-28 22:09:02 -0700

Usage

show agents is active before you connect to a cluster.

## show backupserver config

Description	Displays the nodes on which Backup Server is configured, the associated listening port numbers, and the Backup Server policy.
Syntax	show backupserver config
Examples	Displays configuration information for "mycluster" which has been

Examples Displays configuration information for "mycluster", which has been configured for multiple Backup Servers.

show backupserver config

```
Multiple Backup Servers are configured for cluster. Their configuration is
as follows:
Backup Server policy: Dedicated
1. Backup Server for ase1: ase1_BS
Configured on (host:port) - blade1:23001
2. Backup Server for ase2: ase2_BS
Configured on (host:port) - blade2:23002
3. Backup Server for ase3: ase3_BS
Configured on (host:port) - blade3:23003
```

• Use the show backupserver config command to display Backup Server configuration information.

• If you are configuring multiple Backup Servers, show backupserver config includes the Backup Server policy.

### show cluster

Displays configuration, log, and status information about the cluster.

Syntax

Description

Cluster Config Template Log [Errors] [MinSeverity severity\_level] [StartDate [date\_string]] [EndDate [date\_string]] [Last number\_of\_lines] Status

Parameters

status

Show

displays status information for the cluster. Values are:

- Up
- Down
- Undefined
- Invalid
- Start
- Init
- Quiesce

log

displays logs from all instances in the cluster.

errors [minseverity severity\_level]

display log file entries for errors. Optionally, limit displayed error entries to a severity level and above.

**Note** Error *severities\_level* is an attribute of Adaptive Server error messages, not sybcluster messages.

startdate [ date\_string ]

display log file entries that occur on and after the date specified. The format for *date\_string* is: *mm:dd:yy*.

If you do not specify a startdate or enddate *date\_string*, the default is the current date (today).

enddate [ date\_string ]

display log file entries that occur on or before the date specified.

last num\_lines

Limits the number of lines displayed, counting backward from the last line in the log files.

#### config

displays configuration information for the cluster:

- Maximum number of instances
- Installation mode: shared or private
- Primary and secondary protocols
- Trace flags set
- Location and name of the quorum device
- LDAP information, if LDAP is configured
- Location and name of the master device

#### template

displays formatted configuration information for the cluster.

**Example 1** Displays current configuration and other information about the default cluster.

show	<i>i</i> cluster	status		
Id	Name	Node	State	Heartbeat
1	asel	blade1	Up	Yes
2	ase2	blade2	Up	Yes
3	ase3	blade3	Down	No

**Example 2** Displays configuration information (including LDAP, if it is configured) for the default cluster configured for shared installation mode.

```
show cluster config
**Cluster configuration for "mycluster" **
Installation Mode shared
Interfaces Path "/work2/sybase/ASE-15_0/"
Trace Flags:
        15556
Maximum Instances "4"
Quorum "/dev/raw/raw101"
```

Examples

**Example 3** Displays configuration information for the default cluster configured for private installation mode.

show cluster config

```
**Cluster configuration for "localcluster" **
    Installation Mode "private"
   Trace Flags:
   There are no trace flags
   Maximum Instances "4"
    Ouorum "/dev/raw/raw101"
   Master Device "/dev/raw/raw102"
    loqfile ase1 /remote/work2/sybase/ASE-15 0/install/ase1.loq
    run parameters ase1 null
    logfile ase2 /work2/sybase/ASE-15 0/install/ase2.log
    run parameters ase2 null
Primary Interconnect "udp"
    Server[1]ase1 tigger.sybase.com 26016 26031
    Server[2]ase2 christopher.sybase.com 26032 26047
Secondary Interconnect "udp"
    Server[1]ase1 tigger.sybase.com 26081 26096
    Server[2]ase2 christopher.sybase.com 26097 26112
LDAP server blade1 2250
```

Usage

show cluster status displays the results of a show instance command on each instance in the cluster.

## show instance

Description	Displays information about an instance.			
Syntax	<pre>show instance [instance_name] {     config       status       log       [[errors] minseverity severity_level]        [startdate [ date_string ]]         [enddate [ date_string ]]         [last num_lines]] }</pre>			
Parameters	instance_name specifies a unique name for an instance in the cluster.			
	status displays status information for the instance. Values are: Up Down Undefined Invalid Start Init Quiesce log displays the instance log.			
	errors [minseverity severity_level] displays log file entries for errors. Optionally, limit displayed error entries to a severity level and above.			
	<b>Note</b> Error <i>severities_level</i> is an attribute of Adaptive Server error messages, not sybcluster messages.			
	startdate [ <i>date_string</i> ] displays log file entries that occur on and after the date specified. The format for <i>date_string</i> is: mm:dd:yy.			
	If a startdate or enddate <i>date_string</i> is not specified, <i>date_string</i> defaults to the current day.			

	enddate [ <i>date_string</i> ] displays log file entries that occur on or before the date specified. The format is: mm:dd:yy.
	<pre>last num_lines Limits the number of lines displayed, counting backwards from the last line in the log file.</pre>
Examples	<b>Example 1</b> Displays information about "ase1."
	show instance asel status
	Id Name State
	1 asel Down
	<b>Example 2</b> Displays configuration information for "ase1."
	show instance asel config
	Instance: ase1 at blade6:25001
	Private Primary Network Address: blade1 Port Range: 2541 - 2556 Sybase home: /sybase/sybase_sdc ASE home: /sybase/sybase_sdc/ASE-15_0 Config file: /sybase/sybase_sdc/ase1.cfg
	Private Secondary Network Address: blade1 Port Range: 2557 - 2572
	Log Path: /blade1/sybase/ ASE-15_0/install/mycluster_ase1.log
Usage	• show instance status displays one of seven different states for the named instance:
	• Down
	• Init
	• Invalid
	Quiesce
	• Start
	Undefined

- Up
- show instance config includes this information when the installation mode is private:
  - The \$SYBASE path
  - The ASE path
  - The server configuration file path

### show membership mode

Description

Syntax

Usage

Displays the cluster's current membership mode. Membership mode specifies whether or not Veritas Cluster Integration is supported on the current cluster.

show membership mode

- Values for show membership mode are:
  - vcs VCS is supported for the current cluster.
  - native VCS is not supported for the current cluster.
- If the cluster is running in vcs membership mode, make sure you shut down or start up servers and the cluster using VCS shutdown and start-up mechanisms.

### show session

```
Description
                    Displays current discovery and agent information.
Syntax
                    show session
Examples
                    Displays agent status information.
   show session
   Session information
   Sybase sybcluster Command Line Utility/15.0.1/CE GA
   2/S/jdk1.4.2/sybclustermain/129/Mon Aug 13 09:59:51 PDT 2007
   Connected Cluster: mycluster
   Default Cluster:
     Default Instance:
     Agent Specifications:
       [1]: oddjob:7171
     Discovery Specifications:
     Agent Connections: 1
        Connection[1] URL: rmi://oddjob:7171
           Node Name:
                           oddjob1
           Agent Port:
                           7171
           Agent Version: 2.5.0
           Agent Build:
                           980
           OS Name:
                           Linux
           OS Version: 2.6.9-42.ELsmp
           OS Architecture: amd64
           Agent Service Info:
            Agent Service (Agent) Build:980 Status:running
           BootstrapService (BootstrapService) Build:
             <unavailable> Status: running
           Configuration Service (ConfigService) Build:
             980 Status: running
           Deployment Service (DeploymentService) Build:
             19 Status: running
           Environment Service (EnvironmentDiscoveryService)
             Build: 980 Status: running
           File Transfer Service (FileTransferService)
```

```
Build: 980 Status: running
Plugin Registration Service
  (PluginRegisterService) Build:980 Status:
  running
RMI Service (RMIService) Build: 980 Status:
  running
Remote Shell Service (RemoteShellService) Build:
  980 Status: running
Security Service (SecurityService) Build: 980
  Status: running
Self Discovery Service (SelfDiscoveryService)
  Build: 980 Status: running
Service Registration Service
  (ServiceRegistrationService) Build: 980
  Status: running
Session Service (SessionService) Build: 980
  Status: running
Sybase Home Service (SybaseHomeService) Build:
  14 Status: running
Agent Plugin Info:
ASE Cluster Agent Plugin(com.sybase.ase.cluster)
  Version: 15.0.1 Build: 129 Instance: 1
  Status: running
Cluster Name: mycluster
Env Shell: /oddjob1/work2/
  sybase sybclustermain mycluster vu/SYBASE.sh
  Shell Type: sh
Sybase Home: /oddjob1/
  work2/sybase sybclustermain mycluster vu
ASE Home: /oddjob1/work2/
  sybase sybclustermain mycluster vu/ASE-15 0
ASE Version: Adaptive Server Enterprise/
  15.0.1/EBF 14721 Cluster Edition/B/x86 64/
  Enterprise Linux/asecluster3/2381/64-bit/
  FBO/Mon Nov 12 07:44:23 2007
ASE Login:
             sa
Update time: 300 seconds
Last Update: 2007-11-13 15:27:39 -0800
```

Usage

Use the sybcluster show session command to view information about the current cluster.

## show xpserver

Description	Displays the XP Server nan instance name configured o	ne and listening n each node.	port number, 1	node name, and			
Syntax	show xpserver	show xpserver					
Examples	Displays the XP Server nam name.	Displays the XP Server name, listening port number, node name, and instance name.					
	show xpserver con	show xpserver config					
	**XP Server confi	guration for	the clust	er**			
	XPServer Name	Port	Host	Node			
	ase1_XP	4010	blade1	asel			
	ase2_XP	4011	blade2	ase2			
	ase3_XP	4012	blade3	ase3			
Usage	Use the sybcluster show xps	erver command	to view inform	nation about XP			

Use the sybcluster show xpserver command to view information about XP Server.

## shutdown cluster

Description	Shuts down the cluster by executing a Transact-SQL shutdown command for each instance in the cluster's instance list, in the order specified in the cluster configuration file.
Syntax	shutdown cluster [ nowait ]
Parameters	nowait shuts down the cluster immediately, without waiting for transactions or statements currently executing to conclude. By default, sybcluster waits for all transactions and statements to execute before shutting down the cluster.
Examples	Shuts down the current cluster.
shutdown cluster	
INFO INFO - 01:00:000 INFO - 01:00:000 license for 1 AS	00:00117:2007/06/02 00:23:53.56 kernel ueshutdown: exiting 00:00117:2007/06/02 00:23:53.56 kernel SySAM: Checked in E_CORE (2007.1031/31-oct-2007/1293 6876 8FE7 E217).
Usage	• sybcluster prompts for confirmation before shutting down the cluster.
	If the electronic managed has VCC, should supply should be faile. Very more trans-

• If the cluster is managed by VCS, shutdown cluster fails. You must use VCS shut down mechanisms to shut down the cluster.

## shutdown instance

Description	Shuts down the instance by executing a Transact-SQL	shutdown command.	
Syntax	shutdown instance [ instance_name ] [ nowait ]		
Parameters	instance_name is the unique name of an instance in the cluster.		
	nowait shuts down the instance immediately, without waiti executing transactions or statements to finish.	ing for currently	
Examples	Shuts down the instance "ase1," after waiting for curr transactions or statements to finish.	ently executing	
shutdown instanc	ce asel		
<pre>INFO - 01:00:000 INFO - 01:00:000 process INFO - 01:00:000 server. INFO - 01:00:000 shutdown, newcoo INFO - 01:00:000 cluster. INFO - 01:00:000</pre>	000:00113:2007/06/02 00:31:24/14 kernel sh 000:00113:2007/06/02 00:31:24/14 Server SH 000:00113:2007/06/02 00:31:24/14 ASE is te 000:00113:2007/06/02 00:31:24/14 shut down 000:00113:2007/06/02 00:31:24/14 kernel co o is 0. 000:00113:2007/06/02 00:31:24/14 kernel S: 000:00113:2007/06/02 00:31:24/14 kernel c:	UTDOWN by request. UTDOWN by request. erminating this h local cluster bordinator to be ingle server ipcnode_down():	
Node 1 down even INFO - 01:00:000 request. INFO - 01:00:000 INFO - 01:00:000 license for 1 AS	<pre>ht. 000:00113:2007/06/02 00:31:24/14 server AS 000:00113:2007/06/02 00:31:24/14 kernel ue 000:00113:2007/06/02 00:31:24/14 kernel Sy SE_CORE (2007.1031.31-oct-2007/1293 6876 8</pre>	SE shutdown by eshutdown: exiting ySAM: Checked in BFE7 E 217).	

Usage

- Shutting down the last instance in a cluster also shuts down the cluster.
- sybcluster prompts for confirmation before shutting down the instance.
- If the cluster is managed by VCS, shutdown instance fails. You must use VCS shut down mechanisms to shut down the instance.

Usage

## start cluster

Description	Starts all instances in the cluster.
Syntax	start cluster
Examples	Starts the current cluster.
start cluster	
INFO - [cluster 	boot log]
INFO - 02:00:000 INFO - 02:00:000 80 megabytes, or	00:00002:2007/06/02 00:21:53.56 server 'asel' (ID=1). 00:00002:2007/06/02 00:21:53.56 server Master device size: 40960 virtual pages.

You must connect to the cluster before starting it.

## start instance

Description	Starts an instance.
Syntax	start instance [ instance_name ] [ unlock ]
Parameters	<i>instance_name</i> specifies a unique name for an instance in the cluster. If you do not enter a cluster name, sybcluster uses the instance specified in the sybcluster command line or specified with the use command.
	unlock removes the lock from a cluster that has been terminated unexpectedly. The cluster must be Down before using unlock.
	<b>Warning!</b> Do not use the unlock parameter unless you have verified that all instances in the cluster are shutdown.
Usage	The instance must be Down to use start instance unlock.

# upgrade server

Description	Upgrades a non-clustered Adaptive Server to the Adaptive Server Cluster Edition, and creates a cluster with a single instance. You can perform the upgrade by answering prompts at the command line or via an input file.	
	You can upgrade from Adaptive Server version 12.5 and later to the Cluster Edition.	
Syntax	upgrade server server_name [login login_name] [password password] [agent agent_spec] [discovery discovery_spec] [file input_file_name] [checkonly]	
Parameters	server_name is the name of the non-clustered Adaptive Server.	
	login <i>login_name</i> is the management agent login for the Sybase Common Security Infrastructure in the Unified Agent framework. The default user name after installation is "uafadmin" with no password; this is the Simple Login Module in the Agent configuration. The user name and password can be configured to use several different mechanisms for authentication and authorization, including operating system logins.	
	password <i>password</i> is the management agent password for the Sybase Common Security Infrastructure in the Unified Agent framework. The default user name after installation is "uafadmin" with no password; this is the Simple Login Module in the Agent configuration. The user name and password can be configured to use several different mechanisms for authentication and authorization, including operating system logins.	
	agent agent_spec is the agent specification that identifies the node in the cluster running a Unified Agent, and the port number that sybcluster uses to connect the Unified Agent. When upgrading a non-clustered Adaptive Server, there is only one node. The format for agent_spec is "node_name:port_number". The default port number is "9999."	

discovery discovery\_spec is the discovery method used to identify the agents responsible for the requested cluster. The format is "method[(method\_specification)]". See Table 8-1 for more information about discovery methods. file file name is the input file containing values required for upgrading the server. checkonly performs a check run of the non-clustered Adaptive Server to determine its readiness for upgrade. Examples Upgrades "myserver" to the Cluster Edition: upgrade server Enter the name of the cluster: new cluster Enter the existing Sybase installation directory for server myserver: Enter the name of the subdirectory containing the ASE installation for server myserver: Enter the name of the subdirectory containing the OCS installation for server myserver: Enter the name of an sa login on server exit: [sa] Enter a password: Cluster new cluster - Enter the maximum number of instances: [4] Verifying the supplied agent specifications... 1>tigger 9999 2.5.0 Linux Enter the number representing the cluster node 1 [1] Will this cluster be configured using private SYBASE installations? (Y/N) . . . The information required to upgrade a server or create a cluster are the same. See "create cluster" on page 301 or the installation guide for your platform. upgrade server prompts for these values: Usage The Sybase installation directory of the non-clustered Adaptive Server The release home directory of the non-clustered Adaptive Server ٠ The Open Client home directory of the non-clustered Adaptive Server

- The installation mode, private or shared
- If sybcluster detects a VCS subsystem, asks if you want to include VCS integration with the cluster
- If you have not configured LDAP, the path to the interfaces file
- The name of the first instance in the cluster

- Other values as required to create a cluster
- Use of the checkonly option does not perform any upgrade steps; it does check the server's readiness for upgrade. Any error conditions found by checkonly must be resolved before actually performing the upgrade.

### use

Description	Specifies the default instance.
Syntax	use instance_name
Usage	use overrides the instance name specified in the sybcluster command line.

## **Migration Utility**

This chapter discusses sybmigrate.

Торіс	Page
Overview	345
Before you begin	349
Migration process	352
Using sybmigrate with encrypted columns	377
Post-migration activities	378
Migrate databases in the Replication Server domain	379
Limitations	386
Troubleshooting and error messages	388

### **Overview**

sybmigrate is the migration tool used to migrate data from one server to another.

By default, sybmigrate migrates encrypted columns in ciphertext format. This avoids the overhead of decrypting data at the source and encrypting at the target. In some cases, sybmigrate chooses the reencrypt method of migration, decrypting data at the source and encrypting at the target.

**Note** When migrating from one Adaptive Server to another more recent version of Adaptive Server, you must specify the size and location of a work database on the target server.

### Benefits of sybmigrate

sybmigrate:

• Aids users in changing the page sizes of their database applications.

- Provides a manageable and smooth migration process.
- Allows customers to take advantage of the variable page size feature for existing databases with user data, thus realizing the full benefit of Adaptive Server versions 12.5 and later.

#### What sybmigrate does

During the setup portion of the migration process, the following server data is migrated to the target Adaptive Server:

- Remote servers
- Logins
- Login attributes
- Server roles
- Login roles
- Role attributes
- Users
- Alternate users
- Roles
- Permissions
- Remote logins
- External login attributes
- Timer
- Resource limits
- Replication attributes
- Display level attributes
- User messages in the master database
- Java classes in the master database
- JAR files in the master database
- Proxy objects

During the migration portion of the migration process, the following database-specific data is migrated to the target database:

- Defaults
- User-defined datatypes
- Rules
- User tables
- User table data
- Views
- Triggers
- Indexes
- Stored procedures
- Extended stored procedures
- Users
- Logins
- Roles
- Remote servers
- Database data
  - Users
  - Alternate users
  - Roles
  - Role attributes
  - Permissions
  - User messages
  - Java classes
  - JAR files
- Defaults
- Rules
- User-defined types
- Tables

- Indexes
- Referential constraints
- Views
- Stored procedures
- Triggers

#### What sybmigrate does not do

The following items must be migrated manually:

- Table-level lock promotion attributes
- User-defined thresholds
- Abstract plan definitions maintained in sysqueryplans
- All system databases except the model database
- Any required database options like cache binding, recovery order, and the associated log I/O size as specified by sp\_logiosize
- Proxy databases
- Engine groups
- Engine bindings
- Execution classes
- Cache configurations
- Auditing tables and auditing configuration
- Server-wide row-lock promotion settings
- Access rules

**Note** Drop access rules before beginning data migration; they can prevent the Database Owner from accessing all rows in a table, which prevents complete data migration.

- Compiled objects with hidden SQL text
- User-defined segments

- Constraints **are** migrated but when they are bound by name to user-defined message numbers, the bindings must be re-created manually
- Settings for objects such as ascinserts, indextrips, oamtrips, datatrips, and sortbufsize created using dbcc tune
- Device definitions
- SQLJ functions
- Proxy tables for external files
- Audit options and audit events
- Server configuration
- Database suspect threshold
- · Recovery orders

### Before you begin

sybmigrate requires JRE 1.4, jConnect<sup>TM</sup> for JDBC<sup>TM</sup> 6.0, ddlgen components, and Component Integration Services in the source Adaptive Server.

Because sybmigrate requires a server-to-server connection, two Adaptive Servers must be running. Make sure that you have the appropriate licenses.

#### **Dependencies**

Before you begin the migration process, create databases, devices, and segments on the target Adaptive Server. Server and cache configurations must also be already installed on the target Adaptive Server.

Use ddlgen to extract the corresponding scripts from the source Adaptive Server, and modify them as needed before applying them to the target Adaptive Server. For more information, see ddlgen on page 165.

### Installation

sybmigrate is installed as part of the Adaptive Server software. For information about how to install Adaptive Server, see the installation guide for your platform.

### Permissions

The System Administrator login is needed for the setup portion of the migration process. For the remainder of the process, the login must have "sa\_role" and "sso\_role" privileges to run sybmigrate.

#### Changing target login accounts

Once you have migrated between different platforms, login passwords are not compatible. However, sybmigrate allows you to change the password on target Adaptive Server login accounts during the setup session of the migration process in either of two ways:

- Let sybmigrate generate a password on the target server. sybmigrate outputs a list of passwords used during migration after the process is complete.
- Supply a password file that contains user name and password pairs. sybmigrate sets these passwords on the target server. Thereafter, the System Administrator must run sp\_password to create a new password for each login not included in the password file.

**Note** After the migration process is complete, the System Administrator must change passwords manually on the target Adaptive Server. The System Administrator must issue sp\_password for new login and for each login not reset during the migration process.

In addition to the changing password options, sybmigrate also allows you to lock and unlock target Adaptive Server accounts. This option is provided so that the System Administrator can block a user from logging into the target Adaptive Server during the migration process.

### Platforms

sybmigrate works on both UNIX and Windows platforms.

- For UNIX, the executable file is located in \$SYBASE/\$SYBASE\_ASE/bin/sybmigrate.
- For Windows, the executable file is located in %SYBASE%\%SYBASE\_ASE%\bin\sybmigrate.bat.

### **Environment settings**

The following environment variables must be set correctly. With the exception of SYBMIGRATE\_MEMORY, these environment variables are defined in the *SYBASE.csh* or *SYBASE.sh* files that are created during the installation process.

- SYBASE defines the location of the Sybase release path.
- SYBASE\_ASE defines the location of the Adaptive Server component directory.
- SYBASE\_JRE defines the location of the Java runtime environment. This is generally set to *\$SYBASE/shared/jre-1\_4* in the Adaptive Server release area. This environment variable overrides JAVA\_HOME.

SYBASE\_JRE defaults to *\$SYBASE/shared/jre142* (UNIX) and *%SYBASE%\Shared\Sun\jre142* (Windows).

• SYBMIGRATE\_MEMORY – specifies the amount of memory to be used when invoking the Java virtual machine (JVM). This environment variable should be specified with a number, which refers to the amount of memory in megabytes. If SYBMIGRATE\_MEMORY is not set, JVM uses the default memory setting of 512MB.

If sybmigrate is using a large number of threads, or working on many tables or indexes in parallel, increase the amount of memory allocated to the JVM on the client side.

### Migrating proxy tables

sybmigrate supports the migration of proxy tables. If you are planning to migrate proxy tables, you should do the following before you begin migration.

• Make sure that the remote servers involved in proxy table definitions is present in the target server interface file.

• In order to verify the DDL execution time, the remote server has to be accessible when the migration is performed.

### **Migration process**

The goal of sybmigrate is to provide a means to migrate all objects and user data that exist on the source Adaptive Server. However, when migration takes place, there is some server-wide data that needs to be migrated before any user data or user objects can be migrated to individual databases.

The hierarchy of objects dictates the order in which objects are re-created. Generally, server-wide objects from the master database are created first. Independent objects like default languages and character are migrated to the target server before data from individual databases.

#### **Overview of the migration process**

The migration procedure consists of configuring the source and target Adaptive Servers, setting up the migration paths, migrating objects, and validating the migrated objects.

The setup session establishes the migration paths from the source database to the target database. The setup creates the repository database and the work databases, and registers the option to migrate the server data. The setup session can only be executed by an "sa" login.

The migrate session is used to migrate objects and data from the source database to the target database.

The validate session validates the migrated objects. Validation ensures the integrity of data and objects that have been successfully migrated from the source database to the target database.

sybmigrate does not migrate an archive database if an entire installation is being migrated.

sybmigrate migrates an archive database only if the archive database is specifically selected for migration. When you migrate an archive database to a target server, sybmigrate automatically creates a traditional database—rather than an archive database—on the target server.
## **Pre-migration considerations**

You must have the source Adaptive Server and the target Adaptive Server running concurrently when you migrate data from one to the other.

sybmigrate assumes that the target Adaptive Server has been installed and configured prior to data migration. Use srvbuild or syconfig to create a new Adaptive Server with the required logical page size.

Keep the following items in mind prior to migration, when you are creating the target Adaptive Server and configuring the source Adaptive Server:

- sybmigrate requires allow resource limits to be set to 0.
- If metadata already exists on the target server, you cannot migrate server data.
- When you create a new Adaptive Server with a different logical page size into which you want to migrate data, you must adequately adjust the size of the database on the target Adaptive Server to accommodate the inbound data. If you are migrating data to an Adaptive Server with a larger logical page size, this is especially important.

Use the space estimation report, space\_est, to determine how much space is available on your target database. For more information about space\_est, see "Starting sybmigrate" on page 359.

- To speed the migration process, you can run multiple sessions of sybmigrate within the same server. However, running more than one session of sybmigrate on the same source and target database path is not allowed.
- You must manually create segments on the target database before migrating tables and indexes.
- The data transfer rate for sybmigrate is configured through CIS bulk insert array size. The default configuration for CIS bulk insert array size is 50 rows. This means that as many as 50 rows of data are buffered by CIS before being transferred to the target Adaptive Server.

To increase throughput, increase the configuration of CIS bulk insert array size to a larger value.

However, increasing CIS bulk insert array size causes the source Adaptive Server to use memory from the operating system for local buffers. This can lead to excessive consumption of operating system memory. Sybase recommends that if you do choose to increase the CIS bulk insert array size default value, you do so modestly. See the CIS documentation for more information.

- CIS bulk insert array size has no effect on data throughput if the table being transferred has a text, image, or Java ADT column. When a table has a text, image, or Java ADT column in it, all data is migrated one row at a time, for the duration of the migration of that particular table. Also, no array buffering takes place.
- As the data migration is being done using CIS bulk transfer, the value for the configuration parameter CIS packet size on the source Adaptive Server can affect the speed of the data transfer. The recommended value for CIS packet size on the source Adaptive Server is the logical page size (2K, 4K, 8K, or 16K) of the target Adaptive Server.
- max packet size allowed on the target Adaptive Server should match the value of CIS packet size on the source Adaptive Server.

For more information on max packet size allowed, see the *System Administration Guide*.

• To maximize the performance of sybmigrate, increase the additional network memory configuration parameter on the target Adaptive Server to a value larger than the default.

For more information on additional network memory, see the *System Administration Guide*.

- All the above considerations affect the max memory configuration parameter. Before migrating your data, make sure that max memory is set to a sufficiently large value.
- There are three types of data that are migrated: server data, database data, and user objects. To migrate metadata (the server and database data), the target Adaptive Server must be newly installed so that the migrated metadata does not conflict with any residual data from previous usage.

If you are migrating only user objects, you can use a previously used Adaptive Server. For user data however, the target tables must be empty.

- Before migrating data, create the databases into which you want to migrate data on the target Adaptive Server. The databases should have the same name that they have on the source Adaptive Server.
- To enable conversion of character sets that do not have an internal Adaptive Server conversion routine, configure the target Adaptive Server with enable unicode conversions set to 1.

• Determine the size of the named caches and buffer pools on the target Adaptive Server. sybmigrate does not migrate cache configurations. You can use the information that is generated by ddlgen and apply it to the target Adaptive Server, or you can choose to configure larger amounts of memory, in light of the larger page size being used.

However, sybmigrate migrates cache bindings, therefore if the required cache is not in the target Adaptive Server, warnings are generated in the migration log.

• Before running sybmigrate, you must install the desired languages on the target Adaptive Server. The default language should be the same on the source and the target Adaptive Server.

If there are user messages on the source Adaptive Server that are not installed on the target Adaptive Server, sybmigrate aborts user message migration and reports an error.

• If you are migrating Java columns, you must enable Java on the source and target Adaptive Server prior to migration. Enter:

sp\_configure 'enable java', 1

- To complete the migration, the source and target Adaptive Servers must have different local server names. Set the local server name, and then restart the servers for the change to take effect.
- To migrate an Adaptive Server using single-byte character sets to an Adaptive Server using multibyte character sets (utf8):
  - a Use sybmigrate to migrate to a server using the same, single-byte character set.
  - b Change the character set to multibyte after migration is complete.

sybcluster cannot migrate data directly from an Adaptive Server using single-byte character sets to an Adaptive Server using multibyte character sets.

# Configuration and tuning for higher performance

Depending upon your server resources, you can configure sybmigrate and Adaptive Server for optimal performance.

## Configuration considerations for sybmigrate

Copy threads and create index threads are used to migrate tables and re-create indexes. When you are configuring sybmigrate during setup mode, the values of COPY\_THREADS and INDEX\_THREADS can increase the speed at which sybmigrate copies and migrates data.

The number of copy threads controls the number of tables for which data migration is done simultaneously. One copy thread is assigned to each table. When the thread has successfully completed one task, it moves on to another. Depending upon the size of your database and the resources for your Adaptive Server, you can increase the number of copy threads used during the migration process to improve performance.

**Note** When you are migrating a large number of objects in parallel, check the value of SYBMIGRATE\_MEMORY to verify that there is sufficient memory allocated to sybmigrate.

Index threads control the number of threads used to re-create indexes on the target Adaptive Server tables. One thread per table is used to re-create the indexes. Once the indexes have been re-created on a table, the thread proceeds to the next successfully migrated table. Any threads without a task exits. The number of create index threads is expected to be substantially smaller than the number of copy threads.

If you configure INDEX\_THREADS to a large number, be sure that the target Adaptive Server is also configured with a large number of sort buffers. The use of index threads takes up space in the target database, so make sure that the target database is configured with adequate space for the designated number of index threads. Also, you must configure the target database with extra space if you are going to be re-creating clustered indexes.

## **Configuration considerations for Adaptive Server**

There are several configuration parameters on both the source and target Adaptive Server that affect the performance of the migration process.

On the source Adaptive Server:

- cis packet size should be equal to max page size of the target Adaptive Server.
- number of user connections should be high enough to accommodate the migration of multiple tables simultaneously according to the value of COPY\_THREADS and INDEX\_THREADS.

- max parallel degree should be set to a value that is larger than the largest number of partitions in a single table. Data migration is done in parallel, and if max parallel degree is not set to a value large enough to accommodate the partitioned tables, the tables do not migrate.
- number of worker processes data migration for partitioned tables requires one worker thread per partition. Therefore, if *t* partitioned tables with *p* partitions each are migrating simultaneously, configure a total of *t* multiplied by *p* worker threads on the source Adaptive Server.
- cis bulk insert batch size controls the number of rows after which the data transfer transaction is committed. The default value is 0. Using the default value is the safest way to ensure data integrity while migrating data, but it can result in a large number of page and row locks on the source Adaptive Server. To reduce the number of locks, increase this value.

If you increase the value of cis bulk insert batch size, only a partial data migration completes if an error occurs during the process. In this situation, manually truncate the target table and restart sybmigrate.

• cis bulk insert array size – controls the number of rows that are copied in bulk at one time. The default is 50 rows per batch. For faster data migration, increase this value.

If the table contains text or image columns, the data is transferred one row at a time, regardless of the value for cis bulk insert array size.

The following configuration parameters on the target Adaptive Server affect the performance of sybmigrate:

- max network packet size should be set to a value that is at least equal to max page size.
- number of user connections should be set to accommodate the migration of multiple tables in parallel and partitioned tables.

For parallel data transfer for partitioned tables, worker processes are required on the source Adaptive Server, but user connections are required on the target Adaptive Server. If you are migrating partitioned tables, set the number of user connections on the target Adaptive Server to the same value as number of worker processes on the source Adaptive Server.

• number of sort buffers – the default value of 500 is sufficient during the migration process. You can increase this value when sybmigrate rebuilds the indexes, especially if you are migrating indexes on partitioned tables.

## Possible errors to avoid

Before beginning the data migration process, sybmigrate checks for the following error conditions. If any of these conditions are detected, the migration procedure is aborted.

- A target table with existing data any attempt to migrate data to a table that already contains data results in the failure of sybmigrate.
- A target table with existing indexes the presence of indexes on a target table causes sybmigrate to operate in slow bcp. Manually drop all indexes before you begin the data migration.
- Unmatching numbers of partitions on the source and target tables if the number of partitions on the source and target table do not match, the attempt to migrate data fails. sybmigrate only migrates data; it does not redistribute it across partitions.

## Auto-select dependent objects for migration

sybmigrate selects dependent objects for migration when you use the autoselect feature. The auto-select feature checks for the existence of dependent objects, and automatically migrates them to the target Adaptive Server. For a successful migration, Sybase recommends that you use this feature.

# Migrating an archive database

sybmigrate does not migrate an archive database if an entire installation is being migrated.

sybmigrate migrates an archive database only if the archive database is specifically selected for migration. When you migrate an archive database to a target server, sybmigrate automatically creates a traditional database—rather than an archive database—on the target server.

## Upgrading an Adaptive Server with an archive database

You cannot upgrade an archive database. If you load a database dump from an older version of Adaptive Server onto an archive database hosted on a newer version of Adaptive Server, the database is not internally upgraded when you execute online database.

If you upgrade an Adaptive Server containing an archive database, all the databases except the archive databases are upgraded. The archive database remains on the older version of Adaptive Server.

Sybase recommends you reload the archive database with a dump generated from an already upgraded database.

For more information about upgrading Adaptive Server, see the installation guide for your platform.

### Downgrading an Adaptive Server with an archive database

When you are downgrading to a version of Adaptive Server that does not support archive databases, be aware of the following:

• If you must downgrade an Adaptive Server containing an archive database to a version of Adaptive Server that does not support archive databases, Sybase recommends you drop the archive database before you downgrade.

To eliminate the new sysaltusages table, drop the scratch database before you perform the downgrade procedure. sysaltuages does not cause any problems if the scratch database is not dropped.

Backup Server versions 15.0 ESD #2 and later writes a new format for compression (with compression = compression\_level) so that the dump can be loaded into an archive database. Therefore, if you must load a compressed dump onto a version of Adaptive Server that does not support archive databases access, use the same version of Backup Server that created the compressed dump to load the compressed database dump. An earlier version of Backup Server does not support the new format of the compressed database dump.

When you are downgrading without compression, you need not worry about Backup Server at all.

# Starting sybmigrate

**Warning!** sybmigrate assumes that the source and target Adaptive Servers will not have any activity during the migration. If objects are created, modified, or deleted during the migration process (setup, migrate, and validate), Sybase cannot guarantee migration integrity.

Whether you are running the GUI or the resource file version of sybmigrate, start it with the following relevant command line arguments:

sybmigrate [-v ] [-h ] [-f ] [-D 1 | 2 | 3 | 4 ] [-I interfaces file ] [-r input resource file ] [-m setup | migrate | validate | report ] [-m status | space\_est | repl | diff | password ] [-I log file ] [-t output template resource file ] [-J client\_charset ] [-z language ] [-T trace\_flags ] [-Tase trace flags ] [-f ]

Where:

- -v prints the version string and exits.
- -h prints the help information and syntax usage and exits.
- -f overrides the locking session.

If sybmigrate exited a session inappropriately, use -f to override the source and target database binding that is created so that only one session of sybmigrate can run on a source and target database path.

- -D sets the debug level for sybmigrate. The default debug level is 2.
- -I identifies a specific *interfaces* file to find server names. If no *interfaces* file location is designated, for UNIX *\$SYBASE/interfaces* or for Windows *%SYBASE%\ini\sql.ini* is used.

**Note** You can override sybmigrate, and use the *interfaces* file by providing the -I argument if the LDAP entry is defined in *\$SYBASE/\$SYBASE\_OCS/config/libtcl.cfg* on Unix or in *%SYBASE%\%SYBASE\_OCS%\ini\libtcl.cfg* on Windows.

• -r specifies that the resource file mode is to be used in the migration process. If the input resource file is not specified by using the -r parameter, sybmigrate operates in GUI mode.

If you use the -r parameter, then you also need to use the -m argument to specify the type of operation to perform: setup, migrate, validate, or report. You can run the entire migration process in the resource file mode, or you can choose to run only parts of in this fashion.

- -m designates the types of operations that are performed:
  - setup to set up the repository and migration working database, and to migrate the server-wide data.
  - migrate to perform data and object migration.
  - validate to validate the migrated objects.
  - report to run any of the five reports. The reports can be run in the GUI and resource file mode. The available reports are:
    - status the migrate object status report gives information about objects that have been migrated. To run this report, issue:

```
sybmigrate -r resource file -m report -rn status
```

• space\_est – use the target database space estimation report to verify that you have sufficient resources allocated to your target database. In the resource file mode, issue the following command to run the space\_est report:

```
sybmigrate -r resource file -m report -rn
space_est
```

• repl – use the replication report to check any explicitly replicated objects that have been migrated, determine the type of replication system, and to produce SQL commands for users to execute on the target Adaptive Server and the Replication Server. To run the repl report, issue:

```
sybmigrate -r resource file -m report -rn repl
```

 diff – checks the objects between the source and target databases. Users can run the report on individual objects, or the entire database, except for server and database information or metadata. You can run the diff report at any time. You do not need to run a setup session to run the diff report. The source and target database name do not need to be the same when running the diff report.

The diff report provides the following information for the following object types:

• Server information – compares the master database system catalogs row count between the source and target Adaptive Server. This task is similar to the validation session.

- Database information compares the user database system catalogs row count between the source and target Adaptive Server. This task is similar to the validation session.
- DDL objects the report displays whether the objects exist on the source or the target Adaptive Servers. If the objects exists in both databases, that object is not displayed in the report.
- User table data compares the row count of the user tables in the source and target Adaptive Server. If the table only exists in the source or target databases, the table is not displayed in the report.
- password creates a file for the changed passwords. This report can only be run by a System Administrator.
- -rn indicates what type of report to generate. If -rn is not specified, all five reports are run.
- -I indicates a user-defined log file where the output of the migration process is stored. If -I is not used, the logs are stored in *\$SYBASE/\$SYBASE\_ASE/init/logs* or the working directory.
- -t directs sybmigrate to generate an output template resource file, to be used for subsequent migrations in the resource file mode.

-t requires that you start sybmigrate using the -r argument specifying the login information. This argument also requires -m to specify what type of resource file is to be generated.

Note You can use -t only in the resource file mode.

- -J specifies the character set to be used for the Adaptive Server connection.
- -z specifies the language to be used for the Adaptive Server connection.
- -T sets command line trace flags. They are:
  - DUMP\_SQL specifies that every query issued by sybmigrate is output to the log file.
  - NO\_SORTED\_DATA overrides the default, which specifies that tables with clustered indexes are copied to the target server in order, and the clustered index is recreated using the with\_sorted\_data option.
  - LEAVE\_PTBL\_ON\_ERROR specifies that proxy tables are not deleted on failure.

- SKIP\_CONFIG\_CHECK specifies that configuration compatibility checks are not to be performed.
- SKIP\_PARTITION\_CHECK specifies that partition compatibility checks are not to be performed.
- DUMP\_DDL specifies that DDL commands are to be output to the log file.
- DUMP\_DEPEND\_OBJECT specifies that when the auto\_select\_dependent\_objects option is used, sybmigrate outputs a list of objects added as dependents.
- ONE\_WORK\_THREAD specifies that one work thread is to be used, overriding the current setting for schema creation threads.
- ALLOW\_DATA\_AND\_INDEX overrides default behavior, in which indexes are created after all tables are created. Indexes are created as resources become available.
- -Tase is used to run Adaptive Server trace flags (turned on using dbcc traceon) for all Adaptive Server connections opened by sybmigrate. The trace flags should be specified in a comma-separated list.

When you run sybmigrate, there are three phases of the migration process that you must follow: setup, migrate, and validate.

# **GUI mode**

You can use either the GUI or the resource file mode for the migration process. You can also elect to run parts of the migration process in GUI mode, and parts of it in resource file mode.

## Setup

Before migrating data, indicate your source and target Adaptive Servers and register the paths between the source and target databases they contain. To do this, start sybmigrate with the -m setup command line option, or by selecting "Setup source databases for migration" when you are prompted in the Session Type window.

#### Indicating your source and target Adaptive Servers and registering the paths between the source and target databases

1 The Connect to ASE window allows you to designate the source and the target Adaptive Servers for your migration process.

 You can choose from the drop-down menu in the Server fields. The menus provide a list of Adaptive Servers that are located in the default *interfaces* file (*\$SYBASE/interfaces* on UNIX or *%SYBASE%\ini\sql.ini* on Windows) or in the *interfaces* file that you specify with the -I command line argument.

If you are not using the *interfaces* file, you cannot use the -I command line argument; you must specify the source and the target Adaptive Servers in the *host:port* format.

• During the setup phase, you must be logged in to the servers as a System Administrator. Enter "sa" into the Login field, enter your password, and select Connect.

**Note** You can run only one session of sybmigrate at a time. Therefore, if there is another user running sybmigrate on the same source and target Adaptive Servers, you see the error message "Setup session lock: Either previous setup exit abnormal or there is another setup session running. Do you want to override?" You can override the session lock because it is possible that the previous session may have crashed or quit prematurely.

Before proceeding with the setup and migration process, verify that there are no other users running sybmigrate. If there is more than one user running sybmigrate simultaneously, Sybase cannot guarantee data integrity.

- 2 The Session Type window prompts you to select the type of operation you want to perform. Choose from:
  - Setup source databases for migration
  - Migrate database objects and data
  - Validate the migrated objects and data
  - Reports when you select Reports, a Reports type window displays. You can choose from status, space\_est, repl, diff, or password. When you select either the space estimation or the replication report, a Report Paths Window prompts you to select the database paths on which to run the reports.

The Password, Status, and Replications reports are disabled if the setup session has not been completed between the source and target Adaptive Servers.

If you started sybmigrate with the -m option specifying setup, migrate, validate, or reports you do not see this window.

- 3 Use the Setup wizard to prepare databases for migration. The Setup wizard displays several windows:
  - Choose Database window

This window prompts you to select the source and target databases located within your source and target Adaptive Servers, so that sybmigrate knows where to put the data from the source Adaptive Server in the target Adaptive Server.

Note The source and target databases must have identical names.

The Source Database drop-down list has a list of the databases in your source Adaptive Server.

The Target Database drop-down list has a list of the databases available in the target Adaptive Server. sybmigrate requires that you create the databases in the target Adaptive Server before beginning the migration process.

The migration path is a selected source and target database pair.

• Configure DDL threads

Choose the number of threads to be used to create database objects on the target server for the specified migration path.

• Configure copy threads

Chose the number of threads to be used to copy data from the source to the target for the migration path. Make sure you use sufficient numbers of threads for systems with multiple engines.

• Configure index threads

Chose the number of threads to be used to create indexes on the target server for the specified migration path. Make sure you use sufficient numbers of threads for systems with multiple engines.

You control the number of threads used for parallel table transfer. When several tables are transferred concurrently, each table requires a one-server-to-one-server CIS connection.

Suppose the data migration is performed on unpartitioned tables (each table contains a single partition). When you migrate such tables, a single server-to-server connection is established, which uses a single user connection on the source Adaptive Server and a single user connection on the target Adaptive Server.

If the data migration is performed on *n*-way partitioned tables, the data transfer is performed in parallel with an *n*-way degree of parallelism. This requires *n* worker processes on the source server and 2n user connections on the target server.

For example, suppose you have 10 *n*-way partitioned tables to migrate. You use four threads in sybmigrate, and configure the source Adaptive Server to have at least four worker processes and eight user connections. You must configure the target Adaptive Server to have at least eight user connections.

**Note** The value you assign to each property in the setup session becomes the default value. You can temporarily override default values in the migrate or validate session. Limit these values to the resources available to Adaptive Server.

• Configuring the work database

sybmigrate requires at least one work database during the migration process. The Database size field provides a default value in megabytes. The default value is based on the number of copy and create index threads specified in a previous window. The default is the minimum value; you can increase but not decrease it.

The Device field lets you indicate the device on which to create the work database.

**Note** When migrating from a source Adaptive Server version 12.0 through 12.5.0, sybmigrate also requires a work database on the target server. The wizard prompts for the same information for the target work database.

• Current paths

Review the migration paths you have selected. Right-click a migration path to display edit and delete options.

You can add paths by selecting Add Migration Path. To add paths later on, rerun sybmigate in Setup mode.

Configure repository

sybmigrate creates a repository database on the source server to track the migration of all migration paths. The default database size is a minimum; you can increase but not decrease it. • Migration of server-wide data

You can choose whether or not to migrate information in system catalogs, such as login information. The options are:

- Yes server-wide data is migrated at the end of the Setup phase.
- No server-wide data is not migrated. You can return to this window and choose to migrate data at any time—as long as database migration has not yet begun.
- Undecided allows you to return and choose another migration option later on. However, you cannot begin the Migration phase until you have chosen Yes or No. Undecided is useful when you want to set up the migration process, but plan to migrate data at a later date.

If the target server already has been configured for logins or other server-wide information, sybmigrate defaults this option to No.

The Options button provides advanced options for handling login accounts. The options let you specify:

- Whether or not to lock login accounts after migration
- How to handle login passwords when migrating across platforms
  - No change use when migrating to the same platform (default)
  - Generate random passwords
  - Assign passwords from a list in a file
- Summary

Displays a summary of options chosen. Click Finish to perform the chosen setup tasks.

4 The Setup Progress window displays the progress of the setup phase.

During this time, sybmigrate is creating the repository database, installing the database schema, creating a working database for each selected path, and migrating the server data based on your selection, in that order. If you are running sybmigrate in setup mode a subsequent time, it is creating new paths for data migration. If you do not want to create new paths, there is no reason to run sybmigrate through the setup mode more than once. You can to view the progress in the log by clicking Show Log. The completion of the setup process is indicated when the Current Task window displays DONE, and when the log shows SETUP\_COMPLETE. Click Close to exit the log and the Setup Progress window.

5 You return to the Connect to ASE window. Select Quit to exit sybmigrate. To begin the migration phase of the data migration process, exit sybmigrate and restart it in the migrate mode.

## Migrate

After you have completed setup, you are ready to begin migrating. Restart sybmigrate with the -m migrate command line option, or choose the migrate database objects and data option from the GUI window.

- 1 In the Connect to ASE window, select the source and target Adaptive Servers to which you want to connect.
- 2 If you have not started sybmigrate with the -m migrate command line argument, select the session type in the Session Type window.
- 3 The Object Selection window allows you to choose what types of database data you want to migrate.

In the Object Selection window, you can set the Copy thread, create index thread, and work thread parameters from the Setting menu bar.

In the Object Selection window, you can also request that sybmigrate Auto-Select Dependent Objects on your selected objects by right clicking the object tree node.

When you expand the database data folder, there is a file for each path that you created during setup. Each file allows you to select the data you want to migrate for that particular database. You can choose from the following:

• Database Data

**Note** If you choose to migrate database data, you must migrate all of it. If you deselect parts of the database data, you see an error message asking you whether or not you want to migrate database data.

If you do not migrate the server data during setup, the Database Data selection is disabled.

- Defaults
- Rules

- User-defined Datatypes
- Tables
- Indexes
- Referential Constraints
- Views
- Stored Procedures
- Triggers

The Status field for these objects indicates whether or not the data has successfully migrated. "Success" indicates that the data has already migrated. "Initial" means that the migration has not yet begun. If you find an error in the data that has been migrated, you can reset the Status field to Initial so that the data migrates again. The validation process acts only on those objects that have been migrated successfully, so to begin the validation process without all of the data having successfully migrated, reset the Status field to Success. "Work in Progress" means that the object was selected for migration, but that the migration was not attempted because there was some error causing sybmigrate to exit abnormally.

You can see whether or not the server data has been selected to be migrated, but this is for informational purposes only since the server data has already been migrated at this point in the migration process.

When you have selected the data that you want to migrate, click Migrate.

### Validate

The validation phase is the same as the migrate phase. The windows ask you to indicate the same information, but rather than selecting data for migration, you are selecting data for validation.

You can validate only those objects that have successfully been migrated.

### Migration and validation progress

sybmigrate keeps you informed of the migration and validation progress on the Migration/validation screen. It shows migration progress, messages reported, and a summary count of objects pending, failed, and succeeded for each task type.

You can select the Cancel button at any time, which starts a graceful shutdown of the execution progress.

## **Resource file mode**

You must make the following changes to the resource file mode:

- data\_copy\_thread, create\_index\_thread, and work\_thread attributes are recognized in the setup, migration, and validate sessions of sybmigrate. In the setup session, these values are recorded in the repository database, and used as default values during the migrate and validate sessions. During the migrate and validate sessions, you can override the default values by specifying a new value.
- lock\_account is a new login account management feature. lock\_account tells sybmigrate to lock or unlock all accounts on the target Adaptive Server after copying the login information. Valid values are "Yes" and "No", with "Yes" instructing sybmigrate to lock the target Adaptive Server accounts. To activate lock\_account, you must set migrate\_server\_data to "Yes" in the setup session.

If the lock\_account attribute is not set, nothing is done to target login accounts.

- login\_password\_file has been added to support changing the passwords on the target Adaptive Server. In the setup session, login\_password\_file takes the input password file or the value "<generate>". "<generate>" is a special key used to tell sybmigrate to generate the passwords instead of reading them from the password file. If this attribute is not set in the resource file during the setup session, there is no change to the target Adaptive Server login passwords. To activate login\_password\_file, you must set migrate\_server\_data to "Yes" in the setup session.
- The password file must be in plain text. The content of this file consists of two columns: the login name column and the password string column. The separator between the columns are tabs and or spaces. Any lines beginning with "#" are comments.
- auto\_select\_dependent\_objects is a new value that is available during the migrate and validate sessions. This attribute tells sybmigrate to automatically select the dependent objects for migration and validation. The valid values for this attribute are either "Yes" or "No"; "No" is the default.

- If source\_ase, source\_ase\_login, source\_ase\_password, target\_ase, target\_ase\_login, and target\_ase\_password attributes are not in the resource file, sybmigrate prompts the user for these attributes.
- In the database section of the resource file, if you do not specify any objects or SQL, all objects and types are selected.

For example, in the following resource file all object types (default, rule, table, and so on) are migrated from pubs2 and pubs3 databases:

```
[server}
source_ase=tho:5002
source_ase_login=sa
source_ase_password=
target_ase=tho:6002
target_ase_login=sa
target_ase_password=
[database]
source_database_name=pubs2
target_database_name=pubs3
target_database_name=pubs3
```

Resource file mode is a non-interactive mode. The resource file contains all the information required for migration. You can use the resource file mode if you do not have GUI support or if you need to run batch files.

If you do not specify any object type attributes to migrate in the resource file, sybmigrate migrates the entire database.

If you do not specify the source or target Adaptive Server login or password in the resource file, sybmigrate prompts the user for this information.

Following is the format for the resource file to run sybmigrate in noninteractive mode. To create a resource file, type all the values into a file:

[server] # "<host name>:<port number>" or just server name. source ase=tho:5002 source\_ase\_login=sa source\_ase\_password= # "<host name>:<port number>" or just server name. target\_ase=tho:6002 target\_ase\_login=sa target\_ase\_password= # Repository database setup attributes. This is required with "setup" mode. # Repository database size in MB. repository\_database\_size=7 # Device used to create the "sybmigrate" database. repository\_device=master # Migrate server wide data - logins, roles, remote servers, etc... # valid only with "setup" mode, default is yes migrate\_server\_data=yes # Tell sybmigrate to lock or unlock all login accounts on the # target Adaptive Server. Valid values are "yes" and "no": # "yes" to lock and "no" to unlock. This is only valid if # "migrate\_server\_data" is set to "yes" and run in "setup" mode. # If this attribute is not specified, target Adaptive Server login # accounts are not change. lock\_account=no # Change target Adaptive Server login passwords. This is only valid # if "migrate\_server\_data" is set to "yes" and run in "setup" mode. # If this attribute is not specified, target Adaptive Server login # accounts are not change. # The valid values are "<generate>" and password file. # "<generate>" instructs sybmigrate to use random passwords. # Password file instructs sybmigrate to use the passwords from # this file. # The content of the password file consists of two columns: # the login name column and the password string column. # The separator between the columns are tabs and or spaces. login\_password\_file=<generate> \*\*\*\* # Database information

\*\*\*\*

# # Migrate the "pubs2" database objects [database] # Specify the source target database to migrate. source\_database\_name=pubs2 target\_database\_name=pubs2 # Migrate database data, valid only if "migrate\_server\_data" # was set to "yes" in "setup" mode. This is default to yes. migrate\_database\_data=yes # Work database setup attributes. This is required with "setup" mode. # Work database size in MB. work database size=5 # Device used to create the work database. work\_database\_device=master # Number of threads use to do user table data copy data\_copy\_thread=5 # Number of thread use to create indexes. create\_index\_thread=1 # Number of thread use to do ddl migration/validation work thread=10 # Automatically select the depedent objects for migration and # validation. Valid values are "yes" or "no". auto\_select\_dependent\_objects=yes ## Migrate objects # # These attributes specify the list of DDL object to # migrate or validate. User can directly specify the # list of DDL object or ask Migration tool to query the # list. Directly specifying the list has the higher # precedence. The SQL command will ignore if the list # is given. # Note: # \* The SQL command for the "\*\_list\_from\_sql" attributes # must return column <object name> or columns <user</pre> # name> and <object name> # \* Index type must also specify the table name. For

```
# example, ".<index name>" for
# "index_create_list" attribute or columns ,
# <index name> for "index_create_list_from_sql"
# attribute.
# * Value "<ALL_OBJECTS>" can be used on any of the
# attributes to specify all objects for the type.
# * If none of these attributes are given, all objects
# and data are migrated.
#
user_defined_type_create_list=
id
dbo.tid
default_create_list_from_sql=
select user_name(uid), name from sysobjects
where type = 'D'
rule_create_list=
pub_idrule, title_idrule
table_create_list=
publishers
titles
dbo.authors
dbo.titleauthor
dbo.rovsched
stores
dbo.sales
dbo.salesdetail
dbo.discounts
dbo.au_pix
blurbs
table_migrate_list=
dbo.publishers titles dbo.authors dbo.titleauthor
dbo.roysched
stores dbo.sales dbo.salesdetail dbo.discounts au_pix
dbo.blurbs
index_create_list=
dbo.authors.auidind
dbo.authors.aunmind
publishers.pubind
roysched.titleidind
sales.salesind
salesdetail.titleidind
```

```
salesdetail.salesdetailind
titleauthor.taind
titleauthor.auidind
titleauthor.titleidind
titles.titleidind
titles.titleind
trigger_create_list=
deltitle
totalsales_trig
store_procedure_create_list_from_sql=
select name from sysobjects where type = 'P'
view_create_list_from_sql=<ALL_OBJECTS>
referential constraint create list from sql=<ALL OBJECTS>
logical key create list from sql=<ALL OBJECTS>
****
#
# Migrate the "pubs3" database objects
#
[database]
source_database_name=pubs3
target_database_name=pubs3
# Migrate database data - user, etc.
migrate_database_data=yes
# These two attributes valid only with "setup" mode
work_database_size=5
work_database_device=master
# Number of threads use to do user table data copy
data_copy_thread=5
# Number of thread use to create indexes.
create_index_thread=1
# Number of thread use to do ddl migration/validation
work_thread=10
# Migrate objects
```

```
user_defined_type_create_list=<ALL_OBJECTS>
default_create_list=<ALL_OBJECTS>
rule_create_list=<ALL_OBJECTS>
table_create_list=
dbo.authors
publishers
dbo.titles
dbo.roysched
stores
dbo.sales
dbo.store_employees
salesdetail
dbo.titleauthor
dbo.discounts
blurbs
table_migrate_list_from_sql=<ALL_OBJECTS>
index_create_list=<ALL_OBJECTS>
trigger_create_list=<ALL_OBJECTS>
store_procedure_create_list=<ALL_OBJECTS>
view_create_list=<ALL_OBJECTS>
referential_constraint_create_list_from_sql=<ALL_OBJECTS>
logical key create list from sql=<ALL OBJECTS>
*****
#
# Migrate all the "foo" database objects with default settings.
#
[database]
source_database_name=foo
target_database_name=foo
# Migrate database data - user, etc.
migrate_database_data=yes
# These two attributes valid only with "setup" mode
```

work\_database\_size=5
work\_database\_device=master
# Number of threads use to do user table data copy
data\_copy\_thread=5
# Number of thread use to create indexes.
create\_index\_thread=1
# Number of thread use to do ddl migration/validation
work\_thread=10

# Using sybmigrate with encrypted columns

For databases with encrypted columns, sybmigrate migrates:

- 1 The system encryption password if you specify not to migrate the system encryption password, sybmigrate migrates the encrypted columns using the reencrypt method instead of migrating the ciphertext directly.
- 2 Encrypted columns in cipher text format by default this avoids the overhead of decrypting data at the source and reencrypting it at the target. In some cases, however, sybmigrate chooses the reencrypt method of migration, which does decrypt data at the source and reencrypts it at the target.
- 3 The encryption keys you may select the keys to migrate. sybmigrate automatically selects keys in the current database used to encrypt columns in the same database. If you have selected migration of the system encryption password, sybmigrate migrates the encryption keys using their actual values. The key values from the *sysencryptkeys* system table have been encrypted using the system encryption password and these are the values that are migrated. If you have not migrated the system encryption password, sybmigrate migrates the keys by name, to avoid migrating keys that will not decrypt correctly at the target. Migrating the key value from the key at the source.
- 4 The data by default, the data is transferred in its ciphertext form. Ciphertext data can be migrated to a different operating system. Character data requires that the target server uses the same character set as the source.

sybmigrate works on a database as a unit of work. If your database on the source server has data encrypted by a key in another database, migrate the key's database first.

sybmigrate chooses to reencrypt migrated data when:

- Any keys in the current database are specifically not selected for migration, or already exist in the target server. There is no guarantee that the keys at the target are identical to the keys are the source, so the migrating data must be reencrypted.
- The system password was not selected for migration. When the system password at the target differs from that at the source, the keys cannot be migrated by value. In turn, the data cannot be migrated as ciphertext.
- The user uses the following flag:

sybmigrate -T 'ALWAYS\_REENCRYPT'

Reencrypting data can slow performance. A message to this effect is written to the migration log file when you perform migration with reencryption mode.

To migrate encrypted columns, you must have both sa\_role and sso\_role enabled.

# **Post-migration activities**

- sybmigrate supports the migration of only the objects listed elsewhere in this document. Manually migrate other schema objects and configuration information to ensure the target Adaptive Server is fully functional.
- Statistics for indexes are automatically re-created when you rebuild the indexes. However, sybmigrate does not re-create statistics from non-index columns. Any user-defined step values for index statistics are not retained during migration. To obtain target-server-side statistics similar to the source-server-side statistics, use optdiag to identify the tables with non-index columns that include statistics. Once you have determined which non-index columns include statistics, update the statistics manually.
- Any message requiring user attention preceded by the word "attention" and logged in the migration log.
- Run the object migrations status report to verify that all objects have been migrated.

# Migrate databases in the Replication Server domain

The Replication Server domain includes one or more:

- Primary databases
- Replicate databases
- Replication Server System Databases (RSSDs)

**Note** The RSSD stores Replication Server system tables; in addition, it can also be a primary or a replicate database.

You can migrate any of these databases, but the process requires additional steps to ensure success.

## **Premigration procedures**

Make sure that replication from or into each database is complete before initiating migration. This means that:

- For a primary database all changes have been applied to all subscribing databases
- For a replicate database all changes to which the database subscribes have been applied

**Note** All transactions in the Replication Server inbound and outbound queues must be applied. After migration, there is no way to restore data left in the Adaptive Server transaction log.

#### Before migrating data

1 Log in to the Replication Server and suspend log transfer. Enter:

suspend log transfer from server.database

2 Log in to the Adaptive Server, and shut down the RepAgent. Enter:

use database sp\_stop\_rep\_agent database

3 Suspend all DSI connections to the replicate database. Log in to the Replication Server and enter:

suspend connection to server.database

4 Put the Replication Server in hibernation mode. Enter:

sysadmin hibernate\_on, replication\_server

Before starting the migration process, sybmigrate records replication information in its log. The information needed to restore the replication information during the postmigration steps can be retrieved from this log. See "Postmigration procedures" on page 380 for more information.

## **Postmigration procedures**

After migration, restore the replication information in the database. These steps can be generated by the repl report.

If the page size changes between the source and target, you must also follow directions in "Amending system tables when the logical page size changes" on page 382.

Replication Server identifies all connections by *server\_name.database\_name*. After migration, you must change the name of the target server (the server you are migrating to) to that of the source server (the server you are migrating from).

### **Restoring primary databases**

Follow this procedure for all primary databases, including the RSSD, if it is a primary database.

If the page size changes during the migration, you must also alter the rs\_lastcommit and rs\_threads system tables as described in "Amending system tables when the logical page size changes" on page 382.

#### Restoring primary databases

1 If the original primary database had warm standby on, restore the standby status. Enter:

sp\_reptostandby database\_name, status

sybmigrate saves the standby status in the migration log of the source database.

2 Increase the generation ID by 1. Enter:

dbcc settrunc ("ltm", "gen\_id", gen\_id)

You can view the current generation ID in the migration log of the source database.

3 Reset the secondary truncation point:

dbcc settrunc ("ltm", "valid")

4 Zero the Replication Server locator value for this database. Enter:

rs\_zeroltm server, database\_name

- 5 If this database is an active connection in a warm standby configuration, rematerialize the standby database by dumping the primary and loading the dumps into the standby. See the Replication Server documentation for instructions.
- 6 Start the RepAgent on the primary database. Enter:

sp\_start\_rep\_agent database\_name

7 Log in to the Replication Server and restart log transfer:

resume log transfer from *server.database* 

#### Restoring replicate databases

If the page size does not change during migration, there are no postmigration steps necessary for replicate databases.

If the page size does change, follow the procedure in "Amending system tables when the logical page size changes" on page 382.

### **Restoring the RSSD**

This is the procedure for restoring the RSSD.

#### Restoring the RSSD

1 If the RSSD is a primary database, follow the procedure in "Restoring primary databases" on page 380.

If the page size changes, make sure you alter the rs\_lastcommit and rs\_threads system tables as instructed.

2 Turn off hibernation for the Repliction Server. Log in to Replication Server and enter:

sysadmin hiberate\_off replication\_server

2

### Amending system tables when the logical page size changes

If the logical page size changes during migration, you must alter the rs\_lastcommit and rs\_threads system tables to account for the change.

Follow this procedure for all databases in which the page size has changed.

### Altering the rs\_lastcommit and rs\_threads system tables

1 Alter the rs\_lastcommit table. Enter:

```
declare @pad8 size integer
     declare @alter cmd varchar(200)
     select @pad8 size = (@@maxpagesize / 2)
     - (select sum(A.length) from
     syscolumns A, sysobjects B
     where A.id = B.id
     and B.name = 'rs lastcommit')
     + (select A.length from
     syscolumns A, sysobjects B
     where A.id = B.id
     and B.name = 'rs lastcommit'
     and A.name = 'pad8')
     select @alter_cmd = "alter table rs_lastcommit "
     + "modify pad8 char("
     + convert (varchar(100), @pad8 size)
     + ")"
     execute (@alter cmd)
     qo
Alter the rs threads table. Enter:
     declare @pad4 size integer
     declare @alter cmd varchar(200)
     select @pad4 size = (@@maxpagesize / 2)
     - (select sum(A.length) from
     syscolumns A, sysobjects B
     where A.id = B.id
     and B.name = 'rs threads')
     + (select A.length from
     syscolumns A, sysobjects B
     where A.id = B.id
     and B.name = 'rs threads'
     and A.name = 'pad4')
     select @alter cmd = "alter table rs threads "
```

```
+ "modify pad4 char("
+ convert(varchar(100), @pad4_size)
+ ")"
execute (@alter_cmd)
go
```

### Logs

In the migration tool log, information about replicated objects is preceded by the following banner:

```
=== Replication Information for Database 'pdb1' ===
```

The following is a sample log file for a primary database named pdb1:

```
sp repostandby 'pdb1' is NONE.
```

If the standby status for the database is not NONE, use the standby status as described in the post-migration steps above.

sp\_config\_rep\_agent 'pdb1'

sp\_config\_rep\_agent requests the current RepAgent configuration. The migration tool automatically restores RepAgent configuration, and you can use this log to verify the RepAgent configuration.

Parameter name	Default	Config Value	Run value
priority	5	5	5
fade timeout	30	30	30
scan timeout	15	15	15
retry timeout	60	60	60
rs username	n/a	rs1_user	rs1_user
trace flags	0	8194	8194
batch ltl	true	true	true
rs servername	n/a	rsl	rsl
send buffer size	2k	2k	2k
trace log file	n/a	n/a	n/a
connect database	n/a	pdb1	pdb1
connect dataserver	n/a	pds1	pds1
can batch size	1000	1000	1000
security mechanism	n/a	n/a	n/a
msg integrity	false	false	false
unified login	false	false	falses
kip ltl errors	false	false	false
msg origin check	false	false	false
short ltl keywords	false	false	false
msg confidentiality	false	false	false
data limits filter mode	stop	stop	stop

msg replay detection	false	false	false
mutual authentication	false	false	false
send structured oqids	false	false	false
send warm standby xacts	false	false	false
msg out-of-sequence check	false	false	false
skip unsupported features	false	false	false
send maint xacts to replicate	false	false	false
(28 rows affected)			

This is a list of explicitly replicated tables. sybmigrate automatically restores the replication status for explicitly replicated tables, and you can use this part of the log to verify the replication status of explicitly replicated tables.

sp_	_setre	eptable		
Nar	ne		Repdef	Mode
t1			owner_c	off
t2			owner_c	on
(2	rows	affected)		

This is a list of explicitly replicated stored procedures. The migration tool automatically restores the replication status for explicitly replicated stored procedures, and you can use this part of the log to verify the replication status of explicitly replicated stored procedures.

sp_setrepproc		
Name	Туре	Log Mode
pl	function	log_sproc
p2	function	log_current
р3	table	log_sproc
p4	table	log_current
(4 rows affected)		

This is information about the secondary truncation page. You will need the generation\_id column during the post-migration steps.

dbcc	gettrunc			
secon	dary_trunc_page	<pre>secondary_trunc_state</pre>	dbrepstat	generation_id
	database_id	database_name	ltl_versic	n
621		1	167	0
	6	pdb1	400	
(1 rc	w affected)			

This appears to be a replicated primary database. Make sure the post processing steps for a replicated primary database are performed. Please consult the manuals for the steps that need to be performed.

The following is an example log entry if your database is a replicate database.

This appears to be a replicate database. If the pagesize is greater than 2K, make sure the post processing steps for a replicate database are performed. Please consult the manuals for the steps that need to be performed.

The following is an example log entry for an RSSD database.

This appears to be a replication system database Make sure the post processing steps for a replication system database are performed. Please consult the manuals for the steps that need to be performed

> All three logs can be present for a database, since a database can list the three categories.

## Migrating databases that support wide data

Adaptive Server version 12.5 and later can generate data wider than what Replication Server version 12.1 and earlier can handle. If RepAgent passes wide data to Replication Server 12.1 or earlier, Replication Server threads may shut down.

RepAgent communicates with Replication Server using Log Transfer Language (LTL). When the RepAgent connects to Replication Server, it returns an LTL version as shown in Table 9-1.

LTL version		
< 400		
>= 400		

Table 9-1: Replication Server and LTL versions

If Replication Server returns an LTL version less than 400, RepAgent uses the setting of the data limits filter mode option to determine how to treat wide data.

You can set the data limits filter mode option using sp\_config\_rep\_agent. Values for data limits filter mode are:

stop – RepAgent shuts down when it encounters data too wide for Replication Server to process (the default when the LTL version is less than 400).

- skip RepAgent ignores data too wide for Replication Server to process, and logs an informational message.
- truncate RepAgent truncates wide data so that Replication Server can
  process it. If the table or stored procedures has more than 250 columns or
  parameters, only the first 250 columns or parameters are sent. If the
  column or parameter is wider than 255 bytes, only the first 255 bytes are
  sent.
- off RepAgent sends wide data to the Replication Server; Replication Server threads may shut down.

Table 9-2 shows column and width limits for Replication Server 12.1 and earlier and Replication Server 12.5 and later.

Property	Replication Server 12.1 and earlier	Replication Server 12.5 and later
Column count	250	65535
Column width	255	65535

Table 9-2: Replication Server column number and width limits

# Limitations

		<b>Note</b> When migrating server data, sybmigrate requires that the target Adaptive Server catalog contain only default data. Default data on Windows machines is different from UNIX machines. This causes problems when migrating from UNIX to Windows machines. To successfully migrate from a UNIX machine to a Windows machine, delete the XP Server name and the mon_user login or the target Windows machine.	
High availability		Data migration is not supported while you are in high availability. You must stop high availability before beginning database migration.	
	*	Stopping high availability before beginning database migration	
		1 Decouple primary and secondary Adaptive Servers.	
		2 Migrate primary source Adaptive Server and secondary source Adaptive Server data to the primary target Adaptive Server and secondary target Adaptive Server separately.	

3 Configure the target Adaptive Server for high availability.

**Warning!** The primary and the secondary Adaptive Servers must be configured to the same logical page size to run high availability.

Other limitations • sybmigrate does not do any special processing for a DTM/XA environment. The status of open transactions and outstanding prepared transactions should be given consideration. If any special handling is required, you must do it manually.

• There is no reliable way for sybmigrate to determine the dependency of various objects. sybmigrate does not attempt to create an order in which objects are migrated based on their dependencies on other objects. Views can be dependent upon other views, and they will not be re-created if the view on which they are dependent has not yet been migrated. The migration of stored procedures and triggers may not be successful if the data on which they depend has not yet been migrated. Cross-database dependencies mean that you need to coordinate the migration of related objects. If dependencies are within the selected set, sybmigrate takes care of those dependencies. However, if dependencies exist outside the selected set, you may need to run sybmigrate through migration more than one time. For this reason, you may need to perform some partial retries to successfully complete the data migration.

- Adaptive Server versions 12.5.3 and later allow you to specify the size and location of a work database on your target server. When migrating a database or server from a source server with Adaptive Server Enterprise versions 12.0 and later but earlier than 12.5.0.1, you must specify the size and location of a work database on the target server.
- The name of the source and the target databases must be the same. SQL schema generated by ddlgen may have objects that must be qualified with the source Adaptive Server name.
- sybmigrate does not support any kind of auditing for migration activities.
- When renaming any of the compiled objects (procs, views, rules, defaults) the object name in syscomments is not updated.

During the migration, the DDLGen query the object from syscomments with the old name in the text. This old name in the text causes problems for sybmigrate during the DDL migration.

# **Troubleshooting and error messages**

This section discusses common errors and how to address them, as well as different error messages and their meaning.

Errors	Description
Objects fail to migrate	Objects often fail to migrate on the first attempt. sybmigrate automatically retries all failed migration attempts. However, if you choose to migrate an object that is dependent upon another object that is not migrated, the migration fails.
	To prevent failed migration of objects, examine the dependencies of objects that you select for migration. For example, you cannot migrate a trigger if the table on which the trigger is defined is not also migrated. Similarly, views can be created on other views or tables, and if these objects are not migrated, the migration of the view fails.
Beginning database migration	When you are in the setup phase of the migration process, you are asked to decide whether or not you want to migrate server data. You must select from yes, no, or undecided.
	"Undecided" provides you with the flexibility of setting up the migration process, but being able to return to the process at a later date that is more convenient for migration. If you select Undecided, you cannot begin the database migration until you indicate whether you want to migrate server data.
	If you indicate that you do not want to migrate server data during setup, you cannot migrate database data during migration. You can override this limitation in GUI mode.
"Connection refused"	There are two possible reasons why you may encounter these error messages.
and "Unable to obtain connection to the server"	• If either the source or the target Adaptive Server is not running, sybmigrate cannot establish a connection.
	• The number of user connections configuration parameter must be configured to provide sufficient resources on both the source and target Adaptive Servers.
Target server cannot be reached from source server	The interfaces file is used to start the source Adaptive Server. Verify that it has an entry that identifies the target Adaptive Server.
	Verify that your login can access the target Adaptive Server from the source Adaptive Server.
If sybmigrate hangs during migration	If sybmigrate hangs during the migration process, check the <i>sybmigrate</i> log in <i>\$SYBASE_\$SYBASE_ASE/init/logs</i> for any errors or exceptions.
	Also, check your Adaptive Server logs. If the Adaptive Server logs run out of space on the database, increase the database size, and install the sp_threasholdaction stored procedure to do dump tran when the log is full.
Errors	Description
-----------------------------------	------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------
Merging two databases	To merge two databases on the source Adaptive Server into one database on the target Adaptive Server, use the following procedure.
	• Set up and migrate the first database.
	• After migrating the first database, rename the target database so that it has the same name as the second source database.
	• Set up and migrate the second database.
	<b>Note</b> You cannot migrate the database data for the second database because the users, roles and other database data already exist on the target database. You can still migrate user data.
Post-migration failure cleanup	If sybmigrate fails unexpectedly, rerun sybmigrate on the areas that failed. If it fails again with no more progress, clean up the source and target Adaptive Servers, and begin migration again. There are actions that you must perform on both the source and target Adaptive Server.
	On the source Adaptive Server:
	• Drop the temporary working databases mtpdb\$%.
	• Drop the repository database sybmigratedb.
	• Drop all remote servers mtrs\$%.
	On the target Adaptive Server:
	• If server data was migrated, rebuild the target Adaptive Server with srvbuild or syconfig.
	• Re-create the target databases.
Remigrating one database	To remigrate a specific database:
	1 Start sybmigrate.
	2 In the Setup Paths window, during the setup session, right-click the migration path you want to redo.
	3 Select Delete Migration Path on the pop-up menu.
	4 Clean up or remove the migrated data and objects on the target database, or drop and re- create the target database.
	5 Restart sybmigrate and run it from setup mode.
Re-creating an individual object	To re-create an individual object:
	1 In the target Adaptive Server, drop the object you want to re-create.
	2 Start sybmigrate in the migration session, and go to the Migrate Object Selection window. Highlight the object you want to create and right-click.
	3 From the pop-up menu, select Reset Object to Initial status.
	4 Complete the migration process.

Errors	Description
Connection fail	If you receive a connection fail error message even though the source and target Adaptive Servers are running, you may be using the wrong character set. When you are using sybmigrate, you must use the default character set. Run sybmigrate with the -J <i>charset</i> option, to change the character set you are using.
"Insufficient memory	If you see the following error in the server log, it indicates that you must reconfigure the
in JVM shared class"	size of shared class heap configuration parameter to a larger value.
	01:00000:00036:2002/01/28 14:17:05.63 server Java VM Host: Memory allocation request failed because of insufficient memory in Jvm Shared Class.
"There is not enough memory in the procedure cache"	If you see the error message there is not enough memory in the procedure cache during the migration of indexes, use sp_configure procedure cache size to increase the procedure cache.
java.lang related error	If you receive java.lang.NoClassDefFoundError:com/sybase/jdbcx/SybDriver when you are connecting to Adaptive Server, check to make sure you have jConnect 6.0 installed in your <i>\$SYBASE</i> directory ( <i>\$SYBASE/jConnect-6_0</i> ).

## **Symbols**

!! (exclamation points) operating system commands prefix (isql) 214 < (redirect in) in isql 15 > (redirect out) in isql 15 \ (backslash) escaping special characters 114 \ (backslash) data field terminator in interactive bcp 69 \0 (null) character terminator in interactive bcp 69 "" (enclosing special characters) 114

# A

actions collect 237 compare 238 237 custom start fix stats 237 simple start 237 start\_stats to fix missing statistics 235 Adaptive Server configuration of, for migration 356 executing (dataserver) 157 executing (sqlsrvr) 254 rolling back processes - 84 upgrading (sqlupgrade) 231, 261 upgrading with resource files (sqlupgraderes) 262 add instance 295 adding network transport addresses in dsedit 109.111 server entries in dscp 94 server entries in dsedit 106, 108 additional network memory parameter 354 allow\_dup\_row option to create index, and bcp 87 application programs, copying data from 76 archive database access

downgrading 359 migrating 352, 358 ASCII format, bcp and 60 ascii\_7 character set defncopy and 191

#### В

backing up, compared to bulk copying 89 backslash (>> escaping special characters 114 terminator in interactive bcp 69 Backup Server See also backupserver utility command 120 backup Server 120 backupserver utility command 120 character set, default 121 defined 120 error log file 121 error messages in 125 full path names, specifying 121 interfaces file 124 interfaces file, name and location of 120 language, default 121 LC\_ALL environment variable 121 permissions required for 125 server connections, number of 120server names, specifying 120 starting servers and 124 trace flags 125 -bbatch\_size parameter 84 **bcp** 44 bcp utility command 89, 126 allow\_dup\_row option to create index 87 ASCII format and 60 batch operations in 84 batch size settings 129 -bbatch\_size parameter 84 binary format and 41

character format 60 59 character format files character format, default 60 character formats accepted 41 character set defaults 132 configuration parameters 86 copying data in 50, 52, 79, 82 copying data out 76, 78, 85 copying in batches of table rows 84 data integrity 88 data loss and dumping 49 data storage size in 63 data transfer, preparing for 42 datatypes 69 default values for data 88 defaults for columns and datatypes 88 defined 126 described 40 dump database and 89 error files 86 errors in data conversion 86 examples for using 131 fast version of 48 fast version of, and data recoverability 47 field lengths 60 field terminators 61, 63 file storage types in 63 format files 71.75 **IDENTITY** columns and 57 improving performance of operations 86 improving recoverability when copying data in 84 index creation 87 indexes and triggers, dropping 49 insert and - 89 interactive mode 62, 70 languages, using alternate 82 load database and 89 load transaction and 89 maximum speed, enabling 88 native file format and 59 native format option and 60 non-character to character datatype default field lengths 67 non-interactive 59 non-iso\_1 data files and 82 other Adaptive Server utilities and 88

page allocations, increasing for 53 partitioned tables and 50, 59, 85 password encryption in 133 performance issues with 46, 58, 88 permissions required for 42, 65 prefix length 63 prompts and responses. See Interactive bcp 61, 62 prompts in 63 rolling back processes 84 row terminators 61 88 rules and copying data select into/bulkcopy/pllsort and 49 slow version and deadlocks on index pages 52 slow version of 48 sp\_dboption 49 space needed for data 49 special characters, handling 130 speed, and indexes and triggers 47 speed, modes of 43 storage types 69 system data format (SDF) output in 76 system differences, operating 60 table defaults and copying data 88 terminators used in 41 transferring data between programs 40 triggers and data copying - 88 triggers not fired on target table 47 unique IDENTITY column values and 58 using with row-level access rules 83 warning about data recovery 129 binary data bcp and 41 default in interactive bcp 66 buffer, query 12 buildmaster utility command. See dataserver bulk copy process See also bcp utility command 126

## С

carriage-return data field terminator (\\r) in interactive bcp 69 char datatype, and bcp 59 character formats bcp 41

default in bcp 59,60 terminators for 69 character set specification for migration 362 character sets backupserver, default in 121 bcp, defaults in 132 converting from non-character data 67 installing and modifying (sqllocres) 253 installing and modifying, in GUI (sqlloc) 252 loading, with charset 154 platform default 82 charset utility command 154 defined 154 permissions required for 154 settings for 154 CIS bulk insert array size configuration for migration 353.357 CIS bulk insert batch size 357 **CIS** packet size configuration for migration 356 for migration 354 closing a session dscp 92 104 dsedit collect action of QPTune 237 column precision in numeric or decimal storage formats 75 column scale in numeric or decimal storage formats 75 columns datatype sizes and 67 default values and bcp 88 fixed- and variable-length 66 null 86 separator character (isql) 11 comma-delimited output 76,78 command terminator (isql) 10 statistics option interaction 14 compare action of QPTune 238 component directory for migration 351 297 connect copy threads on sybmigrate 356 copying 96 between sessions in dscp different sessions in dscp 96

new entries with dscp 96 server entries with dscp 95 server entries with dsedit 108, 109, 110, 111 copying data in batch operations in - 84 improving recoverability after rolling back 84 parallel bcp, requirements for 53, 58 partitioned tables 51 partitions, random use of 51 steps, using fast version of bcp 50 copying data in with interactive bcp 79,82 compatibility of datatypes, and failure - 81 delimiters 81 error files and 87 field lengths 79 copying data out with interactive bcp 76, 78 delimiters 77 error files and 87 fixed-length fields 76 for other software 76 85 text and image data copying definitions 190 create cluster 301 create index command, bcp and duplicate rows 87 creating new servers (srvbuild) 263.264 new servers using resource files (srvbuildres) 265 custom start action of QPTune 237

# D

data changing with Adaptive Server commands 89 conversion errors 86, 87 importing and exporting with bcp 40 moving with Adaptive Server commands 88 padding with spaces in interactive bcp 66 parsing. See Field terminators 61 permission required to copy into tables 42.141 recoverability 47 transferring from different programs using bcp 40 data transfer, default formats with bcp 59 database data, migration of 347 database management systems, other 76 database objects

copying using bcp 126 databases, copying with bcp 89 dataserver utility command 157 defined 157 passwords, generating new 162 permissions required for 163, 259 datatypes bcp file storage types for 62,65 bcp format files for 71 bcp, used in 69 char 59 copying and compatibility 81 default values and bcp field lengths in interactive bcp 64, 70 implicit conversions of 64, 65 non-character to character default field lengths in bcp 67 storage (SYB) 73 debug level for sybmigrate 360 debugging utility 247 default network packet size configuration parameter 86 defaults 67 bcp data conversion bcp prompts 62, 70 character sets in backupserver 121 character sets, in bcp 132 copying into tables using data 88 copying, with defncopy 190 languages in backupserver 121 prompts in interactive bcp 62,70 select into/bulkcopy/pllsort option settings in new databases 49 definitions backupserver utility command 120 bcp utility command 126 charset utility command 154 copying. See defncopy utility command 190 dataserver utility command 157 defncopy utility command 190 dscp utility command 196 dsedit utility command 197 isql utility command 205 optdiag utility command 220, 227 showserver utility command 246 sqlloc utility command 252 sqllocres utility command 253

sqlsrvr utility command 254 sqlupgrade utility command 261 sqlupgraderes utility command 262 srvbuild utility command 263 srvbuildres utility command 265 startserver utility command 266 sybdiag utility command 269 276 sybmigrate utility command xpserver utility command 282 defncopy utility command 190 ascii\_7 character set and 191 defined 190 encrypted text 195 examples 193 failure due to long comments 194 passwords and crashing 190 Report Workbench, incompatibility with 190 deleting server entries (dscp) 97 delimiters copying data in with 81 copying data out with 77 deploy plugin 304 diagnose cluster 306 308 diagnose instance directory services entries, adding 106 entries, copying to 108, 110, 111 entries, deleting 107 entries, modifying 106 entries, renaming 107 opening to, with dsedit 103 disconnect 309 **DISPLAY** environment variable setting, in dsedit 102 downgrading an archive database 359 drop cluster 311 drop instance 312 dscp utility command 196 commands, table of 98 defined 91, 196 entries, creating new, by copying 96 examples of 196 exit command 98 help 91, 98 permissions required for 196

quit command 98 server attributes 93 server entries, adding 94 server entries, copying 95 server entries, deleting 97 server entries, listing 96 server entries, modifying 94 97 server entry contents, viewing sessions, closing 92 96 sessions, copying between sessions, copying to different 96 sessions, listing 92 sessions, opening 92 starting - 91 dsedit utility command 197 about 101 command line arguments 101 defined 197 Directory Service Session screen 104 DISPLAY environment variable and 102 libtcl.cfg file 103 109, 111 network transport addresses, adding network transport addresses, editing 109 opening with sql.ini 103 permissions required for 102, 197 remote machines, running from 102 Select a Directory Service screen 102 server attributes 105 server entries, adding 106, 108 server entries, cannot add, modify, or delete 112 server entries, copying 108, 109, 110, 111 server entries, deleting 107 server entries, modifying 107, 108 server entries, renaming 107 sessions, closing 104 104 sessions, opening starting 102 starting from command prompt 101 starting from Windows Explorer 101 SYBASE environmental variable and locating libtcl.cfg 103 troubleshooting 101, 112 xd2 Unable to open X displayxd3 error message 112 DSLISTEN environment variable backupserver and 124

dump database command bcp and 89 dump transaction command bcp and 89 error message recommending use of dump database 47

### Ε

echo input (isql) 15 editing interfaces files 102.104 interfaces files in GUI (dsedit) 197 network transport addresses in dsedit 109 editing interfaces files in GUI 197 See also dsedit utility command enable unicode conversions for migration 354 encrypted hidden text 195 environment variables DSLISTEN (backupserver) 124 LANG (backupserver) 121 LC\_ALL (backupserver) 121release path, for sybmigrate 351 SYBASE\_ASE 351 SYBASE\_JRE environment variable 351 error files bcp and 86,87 copying out and 87 error log files for backupserver 121 error messages dsedit and X display 112 dump database use over dump transaction 47 in backupserver 125 select into/bulkcopy/pllsort in fast bcp on tables with no indexes or triggers 49 error messages for migration 388 errors in data conversions 86.87 operations, saving during copy in 86 operations, saving during copy out 87 examples bcp utility command 131 defncopy utility command 193 dscp utility command 196

isql utility command 206 showserver utility command 246 startserver utility command 266, 267 exclamation points (!!) operating system commands prefix (isql) 214 executing Adaptive Server 157, 254 See also dataserver utility command 157 See also sqlsrvr utility command 254 314 exit exit command in dscp 98 in isql 10 exporting data. See Copying data out with interactive bcp 76

### F

failure cleanup, sybmigrate 389 fast version of bcp 48 copying data in 50 data recoverability and 47 field lengths copy in 79 in interactive bcp 66, 68 prefix length, integer value in 75 field terminators 61 bcp 63 interactive bcp 69, 70 files See also Format files in bcp 71 default formats with bcp 59 error (bcp) 86 native format 59 fixed-length fields 76 format files in bcp 71.75 column numbers 72 column precision 75 column scale 75 elements used in 72 format used for 71 host file column order 73 host file data length 75 host file datatype storage formats (SYB) 73 number of records in 72 prefix length, integer value in 75

saving 71 server column names 75 server column orders 75 TDS version number in 72 terminators 75 formatting isql output 10 full path names, specifying in Backup Server 121

# G

GUI mode for migration 363

#### Η

help 315 help command (dscp) 91,98 hidden encrypted text 195 --hide-vcc parameter 139 high availability migration with 386 host file isgl and reading 15 host files column order 73 75 data length datatype storage formats (SYB) 73 interactive bcp native format 66

# I

IDENTITY columns bcp and 58 parallel bcp and 57, 58 ignore\_dup\_key option, create index, and bcp 87 image datatype interactive bcp and 66 importing data. See Copying data in with interactive bcp 79 index re-creation for migration 378 index threads for **sybmigrate** 356 indexes

bcp, dropping before using 49 slowing down bcp 47 insert command bulk copying, comparing 89 installing character sets (sqllocres) 253 character sets, in GUI (sqlloc) 252 languages (sqllocres) 253 languages, in GUI (sqlloc) 2.52 languages, new (langinstall) 217, 219 sort orders (sqllocres) 253 sort orders, in GUI (sqlloc) 252 interactive bcp 62, 70 backslash terminator (>69 binary data, default 66 carriage-return data field terminator  $(\r)$ 69 character format files, terminators for 69 copying data for other software 62 copying data in 79, 82 copying data out 76, 78 defaults for prompts 62.70 field length 66, 68 field terminators 69.70 fields, prefix length of 65, 66 file storage types 62,65 image datatype, default for 66 implicit conversion of datatypes 64.65 null or invisible character terminator ( $\langle 0 \rangle$ ) 69 null values and 66 padding data with spaces 66 row terminators 69.70 storage length 66, 68 tab data field terminator (\) 69 terminator for new lines (\\n) 69 terminators for tabular data preparation 69 terminators, field and row 68.70 text data copying, default for 66 interactive SQL parser 205 See also isql utility command 205 interfaces file for svbmigrate 360 interfaces files backupserver and 124 backupserver, specifying names and locations of 120 dscp sessions, opening 92

dscp, viewing and editing with 196 dsedit, editing with 104 dsedit, viewing and editing in GUI with 197 dsedit, viewing and editing with 197 opening for editing 102 iso\_1 character set 82 isql utility command 205 < (redirect in) symbol 15 << symbol 213 > (redirect out) symbol 15 column-separator character 11 command terminator 10 command terminator, changing 13 207 command terminator, resetting correcting typing errors 12 defined 205 echo input 15 examples of 206 exit command 10 host files, reading 15 line numbers, removing 11.15 maximum statement size 10 network packet size, setting 15 network packet size, specifying in 15 output file 11 output, formatting 10 packet size, setting 15 queries, editing 12 query buffer, resetting 12 quit command in 10 reset command in 12 statistics 14 statistics option with command terminator 14 Transact-SQL, using with 10

## J

Java columns for migration 355 Java runtime environment migration 351

### L

LANG environment variable in backupserver 121 langinstall utility command 217, 219

defined 217 permissions required for 217 languages alternate, with bcp 82 for migration 355 installing and modifying (sqllocres) 253 installing and modifying, in GUI (sqlloc) 252 installing new (langinstall) 217, 219 362 specification for migration LC\_ALL environment variable in backupserver 121 line numbers, removing in isql 11, 15 load database command and bcp 89 load transaction command bcp and 89 loading character sets 154 See also charset utility command 154 locations of backupserver error log files 121 locking sessions for migration 360

### Μ

manual migration, what is not migrated 348 max memory, for migration 354 max network packet size configuration parameter 86 max network packet size, configuration for migration 357 max packet size allowed, for sybmigrate 354 max parallel degree, configuration for migration 357 merging databases, during migration 389 migrate session, for sybmigrate 352 migrating servers (sybmigrate) 276 migrating an archive database 352, 358 missing statistics fix\_stats action 237 start\_stats action 235 modifying character sets (sqllocres) 253 character sets, in GUI (sqlloc) 252 languages (sqllocres) 253 languages, in GUI (sqlloc) 252 server entries (dscp) 94 server entries with dsedit 107, 108 sort orders (sqllocres) 253 sort orders, in GUI (sqlloc) 252

## Ν

native file format 59 bcp and native format files 59 network packet size isql, specifying in 15 network transport addresses adding with dsedit 109, 111 109 dsedit, editing with network transports 104 new servers, creating 263, 264 See also srvbuild utility command 263 new servers, creating, using resource files 265 See also srvbuildres utility command 265 new-line terminator (n)in bcp 60 in interactive bcp 69 noncharacter datatypes, operating system format for 65 non-printable characters, host file 66 notes 191 ascii\_7 character set compatibility batch size settings in bcp 129 defncopy and Report Workbench 190 hidden encrypted text 195 null terminator versus no terminator 70 passwords, using 114 security 114 select into/bulkcopy/pllsort and copying out data in bcp 49 slow version of bcp and deadlocks 52 special characters, handling in bcp 130 system differences in bcp, operating 60 triggers not fired by bcp in target table 47 null character terminator (\0) in interactive bcp 69 null values 86 interactive bcp and 66 number (quantity of) server connections to backupserver 120 number of sort buffers for migration 357 number of user connections for migration 356, 357 number of worker processes for migration 357 numbers line, removing from isql 11, 15 numeric datatypes bcp conversion to character storage 67

column precision 75 column scale 75 operating system format for 60

# 0

object hierarchy for migrtion 352 objects failed migration of 388 re-creating after migration 389 opening sessions in dscp 92 sessions in dsedit 104 operating system files native format 59 permission required for copying tables into 42, 141 operating systems commands prefix (!!) (isql) 214 non-character datatype formatting 65 numeric datatype formatting 60 optdiag command, changes 225 optdiag utility command 220, 227 defined 220, 227 permissions required for 226 output formats, data. See Copying data out with interactive bcp 76

## Ρ

packet size, network bcp, specifying with 85 isql, specifying in 15 specifying in isql 15 padding data and bcp 68 parallel bcp copying to a specific partition 53, 57 different methods of using 55, 58 IDENTITY columns and 57, 58 syntax 56 parameter 139 --hide-vcc partitioned tables in bcp 50, 59 copying data into randomly 51

copying data into, methods for 51 page allocations, increasing 53 passwords bcp encryption 133 defncopy and 190 new, generating 162 notes about using 114 performance bcp issues and 46, 58, 88 bulk copy and packet size 86 isql network packet size and 15 permissions required for backupserver utility command 125 42,65 bcp utility command charset utility command 154 dataserver utility command 163, 259 dscp utility command 196 dsedit utility command 197 dsedit, required for 102 langinstall utility command 217 operating system file, copying tables into 42, 141 optdiag utility command 226 252 sqlloc utility command sqllocres utility command 253 261 sqlupgrade utility command sqlupgraderes utility command 262 srvbuild utility command 264 srvbuildres utility command 265 42.141 tables, copying data into xpserver utility command 283 post-migration activities, for sybmigrate 378 prefix field lengths in interactive bcp 65,66 prefix length 75 prefix lengths in bcp 63 preupgrade utility command 227 primary database, restoring after migration 380 prompts bcp. See Interactive bcp 62 prompts in bcp utility command 63

# Q

QPTune collect action 237 compare action 238

custom start action for tuning 237 fix stats action 237 parameters 233 permissions 239 reference page 233 simple start action for tuning applications or queries 237 start\_stats action to fix missing statistics 235 syntax 233 query buffer, resetting 12 quick reference dscp commands 98 quit 318 quit command in dscp 98 in isal 10 quotation marks (' ') for enclosing special characters 114 quotation marks (xd2 xd3) for enclosing special characters 114

## R

redirect in symbol (<) in isql 15 redirect out symbol (>) in isql 15 release path, for sybmigrate 351 remigrating a database 389 remote machines 102 remote machines, using dsedit utility on 102 renaming server entries with dsedit 107 replicate database restoring after migration 381 replicated databases post-migration procedures 380 Replication Server, migrating replicated data to Adaptive Server 379 report Workbench, incompatibility with defncopy 190 reports for sybmigrate 277, 361 reset command (isql) 12 resource file mode, for migration 370 roll-back processes 84 row terminators bcp, in 61 interactive bcp, in 69, 70 row-level access rules and bcp 83 rows in bcp, and erroneous table 87

rows, table bulk copying and failed 84 length 55 rules defncopy, copying with 190 tables, copying data into 88

## S

saving errors during copy in operations 86 errors during copy out operations 87 format files (bcp) 71 security Mechanism server attribute (dscp) 94 security, notes about 114 select a Directory Service screen 102 select into command, compared to bulk copying 89 select into/bulkcopy/pllsort database option bcp and 49 server column names 75 orders 75 server connections backupserver, number of 120 server data, migration of 346 server entries adding, with dsedit 106 contents, viewing with dscp 97 108, 109, 110, 111 copying, with dsedit deleting, with dseditdsedit 107 dscp, listing with 96 modifying, with dsedit 107, 108 renaming, with dsedit 107 server entries, adding 108 server Entry Editor window 104 server Name server attribute (dscp) 93 server Object Version server attribute (dscp) 93 server Service server attribute (dscp) 93 server Status server attribute (dscp) 93 servers backupserver, specifying names in 120 backupserver, starting in 124 migrating 276 modes of speed when using bcp 43 startserver utility command 266

startserver, starting in 266 sybdiag utility command 269 sybmigrate utility command 276 sessions listing (dscp) 92 set cluster 320 set instance 321 setup session, for sybmigrate 352 sever attributes (dscp) 93 show agents 323 show cluster 326 329 show instance 246 show servers See also showserver utility command 246 show session 333 showserver utility command 246 defined 246 examples of 246 shutdown cluster 336 shutdown instance 337 simple start action of QPTune 237 size data storage in bcp 63 packet size 85 85 text or image data slow version of bcp 48 deadlocks on index pages 52 sort orders installing and modifying (sqllocres) 253 installing and modifying, in GUI (sqlloc) 252 sp\_dboption system procedure and bcp 49 space requirements and bcp steps - 49 special characters bcp, handling in 130 utility commands, use in 114 specifying full path names in Backup Server 121 specifying server names in backupserver 120SPX/IPX addresses for interfaces entries 110SQL parser utility. See isql utility command 205 sql.ini file dsedit sessions, opening with 103 entries, adding 106 entries, copying to 108, 110, 111 entries, deleting 107 entries, modifying 106 entries, renaming 107

sqldbgr utility 247 sqlloc utility command 252 defined 252 permissions required for 252 sqllocres utility command 253 defined 253 permissions required for 253 sqlsrvr utility command 254 defined 254 sqlupgrade utility command 231, 261 defined 261 permissions required for 261 sqlupgraderes utility command 262 defined 262 permissions required for 262 srvbuild utility command 263, 264 defined 263 permissions required for 264 srvbuildres utility command 265 defined 265 permissions required for 265 start cluster 338 start instance 339 starting dscp utility 91 dsedit utility command 101, 102 servers (startserver) 266 XP Server manually (xpserver) 282, 283 startserver utility command 266 backupserver and 124 defined 266 examples of 266 runserver file examples 267 statistics displaying (optdiag) 220, 227 isql 14 loading updated (optdiag) 220, 227 storage types used in bcp 69 stored procedures copying with defncopy 190 SYBASE environment variable 351 SYBASE environment variable in dsedit 103 SYBASE ASE environment variable 351 SYBASE\_JRE environment variable 351 sybcluster commands add backupserver 294

295 add instance connect 297 create backupserver 299 create cluster 301 create xpserver 303 304 deploy plugin diagnose cluster 306 diagnose instance 308 309 disconnect drop backupserver 310 drop cluster 311 drop instance 312 313 drop xpserver exit 314 help 315 localize 316 quit 318 set backupserver 319 set cluster 320 321 set instance set xpserver port 322 show agents 323 show backupserver config 325 326 show cluster show instance 329 show membership mode 332 333 show session 335 show xpserver shutdown cluster 336 337 shutdown instance start cluster 338 start instance 339 upgrade server 340 use 343 sybcluster utility 285 sybdiag utility command 269 defined 269 sybmigrate additional network memory parameter 354 character set conversion 354 character set specification 362 CIS bulk insert array size 357 CIS bulk insert array size configuration 353 CIS bulk insert batch size configuration 357 **CIS packet size** configuration 354, 356 command line trace flags 362

component directory 351 components for 349 configuration and tuning 355 copy threads 356 debug level 360 dependencies for 349 environment variables 351 errors to avoid 358 351 executable file GUI mode 363 help information 360 378 index re-creation index threads 356 350 installation 360 interfaces file Java columns 355 Java runtime environment 351 language specification 362 languages 355 360 lock session override max packet size allowed configuration 354 max parallel degree configuration 357 memory for the JVM 351 389 merging two database migrate session 352.368 migrating Replication Server data 379 migration failure cleanup 389 migration of database data 347 migration of server data 346 migration with high availability 386 multiple sessions 353 number of sort buffers configuration 357 number of user connections configuration 356, 357 357 number of worker processes configuration object hierarchy 352 objects fail to migrate 388 output template resource file 362 permissions for 350 platforms 351 post-migration activities 378 post-migration procedures for replicated databases 380 pre-migration considerations 353 re-creating an object 389 release path 351

389 remigrating a database reports 277, 361 resource file mode 370 restoring replicate databases 381 restoring the primary database 380 setup session 352, 363 source Adaptive Server configuration 356 starting 359 sybmigrate log 383 syntax 360 trouble shooting and error messages 388 user-defined log file 362 352, 369 validate session version string 360 sybmigrate ,max network packet size configuration 357 sybmigrate utility command 276 defined 276 sybmigrate, max memory configuration 354 sybmigrate, what is not migrated 348 SYBMIGRATE\_MEMORY environment variable for migration 351 sybmultbuf, using to start Backup Server 121 symbols, field terminator (bcp) 69 syntax for sybmigrate 360 system data format (SDF) output in bcp 76 system procedure (sp\_dboption) 49

# Т

tab data field terminator (\) in interactive bcp 69 table rows copying in batches 84 length 55 tables bcp character set defaults 132 bcp prompts in 63 permission required for copying data into 42, 141 permission required to copy into operating system 42, 141 files utility commands 114 tabular data, copying 70 tabular output 76, 78 TCP/IP addresses for interfaces entries 109

terminators (bcp) 75 changing 61 defined 41 field and row, and 68,70 other programs, using for 69 text datatype interactive bcp and 66 125 trace flags and backupserver trace flags, for sybmigrate 362 Transact-SQL 10 using with isql transferring data from programs using bcp 40 transport Address server attribute (dscp) 93 transport Type server attribute (dscp) -93 triggers bcp, dropping before using 49 copying with defncopy 190 slowing down bcp 47 tables, copying data into 88 trouble shooting, for migration 388 troubleshooting dsedit 112

### U

unlogged transactions 47 upgrading Adaptive Server 231, 261 See also sqlupgrade utility command 261 upgrading Adaptive Server using resource files 262 See also sqlupgraderes utility command 262 use 343 utilities bulk copy (bcp) 44 utilities, other Adaptive Server, and bcp 88 utility commands special characters, using 114 table of commands 114

# V

validate session for **sybmigrate** 352 viewing interfaces files in GUI 197 See also dsedit utility command 197 views, copying, with defncopy 190

# W

warnings bcp data loss 49 bcp in data recovery 129 defncopy failure due to long comments 194

# Х

xd2 xd3 (enclosing special characters) 114 XP Server, starting manually 282, 283 See also xpserver utility command 282 xpserver utility command 282, 283 defined 282 permissions required for 283