

SYBASE®

Installation Guide

**Replication Server®**

15.2

[ Windows ]

DOCUMENT ID: DC32236-01-1520-01

LAST REVISED: February 2009

Copyright © 2009 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

To order additional documents, U.S. and Canadian customers should call Customer Fulfillment at (800) 685-8225, fax (617) 229-9845.

Customers in other countries with a U.S. license agreement may contact Customer Fulfillment via the above fax number. All other international customers should contact their Sybase subsidiary or local distributor. Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase trademarks can be viewed at the [Sybase trademarks page](http://www.sybase.com/detail?id=1011207) at <http://www.sybase.com/detail?id=1011207>. Sybase and the marks listed are trademarks of Sybase, Inc. ® indicates registration in the United States of America.

Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

All other company and product names mentioned may be trademarks of the respective companies with which they are associated.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568.

# Contents

<b>About This Book .....</b>	<b>v</b>	
<b>CHAPTER 1</b>	<b>Before You Begin .....</b>	<b>1</b>
	Introduction .....	1
	Replication Server components .....	1
	Installation task overview .....	2
	Licensing overview .....	2
	Pre-installation tasks .....	3
	Read the release bulletin .....	3
	Plan your replication system .....	3
	Review system requirements .....	3
	Understand the installation directory structure .....	5
	Perform administrative tasks .....	8
	Installing SySAM .....	9
<b>CHAPTER 2</b>	<b>Installing Replication Server .....</b>	<b>13</b>
	Using InstallShield for installation .....	13
	Installing Replication Server .....	15
	Installing in command line mode .....	20
	Troubleshooting installation .....	23
	Uninstalling Sybase products .....	23
<b>CHAPTER 3</b>	<b>Post-Installation Tasks .....</b>	<b>27</b>
	Review the log files .....	27
	Start Adaptive Server for the RSSD .....	28
	Start the sample Replication Server .....	28
	Set environment variables .....	29
	Start Replication Server .....	30
	Create a .bat file for Replication Server start-up .....	30
	Start Replication Server automatically .....	30
<b>CHAPTER 4</b>	<b>Installing Replication Manager .....</b>	<b>33</b>

Installing Replication Manager .....	33
Installing in GUI mode and console mode.....	33
Installing in command line mode .....	35
Checking for a valid installation.....	37
Uninstalling Replication Manager.....	38
<b>Index .....</b>	<b>41</b>

# About This Book

## Audience

This book is for System Administrators and other qualified installers who are familiar with their system's environment, networks, disk resources, and media devices.

## How to use this book

Before you install Replication Server®, read Chapter 1, “Preparing to Install and Configure Replication Server” in the *Replication Server Configuration Guide for Windows* to help you plan your installation. However, the step is unnecessary if you plan to install a sample Replication Server.

This guide contains these chapters:

- Chapter 1, “Before You Begin,” describes Replication Server pre-installation information and tasks.
- Chapter 2, “Installing Replication Server,” describes how to install Replication Server.
- Chapter 3, “Post-Installation Tasks,” provides information about the tasks you must perform after installing Replication Server.
- Chapter 4, “Installing Replication Manager,” describes how to install the Replication Manager.

## Related documents

The Sybase® Replication Server documentation set consists of:

- The release bulletin for your platform – contains last-minute information that was too late to be included in the books.

A more recent version of the release bulletin may be available on the World Wide Web. To check for critical product or document information that was added after the release of the product CD, use the Sybase Product Manuals at <http://www.sybase.com/support/manuals/>.

- *Installation Guide* for your platform (this book) – describes installation procedures for all Replication Server and related products.

- 
- *New Features Guide* – describes the new features in Replication Server version 15.2 and the system changes added to support those features.
  - *Administration Guide* – contains an introduction to replication systems. This manual includes information and guidelines for creating and managing a replication system, setting up security, recovering from system failures, and improving performance.
  - *Configuration Guide* for your platform – describes configuration procedures for all Replication Server and related products, and explains how to use the rs\_init configuration utility.
  - *Design Guide* – contains information about designing a replication system and integrating heterogeneous data servers into a replication system.
  - *Getting Started with Replication Server* – provides step-by-step instructions for installing and setting up a simple replication system.
  - *Heterogeneous Replication Guide* and the Replication Server Options documentation set – describes how to use Replication Server to replicate data between databases supplied by different vendors.
  - *Reference Manual* – contains the syntax and detailed descriptions of Replication Server commands in the Replication Command Language (RCL); Replication Server system functions; Sybase Adaptive Server® commands, system procedures, and stored procedures used with Replication Server; Replication Server executable programs; and Replication Server system tables.
  - *System Tables Diagram* – illustrates system tables and their entity relationships in a poster format. Available only in print version.
  - *Troubleshooting Guide* – contains information to aid in diagnosing and correcting problems in the replication system.
  - Replication Manager plug-in help, which contains information about using Sybase Central™ to manage Replication Server.
  - *Sybase Software Asset Management Users Guide* – this manual introduces you to Sybase asset management concepts and provides instructions for establishing and managing your license files.
  - *FLEXnet Licensing End User Guide* – this Macrovision manual explains FLEXnet Licensing for administrators and end users and describes how to use the tools which are part of the standard FLEXnet Licensing distribution kit from Sybase.

**Other sources of information**

Use the Sybase Getting Started CD, the SyBooks CD, and the Sybase Product Manuals Web site to learn more about your product:

- The Getting Started CD contains release bulletins and installation guides in PDF format, and may also contain other documents or updated information not included on the SyBooks CD. It is included with your software. To read or print documents on the Getting Started CD, you need Adobe Acrobat Reader, which you can download at no charge from the Adobe Web site using a link provided on the CD.
- The SyBooks CD contains product manuals and is included with your software. The Eclipse-based SyBooks browser allows you to access the manuals in an easy-to-use, HTML-based format.

Some documentation may be provided in PDF format, which you can access through the PDF directory on the SyBooks CD. To read or print the PDF files, you need Adobe Acrobat Reader.

Refer to the *SyBooks Installation Guide* on the Getting Started CD, or the *README.txt* file on the SyBooks CD for instructions on installing and starting SyBooks.

- The Sybase Product Manuals Web site is an online version of the SyBooks CD that you can access using a standard Web browser. In addition to product manuals, you will find links to EBFs/Maintenance, Technical Documents, Case Management, Solved Cases, newsgroups, and the Sybase Developer Network.

To access the Sybase Product Manuals Web site, go to Product Manuals at <http://www.sybase.com/support/manuals/>.

**Sybase certifications on the Web**

Technical documentation at the Sybase Web site is updated frequently.

**❖ Finding the latest information on product certifications**

- 1 Point your Web browser to Technical Documents at <http://www.sybase.com/support/techdocs/>.
- 2 Click Certification Report.
- 3 In the Certification Report filter select a product, platform, and timeframe and then click Go.
- 4 Click a Certification Report title to display the report.

**❖ Finding the latest information on component certifications**

- 1 Point your Web browser to Availability and Certification Reports at <http://certification.sybase.com/>.

- 
- 2 Either select the product family and product under Search by Base Product; or select the platform and product under Search by Platform.
  - 3 Select Search to display the availability and certification report for the selection.

❖ **Creating a personalized view of the Sybase Web site (including support pages)**

Set up a MySybase profile. MySybase is a free service that allows you to create a personalized view of Sybase Web pages.

- 1 Point your Web browser to Technical Documents at <http://www.sybase.com/support/techdocs/>.
- 2 Click MySybase and create a MySybase profile.

**Sybase EBFs and software maintenance**

❖ **Finding the latest information on EBFs and software maintenance**

- 1 Point your Web browser to the Sybase Support Page at <http://www.sybase.com/support>.
- 2 Select EBFs/Maintenance. If prompted, enter your MySybase user name and password.
- 3 Select a product.
- 4 Specify a time frame and click Go. A list of EBF/Maintenance releases is displayed.

Padlock icons indicate that you do not have download authorization for certain EBF/Maintenance releases because you are not registered as a Technical Support Contact. If you have not registered, but have valid information provided by your Sybase representative or through your support contract, click Edit Roles to add the “Technical Support Contact” role to your MySybase profile.

- 5 Click the Info icon to display the EBF/Maintenance report, or click the product description to download the software.

**Conventions**

This section describes the stylistic and syntactic conventions used in this book.

**Style conventions** Syntax statements (displaying the syntax and options for a command) are printed as follows:

```
alter user user
set password new_passwd
[verify password old_passwd]
```



Examples that show the use of Replication Server commands are printed as follows:

```
alter user louise
set password hFE5t
verify password hFE5t
```

Command names, command option names, program names, program flags, keywords, configuration parameters, functions, and stored procedures are printed as follows:

- Use `alter user` to change the password for a login name.
- Variables, parameters to functions and stored procedures, and user-supplied words are in italics in syntax and in paragraph text, as follows:

The `set password` *new\_passwd* clause specifies a new password.

- Names of database objects, such as databases, tables, columns, and datatypes, are in italics in paragraph text, as follows:

The `base_price` column in the `Items` table is a money datatype.

- Names of replication objects, such as function-string classes, error classes, replication definitions, and subscriptions, are in italics.

**Syntax conventions** Syntax formatting conventions are summarized in Table 1. Examples combining these elements follow.

**Table 1: Syntax formatting conventions**

Key	Definition
<i>variable</i>	Variables (words standing for values that you fill in) are in italics.
{ }	Curly braces mean you must choose at least one of the enclosed options. Do not include braces in the command.
[ ]	Brackets mean you may choose or omit enclosed options. Do not include brackets in the command.
	Vertical bars mean you may choose no more than one option (enclosed in braces or brackets).
,	Commas mean you may choose as many options as you need (enclosed in braces or brackets). Separate your choices with commas, to be typed as part of the command. Commas may also be required in other syntax contexts.
( )	Parentheses are to be typed as part of the command.
...	An ellipsis (three dots) means you may repeat the last unit as many times as you need. Do not include ellipses in the command.

### Obligatory choices

- 
- Curly braces and vertical bars – choose only one option.

```
{red | yellow | blue}
```

- Curly braces and commas – choose one or more options. If you choose more than one, separate your choices with commas.

```
{cash, check, credit}
```

### Optional choices

- One item in square brackets – choose it or omit it.

```
[anchovies]
```

- Square brackets and vertical bars – choose none or only one.

```
[beans | rice | sweet_potatoes]
```

- Square brackets and commas – choose none, one, or more options. If you choose more than one, separate your choices with commas.

```
[extra_cheese, avocados, sour_cream]
```

**Repeating elements** An ellipsis (...) means that you may repeat the last unit as many times as you need. For the alter function replication definition command, for example, you can list one or more parameters and their datatypes for either the add clause or the add searchable parameters clause:

```
alter function replication definition function_rep_def
{deliver as 'proc_name' |
add @parameter datatype[, @parameter
datatype]... |
add searchable parameters @parameter
[, @parameter]... |
send standby {all | replication definition}
parameters}
```

### Accessibility features

This document is available in an HTML version that is specialized for accessibility. You can navigate the HTML with an adaptive technology such as a screen reader, or view it with a screen enlarger.

Replication Server HTML documentation has been tested for compliance with U.S. government Section 508 Accessibility requirements. Documents that comply with Section 508 generally also meet non-U.S. accessibility guidelines, such as the World Wide Web Consortium (W3C) guidelines for Web sites.

---

**Note** You might need to configure your accessibility tool for optimal use. Some screen readers pronounce text based on its case; for example, they pronounce ALL UPPERCASE TEXT as initials, and MixedCase Text as words. You might find it helpful to configure your tool to announce syntax conventions. Consult the documentation for your tool.

---

For information about how Sybase supports accessibility, see Sybase Accessibility at <http://www.sybase.com/accessibility>. The Sybase Accessibility site includes links to information on Section 508 and W3C standards.

**If you need help**

Each Sybase installation that has purchased a support contract has one or more designated people who are authorized to contact Sybase Technical Support. If you cannot resolve a problem using the manuals or online help, please have the designated person contact Sybase Technical Support or the Sybase subsidiary in your area.



# Before You Begin

This chapter provides information about system and licensing requirements for installing Replication Server. It also discusses other pre-installation tasks you must complete before you install Replication Server.

<b>Topic</b>	<b>Page</b>
Introduction	1
Licensing overview	2
Pre-installation tasks	3

## Introduction

This section describes the components of Replication Server and provides an overview of the tasks involved in installing and setting up Replication Server.

## Replication Server components

Replication Server consists of the following components:

- Replication Server
- RepAgent for Adaptive Server Enterprise
- Replication Server support files (for example, scripts and configuration files)
- SQL Anywhere for Embedded Replication Server System Database (ERSSD)
- RepAgent for ERSSD
- Replication Monitoring Services (RMS)

## Installation task overview

The *Replication Server Installation Guide for Windows* explains how to unload the Replication Server software from the distribution media to your hard disk.

The *Replication Server Configuration Guide for Windows* explains how to:

- Gather the information you need to prepare your system for the installation
- Install Replication Servers and add databases to your replication system
- Upgrade existing Replication Server System Databases (RSSDs)
- Downgrade existing RSSDs and then reinstall an earlier version of the software
- Enable password encryption for a Replication Server or RepAgent
- Start and stop Replication Server or RepAgent

## Licensing overview

Replication Server works for a 30-day grace period without a license. You can use the Sybase Software Asset Management (SySAM) system that comes with Replication Server to register your Replication Server product.

Before you begin the installation, Sybase recommends that you get your license files from the Sybase Product Download Center (SPDC) at <https://sybase.subscribenet.com>, to which you are automatically enrolled in when you purchase a Sybase product. Log in to SPDC by using the information in your SPDC welcome e-mail.

---

**Note** If you have purchased your Sybase software from a Sybase reseller, you will receive a Web key rather than an e-mail message.

---

For information about SySAM 2, see the *Sybase Software Asset Management Users Guide*.

## Pre-installation tasks

Before you install Replication Server, follow the steps outlined in this section.

### Read the release bulletin

The release bulletin contains last-minute information about installing and upgrading Replication Server software.

Your Sybase products shipment includes printed release bulletins. They are also available on the Product Manuals Web page at <http://www.sybase.com/support/manuals>.

### Plan your replication system

The *Replication Server Configuration Guide for Windows* provides the necessary information, including an installation worksheet and a database setup worksheet to help you plan your replication system. Become familiar with Chapter 1, “Preparing to Install and Configure Replication Server” and the requirements of your replication system before continuing with the installation.

### Review system requirements

Replication Server requires a computer with the system configuration described in Table 1-1.

**Table 1-1: System requirements for Windows**

Item	Requirement
CPU	A Pentium processor.
RAM	A minimum of 512MB RAM.

Item	Requirement
Disk storage	<p>A minimum of 450MB of available hard disk space:</p> <ul style="list-style-type: none"> <li>• 400MB for the Replication Server software, supporting files, and log files.</li> <li>• 20MB for each Replication Server disk partition. The disk partition may be on a different disk than your Sybase software.</li> <li>• 30MB for temporary usage during installation.</li> </ul> <p>One of the following:</p> <ul style="list-style-type: none"> <li>• Disk space for your Adaptive Server Enterprise database, which serves as your Replication Server System Database (RSSD) if you are not using the Embedded RSSD (ERSSD). See your Adaptive Server Enterprise documentation for system requirements.</li> <li>• 80MB for your SQL Anywhere database, which serves as your ERSSD. The database directory, transaction log directory, and backup directory that make up the 80MB should each reside on different disks.</li> </ul> <p>More disk space may be required, depending on your replication system application.</p>
Operating system	<p>One of the following:</p> <ul style="list-style-type: none"> <li>• Windows XP Professional, Service Pack 2 or later</li> <li>• Windows 2003, Service Pack 2 or later</li> <li>• Windows Vista Enterprise, Service Pack 1</li> <li>• Windows Vista Business, Service Pack 1</li> <li>• Windows Server 2008</li> </ul>
Additional hardware	<p>A minimum of 32-bit network card for better performance.</p>
Supported protocols	<p>TCP/IP, IPX/SPX, Microsoft Named Pipes.</p>

## Review operating system patch requirements

If your operating system requires a service pack, install it before you install Replication Server. Contact your operating system representative for a complete list of service packs, or check the latest Replication Server release bulletin for your platform. First, you must determine which service pack operating system level and build number are installed on the system.

---

**Note** Do not use a service pack that is earlier than the version suggested for your operating system. If a service pack has been superseded by a newer service pack, use the newer service pack.

---

### ❖ Determining service pack operating system level and build number

- 1 Select Start | Programs | Accessories | Windows Explorer.



- 2 Select the Help menu, and click About Windows.
- 3 Find the Service Pack number on the Version line.

In the following example, *xxxx* is the build number and *n* is the service pack number:

```
Version 5.0 (Build xxxx: Service Pack n)
```

## Understand the installation directory structure

Most components of Replication Server are installed in their own subdirectories, with the executable program, installation and configuration tools, and display-related files needed by the component. The naming convention for subdirectories includes a component identifier, such as REP (for Replication Server) or OCS (for Open Client™ and Open Server™), and the software release version, such as 15\_2.

Replication Server 15.2 includes a new version of Replication Server and many of its supporting components. Other Sybase products may contain earlier versions of the same components. Installing Replication Server 15.2 into the same directory containing these existing products, will not impact the products.

However, if you are using other Sybase products, installing Replication Server 15.2 may cause some environment variables to change. You will have to reset the environment variables in order to make the individual products work.

---

**Note** Replication Server 15.2 may be installed in the same directory as Adaptive Server Enterprise and Open Client and Open Server versions 12.5.1 or later.

---

You can install Replication Server 15.2 on top of Replication Server 12.6, in the same `%SYBASE%` directory. Installing 15.2 on top of Replication Server 12.6 will create a duplicate entry in the interfaces file for `SAMPLE_RS`, which is the sample Replication Server. `rs_init` will warn you about the duplicate entry and will use the first instance of `SAMPLE_RS` found in the interfaces file.

---

**Warning!** Do not install Replication Server version 15.2 on top of the following Sybase products:

- Replication Server version 12.5 or earlier
- Adaptive Server version 12.5.0.x or earlier
- Open Client and Open Server version 12.5.0 or earlier
- OpenSwitch version 12.5 or earlier
- DirectConnect™ version 12.5 or earlier

Doing so incapacitates older versions of these products, and can also adversely affect other Sybase products. If you perform one of these installations, you cannot reverse it with an uninstallation, as uninstalling might remove required components of the older Sybase products updated by Replication Server version 15.2. For this reason, Sybase recommends that you back up your current directory before installing Replication Server version 15.2.

---

**Note** If you are installing Replication Server 15.2 in an existing Sybase installation directory that contains Adaptive Server version 15.0.x, you may be asked if you wish to install older locales or charset files on top of newer files. To ensure that you have the latest version of these files select “No to all.”

---

Shared components are installed in subdirectories that are separate from component subdirectories. For example, the Replication Server subdirectory is `%SYBASE%\REP-15_2`. However, Open Client is installed in `$SYBASE/OCS-15_0`. The exception is SQL Anywhere (SA), which is installed in `%SYBASE%\REP-15_2\ASAll`, because it is used only for Replication Server. As a result, the directory structure enables you to install into an existing `%SYBASE%` directory structure, as well as to install and use multiple versions of some components.

---

**Note** If your earlier installation includes custom applications or scripts that refer to `%SYBASE%` subdirectories, change them to reflect the new installation directory structure.

---

A diagnostic server `REP-15_2\bin\drepsrvr.exe` is installed to capture and display information about internal processes. Do not delete this program as you may need to use it at the direction of Sybase Technical Support, to diagnose and resolve Replication Server problems.

---

**Note** The directory structure listed in this section is a partial directory structure. Your actual directory structure may differ, depending on the components you choose to install.

---

## Review the Sybase installation directory contents

The section lists the contents of the Sybase installation directory in alphabetical order.

### Installation directory after installing Replication Server

The following items are installed on your machine.

Within `%SYBASE%`:

- *charsets* – character sets and sort order.
- *collate* – Unicode.
- *ini* – initialization files, including *objectid.dat*, *mnemonic.dat*, *sql.ini*, and *trusted.txt*.
- *locales* – localization files for Open Client and Open Server, and other components used by Replication Server. Does not include Replication Server specific localization files.

- *log.txt* – the log of the installation process.
- *OCS-15\_0* – Open Client and Open Server directories and files, including *bin*, *dll*, *include*, *ini*, *lib*, *lib3p*, *sample*, and scripts.
- *REP-15\_2* – Replication Server 15.2 files, including *ASAI1*, *bin*, *certificates*, *doc*, *locales*, *init*, *install*, *samp\_repsrver*, *scripts*, *sysam*, *ThirdPartyLegal*, and *upgrade*.
- *Shared* – common components shared across products, including the Java runtime environment and files and directories for Unified Agent Framework 2.0.
- *SYBASE.bat*, *SYBASE.env* – files created by InstallShield that you use to reset environment variables.
- *SYSAM-2\_0* – software license manager files, including *bin*, licenses, and *log*.
- *\_jvmrep* – files used by InstallShield.
- *uninstall* – files used by InstallShield to uninstall Replication Server software.
- *UAF-2\_0* – the Unified Agent Framework files for the Replication Monitoring Services (RMS), including *auth*, *common*, *ldap*, *log*, *plugins*, *server*, *services*, *bin*, *conf*, *rllib*, *utility*, *thirdparty*, *shared*, and *uaservice*.
- *vpd.properties* – used by InstallShield to keep track of version of installed and uninstalled software. The *vpd.properties* file gets installed in the *%WINDIR%* directory.

---

**Warning!** Do not modify or remove *vpd.properties*. Modifying or removing this file prevents InstallShield from accurately managing installed component versions when you install or uninstall Sybase software subsequent to this installation.

---

## Perform administrative tasks

This section describes administrative tasks that you must complete before you begin the installation process.

- 1 Back up your current replication system.
- 2 Log in using an account with Windows administrator privileges.

- 3 Close any open applications or utilities, including currently installed Sybase components, to free disk space and system resources.
- 4 Verify that the installation directory does not have a space in the directory name.

## Installing SySAM

Before you install Replication Server, you must plan the type of SySAM license configuration you want to use. Depending on your configuration choice, you may also need to perform additional pre-installation tasks before installing Replication Server.

SySAM allows you to acquire a license using a local file or you can acquire a license from a network license server. For more information about SySAM licensing concepts and choosing a license model, see the *Sybase Software Asset Management Users Guide*.

---

**Note** There can only be one instance of a SySAM license server running on a machine. To set up a SySAM 2 license server on a machine that is already running SySAM 1.0, migrate the SySAM 1.0 license to SySAM 2. A migrated license server can serve licenses for products that are licensed under both SySAM 1.0 and SySAM 2.

For instructions on migrating a license server, see the *Sybase Software Asset Management Users Guide*.

---

### ❖ Installing a new license server

- 1 Insert the CD into the CD drive. The Installer should start automatically. If it does not, start the setup program manually by selecting Start | Run. Browse to *setup.exe*.
- 2 Launch the Sybase installer program by entering:  

```
setup
```
- 3 The Welcome Window displays. Click Next.
- 4 Accept the license agreement.
- 5 Enter or select the destination directory.
- 6 Select the custom installation. A list of components that you can install are displayed.

- 7 Select Sybase Software Asset Management License Server License Server for installation and unselect the other components so that only the Net License Server is installed.
- 8 Click Next to view the summary page.
- 9 Click Next for the installer to install SySAM licensing tools.
- 10 Get the host ID for the machine on which the new license server will run. To get the host ID:

- Open a Command Prompt window and go to `%SYBASE%\SYSAM-2_0\bin` where `%SYBASE%` is the Sybase installation directory.
- Enter:

```
lmutil lmhostid
```

---

**Note** If your machine has multiple network adapters, `lmutil lmhostid` returns host IDs associated with each adapter. Choose one of the IDs. Avoid using IDs for removable network adapters.

---

- Save the host ID to use at the Sybase Product Download Center.
- 11 Go to the Sybase Product Download Center (SPDC) at <https://sybase.subscribenet.com>.
  - 12 Get the license you want to install. See the *Sybase Software Asset Management Users Guide* for more information about acquiring and using your license.
  - 13 Copy the license file in the licenses directory `%SYBASE%\SYSAM-2_0\licenses` on the network license server machine.
  - 14 Start the SySAM network license server:

- In a Command Prompt window, go to:  
`%SYBASE%\SYSAM-2_0\bin`
- Enter:

```
sysam start
```

Or, start the license server from the Windows Services panel (Start | Settings | Control Panel | Administrative Tools | Services).

- 15 Validate that the license daemon is running by entering:

```
sysam status
```

For more information about license server administration, see the *Sybase Software Asset Management Users Guide*.





# Installing Replication Server

This chapter describes how to install the Replication Server using InstallShield.

Topic	Page
Using InstallShield for installation	13
Installing Replication Server	15
Uninstalling Sybase products	23

---

**Note** When you have completed the installation instructions in this chapter, return to the *Replication Server Configuration Guide for Windows* to begin customizing your newly installed Replication Server.

---

## Using InstallShield for installation

When you first install a Sybase product, InstallShield creates a Sybase installation directory, if it does not already exist, which contains the support files for all Sybase products.

When you install Replication Server using InstallShield, its software and support files are stored in the Sybase installation directory. You can install all Sybase software in the same installation directory.

---

**Warning!** Do not install Replication Server into an existing Adaptive Server Enterprise 12.x (64-bit) directory. This may cause some localization (*.loc*) files to be overwritten, resulting in problems with starting Adaptive Server Enterprise.

---

InstallShield is Java-based, so the installation process is similar on both UNIX-based and Windows-based computers.

InstallShield enables you to:

- Install all Replication Server components. You can choose the installation option that works best for you:
  - Typical (default) – installs the Replication Server components considered to be useful for most customers. In this type of installation, only the U.S. English language module and its supported character sets are installed. The components that will be installed and the total disk space required display prior to installation.
  - Full – installs every Replication Server component including all the supported language modules from the CD. The components that will be installed and the total disk space required display prior to installation.
  - Custom – allows you to select the components to install. Recommended for advanced users. When you select Custom install, the next window displayed is the Component Selection window, which allows you to select the components to install.

---

**Note** Certain components are automatically installed if they are required to run other selected components.

---

- Easily view software release version and properties for components on the installation CD.
- Uninstall all Replication Server 15.2 components.

In addition, InstallShield:

- Automatically sets most of the environment variables needed for Replication Server products.
- Creates the *SYBASE.bat* and *SYBASE.env* batch files. You can later use these files to reset environment variables after exiting InstallShield and before configuring Replication Server. See “Set environment variables” on page 29.
- Starts the sample Replication Server when the installation process is complete, if you installed the defaults.
- You must manually start other components, such as Replication Monitoring Services, and the license manager, if needed.

If you did not install the defaults, follow the instructions in the *Replication Server Configuration Guide for Windows* to start, then configure Replication Server.

# Installing Replication Server

Follow the procedures in this section to install Replication Server components.

## ❖ Installing Replication Server components

- 1 Choose one of the following installation modes:
  - Graphical user interface (GUI) – lets you install the components using the InstallShield interface.
  - Console – lets you install components in a command line environment.
  - Response file – lets you record or create a response file. You can install Replication Server in two different ways using a response file:
    - Silent – lets you save the installation settings in a response file and install the product without any interaction required on your part. This is convenient if you are performing identical installations on multiple machines.
    - Console installation using response file – lets you install in console mode but with all the responses already filled in, so that you can accept all the defaults and install Replication Server according to the responses in the response file. This can be convenient if several sites are installing Replication Server in a nongraphical user interface environment and must conform to a standard installation with minor changes.

---

**Note** If you encounter problems during installation, check the installation log file to see a record of the installation process. The file is located in `%SYBASE%\log.txt`, where `%SYBASE%` is the Replication Server installation directory.

---

- 2 Verify that the drive on which you install the products has enough disk space for the products being installed.

Set the TEMP environment variable to a temporary directory, such as `c:\temp`. The installation program uses the extra space and directory to write files temporarily during the installation. The installation program frees this space after the installation is complete.

## ❖ Installing in GUI mode

- 1 Insert the Replication Server CD in the CD drive.  
InstallShield starts automatically.

- 2 If it does not, double-click *setup.exe* or select Start | Run, and enter the following, where *x*: is your CD drive:

```
x:\setup.exe
```

You might see the following error message:

```
Error writing file = There may not be enough
temporary disk space. Try using -is:tempdir to use a
temporary directory on a partition with more disk
space.
```

If so, set the temporary directory to another directory that has more disk space by entering the following at the command line, where *directory\_name* is the name of the temporary directory to which InstallShield will write its temporary files:

```
setup.exe -is:tempdir directory_name
```

This directory should have at least 100MB of disk space.

- 3 Select Next.
- 4 Choose your geographic location in the license and copyright agreement window.
- 5 Read the Sybase license agreement and select “I agree.” Click Next. You must agree to the license and copyright before you can continue.
- 6 In the install directory window, click Next to accept the default directory for the installation (*c:\sybase*), or enter a different directory name.
- 7 If the installation directory you chose does not exist, InstallShield prompts:

```
The directory does not exist. Do you want to create it?
```

- 8 Click Yes. If the installation directory you selected exists, and contains a prior installation, InstallShield prompts you with the following message:

```
You have chosen to install into an existing
directory. Any older versions of the products you
choose to install that are detected in this directory
will be replaced. Do you want to continue with
installation into this directory?
```

Click Yes if you wish to install on top of the previous installation. If the products were previously installed with:

- Studio Installer (for example, if you installed a version of Replication Server earlier than 12.6 or a version of Adaptive Server earlier than 12.5.1), InstallShield overwrites common components.
- InstallShield, the correct course of action is determined by InstallShield without prompting you.

If you are prompted to overwrite a DLL, select Yes only if the version of the new DLL is later than the one InstallShield is attempting to overwrite.

9 Select the type of installation:

- If you choose Full or Typical, InstallShield displays the following default components:
  - Sybase Servers – Replication Server
  - Connectivity
  - Language Modules for Replication Server
  - Language Modules for Connectivity
  - Shared
  - Sybase Software Asset Management
  - Sybase Unified Agent
- If you choose Custom, select the components to install. Certain components are automatically installed if they are required to run your selected components.

Click next. InstallShield displays a summary page showing the installation directory and the Replication Server components that you chose to install.

10 Click Next. InstallShield displays a progress indicator as it installs the components.

If you do not have enough disk space for the installation, InstallShield displays an error message. In this case, exit InstallShield, remove any programs or files that you do not need, and clean out temporary directories. Restart InstallShield.

11 On successful installation, InstallShield displays the following message:

The InstallShield Wizard has successfully installed Replication Server Software, Version 15.2. Choose next to continue the wizard.

- 12 Click Next. The SySAM License Server window opens and displays this prompt:

Will licenses be obtained from the License Server?

- Select Yes if you have a preexisting SySAM network license server installed or install a new license server using “Installing a new license server” on page 9.

Enter the host name and the port number of the license server.

- Select No if you do not have a SySAM license server installed and are going to use a local license file. Click Next. This message is displayed:

Please remember to download and install the license file after this installation.

---

**Note** See the *Sybase Software Asset Management Users Guide* for information on which license model is appropriate for your installation.

---

- 13 Click Next. The SySAM Notification window asks you to configure your server for e-mail notification. When configuration is enabled, you will receive information about license management events requiring attention.

- SMTP server host name
- SMTP server port number
- E-mail Return Address
- Recipient e-mail addresses
- Message severity that triggers e-mail messages

- 14 On the sample Replication Server option window, select:

- Yes – to configure and start a sample Replication Server. InstallShield displays the configuration information for the sample Replication Server. Write this information down.
- No – to complete the installation and configure a fully-featured Replication Server manually.

If you select No, you can configure and start a sample Replication Server after installation. See “Start the sample Replication Server” on page 28 for more information.

- 15 Click Next. If you chose to configure and start a sample Replication Server, InstallShield displays the configuration information related to the sample Replication Server:

This page contains detailed information regarding the sample Replication Server. Please record this information.

The sample Replication Server will be called `SAMPLE_RS` and will run on port 11752. It will be configured with a user of `sa` and no password.

The sample Replication Server will use an embedded RSSD called `SAMPLE_RS_ERSSD` that runs on port 11751. It will be configured with a user of `SAMPLE_RS_RSSD_prim` and a password of `SAMPLE_RS_RSSD_prim_ps`.

The installer has updated the appropriate interfaces file or `sql.ini` file.

All files and logs associated with the sample Replication Server will be located in the directory `%SYBASE%\REP-15_2\samp_repserver`.

The sample Replication Server will be configured using the file `%SYBASE%\REP-15_2\samp_repserver\SAMPLE_RS.res`.

- 16 Click Next. The Configure New Replication Server window displays the progress of the server configuration.
- 17 Click Next. The Installation Completed window appears, verifying that the Replication Server software is now installed.

If you chose to start a sample Replication Server, it is started automatically. If you did not choose to start a sample Replication Server, you must configure and then start your Replication Server manually.

See the *Replication Server Configuration Guide for Windows* for information about configuring your new Replication Server.

- 18 Click Finish. The InstallShield wizard closes.

#### ❖ **Installing in console mode**

The steps for installing components in an interactive text mode are the same as those described in “Installing in GUI mode” on page 15, except that you execute InstallShield from the command line using the `setup -console` command, and you enter text to select installation options.

- 1 Insert the CD into the CD drive. The InstallShield wizard starts.
- 2 Click Cancel. InstallShield closes.
- 3 Open a DOS window and change to the CD drive.

- 4 At the command line, enter:

```
setup.exe -console
```

InstallShield starts and displays the welcome window as follows:

```
-----  
Welcome to the InstallShield Wizard for Sybase  
Replication Server Software, Version 15.2.
```

```
The InstallShield Wizard will install Replication  
Server Software, Version 15.2 on your computer.
```

```
To continue, choose Next.
```

```
Press 1 for Next, 3 to Cancel or 4 to Redisplay [1]  
-----
```

- 5 Follow the remaining prompts to install Replication Server software.

## Installing in command line mode

This section discusses the various installation methods available to you from the command line.

---

**Note** If the environment variable %SYBASE% is set, the installer uses it as the default directory for installation. However, you can explicitly specify a different directory during the installation process to override %SYBASE%.

---

## Installing with a response file

You can install Replication Server using a response file in combination with a console or silent installation. You must first create the response file.

---

**Note** You must provide the absolute path name for the response file you create.

---

To create a response file, do one of the following at the command line:

- Enter the following command, where *REP.response* is name you choose for the response file:



```
setup.exe -options-template REP.response
```

InstallShield creates an options template called *REP.response*. Edit the template with the values you want to use during installation.

- Enter the following command at the command line, where *REP.response* is a name you choose for the response file:

---

**Note** You must provide the absolute path name for the response file you create.

---

```
setup.exe -options-record REP.response
```

InstallShield runs the installation in GUI mode and captures all user choices to a file called *REP.response*. You can also specify the `-console` option to get the same results.

You can use *REP.response* for future installations of Replication Server, either as is or edited for the new installation.

#### ❖ Editing the response file

- 1 Specify the installation location, where *path* is the full path and file name:

```
-P installLocation=path
```

Do not use special characters for the path name, such as blanks or periods.

- 2 Specify the setup type, where *installation\_type* specifies the type of installation (Full, Typical, or Custom):

```
-W setupTypes.selectedSetupTypeId=installation_type
```

If you specify either the Full or Typical installation, you do not need to uncomment the individual features; these features have been predefined as installed.

If you choose the Custom installation, you must uncomment the desired features and set their values to “true.”

- 3 The last line in the response file allows you to specify if you want to start a sample Replication Server. You must uncomment this line and specify either “yes” or “no” (case sensitive; use all lowercase):

```
-W ConfigureReplicationServer.Yes-or-No="no"
```

## Installing in console mode with a response file

A console mode installation using a response file lets you accept all defaults as you move through an interactive text installation, because the values come from a response file that you have set up.

Follow the same steps as you would for a regular console installation, but at the command line, enter:

```
setup.exe -console -options REP.response  
-W SybaseLicense.agreeToLicense=true
```

## Installing in silent mode

A silent mode installation, sometimes referred to as an unattended installation, allows you to install the product using a response file to set default values, without any interaction required on your part. Installing in silent mode is useful when you want multiple identical installations or when you want to automate the installation process.

Follow the same steps as you would for a console installation, but at the command line, enter:

```
setup.exe -silent -options REP.response  
-W SybaseLicense.agreeToLicense=true
```

Or:

```
setupConsole.exe -silent -options REP.response  
-W SybaseLicense.agreeToLicense=true
```

Where:

- *REP.response* – is the name of the file containing the installation options you chose.
- `-W SybaseLicense.agreeToLicense=true` – specifies that you agree with the Sybase License Agreement text.

---

**Note** When running in silent installation mode, Sybase recommends that you use *setupConsole.exe*. *setup.exe* runs in the background, and gives the impression that the installation has terminated immediately. This results in additional installation attempts. Multiple installations at the same time can corrupt the Windows Registry and lead to an operating system restart failure.

---

## Checking for a valid installation

- 1 View the `%SYBASE%\log.txt` file and check for errors. A valid installation does not contain the word “error.”
- 2 Verify that the `vpd.properties` file has been written in the `%WINDIR%` directory.
- 3 Check that the date of the `vpd.properties` file reflects the date of this current installation.

## Troubleshooting installation

For troubleshooting during GUI, console, or silent mode installation using an option file, enter the following at the command line where `ERROR.log` is the name of the log that will capture events specific to the console or silent mode installation:

```
setup.exe -silent -options REP.response -W SybaseLicense.agreeToLicense=true  
-is:log ERROR.log -is:javaconsole
```

Or:

```
setupConsole.exe -silent -options REP.response -W  
SybaseLicense.agreeToLicense=true is:log ERROR.log -is:javaconsole
```

The `-is:log` parameter creates an `ERROR.log` log file, and the `-is:javaconsole` parameter causes errors to be written to the screen.

---

**Note** If you encountered errors during installation using any installation mode, check the installation log file to see a record of the installation process. The log file is located in `%SYBASE%\log.txt`.

---

If this is the first time you have installed a Sybase product on this machine, InstallShield creates a Sybase installation directory. This directory contains the support files for all Sybase products.

## Uninstalling Sybase products

InstallShield includes an uninstall feature that removes the Sybase components you have installed.

You can invoke the uninstall procedure using either GUI or console methods. Sybase recommends that you use the GUI method.

Before uninstalling Sybase software, log on to your machine using an account with administrator privileges, then shut down Replication Server, SySAM, and all other processes for the components you are uninstalling.

---

**Note** InstallShield removes only those files that were loaded from the installation media. Some Sybase files, such as log and configuration files, are left intact for administrative purposes. `_jvmrep` and other installed directories are also not removed by InstallShield. You must remove these directories manually.

---

### ❖ Uninstalling in GUI mode

1 To uninstall in GUI mode, choose one of the following methods:

- From the Start menu, select Settings | Control Panel | Add/Remove Programs.

- From the command line, enter:

```
%SYBASE%\uninstall\REP\uninstall.exe
```

- Click Start | Run and then enter:

```
%SYBASE%\uninstall\REP\uninstall.exe
```

- Open Windows Explorer, and navigate to `uninstall.exe` and double-click it.

The Uninstaller window opens.

2 Click Next.

3 Select the product you want to remove from the list, then click Next.

4 Verify the summary information, then click Next.

The uninstaller removes the files associated with the software.

5 Click Finish.

---

**Note** You may be prompted to decide whether to remove shared files. Sybase recommends that you do *not* remove shared files.

---

### ❖ Uninstalling in console mode

1 Go to the `%SYBASE%` directory. To uninstall:

- Replication Server software, at the command line, enter:

```
%SYBASE%\uninstall\REP\uninstall.exe  
-console
```

The uninstaller program starts.

- 2 Choose the Replication Server software product you want to uninstall.

The Replication Server software product you chose and its associated files are removed.

---

**Note** You may be prompted to decide whether to remove shared files. Sybase recommends that you do not remove shared files.

---



This chapter describes the post-installation tasks that you need to perform after installing the Replication Server software.

For more information, see the *Replication Server Configuration Guide for Windows*.

Topic	Page
Review the log files	27
Start Adaptive Server for the RSSD	28
Start the sample Replication Server	28
Set environment variables	29
Start Replication Server	30

## Review the log files

Information about the configuration of Replication Server is stored in the following log files:

- InstallShield error log file:  
`%SYBASE%\log.txt`
- SQL Anywhere error logs:  
`%SYBASE_REP%\samp_repserver\errorlog\`
- rs\_init log file:  
`%SYBASE%\%SYBASE_REP%\init\logs\logmdd.xxx`  
For example: `%SYBASE%\%SYBASE_REP%\init\logs\log1106.001`
- Replication Server log file:  
`%SYBASE%\%SYBASE_REP%\install\rs_name.log`  
For example:  
`%SYBASE%\%SYBASE_REP%\install\REP_redtail.log`

## Start Adaptive Server for the RSSD

To use the RSSD stored on Adaptive Server Enterprise, install the Adaptive Server Enterprise database, if you have not done so already. For installation instructions, see the *Adaptive Server Enterprise Installation Guide* for your platform.

After successful installation, start Adaptive Server Enterprise. For more information, see the *Adaptive Server Enterprise Configuration Guide* for your platform.

---

**Note** If you are upgrading to a later version of Adaptive Server Enterprise and you have replicated databases, see the *Adaptive Server Enterprise Installation Guide* for your platform.

---

## Start the sample Replication Server

During installation, InstallShield asks if you want to configure and start a sample Replication Server. Regardless of your choice, InstallShield creates a resource file, `%SYBASE%\REP-15_2\samp_repserver\SAMPLE_RS.res`, for the sample Replication Server and updates the `sql.ini` file. If you selected No, you can still configure and start the sample Replication Server after installation using this resource file.

To create and start the sample Replication Server after installation, at the command prompt, enter:

```
%SYBASE%\REP-15_2\install\rs_init -r  
%SYBASE%\REP-15_2\samp_repserver\SAMPLE_RS.res
```

A setup window displays the status of configuration and the `rs_init` utility displays commands in the DOS window as it executes them, then writes this output to its log.

If you encounter errors during configuration and start-up of the sample Replication Server, you can read this log file, `%SYBASE%\REP-15_2\init\logs\logmdd.xxx`, where:

- `mm` – is the month.
- `dd` – is the day.



- *xxx* – is the number of that instance of the log on that day.

The sample Replication Server is configured using the *SAMPLE\_RS.res* resource file. All files and logs associated with the sample Replication Server are in the directory *%SYBASE%\REP-15\_2\samp\_repserver*.

Table 3-1 contains the sample Replication Server configuration information. Keep this information in a safe place for later reference.

**Table 3-1: Sample Replication Server configuration information**

Sample Replication Server item	Definition
Name	<i>SAMPLE_RS</i>
Port	11752
User name	<i>sa</i>
Password	None
ERSSD server name	<i>SAMPLE_RS_ERSSD</i>
ERSSD server port	11751
ERSSD user name	<i>SAMPLE_RS_RSSD_prim</i>
ERSSD password	<i>SAMPLE_RS_RSSD_prim_ps</i>

For more information about *rs\_init*, see Chapter 2, “Configuring Replication Server and Adding Databases with *rs\_init*,” in the Replication Server Configuration Guide for Windows.

## Set environment variables

InstallShield automatically sets system environment variables that are needed by InstallShield, such as *PATH*, as well as additional environment variables required by your newly installed Sybase software. InstallShield installs two files that contain these environment variables:

- *%SYBASE%\SYBASE.bat*
- *%SYBASE%\SYBASE.env*

After exiting InstallShield, you can reset the environment variables using these files, if needed.

Table 3-2 describes the environment variables.

**Table 3-2: Environment variables for Windows**

Environment variable	Description
%LM_LICENSE_FILE%	The subdirectory path to the <i>license.dat</i> file, which SySAM needs to run the license manager.
%PATH%	The directory path to Replication Server files.
%SYBASE%	The home directory where you install all Sybase products.
%SYBASE_JRE6%	The subdirectory path to the Java Runtime Environment (JRE) resides.
%SYBASE_JRE6_32%	The subdirectory path to the Java Runtime Environment (JRE) resides.
%SYBASE_OCS%	The subdirectory path to Open Client files.
%SYBASE_REP%	The subdirectory path to Replication Server.
%SYBASE_UA%	The subdirectory path to the Unified Agent Framework and Replication Monitoring Services.

## Start Replication Server

This section explains how you can start Replication Server by executing a batch file.

### Create a *.bat* file for Replication Server start-up

To create a *.bat* file for Replication Server, insert the contents of the *x:\InstallDirectory\SYBASE.bat* file at the beginning of the *x:\InstallDirectory\REP-15\_2\install\RUN\_servername.bat* file, where:

- *x* is the drive name.
- *InstallDirectory* is the name of the installation directory.
- *servername* is the name of your Replication Server.

When you execute the *.bat* files, you set all environment variables for Replication Server to use the unique Replication Server product directory.

### Start Replication Server automatically

To start Replication Server automatically when you restart the system:

- Go to *C:\Documents and Settings\adminuser\Start Menu\Programs\Startup*.
- Add a new shortcut for *x:\InstallDirectory\REP-15\_2\install\RUN\_servername.bat*, where:
  - *x* is the drive name.
  - *InstallDirectory* is the name of the installation directory.
  - *servername* is the name of your Replication Server.

Replication Server now starts automatically after you restart the system.



# Installing Replication Manager

This chapter describes how to install and uninstall the Replication Manager.

Topic	Page
Installing Replication Manager	33
Checking for a valid installation	37
Uninstalling Replication Manager	38

## Installing Replication Manager

Follow the procedures in this section to install the Replication Manager. Similar to the Replication Server installation, you will use InstallShield to install the Replication Manager. For more information about InstallShield, see “Using InstallShield for installation” on page 13.

### Installing in GUI mode and console mode

This section discusses the installation procedure from the GUI and console modes.

#### ❖ Installing in GUI mode

- 1 Insert the Replication Management DVD into the DVD drive.
- 2 Double-click `setupwin32.exe` or select Start | Run, and enter the following, where x: is your DVD drive:

```
x:\setupwin32.exe
```

- 3 The Welcome window appears. Click Next.

- 4 The License and Copyright Agreement window appears. Read the License and Copyright Agreement. Using the drop-down list at the top of the window, select the geographic location where you are installing to display the agreement appropriate to your region. Select “I agree” and click Next.

---

**Note** You must agree to the license and copyright agreement before you can continue.

---

- 5 If Sybase Central 6.0 has not been installed on your machine, the Choose Directory window appears. Enter the directory path for the installation, where the default path is *C:\Program Files\Sybase*. Click Next.
- 6 If Sybase Central 6.0 is already installed on your machine, the Sybase Central Already Installed window appears. Select one of the two types of installation:

- (Recommended) Register with your existing Sybase Central. Click Next.

This type of installation will install the Replication Manager plug-in and register it with the existing Sybase Central application.

- Install a new version of Sybase Central into a new directory and render the other installation invalid. The Choose Directory window appears to allow you to enter a new directory path. Click Next.

This type of installation will install Replication Manager, as well as all the other necessary components.

---

**Note** This option will make your current Sybase Central installation invalid.

---

- 7 A Summary window appears and lists all the features that you are going to install. Click Next.
- 8 The installation process begins and a Setup window appears. The Setup window shows the percentage (%) of installation that is complete and monitors the decompressing and installing of the Replication Manager files. The installation will register the plug-in with Sybase Central. Click Next.
- 9 A status window appears, showing the Sybase Central registration process. Click Next.
- 10 When installation is completed, click Finish to clear the window.

**❖ Installing in console mode**

The steps for installing components in an interactive text mode are the same as those described in “Installing in GUI mode” on page 33, except that you execute InstallShield from the command line using the `setup -console` command, and you enter text to select installation options.

- 1 Open a DOS window and change to the CD drive.
- 2 At the command line, enter:

```
setupwin32.exe -console
```

InstallShield starts and displays the welcome window as follows:

```
-----  
  
Welcome to the InstallShield Wizard for Sybase  
Replication Manager Version 15.2.  
  
The InstallShield Wizard will install Sybase  
Replication Manager Version 15.2 on your computer.  
  
To continue, choose Next.  
  
Press 1 for Next, 3 to Cancel or 4 to Redisplay [1]  
  
-----
```

- 3 Follow the remaining prompts to install Replication Manager.

## Installing in command line mode

This section discusses the various installation methods available to you from the command line.

### Creating a response file

You can install Replication Manager using a response file in combination with a console or silent installation. You must first create the response file.

---

**Note** You must provide the absolute path name for the response file you create.

---

To create a response file, do one of the following at the command line:

- Enter the following command, where *RMP.response* is the name you choose for the response file:

```
setupwin32.exe -options-template RMP.response
```

InstallShield creates an options template called *RMP.response*. Edit the template with the values you want to use during installation.

- Enter the following command at the command line, where *RMP.response* is a name you choose for the response file:

---

**Note** You must provide the absolute path name for the response file you create.

---

```
setupwin32.exe -options-record RMP.response
```

InstallShield runs the installation in GUI mode and captures all user choices to a file called *RMP.response*. You can also specify the `-console` option to get the same results.

You can use *RMP.response* for future installations of the Replication Manager, either as is or edited for the new installation.

### ❖ Editing the response file

- 1 Specify the installation location, where *path* is the full path and file name:

```
-P installLocation=path
```

Do not use special characters for the path name, such as blanks or periods.

- 2 The setup type is only used when Sybase Central is already installed on the target machine, where *installation\_type*—`ADD_TO_EXISTING_SC` or `CREATE_NEW_SC_INSTALL`—specifies the type of installation:

```
-W  
ExistingWindowsSC60SelectionBean.selectSetupTypeId  
=installation_type
```

If you want to install into the location where the existing Sybase Central is located, specify `ADD_TO_EXISTING_SC`. If you want to install into a new location other than the existing Sybase Central location, specify `CREATE_NEW_SC_INSTALL`.

- 3 Specify the Shared JRE Location path for the appropriate platform where the installation is performed. The path must be the same as the `installLocation` setting. For example:

```
-P installLocation=C:\Sybase
```



```
-W SCPluginRegisterWinBean.sharedJreLocation=  
C:\Sybase\Shared\JRE_6_0_0
```

## Installing in console mode with a response file

A console mode installation using a response file lets you accept all defaults as you move through an interactive text installation, because the values come from a response file that you have set up.

Follow the same steps as you would for a regular console installation, but at the command line, enter:

```
setupwin32.exe -console -options RMP.response  
-W SybaseLicense.agreeToLicense=true
```

## Installing in silent mode

A silent mode installation, sometimes referred to as an unattended installation, allows you to install the product using a response file to set default values, without any interaction required on your part. Installing in silent mode is useful when you want multiple identical installations or when you want to automate the installation process.

Follow the same steps as you would for a console installation, but at the command line, enter:

```
setupwin32.exe -silent -options RMP.response  
-W SybaseLicense.agreeToLicense=true
```

Where:

- *RMP.response* – is the name of the file containing the installation options you chose.
- `-W SybaseLicense.agreeToLicense=true` – specifies that you agree with the Sybase License Agreement text.

## Checking for a valid installation

Check the following to make sure that your Replication Manager installation is valid and successful:

- View the `%SYBASE%\RMP_install_log.txt` file and check for errors.

- Verify that the *vpd.properties* file has been written in the *%WINDIR%* directory.
- Ensure that the date of the *vpd.properties* file reflects the date of the current installation.
- Ensure that you can access Replication Manager from Sybase Central.

For information about using Sybase Central, the Replication Manager, and the Replication Manager plug-in online help, see Chapter 3, “Managing Replication Server with Sybase Central” in the *Replication Server Administration Guide Volume 1*.

---

**Note** Before you use the Replication Manager, make sure that the Replication Manager is registered with Sybase Central. See the “Preparing to manage a replication environment” section in the Replication Manager plug-in online help for information.

---

## Uninstalling Replication Manager

InstallShield includes an uninstall feature that removes the Sybase Replication Manager you have installed.

You can invoke the uninstall procedure using either GUI or console methods. Sybase recommends that you use the GUI method.

Before uninstalling the Replication Manager, log on to your machine using an account with administrator privileges. Then shut down all other processes for the components you are uninstalling.

---

**Note** InstallShield removes only those files that were loaded from the installation media. Some Sybase files, such as log and configuration files, are left intact for administrative purposes.

---

### ❖ Uninstalling in GUI mode

- 1 To uninstall in GUI mode, choose one of the following methods:
  - From the Start menu, select Settings | Control Panel | Add/Remove Programs.
  - From the command line, enter:

```
%SYBASE%\uninstall\RMP1520\uninstall_RMP.exe
```

- Click Start | Run and then enter:

```
%SYBASE%\uninstall\RMP1520\uninstall_RMP.exe
```

- Open Windows Explorer, and navigate to *uninstall\_RMP.exe* and double-click it.

The Uninstaller window opens.

- 2 Click Next.
- 3 Verify the summary information, then click Next.

The uninstaller removes the files associated with the software.

- 4 Click Finish.

---

**Note** You may be prompted to decide whether to remove shared files. Sybase recommends that you do *not* remove shared files.

---

- 5 If you are uninstalling the Replication Manager plug-in from Sybase Central, Java Edition, and you have previously installed both the Replication Manager plug-in and the Adaptive Server plug-in to Sybase Central, Java Edition, unregister the Replication Manager plug-in inside Sybase Central.

See the Replication Manager plug-in online help for more information.

#### ❖ Uninstalling in console mode

- 1 Go to the %SYBASE% directory. To uninstall:

- Replication Server software, at the command line, enter:

```
%SYBASE%\uninstall\RMP1520\uninstall_RMP.exe
-console
```

InstallShield starts and displays the welcome window as follows:

```
-----

Welcome to the InstallShield Wizard for Sybase
Replication Manager Version 15.2.

The InstallShield Wizard will uninstall Sybase
Replication Manager Version 15.2 from your computer.

To continue, choose Next.
```

Press 1 for Next, 3 to Cancel or 4 to Redisplay [1]

-----

- 2 Follow the remaining prompts to uninstall Replication Manager.

---

**Note** You may be prompted to decide whether to remove shared files. Sybase recommends that you do not remove shared files.

---

- 3 If you are uninstalling the Replication Manager plug-in from Sybase Central, Java Edition, and you have previously installed both the Replication Manager plug-in and the Adaptive Server plug-in to Sybase Central, Java Edition, unregister the Replication Manager plug-in inside Sybase Central.

See the Replication Manager plug-in online help for more information.

# Index

## A

- Adaptive Server
  - for the Replication Server System Database 28
  - upgrading 28
- administration tasks 8

## C

- charsets* subdirectory 7
- checking for a valid installation
  - in Replication Manager 37
  - in Replication Server 23
- collate* subdirectory 7
- command line installation
  - of Replication Manager 35
  - Replication Server 20
- complete installation 14
- components of Replication Server 1
- console mode
  - installing Replication Manager 35
  - installing Replication Server 19
  - response file, installing Replication Manager with 37
  - response file, installing Replication Server with 15, 22
  - troubleshooting 23
  - uninstallation 39
  - uninstallation in. *See* uninstalling
- conventions
  - document style viii
  - examples ix
  - syntax statements ix
- CPU requirements 3
- creating
  - a .bat file for Replication Server start-up 30
  - response files for Replication Manager 35
  - response files for Replication Server 20
- custom installation 14, 17

## D

- default directory 16
- details
  - Replication Server Configuration Guide for Windows NT* 2
- diagnosing software problems 7
- directories
  - default 16
  - installation, structure of 5
  - Sybase installation 13
- disk space, not enough for installation 17
- disk storage requirements 4
- DLLs
  - overwriting 17
- drepsrvr.exe** program 7

## E

- editing the response file
  - of the Replication Manager 36
  - Replication Server 21
- Embedded Replication Server System Database (ERSSD) 1, 4
- environment variables
  - %LM\_LICENSE\_FILE%* 30
  - %PATH%* 30
  - setting 14, 29
  - %SYBASE%* 30
  - %SYBASE\_JRE%* 30
  - %SYBASE\_JRE6\_32%* 30
  - %SYBASE\_OCS%* 30
  - %SYBASE\_REP%* 30
  - %SYBASE\_UA%* 30
  - TEMP 15
- errors
  - while starting InstallShield 16
- examples
  - style conventions ix

## Index

existing Adaptive Server Enterprise 12.x (64-bit) directory  
warning about installing into 13  
existing installation directories 16

## F

### files

installation log 23  
*log.txt* 8, 15, 23  
*SYBASE.bat* 8, 14, 29  
*SYBASE.env* 8  
*vpd.properties* 8  
full installation 14

## G

geographic location 16  
graphical user interface (GUI) installation 15  
GUI mode  
installing Replication Manager 33  
installing Replication Server 15  
uninstallation in. *See* uninstalling  
uninstalling 38

## H

hardware requirements 4

## I

*ini* subdirectory 7  
installation  
methods, Replication Manager. *See* installing  
Replication Manager  
methods, Replication Server 15  
not enough disk space for 17  
overview 2  
troubleshooting during silent or console mode 23  
typical software components 17  
installation directories  
contents 7  
existing 16

new 16  
Sybase 13  
installation log file 23  
installing  
a network license server 9  
Adaptive Server for the Replication Server System  
Database 28  
Replication Manager. *See* installing in Replication  
Manager  
Replication Server. *See* installing in Replication  
Server  
SySAM 9  
using InstallShield 13  
installing Replication Manager 33  
in command line mode 35  
in console mode 35  
in GUI mode 33  
using **-W** flag 37  
with response files 35  
installing Replication Server  
in command line mode 20  
in console mode 15, 19  
in GUI mode 15  
in silent mode 15  
methods of installation 15  
using **-W** flag 22  
with response files 15, 20  
InstallShield  
complete installation 14  
custom installation 14, 17  
definition of 13  
errors in starting 16  
GUI mode 15  
*log.txt* 15  
Replication Manager, previous installation with 34  
Replication Server, previous installation with 17  
standard installation 14, 17  
starting 15

## J

*\_jvmrep* subdirectory 8

**L**

- license agreement 16
- licenses 2
  - installing a network license server 9
- `%LM_LICENSE_FILE%` 30
- location
  - geographic 16
- log files, reviewing after installation 27
- `log.txt` file 8, 15, 23

**M**

- methods of installation
  - Replication Manager. *See* installing in Replication Manager
  - Replication Server 15
- Modifying or removing `vpd.properties` file 8

**N**

- new installation directories 16

**O**

- `OCS-15_0` subdirectory 8
- operating system
  - determining service pack levels for 4
  - requirements 4
  - service pack requirements for 4
- overview
  - installation 2
  - SySAM licensing 2
- overwriting DLLs 17

**P**

- `%PATH%` 30
- planning replication system 3
- post-installation tasks
  - Replication Manager 37
  - Replication Server 27

- pre-installation tasks 3
- previous installation
  - with InstallShield, in Replication Manager 34
  - with InstallShield, in Replication Server 17
  - with Studio Installer 17
- programs
  - `drepsrvr.exe` 7

**R**

- RAM requirements 3
- release bulletin 3
- REP.response template file 21
- `REP-15_2` subdirectory 8
- Replication Manager
  - installing. *See* installing Replication Manager
  - uninstalling 38
- Replication Server
  - components 1
  - details 1
  - installing. *See* installing Replication Server
  - licenses 2
  - uninstalling 23
- Replication Server Configuration Guide for Windows NT* 2
- requirements
  - CPU 3
  - disk storage 4
  - hardware 4
  - operating system 4
  - operating system service packs 4
  - RAM 3
  - system 3
- resetting environment variables 14
- response files
  - editing, for Replication Manager 36
  - installing Replication Manager with 35
  - installing Replication Server with 15, 20
  - installing with, Replication Server. *See* installing in Replication Server 15
  - Replication Manager, creating for 35
  - Replication Server, creating for 20
  - Replication Server, editing 21
- reviewing log files after installing 27
- RMP.response template file 36

## Index

*RMS plug-in* subdirectory 8

## S

servers  
    installing a network license server 9  
service pack levels 4  
setting environment variables 14, 29  
*Shared* subdirectory 8  
silent mode installation  
    for Replication Manager 37  
silent mode installations  
    Replication Server 15, 22  
    troubleshooting 23  
software, diagnosing problems 7  
standard installation 14, 17  
    InstallShield 17  
starting  
    InstallShield 15  
    Replication Server 30  
    Replication Server automatically 30  
    the sample Replication Server 28  
Studio Installer, previous installation with 17  
subdirectories  
    *charsets* 7  
    *ini* 7  
    *\_jvmrep* 8  
    *OCS-15\_0* 8  
    *REP-15\_2* 8  
    *RMS plug-in* 8  
    *Shared* 8  
    *SYSAM-2\_0* 8  
    *UAF-2\_0* 8  
    *uninstall* 8  
supported protocols 4  
SYBASE batch files  
    SYBASE.bat 14  
    SYBASE.env 14  
%SYBASE% environment variable 30  
Sybase installation directories 13  
    contents 7  
Sybase Software Asset Management System. See SySAM  
*SYBASE.bat* file 8, 14, 29  
*SYBASE.env* file 8  
%SYBASE\_JRE% environment variable 30

%SYBASE\_JRE6\_32% environment variable 30  
%SYBASE\_OCS% environment variable 30  
%SYBASE\_REP% environment variable 30  
%SYBASE\_UA% environment variable 30  
syntax statements, conventions ix

## SySAM

    description 2  
    install 9  
    installing a network license server 9  
    licensing instruction overview 2  
*SYSAM-2\_0* subdirectory 8  
system requirements 3

## T

tables  
    system requirements 3  
tasks, administration 8  
troubleshooting  
    during console or silent mode installation 23  
    using *log.txt* 15  
types of installations  
    complete installation 14  
    custom 14, 17  
    full 14  
    standard installation 14, 17  
    typical 14, 17  
typical installation 14, 17  
    software components for a 17

## U

*UAF-2\_0* subdirectory 8  
*uninstall* subdirectory 8  
uninstalling  
    console mode 39  
    GUI mode 38  
    in console mode, Replication Server 24  
    in GUI mode, Replication Server 24  
    Replication Manager 38  
    Replication Server 23  
upgrading  
    Adaptive Server Enterprise 28  
using



InstallShield for installation 13

## V

valid installation check  
    Replication Manager 37  
    Replication Server 23  
*vpd.properties* file 8

## W

**-w** flag and setup  
    Replication Server 22  
**-w** flag and setup, Replication Manager 37  
warnings  
    installing into existing Adaptive Server Enterprise  
        12.x (64-bit) directory 13

