



Component Integration Services Users Guide

Adaptive Server[®] Enterprise

15.7

DOCUMENT ID: DC32702-01-1570-01

LAST REVISED: September 2011

Copyright © 2011 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

To order additional documents, U.S. and Canadian customers should call Customer Fulfillment at (800) 685-8225, fax (617) 229-9845.

Customers in other countries with a U.S. license agreement may contact Customer Fulfillment via the above fax number. All other international customers should contact their Sybase subsidiary or local distributor. Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase trademarks can be viewed at the Sybase trademarks page at <http://www.sybase.com/detail?id=1011207>. Sybase and the marks listed are trademarks of Sybase, Inc. ® indicates registration in the United States of America.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP AG in Germany and in several other countries all over the world.

Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

IBM and Tivoli are registered trademarks of International Business Machines Corporation in the United States, other countries, or both.

All other company and product names mentioned may be trademarks of the respective companies with which they are associated.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS 52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568.

Contents

CHAPTER 1	Introduction	1
CHAPTER 2	Understanding Component Integration Services	5
	Basic concepts	5
	Access methods	6
	Server classes	6
	Object types	7
	Interface to remote servers	7
	Proxy tables	8
	Using the create table command.....	8
	Using the create existing table command	9
	Using the create proxy_table command.....	10
	Remote procedures as proxy tables.....	11
	Server limits.....	14
	Cascading proxy tables	18
	Proxy databases	18
	User proxy databases	18
	System proxy databases	21
	File system access	23
	Security considerations	24
	Directory access.....	24
	Recursion through subordinate directories.....	27
	File access	28
	Remote servers	30
	Server class ASEnterprise	31
	Server class ASAnywhere.....	31
	Server class ASIQ	31
	Server class direct_connect	31
	Server class sds	32
	Server class RPCServer	32
	Connection management	33
	Connecting to remote servers without the interfaces file.....	33
	LDAP directory services	34
	Secure communication with SSL.....	35

Secure communication using Kerberos.....	35
Security issues	40
Remote server logins	41
Mapping external logins	42
Remote server connection failover.....	44
Remote server capabilities	44
Query processing	45
Processing steps	45
RPC handling and Component Integration Services.....	50
Site handler and outbound RPCs.....	50
Component Integration Services and outbound RPCs.....	51
Text parameters for RPCs.....	53
Text parameter support for XJS/390	55
Distributed Transaction Management	55
Server classes and ASTC	55
DTM-enabled servers	56
Pre-DTM servers	56
strict DTM enforcement	57
enable xact coordination	57
Enable Component Integration Services.....	58
Transactional RPCs	58
Restrictions on transaction management.....	58
Adaptive Server to Adaptive Server update statistics	59
Limitations	59
Updating statistics on non-Adaptive Server backends.....	60
Java in the database	60
@@textsize	61
@@stringize.....	61
Constraints on Java class columns.....	61
Error messages.....	62
Java abstract datatypes (ADTs)	62
Datatypes	63
Unicode support	63
Datatype conversions.....	66
text and image datatypes	67
Configuration and tuning.....	71
Using sp_configure.....	71
Global variables for status.....	75

CHAPTER 3

SQL Reference	77
dbcc commands	77
dbcc options	78
Trace flags.....	78
Functions.....	80

Support for functions within Component Integration Services	80
Aggregate functions	80
Datatype conversion functions	81
Date functions	81
Mathematical functions	82
Security functions	83
String functions	84
System functions	84
Text and image functions	86
Transact-SQL commands	86
alter table	87
case	89
connect to...disconnect	90
create existing table	91
create index	98
create table	99
delete	101
drop index	101
fetch	102
insert	103
readtext	104
select	105
truncate table	106
update	106
update statistics	107
writetext	109
Passthrough mode	109
connect to	110
sp_autoconnect	111
sp_passthru	112
sp_remotesql	113
Quoted identifier support	114
Delimited identifier support	114
auto identity option	114
Triggers	115

APPENDIX A	Tutorial	117
	Getting started with Component Integration Services	117
	Adding a remote server	117
	Join between two remote tables	119

APPENDIX B	Troubleshooting	123
	Problems accessing Component Integration Services	123

Problems using Component Integration Services	124
Unable to access remote server	124
Unable to access remote object	127
Problem retrieving data from remote objects	127
If you need help	130
Index	133

Introduction

Component Integration Services extends Adaptive Server® capabilities and provides enhanced interoperability.

It also provides location transparency and functional compensation.

Location transparency means that Component Integration Services allows Adaptive Server to present a uniform view of enterprise data to client applications. Enterprise-wide data from heterogeneous sources can be accessed as if it were local.

Functional compensation allows Component Integration Services to emulate all features of Transact-SQL, and interact with a data source only when actual data is needed. With this capability, the full range and power of Transact-SQL can be applied to any data source, whether or not the data source provides support for a particular feature of Transact-SQL. Examples of this capability are built-in functions and Java functions. Component Integration Services allows statements to use these functions even though the data on which these functions may operate is derived from external sources that cannot support the functions.

Component Integration Services, together with Adaptive Server Anywhere, Adaptive Server IQ and various DirectConnect interfaces, extends the reach of Adaptive Server by enabling transparent access to database management systems anywhere in the enterprise. This transparent, extended reach of Adaptive Server Enterprise makes it easy for Enterprise Portal components to:

- Access data from anywhere, and present it as dynamic content to Web pages
- Execute transactions that span heterogeneous boundaries
- View an entire enterprise through a single view provided by the global metadata stored in the Adaptive Server/Component Integration Services system catalogs

Component Integration Services allows users to access both Sybase® and non-Sybase databases on different servers. These external data sources include host data files, tables, views, and RPCs (remote procedure calls) in database systems such as Adaptive Server and Oracle.

Using Component Integration Services, you can:

- Access tables in remote servers as if the tables were local.
- Perform joins between tables in multiple remote, heterogeneous servers. For example, it is possible to join tables between an Oracle database management system (DBMS) and an Adaptive Server, and between tables in multiple Adaptive Servers.
- Transfer the contents of one table into a new table on any supported remote server by means of a select into statement.
- Maintain referential integrity across heterogeneous data sources.
- Access native remote server capabilities using the Component Integration Services passthrough mode.

Component Integration Services can be used by anyone who needs to access multiple data sources or legacy data. It can also be used by anyone who needs to migrate data from one server to another.

A single server is often used to access data on multiple external servers.

Component Integration Services manages the data regardless of the location of the external servers. Data management is transparent to the client application.

Component Integration Services, in combination with EnterpriseConnect™ and MainframeConnect™, provides transparent access to a wide variety of data sources, including:

- Oracle
- Informix
- Microsoft SQL Server
- Adaptive Server Enterprise
- Adaptive Server Anywhere
- Adaptive Server IQ
- Mainframe data, including:
 - ADABAS
 - IDMS
 - IMS
 - VSAM

To start Component Integration Services:

- Install DirectConnect server(s) or gateways for the external data sources you choose to access (for example, Oracle, Informix, Microsoft SQL Server).
- Configure the server to access remote objects as described in Chapter 2, “Understanding Component Integration Services.”



Understanding Component Integration Services

This chapter explains how to use Component Integration Services. It is intended to help you understand how Adaptive Server works with the Component Integration Services option configured.

Topic	Page
Basic concepts	5
Proxy tables	8
Proxy databases	18
File system access	23
Remote servers	30
Query processing	45
RPC handling and Component Integration Services	50
Distributed Transaction Management	55
Adaptive Server to Adaptive Server update statistics	59
Updating statistics on non-Adaptive Server backends	60
Java in the database	60
Datatypes	63
Configuration and tuning	71

Basic concepts

The ability to access remote (or external) tables as if they were local is a hallmark of Component Integration Services. Component Integration Services presents tables to a client application as if all the data in the tables were stored locally. Remote tables are mapped to local proxy tables which hold metadata. Internally, when a query involving remote tables is executed, the storage location is determined, and the remote location is accessed so that data can be retrieved.

The access method used to retrieve remote data is determined by two attributes of the external object:

- The server class associated with the remote object
- The object type

To achieve location transparency, tables must first be mapped to their corresponding external locations.

Access methods

Access methods form the interface between the server and an external object. For each server class, there are separate access methods that handle all interaction between Adaptive Server and remote servers of the same class and object type.

Server classes

A server class must be assigned to each server when it is added using `sp_addserver`. Server classes determine the access method used to interact with the remote server. The server classes are:

- *ASEnterprise* – used if the server is Adaptive Server. This is the default server class.
- *ASAnywhere* – used if the server is Adaptive Server Anywhere version 6.0 or later. This server class should be used for Adaptive Server IQ versions earlier than Adaptive Server IQ 12.5.
- *ASIQ* – used if the server is Adaptive Server IQ version 12.5 and later.
- *local* – the local server. There can be only one.
- *direct_connect* – indicates that the server is an Open Server™ application that conforms to the interface requirements of a DirectConnect™ server. For access to Microsoft SQL Server, DB2, Oracle, or Informix, you must use a DirectConnect server.
- *sds* – indicates that the server conforms to the interface requirements of a Specialty Data Store.
- *RPCServer* – indicates that a server can only handle RPCs. It does not accept SQL statements, transaction control statements, or anything else.

Object types

The server presents a number of object types to client applications as if they were local tables. Supported object types are:

- table – the object in a remote server of any class is a relational table. This is the default type.
- view – the object in a remote server of any class is a view. Component Integration Services treats views as if they were local tables without any indexes.
- remote procedure – the object in a remote server of any class is a remote procedure. Component Integration Services treats the result set from the remote procedure as a read-only table.
- file – the object is an individual file within a file system.
- directory – the object is a file system directory.

Interface to remote servers

The interface between the server and remote servers is handled by the Open Client software, Client-Library™. The Client-Library features that are used to implement the interface are dependent upon the class of server with which Component Integration Services is interacting.

For example, if the server class is *direct_connect*, a number of features such as cursor and dynamic requests are used.

Before the server can interact with a remote server, you must configure the following:

- Remote server addition to directory services
- Remote server definition
- Remote server login information
- Remote object definition

Directory services

Before accessing remote tables with Component Integration Services, you must either have access to LDAP directory services, or an *interfaces* file (*sql.ini* file on Windows platforms). For more information about accessing remote tables, see “Connection management” on page 33. For information on setting up directory services, see the configuration documentation for your platform. See Appendix A, “Tutorial,” which serves as a basic tutorial for Component Integration Services users.

Remote server definition	Remote servers are defined by means of the stored procedure <code>sp_addserver</code> . This procedure is documented in the <i>Reference Manual</i> .
Logging in to remote servers	<p>Once you have configured the remote server, you must provide login information. By default, Component Integraiton Services uses the names and passwords of Adaptive Server clients whenever it connects to a remote server on behalf of those clients. However, this default can be overridden using <code>sp_addexternlogin</code>, which allows a system administrator to define the name and password for each user who connects to a remote server.</p> <p>Using <code>connect</code> to <i>server_name</i>, you can verify that the server configuration is correct. This command establishes a passthrough mode connection to the remote server. Passthrough mode allows clients to communicate with remote servers in native syntax. This passthrough mode remains in effect until you issue a <code>disconnect</code> command.</p>
Defining remote objects	<p>Once you have configured a remote server, you cannot access objects in that remote server as tables until a mapping between them and a local object (proxy table) has been established.</p> <p>You can create new tables on remote servers, and you can define the schema for an existing object in a remote server. The procedures for both are similar.</p>

Proxy tables

Proxy tables are the key to location transparency. A proxy table is a local table containing metadata which points to a remote object. For information about remote objects, see “Object types” on page 7. The remote table is mapped to the proxy table to make it appear as if it were a local table.

The complete description of how to do this is in Chapter 3, “SQL Reference.”

Using the *create table* command

The `create table` command creates a proxy table and a remote table at the same time with the following syntax:

```
create table table_name (column_list) [ [ external {table | file}] at "pathname" ]]
```

The remote location is specified with the `at pathname` clause. `create table` allows external object type `table` and `file`. The datatype of each column is passed to the remote server without conversion.

Using the *create existing table* command

The create existing table command allows the definition of existing tables (proxy tables). The syntax for this option is similar to the create table command:

```
create existing table table_name (column_list)  
[[external {table | procedure | file}] at pathname]
```

The action taken by the server when it receives this command is quite different from the action it takes when it receives the create table command, however. A new table is not created at the remote location; instead, the table mapping is checked, and the existence of the underlying object is verified. If the object does not exist (either host data file or remote server object), the command is rejected with an error message.

If the object does exist, its attributes are obtained and used to update system tables sysobjects, syscolumns, and sysindexes.

- The nature of the existing object is determined.
- For remote server objects (other than RPCs), column attributes found for the table or view are compared with those defined in the *column_list*. Column names must match (case sensitive), column types and lengths must match, or at least be convertible, and the NULL attributes of the columns must match.
- Index information from the host data file or remote server table is extracted and used to create rows for the system table sysindexes. This defines indexes and keys in server terms and enables the query optimizer to consider any indexes that may exist on this table.

After successfully defining an existing table, issue an update statistics command for the table. This allows the query optimizer to make intelligent choices regarding index selection and join order.

Datatype conversions

When you use the create table or create existing table commands, you must specify all datatypes, using recognized Adaptive Server datatypes. If the remote server tables reside on a class of server that is heterogeneous, the datatypes of the remote table are converted into the specified Adaptive Server types automatically when the data is retrieved. If the conversion cannot be made, the create table or create existing table commands do not allow the table to be created or defined.

Example of remote table definition

The following example defines the remote Adaptive Server table authors, starting with the server definition:

- 1 Define a server named SYBASE. Its server class is *ASEnterprise*, and its name in the interfaces file is SYBASE:

```
exec sp_addserver SYBASE, ASEnterprise, SYBASE
```

- 2 Define a remote login alias. This step is optional if the *username* and *password* are the same on both servers. User “sa” is known to remote server SYBASE as user “sa,” password “timothy”:

```
exec sp_addexternlogin SYBASE, sa, sa, timothy
```

- 3 Define the remote authors table:

```
create existing table authors
(
  au_id          varchar(11)      not null,
  au_lname      varchar(40)      not null,
  au_fname      varchar(20)      not null,
  phone         char(12)         not null,
  address       varchar(40)      null,
  city          varchar(20)      null,
  state         char(2)          null,
  country       varchar(12)      null,
  postalcode    char(10)        null
)
EXTERNAL TABLE at "SYBASE.pubs2.dbo.authors"
```

- 4 Update statistics on tables to ensure reasonable choices by the query optimizer:

```
update statistics authors
```

- 5 Execute a query to test the configuration:

```
select * from authors where au_lname = 'Carson'
```

Using the create proxy_table command

Use of the `create proxy_table` command does not require a column list. Component Integration Services derives the column list from the metadata it obtains from the remote table.

If the object does exist, create proxy_table updates sysobjects, syscolumns, and sysindexes.

Remote procedures as proxy tables

You can add an optional clause to the create existing table statement to indicate the remote object is actually a stored (or other) procedure instead of a table. Without this clause, the remote object is assumed to be a table or view:

```
create existing table t1
(
    column_1 int,
    column_2 int
)
EXTERNAL PROCEDURE AT "SYBASE.mydb.dbo.p1"
```

If the remote object is type procedure, several processing differences occur:

- No indexes are created for objects of this type.
- You must provide a column list that matches the description of the remote procedure's result set. No verification of the list's accuracy is provided.
- You can use column names beginning with underscore ('_') to specify columns that are not part of the remote procedure's result set. These columns are referred to as parameter columns. For example:

```
create existing table t1
(
    a int,
    b int,
    c int,
    _p1 int null,
    _p2 int null
)
external procedure
at "SYBASE.sybsystemprocs.dbo.myproc"

select a, b, c from t1
where _p1 = 10 and _p2 = 20
```

- In this example, the parameter columns *_p1* and *_p2* are not expected in the result set, but can be referenced in the query. Component Integration Services passes the search arguments to the remote procedure via parameters, using the names *@p1* and *@p2*.

- If a parameter column is included in the select list, its value is equivalent to the values specified for it in the where clause, if it was passed to the remote procedure as a parameter. If the parameter column did not appear in the where clause, or was not able to be passed to the remote procedure as a parameter, but was included in the select list, its value would be NULL.
- A parameter column can be passed to the remote procedure as a parameter if it is what the Adaptive Server query processor considers to be a searchable argument. It is generally a searchable argument if it is not included in any “or” predicates. For example, the following query would prevent the parameter columns from being used as parameters.

```
select a, b, c from t1
where _p1 = 10 OR _p2 = 20
```

- Rules exist for the definition of parameter columns in the create existing table statement:
 - Parameter columns must allow NULL.
 - Parameter columns cannot precede normal, result columns (they must appear at the end of the column list).

Allowing the definition of remote procedures as local tables allows Component Integration Services to treat the result set of a remote procedure as a “virtual table,” which can be sorted, joined with other tables, or inserted into another table via insert/select syntax. However, virtual tables are considered read-only:

- You cannot issue a delete, update, or insert command against a table of type *procedure*;
- You cannot issue a create index, truncate table, or alter table command against virtual tables.

If an object of the type procedure has been defined within the server, a query is not issued to the remote server on which the object resides. Instead, Component Integration Services issues an RPC and treats the results from the RPC as a read-only table.

Examples

```
create existing table rtable
( col1 int,
  col2 datetime,
  col3 varchar(30)
)
external procedure at "SYBASE...myproc "

select * from rtable
```

When this query is issued, Component Integration Services sends the RPC named *myproc* to server SYBASE. Row results are treated like the results from any other table; they can be sorted, joined with other tables, grouped, inserted into another table, and so forth.

RPC parameters should represent arguments that restrict the result set. If the RPC is issued without parameters, the entire result set of the object is returned. If the RPC is issued with parameters, each parameter further limits the result set. For example:

```
select * from rtable where col1 = 10
```

results in a single parameter, named @col1, that is sent along with the RPC. Its value is 10.

Component Integration Services attempts to pass as many of the search arguments as possible to the remote server, but depending on the SQL statement being executed, Component Integration Services might perform the result set calculation itself. Each parameter represents a search for an exact match, for example, the = operator.

The following rules define the parameters sent to the RPC. If an RPC is used as a Component Integration Services object, you should keep these rules in mind during development.

- Component Integration Services sends = operators in the where clause as parameters. For example, this query results in Component Integration Services sending two parameters:

```
select * from rpc1 where a = 3 and b = 2
```

Parameter a has a value of 3 and parameter b has a value of 2. The RPC is expected to return only result rows in which column a has a value of 3 and column b has a value of 2.

- Component Integration Services does not send any parameters for a where clause, or portion of a where clause, if there is not an exact search condition. For example:

```
select * from rpc1 where a = 3 or b = 2
```

Component Integration Services does not send parameters for a or b because of the or clause.

Another example:

```
select * from rpc1 where a = 2 and b < 3
```

Component Integration Services sends parameters for *a* and *b*, and filters rows containing *b* with values smaller than 3.

Server limits

Adaptive Server configuration allows page sizes of 2K, 4K, 8K, or 16K bytes. Also, the limit of 255 bytes for char/binary columns has been removed. Adaptive Server supports extended sizes of char, varchar, univarchar, unichar, binary, and varbinary datatypes. The new limit depends on the page size of the server. For various page sizes, the new limits are as follows:

Table 2-1: New limits

Page size	Maximum column size
2048	2048
4096	4096
8192	8192
16384	16384

These sizes are approximate. The basic rule specifies that the limit is the maximum size that still allows a single row to fit on a page. These limits also vary depending on the locking scheme specified when the table is created. It is assumed that the bulk of proxy tables are created with the default locking scheme, which is allpages locking.

- Limits on length of Transact-SQL variables and parameters – the size of char, varchar, binary, and varbinary variables are extended to equal the maximum size of columns of the same datatype for a given server. This allows variables to be passed to stored procedures (or RPCs) whose length exceeds the current limit of 255 bytes.
- Limits on number of columns per table – as many as 1024 columns per table are allowed, as long as the columns can still fit on a page. There is a limit of 254 variable-length columns (null columns are also considered variable length).
- Limits on the width of an index – the total width of an index within Adaptive Server can be larger than in earlier versions, depending on server page size. In Table 2-2, maximum index width is shown according to page size:

Table 2-2: Maximum index width

Page size	Index width
2048	600
4096	1250
8192	2600
16384	5300

- Limits on the number of columns per index – 31 columns per index.
- Table names, column names and index names can be up to 255 bytes.
- Identifier names can now be up to 255 bytes.

create new proxy table

create table allows columns of datatype char, varchar, binary, and varbinary to be specified with extended lengths, as described above. These datatypes and lengths are forwarded to the remote server on which the table is to be created.

create existing proxy table

The create existing table command also allows columns to be specified with a length of greater than 255 bytes. This allows Component Integration Services to treat columns in remote databases as char, varchar, binary, or varbinary that previously had to be treated as text or image columns.

There is still an opportunity for column size mismatch errors. For example, in the case where the remote database contains a table with a column length of 5000 bytes, and the Adaptive Server processing create existing table supports columns only up to 1900 bytes, a size mismatch error occurs. In this case, it is necessary to respecify the column as a text or image column.

When the proxy table column size exceeds that of the corresponding column in the remote table, a size mismatch error is detected and the command is aborted.

create proxy_table

create proxy_table imports metadata from a remote server and converts column information into an internal create existing table command, with a column list derived from the imported metadata. When obtaining the column metadata, conversion from the remote DBMS type to internal Adaptive Server Enterprise types is required.

If the size of a remote char, varchar, binary, or varbinary column exceeds the maximum allowed by the local server, its length is truncated to the maximum size possible, which depends on page size. If the size exceeds 16K bytes, the type is converted from char or varchar to text, or from binary or varbinary to image.

alter table

If `alter table` operates on a proxy table, it is first processed locally, then forwarded to the remote server for execution. If the remote execution fails, the local changes are backed out and the command is aborted.

The remote server must process the command appropriately, or raise an error. If an error is produced, the Component Integration Services side of the command is aborted and rolled back.

select, insert, delete, update

Component Integration Services handles large column values when proxy tables are involved in data manipulation language (DML) operations. Component Integration Services handles DML using one of several strategies:

- Tabular data stream (TDS)TM language commands – if the entire SQL statement can be forwarded to a remote server, then Component Integration Services does so using TDS Language commands generated by CT-Library `ct_command` (CS_LANG_CMD).

The text of the language buffer may contain data for long char or binary values that exceeds 255 bytes, and remote servers must handle parsing of these command buffers.

- TDS dynamic commands – if Component Integration Services cannot forward the entire SQL statement to a remote server (for example, Component Integration Services is forced to provide functional compensation for the statement), then an insert, update, or delete may be handled by using TDS dynamic commands, with parameters as needed, using the CT-Library function `ct_dynamic` (CS_PREPARE_CMD, CS_EXECUTE_CMD, CS_DEALLOC_CMD).

The parameters for the dynamic command may be CS_LONGCHAR_TYPE or CS_LONGBINARY_TYPE.

- TDS cursor commands – CT-Library cursor operations can be used to handle proxy table operations for select, update, and delete if functional compensation has to be performed. For example, if you are updating a proxy table and there are multiple tables in the from clause, Component Integration Services may have to fetch rows from multiple data sources, and for each qualifying row, apply the update to the target table. In this case, Component Integration Services uses `ct_cursor` (`{CS_DECLARE_CMD, CS_OPEN_CMD, CS_CURSOR_UPDATE_CMD, CS_CLOSE_CMD, CS_DEALLOC_CMD}`).

After a cursor is prepared, parameters are specified. These parameters may include those of type `CS_LONGCHAR` or `CS_LONGBINARY`.
- Bulk insert commands – when performing a select/into operation, if the target server supports the bulk interface (only true of remote Adaptive Servers and DirectConnect for Oracle), then the remote server must be prepared to handle char and binary values greater than 255 (via `CS_LONGCHAR`, `CS_LONGBINARY` values).

Columns from remote servers may be returned to Component Integration Services as type `CS_LONGCHAR_TYPE` or `CS_LONGBINARY_TYPE`.

RPC handling

RPCs sent to remote servers can contain parameters of types `CS_LONGCHAR` and `CS_LONGBINARY`. The Component Integration Services command `cis_rpc_handling` supports these types.

Sending long parameters to Adaptive Servers older than version 12.5 is not allowed, as earlier versions of Adaptive Server do not support `CS_LONGCHAR` or `CS_LONGBINARY` data. Component Integration Services examines TDS capabilities for the remote server prior to sending the RPC, and if the remote server cannot accept these datatypes, an error results.

sp_tables

The Adaptive Server Anywhere or ASIQ stored procedure `sp_tables` only returns user tables.

Cascading proxy tables

Adaptive Server allows cascading proxy table configurations between any number of instances of Component Integration Services.

There are conditions where this can cause problems, such as circular references, or transactions in which the second proxy table references a local table on the same server as the first proxy table. In this case, application deadlocks can result that are not detected by Component Integration Services. You must configure your systems to avoid these potential pitfalls.

Proxy databases

There are two types of proxy databases: user and system.

User proxy databases

When a user proxy database is created, metadata for the proxy tables is imported automatically from the remote location that contains the actual tables. This metadata is then used to create proxy tables within the proxy database.

To create a proxy database, use:

```
create database <dbname>  
    [create database options]  
    [with default_location = 'pathname']  
    [for proxy_update]]
```

The use of the clause with default_location allows you to specify the storage location of any new tables, and the location from which metadata may be imported for automatic proxy table creation if the for proxy_update clause is also specified. for proxy_update establishes the database as a proxy database; with default_location defines the location from which proxy tables are imported. Without for proxy_update, the behavior of with default_location is the same as that provided by sp_defaultloc — a default storage location is established for new and existing table creation, but automatic import of proxy table definitions does not take place during the processing of the create database command.

The value of path name is a string identifier in the following format:
servername.dbname.owner.

- *servername* – required field; represents the name of the server that owns the objects to be referenced by proxy tables. Must exist in *master.dbo.sys.servers.srvname*.
- *dbname* – optional. The name of the database within *servername* which contains objects to be referenced by proxy tables
- *owner* – optional. The name of the owner of objects to be referenced by proxy tables. This may be restrictive, so that if more than one user owns objects in *dbname*, specifying the owner selects only those objects owned by that user. Do not create proxy tables for objects owned by other users.

If for proxy_update is specified with no default_location, an error is reported.

When a proxy database is created (using the for proxy_update option), Component Integration Services functions are called upon to:

- Provide an estimate of the database size required to contain all proxy tables representing the actual tables/views found in the primary server's database. This estimate is provided in terms of the number of database pages needed to contain all proxy tables and indexes. This size is used if no size is specified, and no database devices are specified.

Note If the database is created with specific size specifications [on device_name = nn], or if a device name is specified with no size [on device_name], then the size requirements for the proxy database are not estimated; it is assumed in this case that the user or data base administrator wants to override the default size calculated for the proxy database.

If you are importing metadata from another Adaptive Server, remote database users are imported before proxy tables are created. Each imported database user must have a corresponding system user name in syslogins.

- Create all proxy tables representing the actual tables/views found in the companion server's database. Proxy tables are not created for system tables.
- Grant all permissions on proxy tables to "public."
- Add the "guest" user to the proxy database.
- Import database users from remote site (if Adaptive Server).
- Grant create table permission to "public."

- Set the database status to indicate that this database is a user proxy database. This is done by setting a status field in *master.dbo.sysdatabases.status3* (0x0001, DBT3_USER_PROXYDB).

After the database has been created, it contains a proxy table for each table or view found in the default location. The behavior for a user proxy database is identical to prior database behavior. Users can create additional objects, such as procedure, views, rules, defaults, and so on, and both DDL and DML statements that operate on proxy tables behave as documented in this book.

The only exception to this is the alter database command. The syntax and capabilities of this command are described in the next section.

User proxy database schema synchronization

At times, it may be necessary for a DBA to force resynchronization of the proxy tables contained within the proxy database. This can be done using the alter database command:

```
alter database <dbname>
    [alter database options]
    [for proxy_update]
```

If the for proxy_update clause is entered with no other options, the size of the database is not extended; instead, the proxy tables, if any, are dropped from the proxy database and re-created from the metadata obtained from the *pathname* specified during create database ... with default_location = 'pathname'.

If create database is used with other options to extend the size of the database, the proxy table synchronization is performed after the size extensions are made.

The purpose of this alter database extension is to provide a DBA with an easy-to-use, single-step operation with which to obtain an accurate and up-to-date proxy representation of all tables at a single remote site.

This resynchronization is supported for all external data sources, and not just the primary server in a HA-cluster environment. Also, a database need not have been created with the for proxy_update clause. If a default storage location has been specified, either through the create database command or using sp_defaultloc, the metadata within the database can be synchronized with the metadata at the remote storage location.

Certain behavior is implied by the use of create/alter database to specify a proxy database:

- Modification to the default location specified with the create database command is not allowed using alter database.
- Local tables cannot be created in the proxy database. create table commands result in the creation of proxy tables, and the actual table is created at the default location.
- The default location of the table may be specified in the create table command, using the at 'pathname' syntax. If the path name differs from the default location, then the alter database command will not synchronize the metadata for this table.
- To change the default location, drop the database, then re-create it with a new path name specified in the default_location = 'pathname' clause. If the location is changed using sp_defaultloc, then the new location is used to provide metadata synchronization, and proxy tables that were created with the prior location not be synchronized, and may be dropped and replaced if the name conflicts with that of tables at the new location.

System proxy databases

System proxy databases behave like user proxy databases, with some notable enhancements and exceptions. System proxy databases are only used in an HA configuration.

System proxy databases allow customer-written applications to run on either node in a high-availability cluster. This does not imply “single-system image” capability; rather, it suggests an environment in which most user-written applications can execute on either node in the cluster. This means that both databases and user-created objects should be visible to both nodes.

A system proxy database has the same name as the database in the primary node it references, and contains handling for the user-defined objects that are necessary to support the application. Proxy tables are created for each user table and view found in the primary database, and stored procedures are converted to RPCs and forwarded to the node referenced by the proxy database.

System proxy database creation

A system proxy database is created automatically under the following circumstances:

- The HA cluster is being configured through the use of the stored procedure `sp_companion ServerName, 'configure', with_proxydb`.

In this case, a system proxy database is created for each user database found in server indicated by `ServerName`.

- A `create database` command is issued in a server whose HA state is one of `MODE_APNC`, `MODE_SNC`, or `MODE_ASNC`.

When the creation of the system proxy database is complete, Component Integration Services functions are called upon to:

- `grant create table to public` – this allows table creation on the primary server to result in proxy table creation in the system proxy database.

Schema synchronization when current database has a system proxy database

In an HA cluster, some of the changes to a primary server's database must be forwarded to the companion server to keep both servers synchronized.

Several DDL commands, when executed within a database that has a system proxy database, cause notification of the companion server and result in automatic synchronization of the resulting changes:

- `create table` and `drop table` – local operation executes, resulting in the local table being created or dropped. The command is then forwarded to the companion server, for execution in the system proxy database, so that a proxy table can be created or dropped
- `create index` and `drop index` – local operation executes, resulting in an index being created or dropped. The server owning the system proxy database is then notified, and the proxy table is dropped and re-created, allowing the change to the index to be represented within the proxy table.
- `create view` and `drop view` – the local operation succeeds, resulting in the local view being created or dropped. The server owning the system proxy database is then notified, and a proxy table is either created or dropped.

If these commands are executed within the system proxy database, similar behavior occurs:

- `create table` and `drop table` – local proxy table is created or dropped. The command is then forwarded to the primary server, so that a local table referenced by the proxy table can be created or dropped.

- create index and drop index – local operation on the proxy table executes, resulting in an index being created or dropped. The server owning the primary database is then notified, and an index is either created or dropped on the local table referenced by the proxy table
- create view and drop view – not allowed within a system proxy database.

Stored procedure execution within a system proxy database

If a system stored procedure request is encountered when the current database is a system proxy database, Component Integration Services attempts to locate the stored procedure first in the local sybssystemprocs database, and execute it. If it is not found in sybssystemprocs, Component Integration Services searches the master database. If the procedure is not a system stored procedure, or if it is but cannot be found locally, the stored procedure request is converted to an RPC and transmitted to the server referenced by the system proxy databases default location.

Additional behavior of the system proxy database

Certain commands, when executed within a system proxy database, are rejected with an error:

- create procedure and drop procedure
- create view and drop view
- create trigger and drop trigger
- create rule and drop rule
- create default and drop default

The error generated in these cases is: `Msg 12818, Severity 16: Cannot create an object of this type in system-created proxy database.`

File system access

Note Directories and files mapped to proxy tables now have a file path limit of 255 bytes.

Adaptive Server provides access to the file system through the SQL language. With file system access, you can create proxy tables that are mapped to file system directories, or to individual files.

To create proxy tables mapped to directories or files, you must have system administrator or System Security Officer privileges.

Security considerations

Only Adaptive Server Enterprise users with system administrator (sa) or System Security Officer (sso) roles are allowed to create proxy tables that are mapped to files or directories. This requirement addresses the concerns over the security aspects of accessing file system data from within the Adaptive Server Enterprise server process (which may have root permission as it runs).

Directory access

Proxy tables can be created to reference file system directories. The supported syntax is:

```
create proxy_table <table_name>  
external directory at "directory pathname[;R]"
```

The directory path name must reference a file system directory visible to and searchable by the Adaptive Server Enterprise process. A proxy table that maps column names to attributes of files that exist within the directory is created. If the ‘;R’ (indicating “recursion”) extension is added to the end of the path name, Component Integration Services includes entries in all subordinate directories. Table 2-3 contains a description of the proxy table columns that are created when this command successfully completes:

Table 2-3: Proxy table columns

Column name	Datatype	Description
id	numeric(24) – on 32-bit machines numeric(36) – on 64-bit machines	Identity value consisting of values from st_dev and st_ino. These two values are converted first to a single string (format: “%d%014d”), and the string is then converted to a numeric value.

Column name	Datatype	Description
filename	varchar(n)	The name of the file within the directory specified in at 'pathname', or within directories subordinate to pathname. The total length (n) of filename is limited to 255 bytes.
size	int	For regular files – specifies the number of bytes in the file. For directories – block special or character special, this is not defined.
filetype	varchar(4)	The file type – legal values are: FIFO, for pipe files; DIR for directories; CHRS for character special files; BLKS for block special files; REG for ordinary files; UNKN for all other file types. Links are automatically expanded, and do not appear as a separate file type.
access	char(10)	Access permissions, presented in a more or less 'standard' UNIX format: "drwxrwxrwx"
uid	varchar(n)	The name of the file owner. The value of n is specified by the system definition L_cuserid, which is 9 on all UNIX systems. This value is 0 on Windows systems.
gid	varchar(n)	The name of the owning group. The value of n is specified by the system definition L_cuserid, which is 9 on all UNIX systems. This value is 0 on Windows systems.
atime	datetime	Date/time file data was last accessed.
mtime	datetime	Date/time when file was last modified.
ctime	datetime	Date/time when file status was last changed.
content	image	The actual physical content of the file (for regular files only). NULL if the file is not a regular file.

A proxy table that maps to a file system directory can support the following SQL commands:

- select – file attributes and content can be obtained from the proxy table using the select command. Built-in functions that are designed to handle text values are fully supported for the content column, (for example, textptr, textvalid, patindex, pattern).

- insert – new files or directories can be created using the insert command. The only columns that have meaning are filename, filetype, and content. The rest of the columns should be left out of the insert statement, and are ignored if they are located. The content column is ignored if file type is *DIR*, which indicates that a new directory is to be created.

To create a new directory, enter:

```
insert D1 (filename, filetype) values ("newdir",
"DIR")
```

To create a new file, enter:

```
insert D1 (filename, content) values
("newdir/newfile", "This is an example.")
```

- delete – files or directories may be removed by the use of the delete command. A directory can be removed only if it is empty. For example:

```
/* delete the files only */
delete D1 where filename = 'newdir/newfile'
/* deletes the directory (if empty) */
delete D1 where filetype = 'DIR' and filename =
'newdir'
```

- update – only the name of a file may be changed using the update command.

Note Some file systems implement update as a deletion followed by the creation of a new directory entry; therefore the same filename could be updated multiple times if the update is not restricted. Sybase recommends that you qualify the update to specific files by having the filename included in the where clause of the update. For example, this statement could cause multiple updates:

```
update t1 set filename=filename + 'old' where filetype
= 'REG'
```

The problem would be avoided by adding a clause such as "and filename like "%.c"

- readtext – the contents of a file may be retrieved using the readtext command.
- writetext – the contents of a file may be modified using the writetext command.

No other SQL commands operate on proxy tables.

Regular file content is available only if the Adaptive Server process has sufficient privileges to access and read the file, and if the file type indicates an “ordinary” file. In all other cases, the content column is NULL. For example:

```
select filename, size, content
   from directory_table
  where filename like '%.html'
```

returns the name, size and content of regular files with a suffix of “.html,” if the Adaptive Server process has access privileges to the file. Otherwise, the content column will be NULL.

create proxy_table fails if the path name referenced by directory path name is not a directory, or is not searchable by the Adaptive Server Enterprise process.

If trace flag 11206 is turned on, messages are written to the error log that contain information about the contents of the directories and the query processing steps needed to obtain that information.

Recursion through subordinate directories

If the path name specified in the create proxy_table statement contains the ;R extension, Component Integration Services traverses all directories subordinate to the path name, and returns information for the contents of each subordinate directory. When this is done, the file name returned by a query contains the complete name of the file relative to the path name. In other words, all subordinate directory names appear in the file name. For example, if path name specifies “/work;R”:

```
create proxy_table d1 external directory at "/work;R"
select filename, filetype from d1
```

Values for files in subordinate directories are returned as outlined in Table 2-4:

Table 2-4: Values for files

File name	File type
dir1	DIR
dir1/file1.c	REG
dir1/file2.c	REG
dir2	DIR
dir2/file1.c	REG

File access

Another class of proxy tables allowed in Adaptive Server enables SQL access to individual files within a file system. The supported syntax is:

```
create proxy_table <table_name>  
    external file at "pathname" [column delimiter "<string>"]
```

When this command is used, a proxy table with one column (named "record", type `varchar(255)`) is created. It is assumed in this case that the contents of the file are readable characters, and that individual records within the file are separated by the newline (`\n`) character.

You can also specify your own column names and datatypes, using the `create [existing] table` command:

```
create existing table fname (  
    column1 int null,  
    column2 datetime null,  
    column3 varchar(1024) null  
    etc. etc.  
) external file at "pathname" [column delimiter "<string>"]
```

Columns may be any datatype except text, image, or a Java ADT. The use of the `existing` keyword is optional, and has no effect on the processing of the statement. If the file referenced by path name does not exist, it is created. If it does exist, its contents are not overwritten. There is no difference in behavior between the `create table` and `create existing table` commands.

When a proxy table is mapped to a file, these assumptions about the file and its contents are made:

- The file is not a directory, block special, or character special file.
- The Adaptive Server process has at least read access to the file. If the file is to be created, the server process must have write access to the directory in which the file is to be created.

- The contents of an existing file are in human-readable form.
- Records within the file are delimited by a newline character.
- The maximum supported record size is 32767 bytes.
- Individual columns, except for the last one, are delimited by the column delimiter string, which can be up to 16 bytes long; the default is a single tab character.
- There is a correspondence between delimited values within each record of the file and the columns within the proxy table.

With proxy tables mapped to files, you can:

- Back up database tables to the file system using either `select/into` or `insert/select`. When an insert statement is processed, each column is converted to characters in the default character set of the server. The results of the conversion are buffered, and all columns (except the last) are delimited by a single tab. The last column is terminated by a newline character. The buffer is then written to the file, representing a single row of data.
- Provide a SQL alternative to using `bcp in` and `bcp out`. The use of a `select/into` statement can easily back up a table to a file, or copy a file's contents into a table.
- Query file content with the `select` statement, qualifying rows as needed with search arguments or functions. For example, you can read the individual records within the Adaptive Server error log file:

```
create proxy_table errorlog
  external file at "/usr/sybase/ASE15_0/install/errorlog"
select record from errorlog where record like "%server%"
```

This query returns all rows from the file that match the like pattern. If the rows are longer than 255 bytes, they are truncated. You can specify longer rows by entering:

```
create existing table errorlog
(
  record varchar(512) null
)
external file at "/usr/sybase/ASE15_0/install/errorlog"
```

In this case, records up to 512 bytes in length are returned. Since the proxy table contains only one column, the actual length of each column is determined by the presence of a newline character.

Only the select, insert, and truncate table statements are supported for file access. update and delete result in errors if the file proxy is the target of these commands.

When inserting values into a file, all datatypes are first converted to char values and then delimited by the column delimiter.

Warning! truncate table sets the file size to 0.

Trace flag 11206 is used to log messages to the error log. These messages contain information about the stages of query processing that are involved with file access.

Remote servers

Use `sp_addserver` to add entries to the `sys.servers` table for the local server and for each remote server that is to be called. The `sp_addserver` syntax is:

```
sp_addserver server_name [,server_class [,network_name]]
```

where:

- `server_name` is a unique name used to identify the server.

- *server_class* is the type of server. The supported server classes with the types of servers that are in each class are described in the following sections. The default is server class ASEnterprise.

Note Component Integration Services no longer supports server class db2.

- *network_name* is the server name in the interfaces file. This name may be the same as *server_name*, or it may differ. The *network_name* is sometimes referred to as the *physical name*. The default is the same name as *server_name*.

Note You need the same sort order and case sensitivity between servers.

Server class ASEnterprise

Adaptive Server uses server class ASEnterprise. When Component Integration Services first establishes a connection to a server in this class, Component Integration Services determines the Adaptive Server version and establishes server capabilities based on the version found.

Server class ASAnywhere

A server with server class ASAnywhere is an instance of Adaptive Server Anywhere:

- Adaptive Server Anywhere 9.0 or later

Server class ASIQ

A server with server class ASIQ is Adaptive Server IQ version 12.5 or later.

Server class *direct_connect*

A server with server class *direct_connect* is an Open Server-based application that conforms to the *direct_connect* interface specification.

Open Server-based applications using server class `direct_connect` are the preferred means of accessing all external, non-Sybase data sources.

Adaptive Server with Component Integration Services enables interacts with clients and Open Server-based applications. For example, a client application interacts with CIS on Adaptive Server, which interacts through the network to a DirectConnect, such as Oracle or Informix. The DirectConnect can also have direct access to the client application, and the client application to the DirectConnect.

Server class `sds`

A server with server class `sds` conforms to the interface requirements of a Specialty Data Store™ as described in the *Adaptive Server Specialty Data Store Developer's Kit* manual. A Specialty Data Store is an Open Server application you design to interface with Adaptive Server.

Server class `RPCServer`

A server configured with `RPCServer` is not capable of handling anything other than RPCs. Servers in this class cannot participate in distributed transactions, and Component Integration Services does not attempt to send SQL statements to a server configured with this class.

To send RPCs to Backup Server or to XP Server, the `sp_serveroption` negotiated logins and server logins must be enabled.

Typically, servers in this class are customer-written Open Server applications intended to either perform a customized operation, or to make data available to an Adaptive Server application that is generated as a result of one or more RPCs. The only Open Server event handlers required for this type of application are:

- `SRV_CONNECT` – handle and authenticate a login request from CIS or client application.
- `SRV_DISCONNECT` – handle disconnect request from CIS or client application.
- `SRV_ATTENTION` – handle CANCEL request from CIS or client application.

- SRV_RPC – handle RPC from CIS. The handling of the RPC may produce a result set, which CIS will forward to the ASE client on whose behalf CIS forwarded the RPC.

Using this server class, it is possible to write an Open Server application that supports CIS proxy tables that map to RPC's:

```
create existing table myRPCTable
(
    <column description(s)
)
external procedure at 'myRpcServerName...rpcname'
```

Connection management

When connecting to a remote server on behalf of a client, Component Integration Services uses Client-Library functions. Once the first connection to a remote server is established for a given client, that connection remains open until the client disconnects from Component Integration Services.

Note When a connection uses Component Integration Services features for the first time, it becomes affiliated with one Adaptive Server engine. The PSS flag `POMNI_AFFINITY_SET` is set and is not cleared automatically.

Connecting to remote servers without the interfaces file

You can establish a connection to remote servers without using corresponding entries in directory services *ldap* or *interfaces* files. This is accomplished through Component Integration Services's use of the CT-Library connection property `CS_SERVERADDR`, which allows a server to be specified in the form:

```
"hostname.domain.com:99999"
"hostname:99999"
"255.255.255.255:99999"
```

where 99999 is the port number, and *hostname* is expressed as a simple name, an IP address, or a complete domain name.

Enter names in this format using `sp_addserver` with the net name argument:

```
sp_addserver S1, ASEnterprise,
```

```
"myhost.sybase.com:11222"
```

or:

```
sp_addserver S1, ASEnterprise, "192.123.321.101:11222"
```

There are some limitations to this usage of net names:

- Adaptive Server site handler does not recognize this syntax.
- Replication Agent threads do not recognize this syntax.

If this syntax is used, CT-Library does not attempt to look up connection information from directory services, whether an interfaces file or LDAP server is configured.

If SSL is configured and you have a pointer to the SSL section in the server docs, you can use the optional SSL syntax:

```
"hostname.domain.com:9999:SSL"  
"hostname:9999:SSL"  
"255.255.255.255.9999:SSL"
```

For more information about configuring Adaptive Server for SSL, see Chapter 19, “Confidentiality of Data,” in the *System Administration Guide: Volume One*.

LDAP directory services

The LDAP directory services means that it is no longer necessary to use an interfaces file in both the client and the server. Adaptive Server supports LDAP services for obtaining server information, and so does Component Integration Services. When a connection to a remote server is attempted, Component Integration Services instructs Open Client software to reference either the interfaces file or an LDAP server unless the net name argument to `sp_addserver` contains a colon (:).

Component Integration Services uses LDAP services only when the configuration file (*libtcl.cfg*) specifies it. *libtcl.cfg* can be found at `$$SYBASE/$$SYBASE_OCS/config/libtcl.cfg` or `$$SYBASE/$$SYBASE_OCS/config/libtcl64.cfg` for 64-bit applications.

Note When an LDAP server is specified in *libtcl.cfg*, server information becomes accessible from the LDAP server only and Adaptive Server and Component Integration Services ignore any (traditional) interfaces file.

Secure communication with SSL

Using SSL, you can establish secure connections from Component Integration Services to any number of remote servers that support the SSL protocol (Adaptive Server and some DirectConnects).

Component Integration Services handles SSL connections as follows:

- The location of the trusted roots file is established. If the current server is SSL-enabled, then all outbound Component Integration Services connections will use the same trusted roots file as Adaptive Server Enterprise.
- If the current server is SSL-enabled, then a connection property is established to define the Open Client callback that will be used to respond to a challenge from a remote SSL-enabled server. If the current server is not SSL-enabled, then the callback used fails any connection to a remote SSL-enabled server.

Trusted roots files

The trusted roots file contains certificates for other servers that the local server treats as trusted when properly added to the system. If `$SYBASE_CERT` is defined, a trusted roots file is accessible by the local server (Adaptive Server) in:

```
$SYBASE_CERT/trusted.txt
```

Otherwise it is in:

```
$SYBASE/$SYBASE_ASE/certificates/servername.txt
```

On UNIX platforms:

```
%SYBASE%\%SYBASE_ASE%\certificates\servername.txt
```

On Windows platforms:

where *servername* is the name of the current Adaptive Server.

Secure communication using Kerberos

Kerberos network-based authentication is a single sign on feature which allows Kerberos clients authenticated with Kerberos system, to be able to connect to any application that supports Kerberos authentication. With one centralized password stored, need not specify a password to connect to an application that supports Kerberos.

Kerberos version 5, the version supported by Adaptive Server, also provides a feature called credential delegation or ticket forwarding, which allows a Kerberos client to delegate the credential when connecting to a server, allowing the server to initiate Kerberos authentication for further connections to other servers on behalf of Kerberos client.

The credential delegation feature is currently only certified with MIT Kerberos GSSAPI libraries version 4.x and later. Clients must obtain a delegatable credential from the Kerberos system (using the `kinit -f` option on UNIX systems) before connecting to Adaptive Server.

A Kerberos client connected to Adaptive server can request a Remote Procedure Call (RPC) to Adaptive Server, and for general distributed query processing requests to a remote Adapter Server through CIS by using the Kerberos credential delegation feature. Kerberos authentication is not supported for site handler based remote server connection.

To use Kerberos unified login, a System Security Office can use the following command to enable the Kerberos security mechanism for CIS to a remote Adaptive Server.

```
sp_serveroption [server, optname, optvalue]
```

For example, the following command executed on local server S1 enables Kerberos authentication for connections to remote server S2 when the current logged in user is authenticated using Kerberos mechanism.

```
sp_serveroption s2, "security mechanism", csfkrb5
```

Kerberos security services

Once the Kerberos security mechanism is enabled for connections to a remote Adaptive Server, one or more of the following security services provided by Kerberos can be used:

- Message confidentiality
Data is encrypted over the network to protect against unauthorized disclosure.
- Message integrity
Verifies that communications have not been modified during transport.
- Mutual authentication

Verifies the identity of the client and the server. The local server initiating the remote connection can request mutual authentication for all remote connection requests to target an Adaptive Server. This allows the client to verify the identity of the remote server.

Note The optional security services provided by Kerberos are not enabled by default.

Message confidentiality

The following command executed on local server S1 sets message confidentiality for all connections to remote server S2 using Kerberos authentication .

```
sp_serveroption s2, "use message confidentiality", true
```

Message integrity

The following command executed on local server S1 sets message integrity for all connections to remote server S2 using Kerberos authentication.

```
sp_serveroption s2, "use message integrity", true
```

Message authentication

The following command executed on local server S1 sets mutual authentication for all connections to remote server S2 using Kerberos authentication.

```
sp_serveroption s2, "mutual authentication", true
```

Configuration for the remote Adaptive Server Kerberos principal name

The Adaptive Server principal name is the default name of the server. Since the principal name of the Adaptive server can be different than the server name, the System Security Officer can specify the server principal name for each remote server.

The following command specifies a remote Adaptive Server principle name for remote server S2.

```
sp_serveroption S2, "server principal", ase2@myrealm.com
```

Configuration for Component Integration Services Remote Procedure Calls

CIS uses persistent client-library connections to handle the RPC request. CIS handles outbound RPCs by determining whether the client already has a client-library connection to the server in which the RPC is intended. If no connection exists, it will be established.

To enable the CIS RPC handling mechanism, set the configuration option `cis_rpc_handling` to 1. When not enabled, the Kerberos user needs to temporarily enable CIS RPC for the current session to use this feature.

The following command enables CIS RPC handling for the current login session.

```
set cis_rpc_handling on
```

Establishing Security for Component Integration Services Remote Procedure Calls

The following describes how to enable Kerberos authentication for all types of Adaptive Server to CIS connections.

In the following example, `user1` is a Kerberos user who logs into Adaptive Server `S1` and request RPC to the remote Adaptive Server `S2`.

- 1 Add an entry to the `interfaces` file or the Directory Service for both servers `S1` and `S2` and a `secmech` line for the Kerberos security mechanism.

- 2 Add a login for the Kerberos user if one does not exist.

```
create login user1 with password pwuser1
```

- 3 Enable the use of security mechanisms by setting the configuration option to `on`.

```
sp_configure "use security services", 1
```

- 4 On the local server `S1`, enable Kerberos Authentication for CIS to remote server `S2`.

Note This assumes that remote server `S2` only receives CIS command requests from `S1`. However, if `S2` can also request CIS commands to other servers and requires enabling Kerberos Authentication, than similar configuration on `S2` will be required.

- a On the local server `S1`, add the remote server `S2`.

```
sp_addserver S2
```

- b Enable Kerberos security mechanism on S1 for outbound RPC requests to S2. The following command enables CIS RPC handling for the current login session.

```
sp_serveroption S2, "security mechanism", csfkrb5
```

- The security mechanism authentication for RPC request to remote server S2 will be initiated only if the security mechanism is configured for remote server S2 using the above command.
- If the security mechanism to S2 is configured and the forwarded ticket of user 'user1' is not available with local server S1, then the RPC connection will not be initiated
- If the security mechanism is not configured for RPC to remote server S2, meaning the server option security mechanism is not set, then security session establishment will not be initiated for RPC to remote server S2. In this case, CIS will initiate password based authentication with the remote server S2. CIS uses the names and passwords of the client whenever it connects to remote server if no external login/password mapping is specified. The client user1 logged in to Adaptive Server using Kerberos unified login authentication will not have any password associated with the login session. The system administrator must configure login mapping using sp_addexternlogin for user user1 to be able to connect to S2 for RPC requests. If no external login and password mapping is specified for user1 then the password will be blank and the CIS connection to the remote server will fail.
- user1 can request for execution of the stored procedure sp_who on S2 by connecting to server S1 and requesting credential delegation as follows:

```
isql -vd -S S1
S2...sp_who
```

- user1 can make a passthrough connection to remote server S2 by using the following command:

```
connect to S2
```

- user1 can execute queries on remote server by using the following command:

```
sp_remotesql S2, "select @@authmech"
go
sp_remotesql S2, "sp_who"
go
```

Security issues

When establishing a connection to a remote Adaptive Server, Client-Library functions are used instead of a site handler when either `cis_rpc_handling` or `set_transactional_rpc` is on. This method of establishing connections prevents the remote server from distinguishing these connections from those of other clients. Thus, any remote server security configured on the remote server to allow or disallow connections from a given server does not take effect.

Another Adaptive Server with Component Integration Services enabled cannot use *trusted mode* for remote server connections. This forces the Adaptive Server to be configured with all possible user accounts if it is going to be used with Component Integration Services.

Passwords are stored internally in encrypted form.

Using encrypted columns in CIS

By default, encryption and decryption are handled by the remote Adaptive Server. CIS makes a one-time check for encrypted columns on the remote Adaptive Server. If the remote Adaptive Server supports encryption, CIS updates the local syscolumns catalog with the encrypted-column-related metadata as follows:

- `create proxy_table` automatically updates syscolumns with any encrypted-column information from the remote tables.
- `create existing table` automatically updates syscolumns with any encrypted-column metadata from the remote tables. The `encrypt` keyword is not allowed in the `column_list` for `create existing table`. CIS automatically marks columns as encrypted if it finds any encrypted columns on the remote table.
- `create table` at the location with encrypted columns is not allowed.
- `alter table` is not allowed on encrypted columns for proxy tables.
- `select into existing` brings the plain text from the source and inserts it into destination table. The local Adaptive Server then encrypts the plain text before insertion into any encrypted columns.

The following columns are updated from the remote server's syscolumns catalog:

- `enctype` – type of data on disk.
- `encrlen` – length of encrypted data.

- status2 – status bits that indicate that column is encrypted.

Remote server logins

To fully support remote logins, Client-Library provides connection properties that enable Component Integration Services to request a *server connection*. This connection is recognized at the receiving server as a server connection (as opposed to an ordinary client connection), allowing the remote server to validate the connection through the use of `sysremotelogins` as if the connection were made by a site handler.

Server connections are not enabled automatically. Instead, the SSO or DBA must request it by executing `sp_serveroption`:

```
exec sp_serveroption <server_name>,  
    'server login', true | false
```

You cannot change the server login property if the current server's `@@servername` global variable is NULL.

If the server login option is true, then Component Integration Services uses Client-Library connection properties to establish connections to the specified server.

Remote passwords specified by the client application are passed unchanged to the remote server. The use of and rules associated with remote passwords in server logins are identical to those associated with site handler connections.

These connection properties are only established if:

- The server option `server login` is set to true.
- The remote server is configured with server class `ASEnterprise`.
- There is a local server name defined for the Component Integration Services-enabled server (in other words the query `select @@servername` returns something other than NULL).

Trusted mode

Trusted mode can be used with Component Integration Services connections if “server logins” is set for a remote server.

Connecting to Backup Server and XP Server

Beginning with Adaptive Server 12.5.1, Component Integration Services can send RPCs to Backup Server or XP Server. Before doing so, the server option negotiated logins must be enabled:

```
exec sp_serveroption server_name, "negotiated logins",  
true
```

This allows Component Integration Services to respond to the login challenge initiated by either of these Sybase-provided servers.

Mapping external logins

Adaptive Server users who invoke Component Integration Services require login names and passwords to remote servers. By default, the user name and password pair used by Component Integration Services to connect to a remote server is the same as is used by the client to connect to Adaptive Server.

Component Integration Services supports a one-to-one mapping of Adaptive Server login names and passwords to remote server login names and passwords. For example, using the stored procedure `sp_addexternlogin`, it is possible to map Adaptive Server user `steve`, password `sybase` to Oracle login name `login1`, password `password1`:

```
sp_addexternlogin Oracle, steve, login1, password1
```

In Adaptive Server version 12.5 and later, you can provide a many-to-one mapping so that all Adaptive Server users who need an Oracle connection can be assigned the same name and password:

```
sp_addexternlogin Oracle, NULL, login2, password2
```

One-to-one mapping has precedence, so that if user `steve` has an external login for Oracle, that would be used rather than the many-to-one mapping.

In addition, you can assign external logins to Adaptive Server roles. With this capability, anyone with a particular role can be assigned a corresponding login name/password for any given remote server:

```
sp_addexternlogin Oracle, null, login3, password3, rolename
```


The role name identifies the name of a role, rather than the name of a user. When a user with this role active requires a connection to Oracle, the appropriate login name/password for the role is used to establish the connection. When establishing a connection to a remote server for a user who has more than one role active, each role is searched for an external login mapping, and the first mapping found is used to establish the login. This is the same order as displayed by `sp_activeroles`.

The general syntax for `sp_addexternlogin` is:

```
sp_addexternlogin
  <servername>,
  <loginname>,
  <external_loginname>,
  <external_password>
  [, <rolename>]
```

`<rolename>` is optional; if specified then `loginname` is ignored.

Precedence for these capabilities are as follows:

- If one-to-one mapping is defined, it is used.
- If no one-to-one mapping is defined, and a role is active and a mapping for it can be found, the role mapping is used to establish a remote connection.
- If neither of the above are true, then many-to-one mapping is used if defined.
- If none of the above is true, then the Adaptive Server login name and password are used to make the connection.

If role mapping is done, and a user's role is changed (via `set role`), any connections made to remote servers that used role mapping are disconnected.

`sp_helpexternlogin` has been updated to allow viewing the various types of external logins that have been added using `sp_addexternlogin`. The syntax for `sp_helpexternlogin` is:

```
sp_helpexternlogin [<servername> [,<loginname> [,<rolename>]]]
```

All three parameters are optional, and any of the parameters can be NULL.

The stored procedure `sp_dropexternlogin` also accepts the `<rolename>` argument. If `<role name>` is specified then the second argument, `<login name>`, is ignored.

Remote server connection failover

If the interfaces file (or LDAP directory service) is set up to define a failover configuration, then Component Integration Services takes advantage of it by automatically failing over connections to the failover server if a connection to the primary server fails.

You can set up remote servers for failover after performing these configuration steps:

- 1 Enable new server option `cis hafailover`:

```
exec sp_serveroption server_name, 'cis hafailover',  
true
```

- 2 Modify directory services (interfaces file or server entries in the LDAP server) to specify a failover server

For example, you can configure server S2 to serve as a failover server for S1, and vice-versa, by additions to the interfaces file, as shown in this example:

```
S1  
  master tcp ether host1 8000  
  query tcp ether host1 8000  
  hafailover S2  
S2  
  master ether host2 9000  
  query ether host2 9000  
  hafailover S1
```

See *Using Sybase Failover in a High Availability System*, Appendix C, for more discussion of the `CS_HAFAILOVER` connection property. Component Integration Services uses the `ct_con_props()` API to set this property, if the `cis hafailover` server option is true.

Remote server capabilities

The first time Adaptive Server establishes a connection to a remote server of class `sds` or `direct_connect`, it issues an RPC named `sp_capabilities` and expects a result set in return. This result set describes functional capabilities of the remote server so that Component Integration Services can adjust its interaction with that remote server to take advantage of available features. Component Integration Services forwards as much syntax as possible to a remote server, according to its capabilities.

Query processing

This section describes query processing within Component Integration Services.

Processing steps

The query processing steps taken when Component Integration Services is enabled are similar to the steps taken by Adaptive Server, except for the following:

- If a client connection is made in passthrough mode, the Adaptive Server query processing is bypassed and the SQL text is forwarded to the remote server for execution.
- When select, insert, delete, or update statements are submitted to the server for execution, additional steps may be taken by Component Integration Services to improve the query's performance, if local proxy tables are referenced.

An overview of the query processing steps follows.

Query parsing

The SQL parser checks the syntax of incoming SQL statements, and raises an error if the SQL being submitted for execution is not recognized by the Transact-SQL parser.

Query normalization

During query normalization, each object referenced in the SQL statement is validated. Query normalization verifies the objects referenced in the statement exist, and the datatypes are compatible with values in the statement.

Example

```
select * from t1 where c1 = 10
```

The query normalization stage verifies that table t1 with a column named c1 exists in the system catalogs. It also verifies that the datatype of column c1 is compatible with the value 10. If the column's datatype is datetime, for example, this statement is rejected.

Query preprocessing

Query preprocessing prepares the query for optimization. It may change the representation of a statement such that the SQL statement Component Integration Services generates is syntactically different from the original statement.

Preprocessing performs view expansion, so that a query can operate on tables referenced by the view. It also takes steps such as reordering expressions and transforming subqueries to improve processing efficiency. For example, subquery transformation may convert some subqueries into joins.

Decision point

After preprocessing, a decision is made as to whether Component Integration Services or the standard Adaptive Server query optimizer handles optimization.

Component Integration Services handles optimization (using a feature known as quickpass mode) when:

- Every table represented in the SQL statement resides within a single remote server.
- The remote server is capable of processing all the syntax represented by the statement.

Component Integration Services determines the query processing capabilities of the remote server by its server class. For example, Component Integration Services assumes that any server configured as server class `sql_server` is capable of processing all Transact-SQL syntax.

For remote servers with server class `direct_connect`, Component Integration Services issues an RPC to ask the remote server for its capabilities the first time a connection is made to the server. Based on the server's response to the RPC, Component Integration Services determines the syntax of the SQL it forwards to the remote server.

- The following is true of the SQL statement:
 - It is a select, insert, delete, or update statement.
 - If it is an insert, update, or delete statement, there are no identity or timestamp columns, or referential constraints.
 - It contains no text or image columns.
 - It contains no compute by clauses.

- It contains no for browse clauses.
- It is not a select...into statement.
- It is not a cursor-related statement (for example, fetch, declare, open, close, deallocate, update, or delete statements that include where current of cursor).
- The remote connection does not include a cursor opened on the remote server.

If the above conditions are not met, quickpass mode cannot be used, and the standard Adaptive Server query optimizer handles optimization.

Component Integration Services plan generation

If quickpass mode can be used, Component Integration Services produces a simplified query plan. When statements contain proxy tables, they are executed more quickly when processed by the remote server than when processed through the Adaptive Server plan generation phase.

Adaptive Server optimization and plan generation

Adaptive Server optimization and plan generation evaluates the optimal path for executing a query and produces a query plan that tells the Adaptive Server how to execute the query.

If the update statistics command has been run for the tables in the query, the optimizer has sufficient data on which to base decisions regarding join order. If update statistics has not been run, the Adaptive Server defaults apply.

For more information on Adaptive Server optimization, see Chapter 7, “The Adaptive Server Query Optimizer,” in the *Performance and Tuning Guide*.

Component Integration Services plan generation

If quickpass mode can be used, Component Integration Services produces a simplified query plan in which the entire statement is pushed to a remote server.

If quickpass mode cannot be used, the Adaptive Server optimizer generates a plan for executing the entire statement. This plan is then examined and portions of the plan are chosen to be pushed off to remote servers. As much of the original plan is pushed off as is possible based on the locations of the tables and the capabilities of the remote servers. The remote statement may come very close to the original statement for a fully capable remote server. A more minimal statement may be produced for other servers with the local Adaptive Server executing the portion of the plan that could not be sent.

For example, if a client entered the statement:

```
select a,b from table1 where cos(a) > 0 and sin(b) > 0
```

If the remote server that owned table1 supported cos() but not sin(), the statement sent to the remote server would be:

```
select a,b from table1 where cos(a) > 0
```

The local server would then have a plan that would apply the check for sin(b) > 0 to the result set returned by the remote server.

Component Integration Services remote location optimizer

Adaptive Server generates a query plan containing the optimal join order for a multi-table query without regard to the storage location of each table. If remote tables are represented in the query, Component Integration Services performs additional optimization taking location into account and possibly rearranging the plan for a join order that allows part of the join to be executed remotely.††

Statistics

To make intelligent plan choices, statistics are required for all tables involved in the query, including proxy tables. These are obtained by executing update statistics for a specific table.

If update statistics has not been run, the Adaptive Server defaults apply. For more information on Adaptive Server optimization, see Chapter 7, “The Adaptive Server Query Optimizer,” in the *Performance and Tuning Guide*.†

Optimizer cost model for proxy tables

The Adaptive Server optimizer incorporates the cost of network access to remote servers based on a “network exchange” unit which specifies the time required to execute the sequence:

- Open a cursor

- Fetch 50 rows
- Close a cursor

The cost of a single exchange is under the user's control, and is specified on a per-server basis, defaulting to 1000 milliseconds, by `sp_serveroption`:

```
sp_serveroption <servername>, "server cost", "nnnn"
```

where *nnnn* is a string of numeric digits representing the number of milliseconds to be used per exchange during the optimizer's calculation of network cost.

Note The server cost limit is 32767. If you exceed that limit, an arithmetic overflow error occurs.

When a new server is added to `sys.servers` using `sp_addserver`, the default cost, 1000 milliseconds, is stored in `sysattributes` for that server. `sp_serveroption` can be used to specify a greater or lesser cost for a given server. `sp_helpserver` shows the current network cost associated with the server.†

Query plan execution

Any command that can affect a table is checked by the server to determine whether the object has a local or remote storage location. If the storage location is remote, then the appropriate access method is invoked when the query plan is executed in order to apply the requested operation to the remote objects. The following commands are affected if they operate on objects that are mapped to a remote storage location:

- alter table
- begin transaction
- commit
- create index
- create table
- create existing table
- deallocate table
- declare cursor
- delete
- drop table

- drop index
- execute
- fetch
- insert
- open
- prepare transaction
- readtext
- rollback
- select
- set
- setuser
- truncate table
- update
- update statistics
- writetext

RPC handling and Component Integration Services

When Component Integration Services is enabled, you can choose between the site handler or Component Integration Services to handle outbound remote procedure calls (RPCs). Each of these mechanisms is described in the following sections.

Site handler and outbound RPCs

Within an Adaptive Server, outgoing RPCs are transmitted by means of a site handler, which multiplexes multiple requests through a single physical connection to a remote server. The RPC is handled as part of a multistep operation:

- 1 Establish connection – the Adaptive Server site handler establishes a single physical connection to the remote server. Each RPC requires that a logical connection be established over this physical connection. The logical connection is routed through the site handler of the intended remote server.

The connection validation process for these connect requests is different from that of normal client connections. First, the remote server must determine if the server from which the connect request originated is configured in its `sys.servers` table. If so, then the system table `sys.remotelogins` is checked to determine how the connect request should be handled. If trusted mode is configured, password checking is not performed. (For more information about trusted mode, see “Trusted mode” on page 41.)

- 2 Transmit the RPC – the RPC request is transmitted over the logical connection.
- 3 Process results – all results from the RPC are relayed from the logical connection to the client.
- 4 Disconnect – the logical connection is terminated.

Because of the logical connect and disconnect steps, site handler RPCs can be slow.

Component Integration Services and outbound RPCs

If Component Integration Services has been enabled, a client can use one of two methods to request that Component Integration Services handle outbound RPC requests:

- Configure Component Integration Services to handle outbound RPCs as the default for all clients by issuing:

```
sp_configure "cis rpc handling", 1
```

If you use this method to set the `cis rpc handling` configuration parameter, all new client connections inherit this behavior, and outbound RPC requests are handled by Component Integration Services. This is a server property inherited by all future connections. The client can, if necessary, revert back to the default Adaptive Server behavior by issuing the command:

```
set cis_rpc_handling off
```

- Configure Component Integration Services to handle outbound RPCs for the current connection only by issuing:

```
set cis_rpc_handling on
```

This command enables cis rpc handling for the current thread only, and does not affect the behavior of other threads.

When cis rpc handling is enabled, outbound RPC requests are not routed through the Adaptive Servers site handler. Instead, they are routed through Component Integration Services, which uses persistent Client-Library connections to handle the RPC request. Using this mechanism, Component Integration Services handles outbound RPCs as follows:

- 1 Determines whether the client already has a Client-Library connection to the server in which the RPC is intended. If not, establish one.
- 2 Sends the RPC to the remote server using Client-Library functions.
- 3 Relays the results from the remote server back to the client program that issued the RPC using Client-Library functions.

RPCs can be included within a user-defined transaction. In fact, all work performed by Component Integration Services on behalf of its client can be performed within a single connection context. This allows RPCs to be included in a transaction's unit of work, and the work performed by the RPC can be committed or rolled back with the other work performed within the transaction.

The benefits of using Component Integration Services to handle outbound RPC requests are as follows:

- Client-Library connections are persistent so that subsequent RPC requests can use the same connection to the remote server. This can result in substantial RPC performance improvements, since the connect and disconnect logic is bypassed for all but the first RPC.
- Work performed by an RPC can be included in a transaction, and is committed or rolled back with the rest of the work performed by the transaction. This transactional RPC behavior is currently supported only when the server receiving the RPC is another Adaptive Server or a DirectConnect which supports transactional RPCs.

- Connect requests appear to a remote server as ordinary client connections. The remote server cannot distinguish the connection from a normal application's connection, unless server logins are enabled. This affects the remote server management capabilities of an Adaptive Server, since no verification is performed against `sysremotelogins`, and all connections must have valid Adaptive Server login accounts established prior to the connect request (trusted mode cannot be used in this case).

Text parameters for RPCs

Adaptive Server can send large chunks of data in a single remote procedure call. This is done by treating certain parameters as text pointers, then dereferencing these text pointers to obtain the text values associated with them. The text data is then packaged into 16K chunks for Adaptive Server and 32K chunks for all other servers, and handed to Client-Library as parameters to the RPC.

A text pointer is identified as a parameter of type `binary(16)` or `varbinary(16)`. The text value referenced by each text pointer parameter is obtained when the RPC is executed, and expanded into 16K chunks for Adaptive Server and 32K chunks for all other servers, each of which is passed to Client-Library as a parameter of type `CS_LONGCHAR_TYPE`.

This behavior is triggered by this set command:

```
set textptr_parameters ON
```

When an RPC is requested (`cis_rpc_handling` must be on), text pointers are dereferenced in the Component Integration Services layer, and the text value obtained is used to construct one or more parameters for Client-Library.

For this to work, the text pointers must be preceded by a path name argument, which is used to identify the table from which the text pointers have been derived. For example:

```
declare @pathname varchar(90)
declare @textptr1 binary(16)
declare @textptr2 binary(16)
select @pathname = "mydatabase.dbo.t1",
       @textptr1 = textptr(c1),
       @textptr2 = textptr(c2)
from mydatabase.dbo.t1
where ... (whatever)
set textptr_parameters ON
exec SYBASE...myrpc @pathname, @textptr1, @textptr2
set textptr_parameters OFF
```

When the RPC named 'myrpc' gets sent to server SYBASE, the *@pathname* parameter is not actually sent, but is used to help locate the text values referenced by the textptr's *@textptr1* and *@textptr2*.

The varchar parameter *@pathname* must immediately precede the binary(16) parameter, otherwise *@textptr1* is considered an ordinary parameter and is transmitted to the server SYBASE as a normal binary(16) value.

The text will be broken into 16K or 32K chunks, each of which is a separate parameter of type CS_LONGCHAR_TYPE.

The current value of *@textsize* is ignored.

This scheme is also designed to work with proxy tables mapped to remote procedures. For example:

```

create existing table myrpctable
(
    id int,      -- result column
    crdate datetime, -- result column
    name varchar(30), -- result column
    _pathname varchar(90), -- parameter column
    _textptr1 binary(16), -- parameter column
    _textptr2 binary(16), -- parameter column
) external procedure at 'SYBASE...myrpc'
go
declare @textptr1 binary(16)
declare @textptr2 binary(16)
select @textptr1 = textptr(c1), @textptr2 = textptr(c2)
from mydatabase.dbo.t1 where <whatever>
set textptr_parameters ON
select id, crdate, name
from myrpctable
where _pathname = "mydatabase.dbo.t1" and
    _textptr1 = @textptr1 and
    _textptr2 = @textptr2
    
```

When the query against the proxy table myrpctable is processed, Component Integration Services sends an RPC named 'myrpc' to the server 'SYBASE'. The parameters will be derived from the search arguments contained in the where clause of the query. Since the textptr_parameter option has been set ON, the textptrs are expanded to CS_LONGCHAR_TYPE, as in the case of the RPC example shown previously.

Text parameter support for XJS/390

Because of the ability to forward large blocks of text as RPC parameters, it is now possible for Component Integration Services to interact with IBM mainframes using XJS/390. XJS/390 scripts (JavaScript-like syntax) can be stored within Adaptive Server tables (or files accessible via proxy tables), and forwarded to the mainframe using an RPC. The syntax of the script is analyzed and executed by XJS/390 facilities, and result sets are generated according to the procedural logic of the script.

Several features are enabled:

- Database events within Adaptive Server can result in the generation of an MQ Series message. Since XJS/390 Mscript supports the generation of messages, an RPC can be sent to the mainframe to request that such a message be generated in response to a triggered event within the database.
- Component Integration Services users have access to VSAM, IMS, and MQSeries data without the need to install third-party middleware such as InfoHub.

Version 2.0 or later of XJS/390 is required for handling scripts as RPC parameters. See the XJS/390 specification for details.

Distributed Transaction Management

Distributed Transaction Management within Adaptive Server tracks the state of a transaction in the local Adaptive Server/Component Integration Services, as well as in all remote servers participating in transactions. When a user application commits a transaction, the commit is propagated to all participating remote servers using Adaptive Server Transaction Coordinator (ASTC). The management of multisite transactions is handled by ASTC in cooperation with Component Integration Services. Component Integration Services registers new participating servers for each transaction, then turns over control of the transaction coordination to ASTC, which calls back into Component Integration Services to execute various commands for transaction management.

Server classes and ASTC

Internally, ASTC views a server as either:

- DTM-enabled
- Pre-DTM

These types map to the three sets of callbacks used, and map to server classes as indicated in Table 2-5:

Table 2-5: Transaction capabilities

ASTC server type	Component Integration Services server class
DTM-enabled	ASEnterprise (12.x or later) DC/Oracle 12.5 or later
Pre-DTM	ASEnterprise (pre-12.0) ASAnywhere ASIQ other Direct Connect sds

Note Before starting a distributed transaction, the local server must be named. @@servername cannot be null.

DTM-enabled servers

Remote servers that are “DTM-enabled” support the full two-phase commit service enabled by ASTC. Servers that support this must allow a separate connection (or session) to either commit or roll back a transaction that was begun by another session. This capability is necessary if the commit coordinator (ASTC) is required to connect to a remote site and commit or roll back in-doubt transactions. Adaptive Server 12.0 and later provide this support, as does DirectConnect for Oracle 12.5 or later.

Pre-DTM servers

Remote servers that are classified as “pre-DTM” are those that support transaction management statements such as begin tran, commit tran, rollback tran, but does not support one session’s ability to commit or rollback a transaction started by another session.

Component Integration Services makes every effort to manage user transactions for pre-DTM servers reliably. However, different access methods incorporated into the server allow varying degrees of support for this capability. The general logic described below is employed by server classes ASEnterprise (prior to 12.0), ASAnywhere, ASIQ, direct_connect, and sds if the Specialty Data Store supports transaction management. The method for managing transactions involving remote servers uses a two-phase commit protocol. Adaptive Server implements a strategy that ensures transaction integrity for most scenarios. However, there is still a chance that a distributed unit of work will be left in an undetermined state. Even though two-phase commit protocol is used, no recovery process is included. The general logic for managing a user transaction is as follows:

Component Integration Services prefaces work to a remote server with a begin transaction notification. When the transaction is ready to be committed, Component Integration Services sends a prepare transaction notification to each remote server that has been part of the transaction. prepare transaction pings the remote server to determine whether the connection is still viable. If a prepare transaction request fails, all remote servers are told to roll back the current transaction. If all prepare transaction requests are successful, the server sends a commit transaction request to each remote server involved with the transaction. Any command preceded by begin transaction can begin a transaction. Other commands are sent to a remote server to be executed as a single, remote unit of work.

strict DTM enforcement

To ensure complete two-phase commit capability, ASTC uses the concept of strict dtm enforcement. When enabled, strict dtm enforcement causes a transaction to abort if an attempt is made to include a pre-DTM server in the transaction.

enable xact coordination

ASTC uses the configuration option enable xact coordination. This option, enabled by default, allows ASTC to manage all transactions involving remote servers. You must enable Component Integration Services before xact coordination is enabled. While xact coordination is enabled, Component Integration Services cannot be disabled. When xact coordination is enabled, transactional_rpcs are implicitly enabled.

Enable Component Integration Services

ASTC relies on Component Integration Services to handle all communication with remote servers. Since ASTC is enabled by default (enable xact coordination), Component Integration Services is also enabled by default.

Transactional RPCs

The server allows RPCs to be included within the unit of work initiated by the current transaction.

Before using transactional RPCs, issue the set transactional_rpc on command.

Assuming that the remote server can support the inclusion of RPCs within transactions, the following syntax shows how this capability might be used:

```
begin transaction
insert into t1 values (1)
update t2 set c1 = 10
execute @status = SYBASE.pubs2.dbo.myproc
if @status = 1
    commit transaction
else
    rollback transaction
```

In this example, the work performed by the procedure *myproc* in server SYBASE is included in the unit of work that began with the begin transaction command. This example requires that the remote procedure *myproc* return a status of “1” for success. The application controls whether the work is committed or rolled back as a complete unit.

The server that is to receive the RPC must allow RPCs to be included in the same transactional context as Data Manipulation Language (DML) commands (select, insert, delete, update). This is true for Adaptive Server and is expected to be true for most DirectConnect products released by Sybase. However, some database management systems may not support this capability.

Restrictions on transaction management

If nested begin transaction and commit transaction statements are included in a transaction that involves remote servers, only the outermost set of statements is processed. The innermost set, containing the begin transaction and commit transaction statements, is not transmitted to remote servers.

Adaptive Server to Adaptive Server update statistics

When you perform update statistics on a remote server proxy table, if the relevant tables, index and column statistics are available, the table catalogs are imported to the local systabstats and sysstatistics.

By default, update statistics for proxy tables always attempts to import the required statistics data. But when the statistics data is unavailable or incomplete on the remote table, Component Integration Services (CIS) reverts to the prior mechanism of gathering statistic data.

You can also force CIS to revert to the prior mechanism of gathering statistic data by turning on Traceflag 11229. This allows you to obtain all data from the database, then calculating the statistics.

Note This is the behavior if update statistics has not been run on the remote tables and there are no statistics available.

Limitations

Key limitations:

- The proxy table must be mapped to another Adaptive Server version 11.9 or later.
- Excludes proxy tables mapped to RPCs, external files, and system directories.
- If the remote servers are not Adaptive Server Enterprise version 11.9 or later, or of another server class, CIS continues to obtain statistics data using prior mechanisms.

Updating statistics on non-Adaptive Server backends

The update statistics command helps the server make the best decisions about which indexes to use when it processes a query, by providing information about the distribution of the key values in the indexes. update statistics does not automatically run when you create or re-create an index on a table that already contains data. It can be used when a large amount of data in an indexed column has been added, changed, or deleted. The crucial element in query optimization is the accuracy of the distribution steps. If there are significant changes in the key values in the index, re-run update statistics on that index.

Only the table owner or the system administrator can issue the update statistics command.

The syntax is:

```
update statistics table_name [index_name]
```

Because running update statistics is resource intensive, try to run update statistics at a time when the tables you specify are not heavily used. update statistics acquires locks on the remote tables and indexes as it reads the data. If you use trace flag 11209, tables are not locked.

You can set update statistics to run automatically at the time that best suits your site and avoid running it at times that hamper your system. For more information see Chapter 4, “Using Statistics to Improve Performance” in the *Performance and Tuning Guide: Monitoring and Analyzing*.

The server performs a table scan for each index specified in the update statistics command.

Since Transact-SQL does not require index names to be unique in a database, you must give the name of the table with which the index is associated.

After running update statistics, run sp_recompile so triggers and procedures that use the indexes use the new distribution:

```
sp_recompile authors
```

Java in the database

Java in the database is supported for remote data access with Component Integration Services.

The following restrictions apply:

- Java is supported for remote Adaptive Server 12.x and later only.
- Java is supported for language events only (no dynamic SQL can be used with remote tables.)

Before using Java for remote data access, read “Java class definitions” on page 63. Then, after installing your Java class files on the local server, install the required Java class files on the remote server.

@@textsize

Data is returned as a serialized Java object using the image datatype format and then deserialized on the local server. @@textsize must be set large enough to hold the serialized object. If @@textsize is set too small, the object is truncated, and the deserialization fails.

@@stringize

@@stringize indicates the amount of character data to be returned from a toString() method. It is similar in behavior to @@textsize, except it applies only the char data returned by the Java Object.toString() method. The default value is 50. The maximum value is 16384. A value of zero means “use the default.” This value can be modified by a set command:

```
set stringize n
```

where *n* is an integer value between 0 and 16384. The value immediately displays in the global variable @@stringize.

Constraints on Java class columns

Constraints defined on Java columns of remote tables must be checked on the remote server. If the constraint checking is attempted on the local server, it fails. Therefore, you must enable trace flag 11220 when you insert, update, or delete data for which constraint checking is done on Java datatypes. See “Trace flags” on page 78.

Error messages

There are two error messages that are specific to Java use with remote data access:

- Error 11275 – a statement referencing an extended datatype contained syntax that prevented it from being sent to the remote server. Rewrite the statement or remove the extended datatype reference.
- Error 11276 – an object in column '<colname>' could not be deserialized, possibly because the object was truncated. Check that the value of @@textsize is large enough to accommodate the serialized object.

Java abstract datatypes (ADTs)

Java Classes in SQL (JCS) is the method of storing and using Java objects within the Adaptive Server. Component Integration Services interaction in this implementation is needed to support Java objects and Java functions on remote servers.

Component Integration Services supports JCS on remote Adaptive Server version 12.0 or later.

Objects are passed between the local and remote servers in a serialized format that is a binary representation used to reinstantiate the object. Component Integration Services treats a serialized object as an image blob, using text and image handling functions to pass objects between servers. The object is reinstated on the destination server before processing continues.

When handling queries containing references to Java objects and functions on remote servers, Component Integration Services attempts to forward as much syntax as possible to the remote server. Any portion of the query that cannot be passed to the remote server is handled on the local server, requiring the serialization and deserialization of all necessary remote objects. Due to the overhead associated with serializing and deserializing Java objects, performance of such queries is significantly less than comparable local access.

To facilitate the interchange of Java objects between servers, Component Integration Services issues:

```
set raw_object_serialization ON
```

to each ASEnterprise server that is Java-enabled. This allows Component Integration Services to easily deserialize the object obtained from the remote site.

Java class definitions

The Java class definitions on the local and remote servers must be compatible to facilitate passing objects between servers. For this reason, Component Integration Services assumes that compatibility exists, and any errors in object definition are detected during deserialization efforts. Objects are considered compatible if the serialized form of the object on the remote server can be used to successfully instantiate an object on the local server, or vice versa. Also, any Java method referenced in the local server in conjunction with a remotely mapped object must be defined on the remote object as well.

It is the responsibility of the database administrator to ensure that class definitions on local and remote servers are compatible. Incompatible objects and invalid method references result in deserialization errors or Java exceptions that cancel the requesting query.

To improve overall performance, increase the `is packet size` configuration variable to better facilitate passing serialized objects between servers. Serialized objects are passed between servers with an `image` datatype, and can vary in size from a few bytes to 2GB.

Datatypes

This section discusses how Component Integration Services deals with various datatype issues.

Unicode support

Adaptive Server contains formal support for the Unicode character set. The datatypes provided are `unichar`, `univarchar`, and `unitext`. They comprise 2-byte characters expressed in Unicode. Adaptive Server provides conversion functions between Unicode data and all other datatypes, consistent with current handling of `char` and `varchar` datatypes. By supporting these datatypes, Component Integration Services is able to present a view of all enterprise character data expressed in Unicode. Character data from mainframes and all other foreign or legacy systems is converted to Unicode when columns of type `unichar` or `univarchar` are used to defined columns in proxy tables.

The Component Integration Services features below are affected by these new datatypes:

create table

create table may contain columns described using the new Unicode datatypes. If the table to be created is a proxy table, Component Integration Services forwards the entire command, including the Unicode datatype names (unichar, univarchar, and unitext) to the remote server where the new table is to be created. If the remote server cannot handle the datatypes, it raises an error.

create existing table

When comparing Adaptive Server column types and lengths with the metadata obtained from a remote server, Unicode datatypes in the proxy table are allowed under the following circumstances:

- The remote server datatype for a column is unichar, unitext, or univarchar with equal length (expressed in characters, not bytes).
- The remote server datatype for a given column is char or varchar. In this case, Component Integration Services performs conversions to Unicode on data fetched from the remote server, and conversions from Unicode to the default Adaptive Server character set (UTF8) on data transmitted as part of DML commands (select, insert, delete, update).
- The remote server datatype for a Unicode column is binary or varbinary. The length of the remote server column must be twice the length of the Unicode column. Component Integration Services performs conversions as required when transmitting data to or from the remote server.

No other datatype mapping for Unicode datatypes is allowed when mapping a proxy table to a remote table. Other types result in a type mismatch error. You can convert data from legacy systems into Unicode simply by creating a proxy table that maps a Unicode column to an existing char or varchar column.

Note Unicode can only be mapped to unitext columns using the create existing table command.

create proxy_table

By using `create proxy_table`, an Adaptive Server user does not have to specify the column list associated with the proxy table. Instead, the column list is derived from column metadata imported from the remote server on which the actual table resides. Unicode columns from the remote server are mapped to Unicode columns in the proxy table only when the remote column is datatype `unicar`, `unitext`, or `univarchar`.

alter table

`alter table` allows column types to be modified. With Adaptive Server version 12.5 and later, a column's type can be modified to and from Unicode datatypes. If the command operates on a proxy table, the command is reconstructed and forwarded to the remote server that owns the actual table. If the remote server (or `DirectConnect`) cannot process the command, an error is expected, and the Adaptive Server command is aborted.

If trace flag 11221 is on, `alter table` does not get forwarded to a remote server; adding, deleting, or modifying columns is done locally on the proxy table only.

Using the `alter table` command, `unitext` can be changed to `char`, `varchar`, `nchar`, `nvarchar`, `unicar`, `univarchar`, `binary`, and `varbinary`. Any of these datatypes can be changed to `unitext`.

select, insert, update, and delete statements

Unicode datatypes impact the processing of `select` statements in two ways when proxy tables are involved. The first involves the construction of SQL statements and parameters that are passed to remote servers; the second involves the conversion of data to Unicode when Component Integration Services fetches non-Unicode data.

A DML command involving a proxy table is handled using either TDS language requests or TDS cursor requests when interacting with the remote server. If a `select` statement contains predicates in the `where` clause that involve Unicode columns and constants, the Unicode constants must be handled in one of two ways, depending on whether language or cursor commands are used to process the statement:

- 1 TDS language – generate clear-text values that can be included in the language text buffer. This involves converting a constant Unicode value to clear text values that can be transmitted as part of a language request.

- 2 TDS cursor – generate Unicode parameters for CT-Library cursor requests. Parameter values may be Unicode data, requiring Component Integration Services to use parameter types of CS_UNICHAR_TYPE.

Component Integration Services handles an insert command involving a proxy table using either TDS language requests or TDS dynamic requests.

If the insert command can be processed in quickpass mode, then TDS language requests are used. If the command cannot be handled in quickpass mode, the insert is processed using TDS Dynamic requests.

In language requests, the issues are the same as with select — Unicode values must be converted to clear-text form so they can be transmitted with the rest of the SQL statement. In dynamic requests, Unicode data (along with all other data values) is transmitted as parameters to the dynamic command. The receiving server is expected to process parameters of type CS_UNICHAR_TYPE.

The issues with update and delete commands are the same as for select and insert. Unicode values must be converted either to clear-text characters for transmission with the rest of the SQL statement, or they must be converted into parameters of type CS_UNICHAR_TYPE.

Datatype conversions

Datatype conversion can take place whenever the server receives data from a remote source, be it Adaptive Server, or an Open Server-based application.

Depending on the remote datatype of each column, data is converted from the native datatype on the remote server to a form that the local server supports.

Datatype conversions are made when the create table, alter table and create existing table commands are processed. The datatype conversions are dependent on the remote server's server class. See the create table, alter table, and create existing table commands Chapter 3, "SQL Reference," for tables that illustrate the datatype conversions that take place for each server class when the commands are processed.

text and image datatypes

The text datatype is used to store printable character data, the column size of which depends on the logical page size of the Adaptive Server. The image datatype is used to store a number of bytes of hexadecimal-encoded binary data that, again, depends on the logical page size of the Adaptive Server. The maximum length for text, image, and unitext data is defined by the server class of the remote server to which the column is mapped.

Note unitext with Component Integration Services is only supported for Adaptive Server version 15.0 and higher.

Restrictions on text, image, and unitext columns

text, image, and unitext columns cannot be used:

- As parameters to stored procedures, except when set textptr_parameters is on
- As local variables
- In order by, compute, or group by clauses
- In indexes
- In subqueries
- In where clauses, except with the keyword like
- In joins

Limits of @@textsize

select statements return text, image, and unitext data up to the limit specified in the global variable @@textsize. The set textsize command is used to change this limit. The initial value of @@textsize is 32K; the maximum value for @@textsize is 2147MB.

Odd bytes padded

image values of less than 255 bytes that have an odd number of bytes are padded with a leading zero (an insert of "0xaaabb" becomes "0x0aaabb"). It is an error to insert an image value of more than 255 bytes if the value has an odd number of bytes.

Converting *text* and *image* datatypes

You can explicitly convert text values to char or varchar and image values to binary or varbinary with the convert function, but you are limited to the maximum length of the character and binary datatypes, which depends on the logical page size of the Adaptive Server. If you do not specify the length, the converted value has a default length of 30 bytes. Implicit conversion is not supported.

Pattern matching with *text* and *unitext* data

Use the patindex function to search for the starting position of the first occurrence of a specified pattern in a text, unitext, varchar, or char column. The % wildcard character must precede and follow the pattern (except when you are searching for the first or last character).

You can use the like keyword to search for a particular pattern. This example selects each text data value from the blurb column of the texttest table that contains the pattern “Straight Talk%”:

```
select blurb from texttest
where blurb like "Straight Talk%"
```

You can use the keyword like to search a unitext column for a specific pattern. However, the like clause is not optimized when it is used with a unitext column. like pattern matching for unitext depends on the default Unicode sort order, which is also used for like pattern matching for unichar and univarchar datatypes.

Entering *text* and *image* values

The DB-Library™ functions dbwritetext and dbmoretext and the Client-Library function ct_send_data are the most efficient ways to enter text, unitext, and image values.

readtext using bytes

If you use the readtext using bytes command on a text column, and the combination of size and offset result in the transmission of a partial character, errors result.

text, image, and unitext with bulk copy

When you use bulk copy to copy text, unitext, and image values to a remote server, the server must store the values in data pages before sending them to the remote server. Once the values have been issued to the remote server, the data pages are released. Data pages are allocated and released row by row. This is important because:

- The overhead of allocating and releasing data pages impacts performance.
- Data pages are allocated in the database where the table resides, so the database must be large enough to accommodate enough data pages for the largest text, unitext, and image values that exist for any given row.

Error logging

Processing of text, unitext, and image data (with remote servers only) can be logged by using trace flag 11207.

text, unitext, and image data with server class ASEnterprise

- A pointer in a text, unitext, or image column is assigned when the column is initialized. Before you can enter text, unitext, or image data into a column, the column must be initialized. This causes a 2K page to be allocated on the remote or Adaptive Server. To initialize text, unitext, or image columns, use the update with a NULL or a non-null insert command.
- Before you use writetext to enter text or unitext data or readtext to read it, the text or unitext, column must be initialized. Use update or insert non-null data to initialize the text column, and then use writetext and readtext.
- Using update to replace existing text, unitext, and image data with NULL reclaims all of the allocated data pages, except the first page, in the remote server.
- writetext, select into, DB-Library functions, or Client-Library functions must be used to enter text, unitext, or image values that are larger than 16KB.
- readtext is the most efficient way to access text, unitext, and image data.
- insert select and select into can be used to insert text, unitext, and image data to proxy tables, but a unique index is required.

text, image, and unitext data with server class direct_connect

- Specific DirectConnect servers support text and image data to varying degrees. See the DirectConnect documentation for information on text, unitext, and image support.
- The server uses the length defined in the global variable @@textsize for the column length. Before issuing create table, the client application should set @@textsize to the required length by invoking set textsize.
- For DirectConnect servers that support text, unitext, and image datatypes but do not support text pointers, the following restrictions apply:
 - The writetext command is not supported.
 - The readtext command is not supported.
 - Client-Library functions that use text pointers are not supported.
 - DB-Library functions that use text pointers are not supported.
- For DirectConnect servers that support text, unitext, and image datatypes but do not support text pointers, some additional processing is performed to allow the following functions to be used:
 - patindex
 - char_length
 - datalength

If text pointers are supported, the server performs these functions by issuing an RPC to the DirectConnect server.

- For DirectConnect servers that do not support text pointers, the server stores data in the sysattributes system table. Data pages are preallocated on a per column per row basis. The column size is determined by @@textsize. If this value is not sufficient an error is returned.
- Specific DirectConnect servers may or may not support pattern matching against the text datatype. If a DirectConnect server does not support this pattern matching, the server copies the text value to internal data pages and performs the pattern matching internally. The best performance is seen when pattern matching is performed by the DirectConnect server.
- You must use writetext, select into, or insert...select to enter text, unitext, or image values that exceed 450 bytes.
- You can use select into and insert...select to insert text, unitext, or image values, but the table must have a unique index.

Configuration and tuning

This section provides information about configuration, tuning, trace flags, backup and recovery, and security issues.

The system administrator or database owner may elect to use the server to optimize performance or to allow use by a required number of clients. Configuration choices might involve being able to review total numbers of reads and writes for a given SQL command.

Once an application is up and running, the system administrator should monitor performance and may choose to customize and fine-tune the system. The server provides tools for these purposes. This section explains:

- Changing system parameters with the `sp_configure` procedure
- Using update statistics to ensure that Component Integration Services makes the best use of existing indexes
- Monitoring server activity with the `dbcc` command
- Setting trace flags
- Executing `ddlgen` and related backup and recovery issues
- Determining database size requirements

Using `sp_configure`

The configuration parameters in `sp_configure` control resource allocation and performance. The system administrator can reset these configuration parameters to tune performance and redefine storage allocation. In the absence of intervention by the system administrator, the server supplies default values for all the parameters.

The procedure for resetting configuration parameters is:

- Execute `sp_configure`, which updates the values field of the system table `master..sysconfigures`.
- Restart the server if you have reset any of the static configuration parameters. The parameters listed below are dynamic:
 - `cis rpc handling`
 - `cis cursor rows`
 - `cis bulk insert batch size`

- cis bulk insert array size
- cis packet size

sysconfigures table

The master.sysconfigures system table stores all configuration options. It contains columns identifying the minimum and maximum values possible for each configuration parameter, as well as the configured value and run value for each parameter.

The status column in sysconfigures cannot be updated by the user. Status 1 means dynamic, indicating that new values for these configuration parameters take effect immediately. The rest of the configuration parameters (those with status 0) take effect only after the reconfigure command has been issued and the server restarted.

You can display the configuration parameters currently in use (run values) by executing `sp_configure` without giving it any parameters.

Changing the configuration parameters

`sp_configure` displays all the configuration values when it is used without an argument. When used with an option name and a value, the server resets the configuration value of that option in the system tables.

See the *System Administration Guide* for a complete discussion of `sp_configure` with syntax options.

To see the Component Integration Services options, enter:

```
sp_configure "Component Integration Services"
```

To change the current value of a configuration parameter, execute `sp_configure` as follows:

```
sp_configure "parameter", value
```

Component Integration Services configuration parameters

The following configuration parameters are unique to Component Integration Services:

- enable cis
- enable file access

- enable full-text search
- max cis remote connections
- cis bulk insert batch size
- cis bulk insert array size
- cis cursor rows
- cis packet size
- cis rpc handling

enable cis	<p>Use this parameter with <code>sp_configure</code> to enable Component Integration Services as follows:</p> <ol style="list-style-type: none"> 1 Log in to Adaptive Server as the system administrator and issue the following command: <pre style="margin-left: 40px;">sp_configure "enable cis", 1</pre> 2 Restart Adaptive Server. <p>Issuing <code>sp_configure "enable cis", 0</code> disables Component Integration Services after restarting the server.</p>
enable file access	This configuration parameter enables access through proxy tables to eXternal File System.
enable full-text search	This configuration parameter enables Enhanced Full-Text Search services. Requires a license for ASE_EFTS.
max cis remote connections	A non-zero value indicates the number of connection data structures pre-allocated during server initialization. The default is zero.
cis bulk insert batch size	<p>This configuration parameter determines how many rows from the source tables are to be bulk copied into the target table as a single batch using <code>select into</code>, when the target table resides in an Adaptive Server or in a DirectConnect server that supports a bulk copy interface.</p> <p>If left at zero (the default), all rows are copied as a single batch. Otherwise, after the count of rows specified by this parameter has been copied to the target table, Component Integration Services issues a bulk commit to the target server, causing the batch to be committed.</p> <p>If a normal client-generated bulk copy operation (such as that produced by the <code>bcp</code> utility) is received, the client is expected to control the size of the bulk batch, and Component Integration Services ignores the value of this configuration parameter.</p>

cis bulk insert array size	<p>When performing a bulk transfer of data from one Adaptive Server to another, Component Integration Services buffers rows internally, and asks the Open Client bulk library to transfer them as a block. The size of the array is controlled by the configuration parameter <code>cis bulk insert array size</code>. The default is 50 rows, and the property is dynamic, allowing it to be changed without server reboot.</p>
cis cursor rows	<p>This configuration parameter allows users to specify the cursor row count for cursor open and cursor fetch operations. Increasing this value means more rows are fetched in one operation. This increases speed but requires more memory. The default is 50.</p>
cis packet size	<p>This configuration parameter allows you to specify the size of Tabular Data Stream™ (TDS) packets that are exchanged between Component Integration Services and a remote server when connection is initiated.</p> <p>The default packet size on most systems is 512 bytes, which is adequate for most applications. However, larger packet sizes may result in significantly improved query performance, especially when text and image or bulk data is involved.</p> <p>If a packet size larger than the default is specified, then the target server must be configured to allow variable-length packet sizes. Adaptive Server configuration parameters of interest in this case are:</p> <ul style="list-style-type: none">• <code>additional netmem</code>• <code>maximum network packet size</code>
cis rpc handling	<p>This global configuration parameter determines whether Component Integration Services handles outbound RPC requests by default. When this is enabled using <code>sp_configure "cis rpc handling" 1</code>, all outbound RPCs are handled by Component Integration Services. When you use <code>sp_configure "cis rpc handling" 0</code>, the Adaptive Server site handler is used. The thread cannot override it with <code>set cis_rpc_handling on</code>. If the global property is disabled, a thread can enable or disable the capability, as required.</p> <p>For more information on using the Adaptive Server site handler versus using Component Integration Services to handle outbound RPCs, see “RPC handling and Component Integration Services” on page 50.</p>

Global variables for status

The following global variables have been added for Component Integration Services users:

- @@cis_rpc_handling
- @@transactional_rpc
- @@textptr_parameters
- @@stringize
- @@bulkbatchsize – contains the value of the current cis bulk insert batch size configured via sp_configure, or set through the set bulk batch size command.
- @@bulkarraysize – contains the value of the current cis bulk insert array size configured via sp_configure or set through the set bulk array size command.

These global variables show the current status of the corresponding configuration parameters. For instance, to see the status of cis_rpc_handling, issue the following command:

```
select @@cis_rpc_handling
```

This returns either 0 (off) or 1 (on).

This chapter provides reference material on the server classes supported by Component Integration Services.

Topic	Page
dbcc commands	77
Functions	80
Transact-SQL commands	86
Passthrough mode	109
Quoted identifier support	114
Delimited identifier support	114
auto identity option	114
Triggers	115

Each server class has a set of unique characteristics that system administrators and programmers need to know about in order to configure the server for remote data access. These properties are:

- Types of servers that each server class supports
- Datatype conversions specific to the server class
- Restrictions on Transact-SQL statements that apply to the server class

***dbcc* commands**

All dbcc commands used by Component Integration Services are available with a single dbcc entry point.

The syntax for dbcc cis is:

```
dbcc cis ("subcommand" [, vararg1, vararg2...])
```

If Component Integration Services is not configured or loaded, the command results in a runtime error.

The use of the dbcc cis command is unrestricted.

dbcc options

The following dbcc options are unique to Component Integration Services.

remcon

remcon displays a list of all remote connections made by all Component Integration Services clients. It takes no arguments.

srvdes

srvdes returns a formatted list of all in-memory SRVDES structures, if no argument is provided. If an argument is provided, this command syncs the in-memory version of a SRVDES with information found in syssservers. The command takes an optional argument as follows:

```
srvdes, [ srvid ]
```

showcaps

showcaps displays a list of all capabilities for servername by capability name, ID, and value as follows:

```
showcaps, servername
```

Example:

```
dbcc cis("showcaps", "servername")
```

Trace flags

The dbcc traceon option allows the system administrator to turn on trace flags within Component Integration Services. Trace flags enable the logging of certain events when they occur within Component Integration Services. Each trace flag is uniquely identified by a number. Some are global to Component Integration Services, while others are spid-based and affect only the user who enabled the trace flag. dbcc traceoff turns off trace flags.

The syntax is:

```
dbcc traceon (traceflag [, traceflag...])
```

Trace flags and their meanings are shown in Table 3-1:

Table 3-1: Component Integration Services trace flags

Trace flag	Description
11201	Logs client connect events, disconnect events, and attention events. (global). Events sent to error log only.
11202	Logs client language, cursor declare, dynamic prepare, and dynamic execute-immediate text (global). Text sent to error log only.
11203	Logs client RPC events (global). Events sent to error log only.

Trace flag	Description
11204	Logs all messages routed to client (global). Messages sent to only the error log.
11205	Logs all interaction with remote server (global). Interaction sent to error log only.
11206	Logs file/directory processing steps. (global)
11207	Logs text and image processing. (global)
11208	Prevents the create index and drop index statements from being transmitted to a remote server. sysindexes is updated anyway. (spid)
11209	Instructs update statistics to obtain only row counts rather than complete distribution statistics, from a remote table. (spid)
11211	Prevents the drop table syntax from being forwarded to remote servers if the table was created using the create table at location syntax.
11212	Prevents escape on underscores (“_”) in table names. (spid)
11213	Prevents generation of column and table constraints. (spid)
11214	Disables Component Integration Services recovery at start-up. (global)
11216	Disables quickpass. (spid)
11217	Disables quickpass. (global)
11218	Makes cursors involving Component Integration Services tables updateable by default.
11220	Disables constraint checking of remote tables on the local server. This avoids duplicate checking. Setting this trace flag on ensures that queries are not rejected by the quickpass mode because of constraints. (spid)
11221	Disables alter table commands to the remote server when ON. This allows users to modify <i>type</i> , <i>length</i> , and <i>nullability</i> of columns in a local table without changing columns in the remote table. Use trace flag 11221 with caution. It may lead to tables that are “out of sync.” (spid)
11223	Disables proxy table index creation during create existing table or create proxy_table command execution. If this flag is set on, no index metadata is imported from the remote site referenced by the proxy table, and no indexes for the proxy table are created. This trace flag should be used with care and turned off when no longer necessary. (global)
11228	Disables proxy table mapping to RPCs.
11229	Instructs Component Integration Services to use pre-Adaptive Server version 12.5.3 methods of gathering statistics data.

Trace flag	Description
11299	Allows connection information to be logged when a connection to a remote server fails.

Functions

This section defines the compatibility of the Component Integration Services server classes with the built-in Adaptive Server functions.

Support for functions within Component Integration Services

When a SQL statement such as a select, insert, delete, or update contains a built-in function, Component Integration Services has to determine whether or not the function can be forwarded to the remote server, or if it must be evaluated within the local server using remote data.

Functions are only sent to a remote server if the statement containing them can be handled by quickpass mode.

In the tables shown below, support for function by server class is indicated by a 'Y'; 'N' indicates no support is provided, and 'C' indicates support for it is determined by capabilities of the underlying DBMS (often the case for DirectConnects).

Aggregate functions

The aggregate functions generate summary values that appear as new columns in the query results.

Table 3-2: Server class support for aggregate functions

Function	ASE	ASA	ASIQ	dir_con
avg	Y	Y	Y	C
count	Y	Y	Y	C
max	Y	Y	Y	C
min	Y	Y	Y	C
sum	Y	Y	Y	C
count_big	Y	N	N	N

Datatype conversion functions

Datatype conversion functions change expressions from one datatype to another and specify new display formats for date/time information.

Table 3-3: Server class support for datatype conversion functions

Function	ASE	ASA	ASIQ	dir_con
convert()	Y	Y	Y	C
inttohex()	Y	N	N	N
hextoint()	Y	N	N	N
biginttohex()	Y	N	N	N
hextobigint()	Y	N	N	N

Date functions

The date functions manipulate values of the datatypes `datetime` or `smalldatetime`. The `getdate()` function is always expanded by the local server; the presence of this builtin function does not cause a query to be eliminated from quickpass mode optimizations, however.

Table 3-4: Server class support for date functions

Function	ASE	ASA	ASIQ	dir_con
dateadd	Y	Y	Y	C
datediff	Y	Y	Y	C
datename	Y	Y	N	C
datepart	Y	Y	Y	C

Mathematical functions

Mathematical functions return values commonly needed for operations on mathematical data. Mathematical function names are not keywords.

Each function also accepts arguments that can be implicitly converted to the specified type. For example, functions that accept approximate numeric types also accept integer types. Adaptive Server automatically converts the argument to the desired type

Table 3-5: Server class support for mathematical functions

Function	ASE	ASA	ASIQ	dir_con
abs	Y	Y	Y	C
acos	Y	Y	N	C
asin	Y	Y	N	C
atan	Y	Y	N	C
atn2	Y	Y	N	C
ceiling	Y	Y	Y	C
cos	Y	Y	N	C
cot	Y	Y	N	C
degrees	Y	Y	N	C
exp	Y	Y	N	C
floor	Y	Y	Y	C
log	Y	Y	N	C
log10	Y	Y	N	C
pi	Y	Y	N	C
power	Y	Y	N	C
radians	Y	Y	N	C
rand	Y	Y	Y	C
round	Y	Y	N	C
sign	Y	Y	N	C
sin	Y	Y	N	C
sqrt	Y	Y	Y	C
tan	Y	Y	N	C

Security functions

Security functions return security-related information.

Table 3-6: Server class support for security functions

Function	ASE	ASA	ASIQ	dir_con
ic_sec_service_on()	N	N	N	N
show_sec_services()	N	N	N	N

String functions

String function operate on binary data, character strings, and expressions. The string functions are:

Table 3-7: Server class support for string functions

Function	ASE	ASA	ASIQ	dir_con
ascii	Y	Y	N	C
char	Y	Y	N	C
charindex	Y	Y	N	C
char_lengt	Y	Y	N	C
difference	Y	Y	Y	C
lower	Y	Y	Y	C
ltrim	Y	Y	Y	C
patindex	N	N	N	N
replicate	Y	Y	N	C
reverse	Y	N	N	Y
right	Y	Y	Y	C
rtrim	Y	Y	Y	C
soundex	Y	N	Y	C
space	Y	Y	N	C
str	Y	Y	N	C
stuff	Y	Y	N	C
substring	Y	Y	Y	C
upper	Y	Y	Y	C

System functions

System functions return special information from the database.

Table 3-8: Server class support for system functions

Function	ASE	ASA	ASIQ	dir_con
col_length	Y	Y	N	C
col_name	Y	Y	N	C
curunreservedp gs	N	N	N	N
data_pgs	N	N	N	N
datalength	Y	Y	N	C
db_id	N	N	N	N
db_name	N	N	N	N
getdate	Y	N	N	N
getutcdate	Y	N	N	N
host_id	N	N	N	N
host_name	N	N	N	N
index_col	N	N	N	N
isnull	Y	Y	N	N
lct_admin	N	N	N	N
mut_excl_roles	N	N	N	N
object_id	N	N	N	N
object_name	N	N	N	N
proc_role	N	N	N	N
ptn_data_pgs	N	N	N	N
reserved_pgs	N	N	N	N
role_contain	N	N	N	N
role_id	N	N	N	N
role_name	N	N	N	N
rowcnt	N	N	N	N
show_role	N	N	N	N
suser_id	N	Y	Y	N
suser_name	N	Y	Y	N
tsequal	Y	Y	N	N
used_pgs	N	N	N	N
user	Y	Y	Y	N
user_id	Y	Y	Y	N
user_name	Y	Y	Y	N
valid_name	N	N	N	N
valid_user	N	N	N	N

Text and image functions

Text and image functions operate on text and image data.

Table 3-9: Server class support for text and image functions

Function	ASE	ASA	ASIQ	dir_con
textptr()	Y	Y	N	C
textvalid()	Y	Y	N	C

Transact-SQL commands

The following pages discuss, in alphabetical order, Transact-SQL commands that directly or indirectly affect external tables, and, as a result, Component Integration Services. For each command, a description of its effect on Component Integration Services, and the manner in which Component Integration Services processes the command is provided. For a complete description of each command, see the *Reference Manual*.

If Component Integration Services does not pass all of a command's syntax to a remote server (such as all clauses of a select statement), the syntax that is passed along is described for each server class.

Each command has several sections that describe it:

- Description – contains a brief description of the command.
- Syntax – contains a description of the full Transact-SQL syntax of the command.
- Usage – contains a general, server class-independent description of handling by Component Integration Services.
- Server class ASEnterprise – contains a description of handling specific to server class ASEnterprise. This includes syntax that is forwarded to a remote server of class ASEnterprise.
- Server class ASAnywhere – contains a description of handling specific to server class ASAnywhere. This includes syntax that is forwarded to a remote server of class ASAnywhere.
- Server class ASIQ – contains a description of handling specific to server class ASIQ. This includes syntax that is forwarded to a remote server of class ASIQ.

- Server class `direct_connect` – contains a description of handling specific to server class `direct_connect`. This includes syntax that is forwarded to a remote server of class `direct_connect`. In this release, all comments that apply to server class `direct_connect`, also apply to server class `sds`.

alter table

Server class
ASEnterprise

Component Integration Services forwards the following syntax to a server configured as class `ASEnterprise`:

```
alter table [database.[owner].]table_name
    {add column_name datatype [{identity | null}]
    {[, next_column]}...}
    | [drop column_name [, column_name]}
    | modify column_name [data_type] [NULL] |
    [not null] [, column_name]}
```

- When a user adds a column with the `alter table` command, Component Integration Services passes the datatype of each column to the remote server without type name conversions.
- For `ASEnterprise` class servers only, the lock clause is also forwarded, if contained in the original query, if the version of Adaptive Server is 11.9.2 or later.

Server class
ASAnywhere

Handling of `alter table` by servers in this class is the same as for `ASEnterprise` servers.

Server class *ASIQ*

- Handling of `alter table` by servers in this class is the same as for `ASEnterprise` servers.
- text and image datatypes are fully supported by server class `ASIQ`.

Server class
direct_connect

Component Integration Services forwards the following syntax to a remote server configured as class `direct_connect`:

```
alter table [database.[owner].]table_name
    add column_name datatype [{identity | null}]
    {[, next_column]}...
```

- Although Component Integration Services requests a capabilities response from a server with class `direct_connect`, support for `alter table` is not optional. Component Integration Services forwards `alter table` to the remote server regardless of the capabilities response.

- The behavior of the server with class `direct_connect` is database dependent. The Transact-SQL syntax is forwarded, and errors may or may not be raised, depending on the ability of the remote database to handle this syntax.
- Server class `direct_connect` does not support `bigint`, `unsigned tinyint`, `unsigned smallint`, `unsigned int`, `unsigned bigint`.
- If the syntax capability of the remote server indicates Sybase Transact-SQL, Adaptive Server datatypes are sent to the remote server. If the syntax capability indicates DB2 SQL, DB2 datatypes are sent.

Direct Connect does not support `bigint`, `unsigned tinyint`, `unsigned smallint`, `unsigned int`, `unsigned bigint`.

The mapping for these datatypes is shown in Table 3-10:

Table 3-10: DirectConnect datatype conversions for alter table

Adaptive Server datatype	DirectConnect default datatype
<code>binary(n)</code>	<code>binary(n)</code>
<code>bit</code>	<code>bit</code>
<code>char</code>	<code>char</code>
<code>date</code>	<code>date</code>
<code>datetime</code>	<code>datetime</code>
<code>decimal(p, s)</code>	<code>decimal(p, s)</code>
<code>float</code>	<code>float</code>
<code>image</code>	<code>image</code>
<code>int</code>	<code>int</code>
<code>money</code>	<code>money</code>
<code>numeric(p, s)</code>	<code>numeric(p, s)</code>
<code>nchar(n)</code>	<code>nchar(n)</code>
<code>nvarchar(n)</code>	<code>nvarchar(n)</code>
<code>real</code>	<code>real</code>
<code>smalldatetime</code>	<code>smalldatetime</code>
<code>smallint</code>	<code>smallint</code>
<code>smallmoney</code>	<code>smallmoney</code>
<code>time</code>	<code>time</code>
<code>timestamp</code>	<code>timestamp</code>
<code>tinyint</code>	<code>tinyint</code>
<code>text</code>	<code>text</code>
<code>unichar</code>	<code>unichar</code>

Adaptive Server datatype	DirectConnect default datatype
unitext	unitext
varbinary(<i>n</i>)	varbinary(<i>n</i>)
varchar(<i>n</i>)	varchar(<i>n</i>)

Useage When the server receives the alter table command, it passes the command to an appropriate access method if:

- The object on which the command is to operate has been associated with a remote or external storage location.
- The command consists of an add column request. Requests to add or drop constraints are not passed to the access methods; instead, they are handled locally.

alter table is passed to remote servers as a language request.

See also alter table in the *Reference Manual*

case

Server class *ASEnterprise* The presence of a case expression in the original query syntax does not cause the query optimizer to reject quickpass mode.

Server class *ASAnywhere* The presence of a case expression in the original query syntax will not cause the query optimizer to reject quickpass mode.

Server class *ASIQ* The ability to handle case expressions is not set for servers in this class. When a SQL statement containing a case expression is optimized, the presence of the case expression causes the Component Integration Services quickpass optimization to reject the statement. When this happens, the case expression must be evaluated by the local Adaptive Server after retrieving data from the remote server.

Server class *direct_connect* The ability to handle case expressions is determined by the result set from the RPC `sp_capabilities`. If `direct_connect` indicates that it can handle case expressions, then Component Integration Services forwards them to the `direct_connect` when quickpass mode is used to handle the query.

See also case in the *Reference Manual*.

connect to...disconnect

Server class ASEnterprise	When disconnect is issued, Component Integration Services forwards disconnect to the remote server, to take it out of passthrough mode. If not in passthrough mode, syntax errors may occur, but they are ignored by Component Integration Services and not forwarded to the client.
Server class ASAnywhere	No interaction occurs with ASAnywhere when connect or disconnect are issued.
Server class ASIQ	No interaction occurs with ASIQ when connect or disconnect are issued.
Server class direct_connect	<p>When connect is issued using a server in class direct_connect, the direct_connect is sent an RPC:</p> <pre>sp_thread_props "passthru mode", 1</pre> <p>When disconnect is issued, and the server for which a passthrough-mode connection has been established is a direct_connect, the direct_connect is sent an RPC:</p> <pre>sp_thread_props "passthru mode", 0</pre>
See also	commit in the <i>Reference Manual</i>

create existing table

Server class
ASEnterprise

- Table 3-11 describes the allowable datatypes that can be used when mapping remote Adaptive Server columns to local proxy table columns:

Table 3-11: Adaptive Server datatype conversions for create existing table

Remote Adaptive Server datatype	Allowable Adaptive Server datatypes
binary(<i>n</i>)	image, binary(<i>n</i>), and varbinary(<i>n</i>); if not image, the length must match
bit	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
char(<i>n</i>)	text, nchar(<i>n</i>), nvarchar(<i>n</i>), char(<i>n</i>), varchar(<i>n</i>), unichar, univarchar; if not text, the length must match
datetime	datetime, smalldatetime, char, and varchar
decimal(<i>p</i> , <i>s</i>)	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
float	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
image	image
int	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
money	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
nchar(<i>n</i>)	text, nchar(<i>n</i>), nvarchar(<i>n</i>), char(<i>n</i>), varchar(<i>n</i>); if not text, the length must match
numeric(<i>p</i> , <i>s</i>)	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
nvarchar(<i>n</i>)	text, nchar(<i>n</i>), nvarchar(<i>n</i>), char(<i>n</i>), varchar(<i>n</i>), unichar, univarchar; if not text, the length must match
real	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
smalldatetime	datetime, smalldatetime, char, and varchar
smallint	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
smallmoney	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
text	text, unitext
timestamp	timestamp

Remote Adaptive Server datatype	Allowable Adaptive Server datatypes
tinyint	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
unichar	char, varchar, unichar, univarchar, text, datetime, and smalldatetime
univarchar	char, varchar, unichar, univarchar, text, datetime, and smalldatetime
unitext	unitext
varbinary(<i>n</i>)	image, binary(<i>n</i>), and varbinary(<i>n</i>); if not image, the length must match
varchar(<i>n</i>)	text, nchar(<i>n</i>), nvarchar(<i>n</i>), char(<i>n</i>), varchar(<i>n</i>) unichar, univarchar; if not text, the length must match
date	
time	
bigint	Implicit: binary, varbinary, bit, tinyint, smallint, int, decimal, numeric, float, real, money, smallmoney Explicit: char, varchar, unichar, univarchar
unsigned tinyint	Implicit: binary, varbinary, bit, tinyint, smallint, unsigned smallint, int, unsigned int, bigint, unsigned bigint, decimal, numeric, float, real money, smallmoney Explicit: char, varchar, unichar, univarchar Unsupported: text, image, date, time, datetime, smalldatetime
unsigned smallint	Implicit: binary, varbinary, bit, tinyint, smallint, unsigned smallint, int, unsigned int, bigint, unsigned bigint, decimal, numeric, float, real money, smallmoney Explicit: char, varchar, unichar, univarchar Unsupported: text, image, date, time, datetime, smalldatetime
unsigned int	Implicit: binary, varbinary, bit, tinyint, smallint, unsigned smallint, int, unsigned int, bigint, unsigned bigint, decimal, numeric, float, real money, smallmoney Explicit: char, varchar, unichar, univarchar Unsupported: text, image, date, time, datetime, smalldatetime

Remote Adaptive Server datatype	Allowable Adaptive Server datatypes
unsigned bigint	Implicit: binary, varbinary, bit, tinyint, smallint, unsigned smallint, int, unsigned int, bigint, unsigned bigint, decimal, numeric, float, real money, smallmoney Explicit: char, varchar, unichar, univarchar Unsupported: text, image, date, time, datetime, smalldatetime

Note Component Integration Services only supports unitext with Adaptive Server version 15.0 and higher.

Server class
ASAnywhere

- Table 3-12 describes the allowable datatypes that can be used when mapping remote Adaptive Server columns to local proxy table columns:

Table 3-12: Adaptive Server Anywhere datatype conversions for create existing table

Remote Adaptive Server Anywhere datatype	Allowable Adaptive Server Anywhere datatypes
binary(<i>n</i>)	image, binary(<i>n</i>), and varbinary(<i>n</i>); if not image, the length must match
bit	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
char(<i>n</i>)	text, nchar(<i>n</i>), nvarchar(<i>n</i>), char(<i>n</i>), varchar(<i>n</i>), unichar, univarchar; if not text, the length must match
datetime	datetime and smalldatetime
decimal(<i>p</i> , <i>s</i>)	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
float	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
image	image
int	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
money	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
numeric(<i>p</i> , <i>s</i>)	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
real	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
smalldatetime	datetime and smalldatetime
smallint	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
smallmoney	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
text	text
timestamp	timestamp
tinyint	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
varbinary(<i>n</i>)	image, binary(<i>n</i>), and varbinary(<i>n</i>), unichar, unitext, univarchar; if not image, the length must match
varchar(<i>n</i>)	text, nchar(<i>n</i>), nvarchar(<i>n</i>), char(<i>n</i>), varchar(<i>n</i>), unichar, univarchar; if not text, the length must match
date	

Remote Adaptive Server Anywhere datatype	Allowable Adaptive Server Anywhere datatypes
time	
bigint	<p>Implicit: binary, varbinary, bit, tinyint, smallint, unsigned smallint, int, unsigned int, bigint, unsigned bigint, decimal, numeric, float, real money, smallmoney</p> <p>Explicit: char, varchar, unichar, univarchar</p> <p>Unsupported: text, image, date, time, datetime, smalldatetime</p>
unsigned tinyint	<p>Implicit: binary, varbinary, bit, tinyint, smallint, unsigned smallint, int, unsigned int, bigint, unsigned bigint, decimal, numeric, float, real money, smallmoney</p> <p>Explicit: char, varchar, unichar, univarchar</p> <p>Unsupported: text, image, date, time, datetime, smalldatetime</p>
unsigned smallint	<p>Implicit: binary, varbinary, bit, tinyint, smallint, unsigned smallint, int, unsigned int, bigint, unsigned bigint, decimal, numeric, float, real money, smallmoney</p> <p>Explicit: char, varchar, unichar, univarchar</p> <p>Unsupported: text, image, date, time, datetime, smalldatetime</p>
unsigned int	<p>Implicit: binary, varbinary, bit, tinyint, smallint, unsigned smallint, int, unsigned int, bigint, unsigned bigint, decimal, numeric, float, real money, smallmoney</p> <p>Explicit: char, varchar, unichar, univarchar</p> <p>Unsupported: text, image, date, time, datetime, smalldatetime</p>
unsigned bigint	<p>Implicit: binary, varbinary, bit, tinyint, smallint, unsigned smallint, int, unsigned int, bigint, unsigned bigint, decimal, numeric, float, real money, smallmoney</p> <p>Explicit: char, varchar, unichar, univarchar</p> <p>Unsupported: text, image, date, time, datetime, smalldatetime</p>
nchar(n)	text, nchar(n), nvarchar(n), char(n), varchar(n), unichar, univarchar; if not text, the length must match

Remote Adaptive Server Anywhere datatype	Allowable Adaptive Server Anywhere datatypes
nvarchar(n)	text, nchar(n), nvarchar(n), char(n), varchar(n), unichar, univarchar; if not text, the length must match

Server class *ASIQ*

- text and image datatypes are supported by ASIQ version 12.6 and requires a license.
- Behavior is the same as for server class ASAnywhere.

Server class *direct_connect*

- The RPC `sp_columns` queries the datatypes of the columns in the existing table.
- Local column datatypes do not need to be identical to remote column datatypes, but they must be convertible as shown in Table 3-13. If not, a column type error is raised and the command is aborted.

Table 3-13: DirectConnect datatype conversions for create existing table

DirectConnect datatype	Allowable Adaptive Server datatypes
binary(<i>n</i>)	image, binary(<i>n</i>), varbinary(<i>n</i>); if the length does not match, the command is aborted
binary(16)	timestamp
bit	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
char(<i>n</i>)	text, nchar(<i>n</i>), nvarchar(<i>n</i>), char(<i>n</i>) and varchar(<i>n</i>), unichar, univarchar; if the length does not match, the command is aborted
datetime	datetime, smalldatetime
decimal(<i>p</i> , <i>s</i>)	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
float	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
image	image
int	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
money	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
nchar(<i>n</i>)	text, nchar(<i>n</i>), nvarchar(<i>n</i>), char(<i>n</i>) and varchar(<i>n</i>), unichar, univarchar; if the length does not match, the command is aborted
numeric(<i>p</i> , <i>s</i>)	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
nvarchar(<i>n</i>)	text, nchar(<i>n</i>), nvarchar(<i>n</i>), char(<i>n</i>) and varchar(<i>n</i>), unichar, univarchar; if the length does not match, the command is aborted
real	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
smalldatetime	datetime, smalldatetime
smallint	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
smallmoney	bit, decimal, float, int, money, numeric, real, smallint, smallmoney, and tinyint
text	text
timestamp	timestamp, binary(8), varbinary(8)
unichar	text, nchar(<i>n</i>), nvarchar(<i>n</i>), char(<i>n</i>), varchar(<i>n</i>), unichar, univarchar; if not text, the length must match

DirectConnect datatype	Allowable Adaptive Server datatypes
univarchar	text, nchar(<i>n</i>), nvarchar(<i>n</i>), char(<i>n</i>), varchar(<i>n</i>), unichar, univarchar; if not text, the length must match
date	
time	
bigint	UDB and DC/Microsoft support bigint.

- Datatype information is passed in the CS_DATAFMT structure associated with the parameter. The following fields of the structure contain datatype information:
 - *datatype* – the CS_Library datatype representing the Adaptive Server datatype. For example, CS_INT_TYPE.
 - *usertype* – the native DBMS datatype. sp_columns passes this datatype back to Component Integration Services during a create existing table command as part of its result set (see sp_columns in the *Reference Manual*). Adaptive Server returns this datatype in the *usertype* field of parameters to assist the DirectConnect in datatype conversions.

Usage

When a create existing table command is received, it is interpreted as a request to import metadata from the remote or external location of the object for updating system catalogs. Importing this metadata is performed by means of three RPCs sent to the remote server with which the object has been associated:

- sp_tables – verifies that the remote object actually exists.
- sp_columns – obtains column attributes of the remote object for comparison with those defined in create existing table.
- sp_statistics – obtains index information to update the local system table, sysindexes.

See also

create existing table in the *Reference Manual*

create index

Server class
ASEnterprise

Component Integration Services forwards everything except the on *segment_name* clause to the remote server.

Server class
ASAnywhere

Component Integration Services forwards everything except the on *segment_name* clause to the remote server.

Server class <i>ASIQ</i>	Component Integration Services forwards everything except the on <i>segment_name</i> clause to the remote server.
Server class <i>direct_connect</i>	<ul style="list-style-type: none"> • When the language capability is set to “Transact-SQL”, Component Integration Services forwards all syntax except the <i>max_rows_per_page</i> and on <i>segment_name</i> clauses to the remote server.
Usage	<p>When the server receives the create index command, it passes the command to an appropriate access method, if the object on which the command is to operate has been associated with a remote or external storage location.</p> <p>The command is reconstructed using a syntax appropriate for the class and is passed to the remote server for execution.</p> <p>create index is passed to remote servers as a language request.</p>
See also	create index in the <i>Reference Manual</i>

create table

Server class <i>ASEnterprise</i>	Component Integration Services passes the datatype of each column to the remote server without conversion.
Server class <i>ASAnywhere</i>	Component Integration Services passes the datatype of each column to the remote server without conversion.
Server class <i>ASIQ</i>	Component Integration Services passes the datatype of each column to the remote server without conversion.
Server class <i>direct_connect</i>	<ul style="list-style-type: none"> • Component Integration Services reconstructs create table and passes commands to the targeted DirectConnect. The gateway transforms the commands into a form that the underlying DBMS recognizes. • Direct Connect does not support bigint, unsigned tinyint, unsigned smallint, unsigned int, unsigned bigint. • Adaptive Server datatypes are converted to either the DirectConnect syntax mode datatypes shown in Table 3-14.

Table 3-14: DirectConnect datatype conversions for create table

Adaptive Server datatype	DirectConnect default datatype
binary(<i>n</i>)	binary(<i>n</i>)
bit	bit
char	char
datetime	datetime
decimal(<i>p, s</i>)	decimal(<i>p, s</i>)
float	float
image	image
int	int
money	money
numeric(<i>p, s</i>)	numeric(<i>p, s</i>)
nchar(<i>n</i>)	nchar(<i>n</i>)
nvarchar(<i>n</i>)	nvarchar(<i>n</i>)
real	real
smalldatetime	smalldatetime
smallint	smallint
smallmoney	smallmoney
timestamp	timestamp
tinyint	tinyint
text	text
unichar(<i>n</i>)	unichar
univarchar(<i>n</i>)	char(<i>n</i>) for bit data
varbinary(<i>n</i>)	varbinary(<i>n</i>)
varchar(<i>n</i>)	varchar(<i>n</i>)
date	
time	
bigint	UDB and DC/Microsoft support bigint

Usage

When the server receives a create table command, the command is interpreted as a request for new table creation. The server invokes the access method appropriate for the server class of the table that is to be created. If it is remote, the table is created. If this command is successful, system catalogs are updated, and the object appears to clients as a local table in the database in which it was created.

create table is reconstructed in a syntax that is appropriate if the server class. For example, if the server class is `direct_connect` and the remote server is DB2, the command is reconstructed using Adaptive Server Anywhere syntax before being passed to the remote server. Datatype conversions are made for datatypes that are unique to the Adaptive Server environment.

Some server classes have restrictions on what datatypes can and cannot be supported.

create table is passed to remote servers as a language request.

See also

create table in the *Reference Manual*

delete

Server class
ASEnterprise

If Component Integration Services cannot forward the original query without alteration, it performs the delete using method 2.

Server class
ASAnywhere

If Component Integration Services cannot forward the original query without alteration, it performs the delete using method 2.

Server class *ASIQ*

If Component Integration Services cannot forward the original query without alteration, you get an error because ASIQ does not support updatable cursors.

Server class
direct_connect

- The syntax forwarded to servers of class `direct_connect` is dependent on the capabilities negotiation, which occurs when Component Integration Services first connects to the remote DirectConnect. Examples of negotiable capabilities include: subquery support, group by support, and built-in support.
- Component Integration Services passes data values as parameters to either a cursor or a dynamic SQL statement. Language statements can also be used if the DirectConnect supports it. The parameters are in the datatype native to Adaptive Server and must be converted by the DirectConnect into formats appropriate for the target DBMS.

See also

delete in the *Reference Manual*

drop index

Server class
ASEnterprise

Component Integration Services forwards the following drop index syntax to a remote server configured as class `ASEnterprise`:

drop index *table_name.index_name*

Component Integration Services precedes this statement with a use database command since the drop index syntax does not allow you to specify the database name.

Server class
ASAnywhere

- Component Integration Services forwards the following drop index syntax to a remote server configured as class ASAnywhere:

drop index *table_name.index_name*

Component Integration Services precedes this statement with a use database command since the drop index syntax does not allow you to specify the database name.

Server class *ASIQ*

Component Integration Services forwards the following drop index syntax to a remote server configured as class ASIQ:

drop index *table_name.index_name*

Component Integration Services precedes this statement with a use database command since the drop index syntax does not allow you to specify the database name.

Server class
direct_connect

Component Integration Services forwards the following drop index syntax to a remote server configured as class direct_connect:

drop index *table_name.index_name*

Usage

When the server receives the drop index command, it passes the command to an appropriate access method, if the object on which the command is to operate has been associated with a remote or external storage location.

drop index is reconstructed using a syntax appropriate for the class and is passed to the remote server for execution.

This command is passed to remote servers as a language request.

See also

drop index in the *Reference Manual*

fetch

Server class
ASEnterprise

If the cursor is read only, Component Integration Services sends a language request to the remote server when the first fetch is received after the cursor is opened. Otherwise, Component Integration Services declares a cursor to the remote server by means of Client-Library.

Server class
ASAnywhere

Handling of the fetch statement is the same as for ASEnterprise.

Server class <i>ASIQ</i>	Component Integration Services sends a language request to the remote server when the first fetch is requested after the cursor is opened.
Server class <i>direct_connect</i>	Component Integration Services treats servers in this class the same as servers in ASEnterprise.
See also	close, deallocate cursor, declare cursor, open fetch in the <i>Reference Manual</i>

insert

Server class <i>ASEnterprise</i>	<ul style="list-style-type: none"> • insert commands using the values keyword are fully supported. • insert commands using a select command are supported for all datatypes except text and image. text and image columns are only supported when they contain null values. • If all insert and select tables reside on the same remote server, the entire statement is forwarded to the remote server for execution. This is referred to as quickpass mode. Quickpass mode is not used if select does not conform to all the quickpass rules for a select command. • If the select tables reside on one remote server, and the insert table resides on a different server, Component Integration Services selects each row from the source tables, and inserts the row into the target table. • You cannot insert into a computed column.
Server class <i>ASAnywhere</i>	Handling of the insert statement is the same as for ASEnterprise.
Server class <i>ASIQ</i>	Handling of the insert statement is the same as for ASEnterprise.
Server class <i>direct_connect</i>	<ul style="list-style-type: none"> • insert commands using the values keyword are fully supported. • insert commands using a select command are fully supported, but the table must have a unique index if the table has text or image columns. When using insert with a select command, the entire command is sent to the remote server if: <ul style="list-style-type: none"> • All tables referenced in the command reside on the remote server. • The capability's response from the DirectConnect indicates that insert-select commands are supported. • If you use the TopN feature, you must have an order by clause.

If both conditions are not met, Component Integration Services selects each row from the source tables, and inserts the row into the target table.

- Component Integration Services passes data values as parameters to either a cursor or a dynamic SQL statement. Language statements can also be used if the DirectConnect supports it. The parameters are in the datatype native to Adaptive Server and must be converted by the DirectConnect into formats appropriate for the target DBMS.

See also `insert` in the *Reference Manual*

readtext

Server class
ASEnterprise

Component Integration Services forwards the following syntax to the remote server when the underlying table is a proxy table:

```
readtext [[database.]owner.]table_name.column_name
         text_pointer offset size
[using {chars | characters}]
```

Server class
ASAnywhere

Handling of the readtext statement is the same as for ASEnterprise.

Server class *ASIQ*

Handling of the readtext statement is the same as for ASEnterprise.

Server class
direct_connect

- If the DirectConnect does not support text pointers, readtext cannot be sent and its use results in errors.
- If the DirectConnect does support text pointers, Component Integration Services forwards the following syntax to the remote server:

```
readtext
[[database.]owner.]table_name.column_name
text_pointer offset size
[using {chars | characters}]
```

- readtext is issued anytime text or image data must be read. readtext is called when a select command refers to a text or image column in the select list, or when a where clause refers to a text or image column.

For example, you have a proxy table books that is mapped to the books table on the remote server foo. The columns are id, name, and the text column blurb. When the following statement is issued:

```
select * from books
```

Component Integration Services sends the following syntax to the remote server:

```
select id, name, textptr(blurb) from foo_books
```

readtext foo_books.blurb @p1 0 0 using chars

See also

readtext in the *Reference Manual*

select

Server class
ASEnterprise

- All syntax is supported. Since the remote server is assumed to have all capabilities necessary to process Transact-SQL syntax, all elements of a select command, except those mentioned above, are forwarded to a remote server, using quickpass mode.
- A bulk copy transfer is used to copy data into the new table when a select...into command is issued and the into table resides on a remote Adaptive Server. Both the local and remote databases must be configured with dboption set to select into / bulkcopy.

Server class
ASAnywhere

- All syntax is supported. Since the remote server is assumed to have all capabilities necessary to process Transact-SQL syntax, all elements of a select command, except those mentioned above, are forwarded to a remote server, using quickpass mode.
- If the select...into format is used and the into table is accessed through the ASAnywhere interface, bulk inserts are not used. Instead, Component Integration Services uses Client-Library to prepare a parameterized dynamic insert command, and executes it for each row returned by the select portion of the command.

Server class *AS/Q*

- All syntax is supported. Since the remote server is assumed to have all capabilities necessary to process Transact-SQL syntax, all elements of a select command, except those mentioned above, are forwarded to a remote server, using quickpass mode.

Server class
direct_connect

- The first time Component Integration Services requires a connection to a server in class direct_connect, a request for capabilities is made of the DirectConnect. Based on the response, Component Integration Services determines the parts of a select command to forward to the DirectConnect. In most cases, this is determined by the capabilities of the DBMS with which the DirectConnect is interfacing.
- If the entire statement cannot be forwarded to the DirectConnect using quickpass mode, Component Integration Services compensates for the functionality that cannot be forwarded. For example, if the remote server cannot handle the order by clause, quickpass is not used and Component Integration Services performs a sort on the result set.

- Component Integration Services passes data values as parameters to either a cursor or a dynamic SQL statement. Language statements can also be used if the DirectConnect supports it. The parameters are in the datatype native to Adaptive Server and must be converted by the DirectConnect into formats appropriate for the target DBMS.
- The select...into command is supported, but the table must have a unique index if the table has text or image columns.
- If the select...into format is used and the into table is accessed through a DirectConnect, bulk inserts are not used. Instead, Component Integration Services uses Client-Library to prepare a dynamic insert command, and executes it for each row returned by the select portion of the command.

See also *select* in the *Reference Manual*

truncate table

Server class
ASEnterprise

Component Integration Services forwards the truncate table command to servers of class ASEnterprise.

Server class
ASAnywhere

Component Integration Services forwards the truncate table command to servers of class ASAnywhere.

Server class *ASIQ*

Component Integration Services forwards the truncate table command to servers of class ASIQ.

Server class
direct_connect and
sds

Transact-SQL syntax is sent:
`truncate table [[database.]owner.]table_name`

See also *truncate table* in the *Reference Manual*

update

Server class
ASEnterprise

- If Component Integration Services cannot pass the entire statement to a remote server, a unique index must exist on the table.
- The update command is fully supported for all datatypes except text and image. text and image data cannot be changed with the update command, except when setting the text or image value to null. Use the writetext command instead.

- If quickpass mode is not used, data is retrieved from the source tables, and the values in the target table are updated using a separate cursor designed for handling a positioned update.

Server class
ASAnywhere

Handling of the update statement is the same as for ASEnterprise.

Server class *ASIQ*

Handling of the update statement is the same as for ASEnterprise.

If Component Integration Services cannot forward the original query without alteration, you get an error because ASIQ does not support updatable cursors.

Server class
direct_connect

- The following syntax is supported by servers of class *direct_connect*:

```
update [[database.]owner.]{table_name | view_name}
set [[[database.]owner.]{table_name.|view_name.}]
  column_name1 =
    {expression1|NULL|{select_statement}}
[, column_name2 =
  {expression2|NULL|{select_statement}}]...
```

[where *search_conditions*]

update commands that conform to this syntax use quickpass mode, if the capabilities response from the remote server indicates that all elements of the command are supported. Examples of negotiable capabilities include: subquery support, group by support, and built-in support.

- If the remote server does not support all elements of the command, or the command contains a from clause, Component Integration Services issues a query to obtain the values for the set clause, and then issues an update command to the remote server.
- Component Integration Services passes data values as parameters to either a cursor or a dynamic SQL statement. Language statements can also be used if the DirectConnect supports it. The parameters are in the datatype native to Adaptive Server and must be converted by the DirectConnect into formats appropriate for the target DBMS.

See also

update in the *Reference Manual*

update statistics

Server class
ASEnterprise

- If the table on which the statistics are requested has no indexes, Component Integration Services issues the following command:

```
select count(*) from table_name
```

It is also the only command issued when trace flag 11209 is on.

- If the table has an index and the index is specified in the command, Component Integration Services issues the following commands:

```
select count(*) from table_name
select count(*) column_name [,column_name, ...]
from table_name
group by column_name [,column_name, ..]
```

The column name(s) represent the column or columns that make up the index.

For example, when the following command is issued:

```
update statistics customers ind_name
```

Component Integration Services issues:

```
select count(*) from customers
select count(*) last_name, first_name
from customers
group by last_name, first_name
```

- If the table has one or more indexes but no index is specified in the statement, Component Integration Services issues the select count (*) once, and the select/order by commands for each index.
- You must have the sa_role to run update statistic on a proxy table using a remote login.
- In Adaptive Server version 15.0 or later, if a proxy table points to a partitioned table, only global statistics are imported. These are aggregated statistics since proxy tables in Adaptive Server version 15.0 are not partitioned.

Server class
ASAnywhere

The processing of update statistics in this server class is identical to pre-Adaptive Server version 15.0 servers.

Server class *AS/Q*

The processing of update statistics in this server class is identical to pre-Adaptive Server version 15.0 servers.

Server class
direct_connect

- The processing of update statistics in this server class is identical to that of server class *ASEnterprise* described above.
- If the *direct_connect* indicates that it cannot handle the group by or the count(*) syntax, statistics are not collected for the *direct_connect*.

See also

update statistics in the *Reference Manual*

writetext

Server class <i>ASEnterprise</i>	The writetext command is processed using a separate connection to the remote server.
Server class <i>ASAnywhere</i>	The writetext command is processed using a separate connection to the remote server.
Server class <i>AS/Q</i>	The writetext command is processed using a separate connection to the remote server.
Server class <i>direct_connect</i>	If the DirectConnect supports text pointers, Component Integration Services treats the DirectConnect as if it were a server in class ASEnterprise.
See also	writetext in the <i>Reference Manual</i>

Passthrough mode

Passthrough mode is provided within Component Integration Services as a means of enabling a user to perform native operations on the server to which the user is being “passed through.”

For example, requesting passthrough mode for an Oracle server allows you to send native Oracle SQL statements to the Oracle DBMS. Results are converted into a form that is usable by the Open Client application and passed back to the user.

The Transact-SQL parser and compiler are bypassed in this mode, and each language batch received from the user is passed directly to the server to which the user is connected in passthrough mode. Results from each batch are returned to the client.

There are several ways to use passthrough mode:

- connect to
- sp_autoconnect
- sp_passthru
- sp_remotesql

connect to

The connect to command enables users to specify the server to which a passthrough connection is required. The syntax of the command is:

```
connect to server_name
```

where *server_name* is the name of a server added to the *sys.servers* table, with its server class and network name defined. See *sp_addserver* in the *Reference Manual*.

When establishing a connection to *server_name* on behalf of the user, the server uses:

- A remote login alias set using *sp_addexternlogin*, or
- The name and password used to communicate with the Adaptive Server.

In either case, if the connection cannot be made to the server specified, the reason is contained in a message returned to the user.

Once a passthrough connection has been made, the Transact-SQL parser and compiler are bypassed when subsequent language text is received. Any statements received by the server are passed directly to the specified remote server.

Note Some database management systems do not recognize more than one statement at a time and produce syntax errors if, for example, multiple select statements were received as part of a single language text buffer.

After statements are passed to the requested server, any results are converted into a form that can be recognized by the Open Client interface and sent back to the client program.

To exit from passthrough mode, issue the *disconnect*, or *disc*, command. Subsequent language text from this client is then processed using the Transact-SQL parser and compiler.

Permission to use *connect to* must be explicitly granted by the system administrator. The syntax is:

```
grant connect to user_name
```

To revoke permission to use *connect to*, the syntax is:

```
revoke connect from user_name
```

The connect to permissions are stored in the master database. To globally grant or revoke permissions to “public”, the system administrator sets the permissions in the master database; the effect is server-wide, regardless of what database is being used. The system administrator can only grant or revoke permissions to or from a user if the user is a valid user of the master database.

The system administrator can grant or revoke “all” permissions to or from “public” within any database. If the permissions are in the master database, “all” includes the connect to command. If they are in another database, “all” does not include the connect to command.

Example

The system administrator wants to revoke permission from “public” and wants only the user “fred” to be able to execute the connect to command. “fred” must be made a valid user of master. To do this, the system administrator issues the following commands in master:

```
revoke connect from public
sp_adduser fred
grant connect to fred
```

sp_autoconnect

Some users may always require a passthrough connection to a given server. If this is the case, Component Integration Services can be configured so that it automatically connects these users to a specified remote server in passthrough mode when the users connect to the server. This feature is enabled and disabled by `sp_autoconnect` using this syntax:

```
sp_autoconnect server_name, true|false [,loginname]
```

Before using `sp_autoconnect`, add the *server_name* to `sys.servers` using `sp_addserver`.

A user can request automatic connection to a server using `sp_autoconnect`, but only the system administrator can enable or disable automatic passthrough connection for another user. Thus, only the system administrator can specify a third argument to this procedure.

If the second argument is `true`, the autoconnect feature is enabled for the current user (or the user specified in the third argument). If the second argument is `false`, autoconnect is disabled.

When a user connects to the server, that user's autoconnect status in syslogins is checked. If enabled, the *server_name*, also found in syslogins (placed there by *sp_autoconnect*), is checked for validity. If the server is valid, the user is automatically connected to that server, and a passthrough status is established. Subsequent language statements received by the server from this user are handled exactly as if the user explicitly entered the connect command. This user then views the server similar to a passthrough gateway to the remote server.

When an "autoconnected" user executes a disconnect, she or he is returned normally to the server.

If the remote server cannot be reached, the user (unless the user is assigned the "sa" role) will not be connected to the local Adaptive Server. A "login failed" error message is returned.

sp_passthru

sp_passthru allows the user to pass a SQL command buffer to a remote server. The syntax of the SQL statements being passed is assumed to be the syntax native to the class of server receiving the buffer; no translation or interpretation is performed. Results from the remote server are optionally placed in output parameters. The syntax for *sp_passthru* follows:

```
sp_passthru server, command, errcode, errmsg, rowcount  
[, arg1, arg2, ... argn]
```

where:

- *server* is the name of the server that is to receive the SQL command buffer; the datatype is *varchar(255)*.
- *command* is the SQL command buffer; the datatype is *varchar(255)*.
- *errcode* is the error code returned by the remote server; the datatype is *int* output.
- *errmsg* is the error message returned by the remote server; the datatype is *varchar(1024)* output.
- *rowcount* is the number of rows affected by the last command in the command buffer; the datatype is *int* output.
- *arg1 – argn* are optional parameters. If provided, these output parameters will receive the results from the last row returned by the last command in the command buffer. The datatypes may vary. All must be output parameters.

Example

```
sp_passthru ORACLE, "select date from dual",
@errcodeoutput, @errmsg output, @rowcount output,
@oradate output
```

This example returns the date from the Oracle server in the output parameter @oradate. If an Oracle error occurs, the error code is placed in @errcode and the corresponding message is placed in @errmsg. The @rowcount parameter is set to 1.

For more information on sp_passthru and its return status, see the *Reference Manual*.

sp_remotesql

sp_remotesql allows you to pass native syntax to a remote server. The procedure establishes a connection to a remote server, passes a query buffer, and relays the results back to the client. The syntax for sp_remotesql is as follows:

```
sp_remotesql server_name, query_buf1
[, query_buf2, ... , query_buf254]
```

where:

- *server_name* is the name of a server that has been defined using sp_addserver.
- *server_name* is a varchar(255) field. If *server_name* is not defined or is not available, the connection fails, and the procedure is aborted. This parameter is required.
- *query_buf1* is a query buffer of type char or varchar with a maximum length of 255 bytes. This parameter is required.

Each additional buffer is char or varchar with a maximum length of 255 bytes. If supplied, these optional arguments are concatenated with the contents of *query_buf1* into a single query buffer.

Example

```
sp_remotesql fred_s_server, "select @@version"
```

In this example, the server passes the query buffer to *fred_s_server*, which interprets the select @@version syntax and returns version information to the client. The returned information is not interpreted by the server.

For more information on sp_remotesql and its return codes, see the *Reference Manual*.

Quoted identifier support

Quoted identifiers are forwarded to remote servers that support them. This is triggered by a set command:

```
set quoted_identifier on
```

If this thread property is enabled, Component Integration Services quotes identifiers before sending SQL statements to remote servers.

Remote servers must have the ability to support quoted identifiers. There is a capability in the `sp_capabilities` result set reserved for this purpose:

- Capability ID: 135
- Capability name: quoted identifier
- Capability value: 0 = no support; 1 = supported

The capability defaults to 0 for DirectConnects that do not provide a value for this capability.

Delimited identifier support

The behavior of bracketed identifiers is identical to quoted identifiers, with the exception that you do not need to set `quoted_identifier` on in order to use them.

auto identity option

When the Adaptive Server auto identity database option is enabled, an `IDENTITY` column is added to any tables that are created in the database. The column name is `CIS_IDENTITY_COL`, for proxy tables, or `SYB_IDENTITY_COL`, for local tables. In either case, the column can be referenced using the `syb_identity` keyword.

Triggers

Component Integration Services allows triggers on proxy tables; however, their usefulness is limited. You can create a trigger on a proxy table and the trigger is invoked just as it would be for a normal Adaptive Server table. However, before and after image data is not written to the log for proxy tables because the insert, update, and delete commands are passed to the remote server. The inserted or deleted tables, which are actually views into the log, contain no data for proxy tables. Users cannot examine the rows being inserted, deleted, or updated, so a trigger with a proxy table has limited value.

In Adaptive Server version 15.0 and later, there is no support for the updated function with triggers.

Tutorial

This chapter provides a tutorial for setting up Component Integration Services and accessing a remote server.

Note This tutorial assumes that the pubs2 database has been installed.

Getting started with Component Integration Services

This section provides a step-by-step guide to configuring the server to access remote data sources. It includes instructions for:

- Adding a remote server
- Mapping remote objects to local proxy tables
- Performing joins between remote tables

Routine system administration tasks such as starting and stopping Adaptive Server, creating logins, creating groups, adding users, granting permissions, and password administration are explained in the Adaptive Server documentation.

Adding a remote server

You can use the server to access data on remote servers. Before you can do this, you must configure Component Integration Services.

Overview

- 1 Add the remote server to the interfaces file.
- 2 Add the name, server class, and network name of the remote server to system tables.

- 3 Optionally, assign an alternate login name and password.

Adding the remote server to the interfaces file

Use the dsedit or dscp utility to edit the interfaces file located in the `$$SYBASE` directory:

- In UNIX, the interfaces file is called *interfaces*.
- In Windows, the interfaces file is called *sql.ini*.

For a complete discussion of the interfaces file, see the *Adaptive Server Configuration Guide* for your platform.

Creating server entries in system tables

Use `sp_addserver` to add entries to the `syssservers` table. `sp_addserver` creates entries for the local server and an entry for each remote server that is to be called. The `sp_addserver` syntax is:

```
sp_addserver server_name [,server_class [,network_name]]
```

where:

- *server_name* is the name used to identify the server. It must be unique.
- *server_class* is one of the supported server classes. The default value is ASEnterprise. If *server_class* is set to local, *network_name* is ignored.
- *network_name* is the server name in the interfaces file. This name may be the same as *server_name*, or it may differ. The *network_name* is sometimes referred to as the *physical name*.

Example

The following examples create entries for the local server named SYBASE and for the remote server CTOSDEMO with server class ASEnterprise.

```
sp_addserver SYBASE, local
sp_addserver CTOSDEMO, ASEnterprise, CTOSDEMO
```

You must reboot Adaptive Server after you add a local server.

Adding an alternate login and password

Use `sp_addexternlogin` to assign an alternate login name and password to be used when communicating with a remote server. This step is optional. The syntax for `sp_addexternlogin` is:

```
sp_addexternlogin remote_server, login_name, remote_name [,
remote_password]
```

where:

- *remote_server* is the name of the remote server. The *remote_server* must be known to the local server by an entry in the master.dbo.sys.servers table.
- *login_name* is an account known to the local server. *login_name* must be represented by an entry in the master.dbo.syslogins table. The “sa” account, the “sso” account, and the *login_name* account are the only users authorized to modify remote access for a given local user.
- *remote_name* is an account known to the *remote_server* and must be a valid account on the node where the *remote_server* runs. This is the account used for logging in to the *remote_server*.
- *remote_password* is the password for *remote_name*.

Examples

```
sp_addexternlogin FRED, sa, system, sys_pass
```

Allows the local server to gain access to remote server FRED using the remote name “system” and the remote password “sys_pass” on behalf of user “sa”.

```
sp_addexternlogin OMNI1012, bobj, jordan, hitchpost
```

Tells the local server that when the login name “bobj” logs in, access to the remote server OMNI1012 is by the remote name “jordan” and the remote password “hitchpost”. Only the “bobj” account, the “sa” account, and the “sso” account have the authority to add or modify a remote login for the login name “bobj”.

Verifying connectivity

Use the connect to *server_name* command to verify that the configuration is correct. connect to requires that “sa” explicitly grant connect authority to users other than “sa.” The connect to command establishes a passthrough mode connection to the remote server. This passthrough mode remains in effect until you issue a disconnect command.

Join between two remote tables

With Component Integration Services, you can perform joins across remote tables.

Adding the remote servers to the interfaces file

Edit the interfaces file using dsedit.

Defining the remote servers

Use `sp_addserver` to add entries to the `sys.servers` system table. On the server originating the call, there must be an entry for each remote server that is to be called. The `sp_addserver` syntax is:

```
sp_addserver server_name [,server_class] [,network_name]
```

where:

- *server_name* is the name used to identify the server. It must be unique.
- *server_class* is one of the supported server classes. The default value is `sql_server`. If the value is `local`, *network_name* is ignored.
- *network_name* is the server name in the interfaces file. This name may be the same as the *server_name* specification, or it may be different. If *network_name* is not provided, the default value is the *server_name*.

Example

The following examples create entries for the local server named SYBASE and for the remote server SYBASE of class ASEnterprise.

```
sp_addserver SYBASE, local
sp_addserver CTOSDEMO, ASEnterprise, SYBASE
```

Mapping the remote tables to Adaptive Server

`create existing table` enables the definition of existing (proxy) tables. The syntax for this option is similar to the `create table` command and reads as follows:

```
create proxy_table
table_name
at "pathname"
```

When the server processes this command, it does not create a new table. Instead, it checks the table mapping and verifies the existence of the underlying object. If the object does not exist (either host data file or remote server object), the server rejects the command and returns an error message to the client.

After you define an existing table, issue an `update statistics` command for that table. This helps the query optimizer make intelligent choices regarding index selection and join order.

Example

To illustrate the remote Adaptive Server tables publishers and titles in the sample `pubs2` database mapped to a local server, follow these steps:

Mapping the remote tables

The steps required to produce the mapping illustrated above are as follows:

- 1 Define a server named SYBASE. Its server class is ASEnterprise, and its name in the interfaces file is SYBASE:

```
exec sp_addserver SYBASE, ASEnterprise, SYBASE
```

- 2 Define a remote login alias. This step is optional. User "sa" is known to remote server SYBASE as user "sa," password "timothy":

```
exec sp_addexternlogin SYBASE, sa, sa, timothy
```

- 3 Define the remote publishers table:

```
create proxy_table publishers  
at "SYBASE.pubs2.dbo.publishers"
```

- 4 Define the remote titles table:

```
create proxy_table titles  
at "SYBASE.pubs2.dbo.titles"
```

Performing the join

Use the select statement to perform the join.

```
select Publisher = p.pub_name, Title = t.title  
from publishers p, titles t  
where p.pub_id = t.pub_id  
order by p.pub_name
```


Troubleshooting

This appendix provides troubleshooting tips for problems that you may encounter when using Component Integration Services. The purpose of this chapter is to provide:

- Enough information about certain error conditions so that you can resolve problems without help from Technical Support
- Lists of information that you can gather before calling Technical Support, which may help resolve your problem more quickly
- You with a greater understanding of Component Integration Services

The *Troubleshooting and Error Messages Guide* should also be used for troubleshooting. While this appendix provides troubleshooting tips for most frequently asked Component Integration Services questions, lists all error messages with a one-line recovery procedure; the *Troubleshooting and Error Messages Guide* provides tips on Adaptive Server problems that are not specific to Component Integration Services.

Topic	Page
Problems accessing Component Integration Services	123
Problems using Component Integration Services	124
If you need help	130

Problems accessing Component Integration Services

If you issue a command that accesses a remote object and Component Integration Services is not found, the following error message appears:

```
cis extension not enabled or installed
```

- Verify that the enable cis configuration parameter is set to 1 by running:

```
sp_configure "enable cis"
```

sp_configure returns the following row for the enable cis parameter:

name	min	max	config value	run value
enable cis	0	1	1	1

Both “config value” and “run value” should be 1. If both values are 0, set the enable cis configuration parameter to 1, and restart the server. Use the syntax:

```
sp_configure "enable cis" 1
```

If “config value” is 1 and “run value” is 0, the enable cis configuration parameter is set, but does not take effect until the server is restarted.

Note Component Integration Services is enabled by default beginning with Adaptive Server version 12.0.

Problems using Component Integration Services

This section provides tips on how to correct problems you may encounter when using Component Integration Services.

Unable to access remote server

When you cannot access a remote server, the following error message is returned:

```
11206 Unable to connect to server server_name.
```

The message is preceded by one of the following Client-Library messages:

```
Requested server name not found  
Driver call to connect two endpoints failed  
Login failed
```

The Client-Library message indicates why you cannot access the remote server as described in the following sections.

Requested server name not found

The server is not defined in the interfaces file when the following messages display:

```
Requested server name not found
11206 Unable to connect to server server_name.
```

When a remote server is added using `sp_addserver`, the interfaces file is not checked. It is checked the first time you try to make a connection to the remote server. To correct this problem, add the remote server to the interfaces file that is being used by Component Integration Services.

Driver call to connect two endpoints failed

If the remote server is defined in the interfaces file, but no response was received from the connect request, the following messages are displayed:

```
Driver call to connect two endpoints failed
11206 Unable to connect to server server_name.
```

- Verify that your environment is set up correctly.

To test this, try to connect directly to the remote server using `isql` or a similar tool:

- a Log in to the machine where Component Integration Services is running.
- b Set the SYBASE environment variable to the same location that was used when Component Integration Services was started. Component Integration Services uses the interfaces file in the directory specified by the SYBASE environment variable, unless it is overridden in the `runserver` file by the `-i` argument.

Note These first two steps are important to ensure that the test environment is the same environment that Component Integration Services was using when you could not connect to the remote server.

- c Use `isql` or a similar tool to connect directly to the remote server.

If the environment is set up correctly and the connection fails, continue through this list. If the connection is made, there is a problem with the environment being used by Component Integration Services.

- Verify that the remote server is up and running.

Log in to the machine where the remote server is located to verify that the server is running. If the server is running, continue through this list. If the server is not running, restart the server and try your query again.

- Verify that the entry for the remote server in the interfaces file is correct:

- Verify that the machine name is the correct name for the machine the software is loaded on.
- Verify that if the interfaces file is a text file, the query and master lines start with a tab and not spaces.
- Verify that the port number is available. Check the *services* file in the */etc* directory to ensure that the port number is not reserved for another process.

Login failed

If you can access the remote server, but the login name and password are correct, the following messages display:

```
Login failed
11206 Unable to connect to server server_name.
```

See if there is an external login established for the remote server by executing:

```
exec sp_helpexternlogin server_name
```

If no external login is defined, Component Integration Services uses the user login name and password that was used to connect to Adaptive Server. For example, if the user connected to Adaptive Server using the “sa” account, Component Integration Services uses the login name “sa” when making a remote connection. Unless the remote server is another Adaptive Server, the “sa” account probably does not exist, and an external login must be added using `sp_addexternlogin`.

If an external login is defined, verify that the user’s login name is correct. Remote server logins are case sensitive. Is the case correct for the user login name you are using and the entry in *externlogins*?

If the login name is correct, the password might be incorrect. You cannot display the password. If the user login name is incorrect or if the password might be incorrect, drop the existing external login and redefine it by executing the commands:

```
exec sp_dropexternlogin server_name, login_name
go
exec sp_addexternlogin server_name, login_name,
remote_login, remote_password
go
```

Unable to access remote object

When you are unable to access a remote object, the following error message appears:

```
Error 11214 Remote object object does not exist.
```

The problem may be in the local proxy table definition or in the table itself on the remote server.

Verify that:

- The object has been defined in Component Integration Services.

To confirm, run:

```
sp_help object_name
```

If the object does not exist, create the object in Component Integration Services.

- If the object has been defined in Component Integration Services, the definition is correct.

Table names can have four parts with the format *server.dbname.owner.tablename*. The *dbname* part is not valid for Oracle, or InfoHUB servers.

If the object definition is incorrect, delete it using `sp_dropobjectdef`, and define it correctly using `sp_addobjectdef`.

- If the local object definition is correct, check the table on the remote server, to verify that:
 - Permissions are set to allow access to both the database and table.
 - The database has been marked suspect.
 - The database is available.
 - You can access the remote table using a native tool (for example, SQL*Plus on Oracle).

Problem retrieving data from remote objects

When you receive error messages pertaining to mismatches in remote objects, the Component Integration Services object definition does not match the remote object definition. This happens if:

- The object definition was altered outside of Component Integration Services.
- An index was added or dropped outside of Component Integration Services.

Object is altered outside Component Integration Services

Once an object is defined in Component Integration Services, alterations made to an object at the remote server are not made to the local proxy object definition. If an object is altered outside of Component Integration Services, the steps to correct the problem differ, depending on whether create existing table or create table was used to define the object.

To determine which method was used to define the object, run:

```
sp_help object_name
```

If the object was defined via create existing table, the following message is returned in the result set:

```
Object created with 'existing' option
```

If this message is not displayed, the object was defined via create table.

If create existing table was used to create the table in Component Integration Services:

- 1 Use drop table in Component Integration Services.
- 2 Create the table again in Component Integration Services using create existing table. This creates the table using the new version of the table on the remote server.

If the table was created in Component Integration Services using create table, you will drop the remote object when you use drop table. To prevent this, follow these steps:

- 1 Rename the table on the remote server so the table is not deleted when you use drop table.
- 2 Create a table on the remote server using the original name.
- 3 Use drop table in Component Integration Services to drop the table in Component Integration Services and on the remote server.
- 4 Rename the saved table in step 1 with its original name on the remote server.

- 5 Create the table again in Component Integration Services using `create existing table`.

Warning! Do not use `drop table` in Component Integration Services before renaming the table on the remote server, or you will delete the table on the remote server.

A good rule to follow is to create the object on the remote server, and then execute `create existing table` to create the object in Component Integration Services. This enables you to correct mismatch problems with fewer steps and with no chance of deleting objects on the remote server.

Index is added or dropped outside Component Integration Services

Component Integration Services is unaware of indexes that are added or dropped outside Component Integration Services. Verify that the indexes used by Component Integration Services are the same as the indexes used on the remote server. Use `sp_help` to see the indexes used by Component Integration Services. Use the appropriate command on your remote server to verify the indexes used by the remote server.

If the indexes are not the same, the steps to correct the problem differ, depending on whether `create existing table` or `create table` was used to define the object.

To determine which method was used to define the object, run:

```
sp_help object_name
```

If the object was defined via the `create existing table` command, the following message is returned in the result set:

```
Object created with 'existing' option
```

If this message is not displayed, the object was defined via `create table`.

If `create existing table` was used to create the object:

- 1 Use `drop table` in Component Integration Services.
- 2 Re-create the table in Component Integration Services using `create existing table`. This will update the indexes to match the indexes on the remote table.

If `create table` was used to create the object:

- 1 Use `drop index` to drop the index from the remote table.

- 2 Re-create the index in Component Integration Services using `create index`. This creates the index in Component Integration Services and the remote server.

If `create table` was used to define the object, an alternative method is to turn on trace flag 11208. This trace flag prevents `create index` from transmitting to the remote server. To use trace flag 11208, follow these steps:

- 1 Turn on trace flag 11208:

```
dbcc traceon(11208)
```

- 2 Create the index using `create index`.

- 3 Turn off trace flag 11208:

```
dbcc traceoff(11208)
```

If you need help

If you encounter a problem that you cannot resolve using the manuals, ask the designated person at your site to contact Sybase Technical Support. Gather the following information prior to calling Technical Support to help resolve your problem more quickly.

- If a problem occurs while you are trying to access remote data, execute the same script against a local table. If the problem does not exist on the local table, it is specific to Component Integration Services and you should continue through this list.
 - Find out what version of Adaptive Server you are using:
- ```
select @@version
```
- Note the SQL script that reproduces the problem. Include the script that was used to create the tables.
  - Find the processing plan for your query. This is generated using `set showplan`. An example of this is:

```
set showplan, noexec on
go
select au_lname, au_fname from authors
where au_id = 'A1374065371'
go
```

The output for this query looks like this:



```

set showplan, noexec on
go
select au_lname, au_fname from authors where au_id = 'A1374065371'
go
The Abstract Plan (AP) of the final query execution plan:
(remote_sql)
To experiment with the optimizer behavior, this AP can be modified and
then
passed to the optimizer using the PLAN clause:
SELECT/INSERT/DELETE/UPDATE ...
PLAN '(...)

QUERY PLAN FOR STATEMENT 1 (at line 1).

1 operator(s) under root

The type of query is SELECT.

ROOT:EMIT Operator

|LE_REMSCANOP Operator
| SELECT "au_lname" , "au_fname" FROM pubs2.dbo."authors"
WHERE "au_
| id" = 'A1374065371'

```

The noexec option compiles the query, but does not execute it. No subsequent commands are executed until noexec is turned off.

- Obtain the event logging when executing the query by turning on trace flags 11201 – 11205. These trace flags log the following:
  - 11201 – client connect, disconnect, and attention events.
  - 11202 – client language, cursor declare, dynamic prepare, and dynamic execute-immediate text.
  - 11203 – client RPC events.
  - 11204 – messages routed to client.
  - 11205 – interaction with remote servers.
  - 11206 – logs file and directory processing steps.
  - 11207 – logs text and image processing.

After executing the script with the trace flags turned on, the logging is found in the error log in the *\$\$YBASE/install* directory. For example:

```
dbcc traceon (11201,11202,11203,11204,11205)
go
select au_lname, au_fname from authors
where au_id = 'A1374065371'
go
dbcc traceoff (11201,11202,11203,11204,11205)
go
```

The error log output is as follows (the timestamps printed at the beginning of each entry have been removed to improve legibility):

```
server TDS_LANG, spid 15: command text:
select au_lname, au_fname from authors where au_id = 'A1374065371'

server RemoteAccess constructed
server EXECLANG, spid 15, server huntington0_19442, quickpass statement:

ELECT "au_lname" , "au_fname" FROM pubs2.dbo."authors" WHERE "au_id" =
'A1374065371'

server BINDCOLS, spid 15: column 1, name au_lname, fmt.type 'CHAR',
fmt.maxlen 40, fmt.stat 16, con.type 'VARCHAR', con.maxlen 40

server BINDCOLS, spid 15: column 2, name au_fname, fmt.type 'CHAR',
fmt.maxlen 20, fmt.stat 16, con.type 'VARCHAR', con.maxlen 20
server BINDCOLS, spid 15: bind array size 50, total memory required is
4304 bytes

server FETCH , spid 15: cursor C1; ct_fetch() returned 0 rows; status
-204

server RemoteAccess deleted
```

This tracing is global, so once the trace flags are turned on, any query that is executed is logged; therefore, turn tracing off once you have your log. Also, clean out the error log periodically by bringing the server down, renaming the error log, and restarting the server. This creates a new error log.

# Index

## A

- access methods 6
- aliases, user
  - remote logins 118
- allocating resources with `sp_configure` 71
- ASTC server type 56
- `@@textsize` global variable 67
- auto identity
- auto identity database option 10
- automatic connections 111

## B

- `bcp` (bulk copy utility)
  - for text and image datatypes 69

## C

- `cis connect timeout` configuration parameter 73
- `cis packet size` configuration parameter 74
- `cis rpc handling` configuration parameter 74
- Client-Library functions 7
  - connection management 33
  - `ct_send_data` 68
- columns
  - creating indexes on proxy table 98
- Component Integration Services
  - configuring and tuning 121
  - running 2
  - setting up 2, 117
  - users 2
- configuration (server)
  - Component Integration Services 117, 121
- configuration and tuning 71
- configuration parameters
  - Component Integration Services 72, 74
- connect to command 110, 119

- connect to option, grant 110
- connection management 33
- connections
  - listing of remote 78
  - management of 33
  - permission 110
  - physical and logical 51
  - verification 119
- constraints
  - preventing 79
- converting remote server datatypes 9
- copying
  - text and image datatypes 69
- create existing table 9, 10
- create existing table command 9
  - datatype conversions and 9
  - example 10
  - proxy tables 90
- create index command 98
  - query plan for remote tables 99
- create table command
  - proxy tables 99
  - query plan 100
  - remote tables 9
- creating
  - indexes on proxy tables 98
  - proxy tables 90, 99
- `ct_send_data` Client-Library function 68
- cursors
  - row count, setting 74

## D

- database syntax, using native. *See* passthrough mode
- datatype conversions 66
  - remote servers 9
  - server class `direct_connect` 98
- datatypes 63
- `dbcc` (Database Consistency Checker) 53

## Index

dbmoretext DB-Library function 68  
dbwritetext DB-Library function 68  
deallocate cursor command  
    remote servers and 101  
defining  
    indexes 9  
    remote objects 8  
    remote servers 8, 117, 119  
    tables 9, 10  
direct\_connect server class  
    with text and image datatypes 70  
DirectCONNECT servers 3  
directory access 24  
disconnect command 110  
distributed transaction management 55  
drop database command  
    remote servers 101  
drop index command  
    query plan for remote tables 102  
drop table command  
    proxy tables 102  
DTM-enabled servers 56

## E

enable cis configuration parameter 73  
error logging of text and image datatypes 69  
event logging 78  
external logins 118

## F

file access 28  
file system access 24  
files  
    interfaces 118  
    sql.ini file 118

## G

grant command  
    passthrough connections 110  
grant connect to command 110

## I

IDENTITY columns 10  
image datatype 67  
    bulk copy to remote servers 69  
    converting 68  
    entering values 68  
    error logging 69  
    padding 67  
    pattern matching 68  
    restrictions 67  
    with server class direct\_connect 70  
import statistics  
    proxy tables 59  
indexes  
    defining 9  
    updating 79  
insert command  
    proxy tables 103  
integrity of data  
    remote tables and 115  
interface to remote servers 7  
interfaces file  
    adding remote servers 118

## J

Java in the database 60  
joins  
    between remote tables 119, 120

## L

LDAP directory services 34  
like keyword 68  
local tables. *See* proxy tables  
lock timeout interval configuration parameter 53  
logging  
    events 78  
logging in  
    to remote servers 8  
logical connections 51  
logins  
    external 118

**M**

- mapping external logins 42
- memory usage report 78
- modes, trusted/untrusted 41

**O**

- object types 7
- open command 104
- optimization
  - defining existing tables and 9
  - quickpass mode 46, 103
  - remote tables 60
- outbound remote procedure calls 74

**P**

- packets, network
  - size for remote servers 74
- passthrough connection permission 110
- passthrough mode
  - connect to command 110, 119
  - sp\_autoconnect system procedure 111
  - sp\_passthru system procedure 112
  - sp\_remotesql system procedure 113
- patindex string function 68
- pattern matching
  - remote tables 68
  - with text datatype 68
- performance
  - configuration parameters 71
  - remote tables 60
- permissions
  - passthrough connections 110
- physical connections 51
- pre-DTM servers 56
- processing remote procedure calls 51
- proxy databases 18
- proxy tables 8
  - import statistics 59
  - triggers 115
  - update statistics** 59

**Q**

- query optimization 45
- query plans 49
  - create table 100
- query processing 45
- quickpass mode 46, 103
- quoted identifier support 114

**R**

- readtext command
  - errors from 68
- recovery
  - disabling CIS at start-up 79
- reference information
  - Transact-SQL commands for CIS 86
- referential integrity 115
- remcon option, dbcc 78
- remote connection listing 78
- remote logins. *See* external logins
- remote objects
  - defining 8
- remote procedure calls
  - handling outbound 74
  - transmitting 51
- remote servers 30
  - adding 117, 119
  - connection verification 119
  - definition 8
  - interface to 7
  - interfaces file entries 118
  - joins 119, 120
  - logging in 8
  - security issues 40
  - setting up external logins 118
- remote tables
  - joins 119, 120
- reports
  - memory usage 78
  - remote connections 78
- resource allocation (sp\_configure) 71
- rollback command
  - remote servers and 105
- RPC handling 17, 50
- running Component Integration Services 117

## Index

rusage option, dbcc 78

## S

schema synchronization 22  
sds server class 32  
search conditions  
  remote tables 68  
security  
  issues for remote servers 40  
security issues 41  
server class direct\_connect  
  with text and image datatypes 70  
server class sds 32  
server classes 6  
  *See also* individual server class names  
  sds 32  
set command  
  *See also* individual set options  
  remote queries 106  
setting up Component Integration Services 117  
sp\_addexternlogin system procedure 118  
sp\_addserver system procedure 118, 120  
sp\_autoconnect system procedure 111  
sp\_capabilities system procedure 44  
sp\_configure system procedure 71  
sp\_passthru system procedure 112  
sp\_remotelogin system procedure 41  
sp\_remotesql system procedure 113  
sql.ini file 118  
SSL 35  
start-up recovery, disabling 79  
statistics  
  update statistics 107  
syntax, using native database. *Seepassthrough* mode  
sysconfigures system table  
  updating values in 72  
syssservers system table  
  remote servers for Component Integration Services  
    30, 118

## T

tables

  read-only 12  
  remote, joins 119, 120  
tables, proxy  
  defining 9, 10  
  triggers 115  
text datatype 67  
  bulk copy to remote servers 69  
  converting 68  
  entering values 68  
  error logging 69  
  padding 67  
  pattern matching 68  
  restrictions 67  
  with server class direct\_connect 70  
@@textsize global variable 67  
textsize option, set 67  
trace flags 78  
tracemon/traceoff option, dbcc 78  
transaction management 55, 58  
transactional RPCs 58  
transactional\_rpc on option, set command 58  
transmitting remote procedure calls 51  
trusted mode 41  
tuning  
  Component Integration Services 121

## U

update command  
  remote tables 106  
update statistics 60  
**update statistics**  
  proxy tables 59  
update statistics command  
  defining existing tables and 9  
  obtaining complete distribution statistics 79  
  remote tables 60  
updating  
  image datatype 69  
  indexes 79  
  text datatype 69  
using option, readtext  
  errors from 68

## V

variables, configuration. *See* configuration parameters

verifying connectivity 119

## W

wildcard characters 68

writetext command

remote tables 108

