



Configuration Guide

SAP Replication Server® 15.7.1
SP200

Windows

DOCUMENT ID: DC35818-01-1571200-01

LAST REVISED: March 2014

Copyright © 2014 by SAP AG or an SAP affiliate company. All rights reserved.

No part of this publication may be reproduced or transmitted in any form or for any purpose without the express permission of SAP AG. The information contained herein may be changed without prior notice.

Some software products marketed by SAP AG and its distributors contain proprietary software components of other software vendors. National product specifications may vary.

These materials are provided by SAP AG and its affiliated companies ("SAP Group") for informational purposes only, without representation or warranty of any kind, and SAP Group shall not be liable for errors or omissions with respect to the materials. The only warranties for SAP Group products and services are those that are set forth in the express warranty statements accompanying such products and services, if any. Nothing herein should be construed as constituting an additional warranty.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP AG in Germany and other countries. Please see <http://www.sap.com/corporate-en/legal/copyright/index.epx#trademark> for additional trademark information and notices.

Contents

Conventions	1
Preparation for Installing and Configuring SAP	
Replication Server	5
Plan the Replication System	5
Primary and Replicate Data	5
Required Replication Servers	6
Replication Server System Database Location	6
Initial Disk Partition for Each Replication Server	7
ID Server	7
Databases that Require Replication Agents	8
Databases that Require Warm Standby	9
Complete the Replication Server Installation	
Worksheet	9
Replication Server Installation Worksheet	
Sample	10
Release Directory	13
Replication Server Information	14
Replication Server Security Information	17
Replication Server Interfaces Information	18
ID Server Information	19
Replication Server System Database	
Information	21
Adaptive Server Enterprise RSSD Device	
Information	23
Disk Partition Information	25
Remote Site Connections Information	26
Database Replication Agent Information	27
Complete the Database Setup Worksheet	27
Database Setup Worksheet Sample	27
Replication Server Information	29

Replication Server Interfaces Information	29
Database Information	30
Logical Connection Information	30
Database RepAgent Information	32
Configure SAP Replication Server and Add Databases	
Using rs_init	33
rs_init in Interactive Mode	33
Starting rs_init	33
rs_init With a Resource File	34
Using a Resource file for rs_init	34
rs_init Command Line Options	45
Configuring a New Replication Server	47
Entering Replication Server Information	48
Editing the Interfaces File	48
Entering ID Server Information	49
Selecting the RSSD Type	49
Entering Embedded Replication Server System	
Database Information	50
Entering Replication Server System Database	
Information	51
Entering RSSD Device Information	51
Entering RSSD RepAgent Information	51
Entering Disk Partition Information	52
Entering Remote Site Connections Information	
.....	52
Adding a Database to the Replication System	52
Completing Database Information	53
Completing Logical Connection Information	54
Completing the Configuration	54
Upgrade or Downgrade SAP Replication Server	57
Requirements for Upgrading	57
Preparing to Upgrade	58
Upgrading Replication Server	59
Stopping Replication Agent and Quiescing	
Replication Server	60

Deciding the Upgrade Method to Use	61
Upgrades to RSSD or ERSSD and User Databases	61
Upgrading RSSD or ERSSD and User Databases with repserver	62
Upgrading RSSD or ERSSD with rs_init	64
Fixing a Failed Replication Server Upgrade	67
Fixing User Database Upgrades with sysadmin upgrade, "database"	68
Upgrading an SAP ASE User Database with rs_init	68
Upgrading Non-SAP ASE User Databases and User Databases Not Supported by sysadmin upgrade	69
Commit a Local Site to a New Version Level	71
Backing Up the RSSD or ERSSD	76
Upgrading Adaptive Server in a Replication System	76
Suspending Replication and Transaction Activity in the Database	77
Draining Transaction Logs for Primary Databases	77
Draining the RSSD Transaction Log	78
Disabling the Secondary Truncation Point	79
Upgrading Adaptive Server	79
Updating the Adaptive Server System Catalog to Support Quoted Identifiers	79
Restoring Replication	80
Downgrading Replication Server	81
Downgrade Restrictions	83
Migrating Between 32-Bit and 64-Bit Platforms	83
Upgrades and Downgrades Using Existing Directories .	87
Upgrading Using Existing Directories	87
Downgrading to an Earlier Version in Existing Directories	89
Password Encryption	91

Enabling Password Encryption for a Replication Server	91
Altering an Encrypted Password for a Replication Server	92
Secure Sockets Layer	95
Setting Up SSL Services	95
Include Trusted CA certificates	96
Obtain a Certificate for Each SSL-Enabled Replication Server	96
Creating an Identity File	97
Adding an Encrypted Password to the Configuration File	97
Creating SSL Entries in the Directory Service	97
Enabling or Disabling SSL on Replication Server	98
Restarting Replication Server After SSL Changes	98
Start or Stop a Replication Server	101
Start-up Sequence for Servers	101
Starting or Stopping a Server Using the Services Manager	101
Runserver File	102
Starting Replication Server with Sufficient Memory ...	102
Configuring a New Server to Start at System Start-up	102
Stopping a Replication Server Using isql	103
Install and Implement Non-SAP ASE Support Features 	105
Components for Non-SAP ASE Support Installed with Replication Server	105
Setting Up and Configuring Non-SAP ASE Support ...	106
Sample Replication System	107
Setting Up the Sample Replication System	108
Establishing the Sample Replication	109
Troubleshooting and Testing the Replication System .	112

Index	115
--------------------	------------

Conventions

These style and syntax conventions are used in SAP® documentation.

Style conventions

Key	Definition
<code>monospaced(fixed-width)</code>	<ul style="list-style-type: none"> SQL and program code Commands to be entered exactly as shown File names Directory names
<i>italic monospaced</i>	In SQL or program code snippets, placeholders for user-specified values (see example below).
<i>italic</i>	<ul style="list-style-type: none"> File and variable names Cross-references to other topics or documents In text, placeholders for user-specified values (see example below) Glossary terms in text
bold san serif	<ul style="list-style-type: none"> Command, function, stored procedure, utility, class, and method names Glossary entries (in the Glossary) Menu option paths In numbered task or procedure steps, user-interface (UI) elements that you click, such as buttons, check boxes, icons, and so on

If necessary, an explanation for a placeholder (system- or setup-specific values) follows in text. For example:

Run:

```
installation directory\start.bat
```

where *installation directory* is where the application is installed.

Syntax conventions

Key	Definition
{ }	Curly braces indicate that you must choose at least one of the enclosed options. Do not type the braces when you enter the command.
[]	Brackets mean that choosing one or more of the enclosed options is optional. Do not type the brackets when you enter the command.
()	Parentheses are to be typed as part of the command.
	The vertical bar means you can select only one of the options shown.
,	The comma means you can choose as many of the options shown as you like, separating your choices with commas that you type as part of the command.
...	An ellipsis (three dots) means you may repeat the last unit as many times as you need. Do not include ellipses in the command.

Case-sensitivity

- All command syntax and command examples are shown in lowercase. However, replication command names are not case-sensitive. For example, **RA_CONFIG**, **Ra_Config**, and **ra_config** are equivalent.
- Names of configuration parameters are case-sensitive. For example, **Scan_Sleep_Max** is not the same as **scan_sleep_max**, and the former would be interpreted as an invalid parameter name.
- Database object names are not case-sensitive in replication commands. However, to use a mixed-case object name in a replication command (to match a mixed-case object name in the primary database), delimit the object name with quote characters. For example:
pdb_get_tables "TableName"
- Identifiers and character data may be case-sensitive, depending on the sort order that is in effect.
 - If you are using a case-sensitive sort order, such as “binary,” you must enter identifiers and character data with the correct combination of uppercase and lowercase letters.
 - If you are using a sort order that is not case-sensitive, such as “nocase,” you can enter identifiers and character data with any combination of uppercase or lowercase letters.

Terminology

SAP® Replication Server® works with various components to enable replication between supported database such as, SAP® Adaptive Server® Enterprise (SAP® ASE), SAP HANA® database, SAP® IQ, Oracle, IBM DB2 UDB, and Microsoft SQL Server. SAP Replication Server uses SAP ASE for its Replication Server System Database (RSSD) or it uses SAP® SQL Anywhere® for its embedded Replication Server System Database (ERSSD).

Replication Agent™ is a generic term used to describe the Replication Agents for SAP ASE, SAP HANA database, Oracle, IBM DB2 UDB, and Microsoft SQL Server. The specific names are:

- RepAgent – Replication Agent thread for SAP ASE
- Replication Agent for Oracle
- Replication Agent for Microsoft SQL Server
- Replication Agent for UDB – for IBM DB2 on Linux, Unix, and Windows
- Replication Agent for DB2 for z/OS

Preparation for Installing and Configuring SAP Replication Server

Prepare and organize the information you require for the replication system and SAP® Replication Server® you plan to install and configure.

Before you begin:

1. Plan your replication system.
2. Use the Replication Server Installation and Database Setup worksheets to collect and record the information you need to install and configure a Replication Server, and to add a database to your replication system.
3. Use the worksheets and the *Installation Guide* to install Replication Server and the included sample Replication Server.

Plan the Replication System

Obtain the information you require to plan the replication system you intend to install and configure.

In your planning, you need to know:

- Where is the primary and replicate data?
- What Replication Servers will you need?
- Where is the RSSD for each Replication Server?
- Where is the initial disk partition for each Replication Server?
- Which Replication Server is the ID Server?
- Which databases require Replication Agents?
- Which databases require warm standby?

Primary and Replicate Data

Primary data is the set of data that is replicated from a source—the primary database, to another database—the replicate database, through the replication system. The set of data replicated from the primary database to the replicate database is the replicate data. The primary database is known to all of the Replication Servers with subscriptions for the data.

When planning your replication system, you need to:

- Determine which databases contain the data you want to replicate to other databases.

Note: Although this document refers to SAP® Adaptive Server® Enterprise (SAP® ASE) databases, you can use non-SAP ASE databases with Replication Server.

Preparation for Installing and Configuring SAP Replication Server

- Determine the databases where Replication Server will maintain copies of the data.

See also

- *Install and Implement Non-SAP ASE Support Features* on page 105

Required Replication Servers

When you design a replication system, you decide how many Replication Servers will be installed, which databases they will manage, and on which machine they will execute.

A Replication Server can manage one or more databases. One Replication Server is adequate for some replication systems. Other systems require a Replication Server at each geographic site to manage all of the databases at that site. Still others require multiple Replication Servers at each site to handle many databases or heavy transaction volumes.

When you upgrade Replication Servers, you can phase in the upgrades and install newer versions of Replication Servers initially only at certain sites. Consider the timing of such upgrades with care, and assess the need at each site for the new Replication Server features.

See also

- *Upgrade or Downgrade SAP Replication Server* on page 57

Replication Server System Database Location

Replication system data is stored in a dedicated SAP ASE database called the Replication Server System Database (RSSD), or in an embedded Replication Server System Database (ERSSD) using SAP® SQL Anywhere®.

RSSD must be actively managed, while ERSSD is automatically created, configured, and maintained by Replication Server. If you choose to use RSSD, it is created when the Replication Server is installed.

Before you begin the installation, decide which Adaptive Server will store the RSSD for the Replication Server and the devices on which the database and its log will be stored. You can create the Adaptive Server database devices during installation, but identify their physical disk location before you install the Replication Servers.

If you use ERSSD, decide the directory paths for the ERSSD database file, transaction log, and backup. For better performance and recoverability, the database file, transaction log, and backup directory should be on different disk devices.

See also

- *Replication Server System Database Information* on page 21

Initial Disk Partition for Each Replication Server

Replication Server stores messages, such as replicated transactions, on disk in stable queues. Disk space for the queues is allocated from disk partitions you create. Disk partitions are Windows disk files.

You must allocate a disk partition of at least 20MB for each Replication Server you install. You can add more partitions later if necessary. Check each partition to make sure that it is available and that the Windows System Administrator can write to it. To use an operating disk for a partition, create an empty file. Verify that there is enough space on the file system for Replication Server to extend the disk partition file to full partition size.

Allocate the entire partition to the Replication Server. If you allocate only a portion of the partition to Replication Server, you cannot use the remainder for any other purpose. Allow read or write permissions on the partition only if the user must have permission to start Replication Server.

See *System Requirements* in the *Installation Guide*.

ID Server

The ID Server is a Replication Server that registers all Replication Servers and databases in the replication system.

In addition to the usual Replication Server tasks, the Replication Server acting as the ID Server assigns a unique ID number to every Replication Server and database in the replication system. The ID Server also maintains version information for the replication system. Otherwise, the ID Server is like any other Replication Server.

To allow a new Replication Server, or the Replication Server that manages the new database, to log in and retrieve an ID number, the ID Server must be running each time a:

- Replication Server is installed
- Route is created
- Database connection is created or dropped

Because of these requirements, the ID Server is the first Replication Server that you install and start when you install a replication system. If you have only one Replication Server, or if you are installing Replication Server for the first time, then that Replication Server is also the ID Server. If you are adding a Replication Server to an existing replication system, you must know the name of the Replication Server in the system that is the ID Server.

The ID Server must have a login name for Replication Servers to use when they connect to the ID Server. The login name is recorded in the configuration files of all Replication Servers in the replication system by the **rs_init** configuration program when you are setting up and managing the replication system.

Warning! The ID Server is critical to your replication environment, and is difficult to move once it has been installed. Once you have selected a name for the ID Server, you cannot change

to a different Replication Server. SAP does not support any procedures that change the name of the ID Server in the configuration files.

See also

- *Replication Server Information* on page 14

Replication System Domain

Replication system domain refers to all replication system components that use the same ID Server.

Some organizations have multiple independent replication systems. Since the ID Server determines member Replication Servers and databases in a replication system, one replication system in an organization with multiple replication systems is also called an ID Server domain.

No special steps are required to set up multiple ID Server domains. Every Replication Server or database belongs to one replication system and has a unique ID number in that ID Server domain.

You can set up multiple replication system domains, with the following restrictions:

- Replication Servers in different domains cannot exchange data. Each domain must be treated as a separate replication system with no cross-communication between them. You cannot create a route between Replication Servers in different domains.
- A database can be managed by only one Replication Server in one domain. Any given database is in one, and only one, ID Server's domain. This means that you cannot create multiple connections to the same database from different domains.

Databases that Require Replication Agents

A Replication Agent™ retrieves transactions from a database log and passes them to the replication system through the Replication Server that manages the database.

You can configure multiple replication paths from Adaptive Server with an Adaptive Server Replication Agent (RepAgent) for each replication path. See *Multi-Path Replication* in the *Administration Guide Volume 2*. For non-SAP databases there is only one Replication Agent per database. Because you must configure the Replication Agent when you set up a database for replication, you must know whether the database requires a Replication Agent before you add the database to the replication system. A user database requires a Replication Agent if:

- The database holds primary data that is replicated to other databases managed by the same or different Replication Servers.
- The Replication Server manages a database that is a source of replicated stored procedure execution.
- You plan to replicate a stored procedure execution from a primary to replicate databases or from a replicate to a primary database. Replication Agent retrieves the procedure call information from the database transaction log. See the *Administration Guide Volume 1*.

- The database is the active or standby database in a warm standby application. Replication Agent for a standby database is needed only when you switch to the standby database. See the *Administration Guide Volume 1*.

An RSSD requires a Replication Agent if the Replication Server using that RSSD has a route to another Replication Server; for example:

- The Replication Server manages primary data that is replicated to databases managed by other Replication Servers.
- The Replication Server manages a database that is a source of replicated stored procedure execution.
- The Replication Server is an intermediate site in an indirect route.

An RSSD does not require a Replication Agent if the replication system has only one Replication Server. Replication Agent for ERSSD is managed by Replication Server. It is automatically started when a route is created. You do not need to decide the ERSSD Replication Agent requirements at installation or configuration time of Replication Server.

See also

- *Database Replication Agent Information* on page 27

Databases that Require Warm Standby

Replication Server can maintain a warm standby database for an Adaptive Server or Oracle database. If the active database fails, clients can switch to the standby database with little interruption.

To set up a warm standby application, you must perform some tasks in Replication Server before and after you add databases to the replication system.

Before you install Replication Server, see *Manage Warm Standby Applications* in the *Administration Guide Volume 2*.

To configure warm standby for Oracle databases, see *Heterogeneous Warm Standby for Oracle* in the *Heterogeneous Replication Guide*.

Complete the Replication Server Installation Worksheet

Use the worksheet to record configuration information you need during the Replication Server installation.

The **rs_init** program is used to configure Replication Server software. The sections in the Replication Server Installation Worksheet correspond to the **rs_init** menus, so you can enter information from the worksheet directly into **rs_init**.

rs_init supplies default values for most of the items in the Replication Server installation worksheet and Database setup worksheet. Many of the defaults are constructed from values that you enter. For example, if you enter “TOKYO_RS” for the Replication Server name,

Preparation for Installing and Configuring SAP Replication Server

rs_init names the log file `TOKYO_RS.log`. You can accept the displayed value or enter a different value.

Note: Replication Server reserves identifiers that begin with “rs_”. Do not use names that begin with “rs_” for Adaptive Servers, Replication Servers, database objects, or login names. See the *Reference Manual* for other restrictions.

Replication Server Installation Worksheet Sample

Make a copy of this worksheet for each Replication Server you install. Complete each section the worksheet as you prepare to install and configure Replication Server.

Keep the worksheet copy to use if you reconfigure your replication system.

Required worksheet items are marked with an asterisk (*). **rs_init** has default values for items that are not marked. To use a default value, leave the unmarked fields blank and fill it in on the worksheet when you run **rs_init**.

Release Directory			
	Release directory:		

Release Server Information			
	Replication Server name:*		
	Is this Replication Server the ID Server?	Yes	No
	*		
	Replication Server error log:		
	Replication Server configuration file:		
	Replication Server password encryption:	Yes	No
	Replication Server character set:		
	Replication Server language:		
Replication Server sort order:			

Replication Server Security Information			
	Enable network security?*	Yes	No
	If Yes, security system:	dce	csfkrb5
	If Yes, login name:		
	If Yes, keytab file name:		

Replication Server Security Information			
	Use Secure Sockets Layer (SSL) security?	Yes	No
	If Yes, SSL identity file:		
	If Yes, SSL private key password (default is password):		

Replication Server Interfaces Information	
	Network driver:* _____ Windows Sockets _____ Named Pipes _____ IPX/SPX
	Connection information:*

ID Server Information	
	ID Server name:*
	ID Server user:
	ID Server password:
	Starting Replication Server ID:
	Starting database ID:

Replication Server System Database Choice			
	Will RSSD be embedded? (default is no)	Yes	No

SQL Anywhere Embedded Replication Server System Database Information	
Complete if you selected Yes for "Will RSSD be embedded?"	ERSSD name:*
	ERSSD database file directory:*
	ERSSD transaction log directory:*
	ERSSD backup directory:*
	ERSSD error log directory:*

Adaptive Server Enterprise Replication Server System Database Information			
Complete if you selected No for "Will RSSD be embedded?"	RSSD Adaptive Server name:*		
	RSSD name:		
	Will RSSD be replicated?*	Yes	No

Adaptive Server Enterprise Replication Server System Database Information			
	Allow HA failover for RSSD connections?	Yes	No
	Create RSSD:*	Yes	No
	SA user:		
	SA password:*		
	Primary user:		
	Primary password:		
	Maintenance login:		
	Maintenance password:		

Adaptive Server Enterprise RSSD Device Information			
	Size of the RSSD database:		
	RSSD device name:*		
	Create the RSSD device:*	Yes	No
	RSSD device physical name:		
	RSSD device size:		
	Size of the RSSD log:		
	RSSD log device name:*		
	Create the RSSD log device:*	Yes	No
	RSSD log device physical name:		
	RSSD log device size:		

Disk Partition Information	
	Disk partition path:*
	Logical identifier for disk partition:*
	Size of disk partition:
	Start value for partition:

Remote Site Connections Information	
	Replication Server login name:
	Replication Server password:
RSSD RepAgent Information	
Complete if you selected Yes for “Will RSSD be replicated?”	RS user:
	RS password:

Release Directory

The release directory—also called the installation directory—is where you install Replication Server.

The first eight characters of the Adaptive Server and Replication Server names must be unique on your network. Replication Server creates a new directory structure that allows you to use multiple versions of some components.

See *Installation Directory Structure* in the *Installation Guide*.

Choosing an Installation Directory

Consider where you want to install the software.

1. If this is the first time that you are installing the software on your computer, select a path for the release directory. The installation program performs these steps when it sets the default release directory:
 - a) If the SYBASE variable exists, it sets the default release directory specified by the variable.
 - b) If the SYBASE variable does not exist, but the Registry entry HKEY_LOCAL_MACHINE\Software\Sybase\Setup\Sybase exists, it sets the default release directory to the directory specified by the Registry.
 - c) If neither the SYBASE variable nor the Registry entry exists, the installation program creates the default release directory by concatenating the drive name of the system disk with \SYBASE. For example, if the system drive is C, then the default directory is C:\SYBASE.
2. Record the release directory on your worksheet.

Installing in a New Release Directory

Install the software in a new directory without any other SAP software products for a clean setup.

Perform these if you do not install Replication Server in the same directory with other SAP software:

Preparation for Installing and Configuring SAP Replication Server

1. Set the environment variable to point to the correct release directory before you start each SAP software.

Note: Replication Server uses a directory structure that installs all Replication Server files in a directory called `REP-15_5`, which you can set with the `%SYBASE_REP%` environment variable.

2. Set the `PATH` variable so that it uses the correct DLL versions.
3. Keep a copy of `sql.ini` in each release directory, or use command line options to specify the correct `sql.ini` file when you start each SAP software.

Replication Server Information

Lists the Replication Server information that you need to complete in the corresponding section in the worksheet.

These are the worksheet fields:

Field	Description
Replication Server name	(Required) A name for the Replication Server. The name must be unique in the replication system. The name is not case-sensitive. However, if the Replication Server is part of a multiplatform replication system, ensure the same case is used in all instances. Warning! The first eight characters of Adaptive Server and Replication Server must be unique on your network.
Is this Replication Server the ID Server?	(Required) Select Yes if you are installing the ID Server.
Replication Server error log	The path for the Replication Server error log file. Replication Server writes informational and error messages to this text file.
Replication Server configuration file	The path for the Replication Server configuration file, which contains parameters that Replication Server reads at start-up. See <i>Manage a Replication System</i> in the <i>Administration Guide Volume 1</i> .
Replication Server password encryption	Select Yes if you want passwords to be encrypted in the Replication Server configuration file and in the RSSD. Warning! If you do not encrypt passwords, anyone with the required permissions can look at the passwords in the configuration files and in the RSSD <code>rs_users</code> system table.
Replication Server character set	The character set that the Replication Server will use. You can specify any SAP-supported character set that is available for your language.

Field	Description
Replication Server language	The language Replication Server should use to print messages to the error log and to clients. It can be any language that is compatible with the character set you install. Additional information about character sets is available in the <i>Adaptive Server Enterprise Configuration Guide</i> .
Replication Server sort order	The sort order for the Replication Server.

See also

- *ID Server* on page 7

Replication Server Character Sets

The character set used by the Replication Server must match the character set used by the data servers and Replication Agents it controls for replication to work properly.

The character set must be compatible with the character sets of the other Replication Servers in the system. By default, **rs_init** configures Replication Server with the native character set for your platform.

When you create a subscription, Replication Server copies the requested data from the primary database to the replicate database in a process known as subscription materialization. During subscription materialization, the primary data server converts character data to the replicate Replication Server character set. Make sure that the replicate Replication Server character set is installed at the primary data server if it is different from the primary data server character set.

Similarly, when you create a route, make sure that the character set of the destination Replication Server is installed at the data server of the source Replication Server RSSD.

Supported Character Sets

Lists the character sets that Replication Server supports.

The supported character sets in the English language version of Replication Server include:

- cp437 (Code Page 437) – character set used in IBM PCs.
- cp850 (Code Page 850) – IBM/Microsoft Multilingual Character Set, used in IBM PCs.
- deckanji – DEC Kanji Code for JIS-X0208.
- eucgb – EUC GB encoding for Simplified Chinese character sets.
- eucjis – extended UNIX Code for JIS-X0201 and JIS-X0208.
- eucksc – (Code Page 949) EUC KSC Korean encoding.
- gb18030 – GB 18030-2000 standard for Chinese characters, established by the government of the People's Republic of China.
- iso15 – similar to iso_1.

Preparation for Installing and Configuring SAP Replication Server

- iso_1 (ISO-8859/1) – 8-bit character set for many systems. This is the default for Adaptive Server with Solaris and IBM RISC System 6000 AIX.
- mac – default Macintosh character set.
- roman8 – Hewlett-Packard character set.
- roman9 – the same as roman8, except for codepoint 0xBA, previously treated as the universal currency symbol, now representing the euro currency symbol.
- sjis (Shift-JIS) – IBM/Microsoft Code for JIS-X0201 and JIS-X02081.
- utf8 – an ASCII-preserving encoding method for Unicode.

The Chinese language includes these character sets:

- eucgb
- gb18030
- utf8

The Japanese language includes these character sets:

- deckanji
- eucjis
- sjis
- utf8

The Korean language includes these character sets:

- eucksc
- utf8

The French, German, and Spanish languages include these character sets:

- cp437
- cp850
- iso15
- iso_1
- mac
- roman8
- roman9
- utf8

Replication Server Language

rs_init configures Replication Server to print messages in U.S. English by default.

Other available languages are Chinese, French, German, Japanese, Korean, and Spanish.

rs_init uses the same identifiers for language names as Adaptive Server. You can select any language when you install Replication Server as long as the language is compatible with the character set you install.

If the language for the Replication Server and the language for its connected data servers are different, the language for the Replication Server must be installed at the data servers. This lets

the data servers return messages to Replication Server in the configured language and recognize and format dates for the configured language.

For example, the date format “01/02/99” is equivalent to “January 2, 1999” in us_english but “February 1, 1999” in french. Data servers can format the date correctly only if the Replication Server configured language is installed.

Replication Server Sort Order

The sort order controls which rows of a table belong in a subscription that has a where clause involving character data.

The sort order also controls how the identifiers you enter are recognized with regard to case sensitivity, accents, and so forth.

You can specify any SAP-supported sort order that is compatible with your character set. For replication to work properly, all sort orders in your replication system should be the same.

By default, **rs_init** configures Replication Server with the binary sort order. Available sort orders vary, depending on the character set you plan to install. Sort orders are located in the release directory in the directory `charsets/charset_name`, where *charset_name* is the name of the character set.

See the *Design Guide* for guidelines on configuring languages, character sets, and sort orders in your replication system.

Replication Server Security Information

Lists the Replication Server security information that you need to complete in the corresponding section in the worksheet.

These are the worksheet fields:

Field	Description
Enable network security	(Required) Select Yes to enable external network security.
Type of security system	If you are enabling network security, select DCE or Kerberos.
Login name	The name of the primary user who will make the secure connections. SAP recommends that you use the name of the Replication Server as the principle user name.
Keytab file name	The full path to the location of the keytab file.
Use SSL security	Select Yes if you are using Secure Sockets Layer (SSL) security.
SSL identity file	The full path to the location of the SSL identity file.
SSL private key password	The private key password. The default password is password .

See *Manage Replication Server Security* in the *Administration Guide Volume 1* for more information on security.

See also

- *Secure Sockets Layer* on page 95

Replication Server Interfaces Information

Use the Replication Server interfaces information section of the worksheet to record information that defines the network port where Replication Server listens for connections. Each entry in the `sql.ini` file (in the `ini` subdirectory of the release directory) is called a listener service.

These are the worksheet fields:

Field	Description
Network driver	(Required) Check the box next to the type of network you want to use: Windows Sockets, Named Pipes, or NWLink IPX/SPX.
Connection information	(Required) Your entry depends on your choice of network driver. See the connection information syntax table for each network driver.

Connection Information Syntax

Lists the formats for each network driver.

Protocol	Syntax
Windows Sockets TCP/IP	Two formats: <i>computer_name,port_number</i> <i>ip_address,port_number</i> where: <ul style="list-style-type: none">• <i>computer_name</i> – is the name of your machine.• <i>ip_address</i> – is the IP address.• <i>port_number</i> – is a number between 1025 and 65535 that is unique on the machine. Examples: FASTCAR,8877 130.214.30.25,8877

Protocol	Syntax
Named Pipes	<p>(Local) \pipe\identifier_1\[identifier_2]</p> <p>(Remote) \\computer_name\pipe\identifier_1\[identifier_2]</p> <p>“pipe” is a required prefix to all pipe names. identifier_1 and identifier_2 are unique names that conform to the eight-character MS-DOS naming convention. identifier_2 is optional; however, each pipe name should be uniquely defined. Server pipes can only be local.</p> <p>Example (local):</p> <p>\pipe\sybase\tokyo</p> <p>Example (remote):</p> <p>\\FASTCAR\pipe\sybase\sydney</p>
NWLink IPX/SPX	<p>Three formats:</p> <p><i>computer_name</i></p> <p><i>net_number, node_number, socket_number</i></p> <p><i>computer_name, socket number</i></p> <p>where:</p> <ul style="list-style-type: none"> • <i>computer_name</i> – is the name of the machine. • <i>net_number</i> and <i>node_number</i> – are obtained from the network. • <i>socket_number</i> – is in hexadecimal format. <p>Example:</p> <p>FASTCAR</p> <p>16, 1, 83BD</p> <p>FASTCAR, 83BD</p>

ID Server Information

Lists the ID Server information that you need to complete its corresponding section in the worksheet.

These are the worksheet fields:

Preparation for Installing and Configuring SAP Replication Server

Field	Description
ID Server name	<p>(Required) If the Replication Server you are installing is the ID Server, rs_init assigns an ID Server name identical to this Replication Server name.</p> <p>If you are installing a new Replication Server in an existing Replication Server domain, enter the name of the Replication Server that is acting as the ID Server.</p>
ID Server user	<p>If the Replication Server you are installing is the ID Server, enter the login name that other Replication Servers will use to connect to this ID Server.</p> <p>If you are installing a new Replication Server to an existing Replication Server domain, copy the ID Server user name from the worksheet you completed when you created the ID Server.</p>
ID Server password	<p>If the Replication Server you are installing is the ID Server, enter the password for the ID Server user.</p> <p>If you are adding a new Replication Server to an existing Replication Server domain, copy the ID Server password from the worksheet you completed when you created the ID Server.</p>
Starting Replication Server ID and Starting Database ID	<p>These two configuration parameters allow you to specify separate ranges of Replication Server ID numbers and database ID numbers that an ID Server will assign. Although you are not required to specify ranges, specifying ranges makes it easier to merge replication systems later.</p> <hr/> <p>Note: “Starting Replication Server ID” and “Starting Database ID” in the worksheet apply only to the ID Server. If you are not installing the ID Server, skip to “Replication Server System Database Information”.</p>

See also

- *ID Server* on page 7
- *Replication Server System Database Information* on page 21

Default ID Number Ranges and ID Number Allocation for ID Server Domains

An ID Server assigns ID numbers sequentially. Separate ranges of values are maintained for databases and Replication Servers.

Table 1. Database and Replication Server Default ID Number Ranges

Object Type	Minimum ID Number	Maximum ID Number
Database	101	16777215
Replication Server	16777317	33554431

Minimum values for each ID Server must be within the ranges specified. For example, if your organization has three separate ID Server domains, you can set the minimum ID numbers as shown in "Example ID Number Allocation for ID Server Domains."

Table 2. Example ID Number Allocation for ID Server Domains

ID Server Domain	Starting Database ID	Starting Replication Server ID
Finance division	101	16777317
Manufacturing division	100101	16877317
Sales division	200101	16977317

This arrangement provides the ID Server in each domain at least 100,000 ID numbers for databases and 100,000 ID numbers for Replication Servers. You need not set a maximum value, since it is unlikely that you will install more than 100,000 Replication Servers or add more than 100,000 databases to a replication system.

See *Manage a Replication System* in the *Administration Guide Volume 1* for more information about adding replication system domains.

Replication Server System Database Information

Replication Server maintains its system tables in its system database. You can choose to set up a Replication Server System Database (RSSD) in an Adaptive Server Enterprise database, or an Embedded Replication Server System Database (ERSSD) in a SQL Anywhere (SA) database.

Adaptive Server Enterprise RSSD Information

Lists the Adaptive Server Enterprise RSSD information that you need if you want to have an RSSD.

These are the worksheet fields:

Preparation for Installing and Configuring SAP Replication Server

Field	Description
RSSD Adaptive Server name	(Required) The name of the Adaptive Server that will hold the system database for the Replication Server.
RSSD name	The name of the database where the Replication Server system tables will be stored.
Will RSSD be replicated?	(Required) Select Yes if the RSSD for the Replication Server requires a Replication Agent.
Allow HA failover for RSSD connections?	Select Yes if the Adaptive Server managing the RSSD supports HA failover and you want RSSD connections to fail over to an alternative Adaptive Server.
Create RSSD	<p>(Required) Select Yes if you want rs_init to create the system database.</p> <p>Select No if the system database already exists or if you want to create it manually.</p> <p>If the database already exists, it should be dedicated to this Replication Server. See the <i>Installation Guide</i> for disk space and system requirements.</p>
SA user	<p>The login name for the “sa” user for the Adaptive Server that will hold the RSSD. The default is “sa.”</p> <p>rs_init uses the “sa” login name to create user login names and the system tables in the RSSD.</p>
SA password	(Required) The “sa” password for the Adaptive Server that will hold the RSSD.
Primary user	The login name for the RSSD primary user. Replication Server uses this login name for system table updates. rs_init creates the primary user.
Primary password	The password for the RSSD primary user.
Maintenance login	The name of the maintenance user for the RSSD. Replication Server uses this login name to perform operations on the system tables that are replicated from other sites. rs_init creates the maintenance user and adds the maintenance user to the RSSD.
Maintenance password	The password for the RSSD maintenance user.

SQL Anywhere ERSSD Information

Lists the SQL Anywhere ERSSD information that you need if you plan to have an ERSSD.

These are the worksheet fields:

Field	Description
ERSSD name	The name of the SQL Anywhere server that will hold the system database for the Replication Server.
ERSSD database file directory	The directory for the SQL Anywhere server database file.
ERSSD transaction log directory	The directory for the SA server transaction log.
ERSSD backup directory	The directory for the SQL Anywhere server backup files.
ERSSD error log directory	The directory for the SQL Anywhere server error log file.

Note: **rs_init** automatically fills these fields with default values on the same device. However for better performance and recoverability, place the ERSSD database directory, ERSSD transaction log directory, and ERSSD backup directory on separate devices.

See *Manage a Replication System* in the *Administration Guide Volume 1*.

Adaptive Server Enterprise RSSD Device Information

Complete the "RSSD Device Information" section of the worksheet if you want **rs_init** to create the RSSD and you selected Yes for "Create RSSD".

However, if you do not want **rs_init** to create the RSSD, skip this section and go to "Disk partition information" to complete its corresponding section in the worksheet.

These are the worksheet fields:

Field	Description
Size of the RSSD database	The size, in megabytes, of the data portion.
RSSD device name	(Required) The name of the Adaptive Server logical device where you want to create the RSSD. If the device already exists, it must have enough space available to create the new database.
Create the RSSD device	(Required) Select Yes if you want rs_init to create the RSSD data device on the Adaptive Server database device. Select No if the RSSD data device already exists, or if you will create it before you run rs_init .

Field	Description
RSSD device physical name	<p>If you want rs_init to create the RSSD device, enter the physical device name for the database device on which you want to store the RSSD.</p> <p>In Windows, the physical name is the name of the disk file.</p> <p>If you do not want rs_init to create the RSSD data device, leave this field blank.</p>
RSSD device size	<p>If you want rs_init to create the RSSD device, enter the capacity, in megabytes, of the physical device. The device size must be at least the size you specified for the data portion of the RSSD database.</p> <p>If you do not want rs_init to create the RSSD device, leave this entry blank.</p>
Size of the RSSD log	<p>The size, in megabytes, for the RSSD database log.</p> <hr/> <p>Note: SAP recommends that you store the RSSD log on a device other than the master device, and on a different device from the RSSD data.</p> <hr/>
RSSD log device name	(Required) The logical name for the device you want rs_init to use for the RSSD log.
Create the RSSD log device	<p>(Required) Select Yes if you want rs_init to create the RSSD log device in Adaptive Server.</p> <p>Select No if the device already exists or if you will create it before you run rs_init.</p>
RSSD log device physical name	<p>If you want rs_init to create the RSSD log device, enter the physical device name for the device.</p> <p>This is a Windows file name.</p> <p>If you do not want rs_init to create the RSSD log device, or if you are using a single device for both the RSSD and its log (this is not recommended), leave this field blank.</p>
RSSD log device size	<p>If you want rs_init to create the RSSD log device, enter the capacity, in megabytes, of the physical device. The device size must be at least the size you specified for the RSSD log.</p> <p>If you do not want rs_init to create the RSSD log device, or if you are using a single device for both the RSSD and its log (this is not recommended), leave this field blank.</p>

RSSD Device

The RSSD device is the Adaptive Server database device where **rs_init** creates the Replication Server RSSD.

Therefore, choose a database device other than the default master device, that has the minimum amount of space required. Use **sp_helpdevice** to list the available devices.

Note: **rs_init** by default uses a minimum of 40MB for the database size, and 16MB for the RSSD log size.

Select one of the following if the Adaptive Server does not have a device available for the RSSD:

- Add a device and record the information on your worksheet
- Have **rs_init** create the device when it installs Replication Server

Note: If the Adaptive Server is not on the local machine, you must create the device yourself. **rs_init** incorrectly evaluates the local machine's file system instead of the remote machine's file system when it validates the path name and disk space requirements of the device.

If you want **rs_init** to create the device, verify that the Windows System Administrator account can create the file you specify and that there is sufficient disk space for the file. Execute **sp_configure** devices in Adaptive Server to verify that the value for devices is high enough to allow you to add a new device. See the *Adaptive Server Enterprise System Administration Guide* for information about device requirements.

Disk Partition Information

Lists the disk partition information that you need to complete the corresponding section in the worksheet.

Replication Server uses disk partitions for stable queues, which temporarily store the data it receives and sends.

In Windows, Replication Server uses operating system files for partitions.

Note: In Windows, you must not use a raw device to create a partition.

The minimum partition size is 20MB. You can add more partitions after the Replication Server is installed.

Preparation for Installing and Configuring SAP Replication Server

Field	Description
Disk partition path	(Required) The name of the physical disk device or the full path name of a file to be used for the disk partition. If you use an operating system file, there must be enough space on the file system for Replication Server to extend the file to the size you specify. You must have already created the operating system file.
Logical identifier for disk partition	(Required) A logical identifier for the partition. This name is used in commands and in Replication Server messages to identify the disk partition. <i>See Replication Server Reference Manual > Topics > Identifiers.</i>
Size of disk partition	The size, in megabytes, of the disk partition. The partition must be at least 20MB. <i>See Replication Server Administration Guide Volume 1 > Replication Server Technical Overview > Transaction Handling with Replication Server > Stable Queues > Partitions for Stable Queues and Replication Server Design Guide > Capacity Planning.</i>
Start value for partition	This value prevents Replication Server from using the beginning of a raw disk partition. It is required if your operating system stores information, such as configuration maps, at the beginning of the disk partition. Enter the number of megabytes Replication Server should ignore. For example, if you enter 1, Replication Server will not use the first megabyte of the raw disk partition.

Remote Site Connections Information

The Remote site connections information section of the worksheet defines a login name for other Replication Servers to use when logging in to this Replication Server.

These are the worksheet fields:

Field	Description
Replication Server login name	The login name that other Replication Servers will use to connect to this Replication Server.
Replication Server password	Replication Server password

Database Replication Agent Information

Lists the database Replication Agent information that you need to complete the corresponding section in the worksheet.

These are the worksheet fields:

Field	Description
RS user	The login name that the RSSD Replication Agent will use to connect to the Replication Server
RS password	The password for the RS user login name.

See also

- *Databases that Require Replication Agents* on page 8

Complete the Database Setup Worksheet

Use the worksheet to record configuration information you need for each database you plan to add to the replication system. Refer to the information on the worksheet when you use **rs_init** to add the database to your replication system.

Each primary or replicate database in your replication system is managed by a Replication Server. The database may also require a Replication Agent.

See the *Design Guide* for guidelines on configuring character sets, languages, and sort orders in your replication system.

Database Setup Worksheet Sample

Make a copy of this worksheet for each database you add to the replication system. Complete the worksheet as you prepare to install and configure Replication Server.

Keep the worksheet copy to use if you reconfigure your replication system.

Required worksheet items are marked with an asterisk (*). **rs_init** has default values for items that are not marked. To use the default values, leave the unmarked field blank and fill it on the worksheet when you run **rs_init**.

Replication Server Information	
	Replication Server name:*
	RS SA user:*
	RS SA password:*

Replication Server Interfaces Information			
	Network driver:* _____ Windows Sockets _____ Named Pipes _____ IPX/SPX		
	Connection information:*		
Database Information			
	Adaptive Server name:*		
	SA user:		
	SA password:		
	Database name:		
	Will the database be replicated?*	Yes	No
	Maintenance user:		
	Maintenance password:		
	Is this a physical connection for an existing logical connection?	Yes	No
Logical Connection Information			
Complete if you selected Yes for “Is this a physical connection for an existing logical connection?”			
	Is this an active connection or a standby connection?*	Active	Standby
	Logical DS name:*		
	Logical DB name:*		
Complete the rest of the items in this section only if you selected “Standby” in response to “Is this an active connection or standby connection?”			
	Active DS name:*		
	Active DB name:*		
	Active DB SA user:*		
	Active DB SA password:*		
	Initialize standby using dump and load ?*	Yes	No

	Use dump marker to start replicating to standby?*	Yes	No
Database RepAgent Information			
Complete the following if you selected Yes for “Will the database be replicated?”			
	RS user:		
	RS password:		

Replication Server Information

The Database Setup Worksheet includes Replication Server information needed to identify the Replication Server that will manage the database.

The Replication Server must be installed and running before you can add the database to the replication system.

These are the worksheet fields:

Field	Description
Replication Server name	(Required) The name of the Replication Server that will manage the database.
RS SA user	(Required) The Replication Server System Administrator (RS SA) login name (usually “sa”).
RS SA password	(Required) The password for the Replication Server SA user.

Replication Server Interfaces Information

Copy the information you have provided in the “Replication Server interfaces information” section of the Replication Server installation worksheet for the Replication Server that will manage this database. Since the Replication Server is already installed, you do not have to enter this information again unless you run **rs_init** in a release directory that uses a different `sql.ini` file.

These are the worksheet fields:

Field	Description
Network driver	(Required) Check the box next to the type of network you want to use: Windows Sockets, Named Pipes, or NWLink IPX/SPX.
Connection information	(Required) Your entry depends on your choice of network driver. See the connection information syntax table for each network driver.

Database Information

The Database Setup Worksheet includes database information that identifies the database you are adding to the replication system.

Field	Description
Adaptive Server name	(Required) The name of the Adaptive Server where the database resides.
SA user	The “sa” login name for the Adaptive Server managing the database.
SA password	The password for the SA user login name.
Database name	The name of the database.
Will the database be replicated?	(Required) Select Yes if the database requires a Replication Agent.
Maintenance user	A login name for Replication Server to use when updating replicated data. This user must be granted all permissions necessary to maintain the replicated data. rs_init creates this login, if it does not already exist, and grants the necessary permissions. See the <i>Administration Guide Volume 1</i> for more information about login names for replication system components.
Maintenance password	The password for the maintenance user.
Is this a physical connection for an existing logical connection?	Select Yes if you are adding an active or standby database for a warm standby application, and No if you are not. See the instructions for setting up warm standby databases in <i>Managing Warm Standby Applications</i> in the <i>Administration Guide Volume 2</i>

See also

- *Databases that Require Replication Agents* on page 8

Logical Connection Information

The Database Setup Worksheet includes logical connection needed if you are adding a database that is part of a warm standby database application.

Setting up a warm standby application requires that you perform additional tasks in the Replication Server before and after you use **rs_init** to add the databases to the replication system.

To configure warm standby for Adaptive Server databases, see *Manage Warm Standby Applications* in the *Administration Guide Volume 2*. To configure warm standby for Oracle

databases, see *Heterogeneous Warm Standby for Oracle* in the *Heterogeneous Replication Guide*.

These are the worksheet fields:

Field	Description
Is this an active connection or standby connection?	(Required) Select Active if you are adding the active database for the warm standby application. Select Standby if you are adding the standby database for the warm standby application.
Logical DS name	(Required) The name of the logical data server for the logical connection. You must have already created it using create logical connection .
Logical DB name	(Required) the name of the logical database for the logical connection. You must have already created it using create logical connection . Complete the rest of the items in this section only if you have selected a standby connection over an active connection.
Active DS name	(Required) The name of the data server with the active database. Enter the actual data server name, not the logical data server name defined for the warm standby database pair.
Active DB name	(Required) The name of the active database. Enter the actual database name, not the logical database name defined for the warm standby database pair.
Active DB SA user	(Required) The login name of the system administrator for the data server of the active database. Replication Server uses this login name to set up warm standby applications.
Active DB SA password	(Required) The password for the system administrator login name of the data server of the active database.
Initialize standby using dump and load?	(Required) Select Yes if you plan to initialize the standby database with the contents of the active database with the dump and load commands. Select No if you plan to initialize the standby database with the bcp utility, or if you do not need to initialize the standby database.
Use dump marker to start replicating to standby?	(Required) Select Yes if transactions will be executed in the active database while the standby database is initialized.

Database RepAgent Information

The Database Setup Worksheet includes database RepAgent information needed if the database requires a Replication Agent and you have selected to replicate the database.

These are the worksheet fields:

Field	Description
RS user	<p>The Replication Server login name that the Replication Agent will use to connect to the Replication Server.</p> <p>The default Replication Server user login name and password for this Replication Agent is the default login name and password for the Replication Server user for the RSSD RepAgent, which you noted in the “RSSD RepAgent” section of the Replication Server installation worksheet. If you want this user to use a different login name and password, you must first create the user in the Replication Server and then grant connect source permission to the user.</p>
RS password	The password for the RS user login name.

Configure SAP Replication Server and Add Databases Using rs_init

Use **rs_init** to configure SAP Replication Server and to add databases to your replication system. You can use **rs_init** interactively or with a resource file.

rs_init in Interactive Mode

Using **rs_init** in interactive mode is easy to use and catches mistakes that might be missed when using **rs_init** with a resource file.

rs_init in interactive mode provides command keys and menu prompts to help you make selections and move between windows. It also rejects invalid entries and displays warnings or error messages when you make improper selections. If you make a mistake, you can change your entry and continue with the installation session.

Starting rs_init

Run **rs_init** and provide the information from the Replication Server installation worksheet.

Each section of the worksheet corresponds to a window or a menu in **rs_init**. You can also start **rs_init** with other command line options for your replication environment.

1. Log in to Windows using the Replication Server System Administrator account.
2. Start **rs_init**.
 - If you use Windows 7 and later, select **Start > All Programs > Sybase > rs_init** and right-click **rs_init** to select **Run as Administrator**.
 - If you use versions earlier than Windows 7, select **Start > Programs > Sybase > rs_init**. You see the RS_Init dialog box.

3. Choose Configure a Server Product, then Replication Server.

From the Configure Replication System menu you can:

- Configure a new Replication Server.
- Add a database to the replication System.
- Upgrade or downgrade Replication Server.
- Enable password encryption for a Replication Server or alter passwords in configuration files.

See also

- *Password Encryption* on page 91
- *rs_init Command Line Options* on page 45

Configure SAP Replication Server and Add Databases Using rs_init

- *Configuring a New Replication Server* on page 47
- *Adding a Database to the Replication System* on page 52

rs_init Interactive Command Buttons

rs_init has four command buttons that can help you make selections and move between dialog boxes.

Command Button	Action
Continue	Accept the values currently listed in the dialog box and move to the next dialog box.
Back	Exit the current dialog box or prompt and return to the previous dialog box.
Exit	Quit rs_init and return to the shell prompt.
Help	Display an online help window.

rs_init With a Resource File

Using **rs_init** with resource files to install, configure, upgrade, or downgrade may save time if you plan to install multiple Replication Servers and many of the **rs_init** values are similar.

A resource file is an ASCII-formatted file that contains configuration information for **rs_init**. Instead of entering configuration variables during an interactive **rs_init** session, use any text editor to edit the resource file to specify the variables, then specify the resource file name on the **rs_init** command line.

Using a Resource file for rs_init

Prepare and use a resource file for **rs_init**.

SAP supplies several resource file templates for Replication Server. Each template contains the attributes that are valid for a certain **rs_init** operation. Copy and edit a template file, which is supplied with the Replication Server software.

1. Select the resource file template you want to use.
2. Make a copy of the template and rename it to distinguish it from the original. For example:

```
copy install.rs install.rsx
```

Note: You must have read and write permissions on the copy of the resource file template that you want to edit. You may need to grant write permission to yourself as the file owner.

3. Use a text editor to edit the new resource file.

For example, enter:

```
edit install.rsx
```

4. When you have finished editing the resource file, start **rs_init** from the operating system prompt, using the **-r** flag to specify your resource file. For example:

```
%SYBASE%\%SYBASE_REP%\install\rs_init -r  
install.rsx
```

Warning! If you try to start a resource file session with an input file that is not an edited copy of one of the resource file templates, **rs_init** fails upon validation of the input file.

You can also start **rs_init** using a resource file with other command line options for your replication environment.

See also

- *rs_init Command Line Options* on page 45

Replication Server Resource File Templates

The resource file templates for Replication Server are located in subdirectories under the **init** subdirectory of the installation directory.

Template Name	Description
install.rs	Configures a new Replication Server.
setupdb.rs	Adds a database to the replication system.
upgr.rs	Upgrades an RSSD for a Replication Server. Use this template after installing new Replication Server software.
upgrdb.rs	Upgrades a user database that is already part of a replication system.
downgr.rs	Downgrades an RSSD for a Replication Server. Use this template before reinstalling the previous Replication Server software release.
eers.rs	Enables password encryption for a Replication Server.
updrscf.rs	Alters a password in a Replication Server configuration file.

Syntax and Parameters for a Resource File

Resource files list the attributes and their values to be defined during an **rs_init** session.

Syntax

Attribute entries are in this format:

```
product_name.attribute:value
```

Parameters

- **product_name** – Either sybinit or rs.
- **attribute** – An item for which you are supplying information, such as a server name or network protocol.
- **value** – The value you want to assign to the attribute.

Usage

- Resource file entries can be only one line long (80 characters).
- rs_init does not recognize end-of-line characters, carriage returns, or backslashes.
- rs_init ignores blank lines and lines that begin with a pound sign (#).
- If you do not enter a valid value for every required attribute, **rs_init** returns an error when you use the resource file.
- If an SAP-defined default value exists for an attribute, you can specify the default with the special value **USE_DEFAULT**.
- Certain resource file attributes can take lists of values. Attributes that can accept lists of values end with “_list.” Use commas to separate values. For example:

```
rs.rs_rs_network_protocol_list:tcp,ipx
```
- If you use a resource file to upgrade or modify a Replication Server, you can use the **UNCHANGED** value to indicate that a particular attribute should remain unchanged.
- You cannot use the **USE_DEFAULT** or the **UNCHANGED** value for required attributes with a null default value and you cannot enter **USE_DEFAULT** or **UNCHANGED** for the passwords that you specify with these attributes:

Password Attribute	User ID
rs.rs_idserver_pass	ID Server user
rs.rs_rs_sa_pass	Replication Server sa login
rs.rs_rssd_prim_pass	RSSD primary user
rs.rs_db_maint_password	Database maintenance user
rs.rs_rssd_maint_pass	RSSD maintenance user
rs.rs_ltm_rs_pass	Log transfer manager login ID
rs.rs_rs_pass	Replication Server login name

You must provide passwords for these attributes. If the attribute has no value or is not in the resource file, you see a message in the **stdout**. For example, if you do not provide a value for the rs_db_maint_password attribute in the setupdb.rs resource file, you see:

```
Attribute 'rs_db_maint_password' could not be set because '' is an invalid value
```

To ensure security, you must enter a password that complies with the password security requirements such as a minimum password length that administrator has enforced. See

Replication Server Administration Guide Volume 1 > Manage Replication Server Security > Managing Replication Server User Security > Manage Replication Server Login Names and Passwords > Password Configuration Options for All Users.

- If you are rebuilding an existing Replication Server, you must drop the RSSD or ERSSD before you start **rs_init**.

Sample Replication Server Resource File

See a sample resource file. Your resource file will have different values for many of the attributes, but will be similar to the sample.

```
#####
# RESOURCE TEMPLATE
#
# This file contains a list of configuration attributes
# for Replication Server. This is the template
# for configuring a new Replication Server. DO NOT EDIT
# THIS FILE.
# Copy the template to another file and edit that.
#
# Syntax of the resource file is:
#
#   product_name.attribute:value
#
# Attributes with a value of USE_DEFAULT will use the
# Sybase defaults for this platform.
#
# NOTES:
# Generic attributes are prefaced by "sybinit." The
# only generic attributes are "release_directory" and
# "product."
#
#####

#####
# RELEASE LOCATION
#
sybinit.release_directory: c:\sybase

# The product that you wish to configure. Possible
# values are:
# rs
#
sybinit.product: rs

#####

# REPLICATION SERVER ATTRIBUTES
## This operation installs a new Replication Server.
rs.rs_operation: rs_install

#####

# ID SERVER INFORMATION
#
```

Configure SAP Replication Server and Add Databases Using rs_init

```
# Name of the ID Server
rs.rs_idserver_name: IDRS
# Replication Server sa password. This is a required field.
rs.rs_rs_sa_pass:

# Is the ID Server the same as the Replication Server
# that is being installed ? Default is no
rs.rs_id_server_is_rs_server: yes

# Login that other Replication Servers will use to
# connect with the ID Server. Default is
# <rs_idserver_name>_id_user.
rs.rs_idserver_user: USE_DEFAULT

# Password for the ID Server user. This is a required field.
rs.rs_idserver_pass:
# The next two attributes should be set only when
# installing an ID Server and there are multiple ID
# Server domains

# First ID used for Replication Servers in this ID
# Server domain
rs.rs_start_rs_id: USE_DEFAULT

# First ID used for databases in this ID Server domain
rs.rs_start_db_id: USE_DEFAULT

#####

# REPLICATION SERVER INFORMATION
#
# Replication Server name
rs.rs_name: NYRS

# Name of the Replication Server run file. This file will
# start Replication Server with any configured arguments.
# Default is RUN_<rs name>.
rs.rs_rs_run_file: USE_DEFAULT

# Will the Replication Server manage databases with
# primary data, submit asynchronous transactions, or
# serve as an intermediate site in an indirect route ?
# Default is no
rs.rs_requires_ltm: no

# Will the Replication Server manage databases with primary data,
# submit asynchronous transactions, or serve as an intermediate
# site in an indirect route and the RSSD is an eRSSD? Default is no
rs.rs_erssid_requires_ltm: no

# Will the Replication Server(11.0 or higher) manage
# databases with primary data, submit asynchronous
# transactions, or serve as an intermediate site in an
```

```
# indirect route ? Default is yes
rs.rs_needs_repagent: yes

# Locations of the errorlog and config file for the
# Replication Server.

# The default names of these files are <rs_name>.log and
# <rs_name>.cfg respectively.
# The default directory in which these files are located
# is the current working directory on Unix platforms,
# and in %SYBASE%\install on PC platforms.
rs.rs_rs_errorlog: USE_DEFAULT
rs.rs_rs_cfg_file: USE_DEFAULT

# Character set to be used by this Replication Server
#(and the RSSD LTM if needed)
rs.rs_charset: USE_DEFAULT

# Language to be used by this Replication Server (and
# the RSSD LTM if needed)
rs.rs_language: USE_DEFAULT

# Sort order to be used by this Replication Server (and
# the RSSD LTM if needed)
rs.rs_sortorder: USE_DEFAULT

#####

# REPLICATION SERVER SYSTEM DATABASE CHOICE
#

# Is this an embedded rssd
rs.rs_rssd_embedded: no

#####

# EMBEDDED REPLICATION SERVER SYSTEM DATABASE
# INFORMATION

# The following only applies if embedded RSSD is chosen
#
# erssid name
rs.rs_erssid_name: rep_erssid

# embedded rssd database directory
rs.rs_erssid_database_dir: C:\sybase\data\database

# embedded rssd transaction log directory
rs.rs_erssid_translog_dir: C:\sybase\data\translog

# embedded rssd backup directory
rs.rs_erssid_backup_dir: C:\sybase\data\backup

# embedded rssd error log directory
rs.rs_erssid_errorlog_dir: C:\sybase\data\errorlog
```

Configure SAP Replication Server and Add Databases Using rs_init

```
#####  
# REPLICATION SERVER SYSTEM DATABASE INFORMATION  
  
# The following only applies if embedded RSSD is not  
# chosen Name of the Adaptive Server that will manage  
# the Replication Server's system database.  
rs.rs_rssd_sqlsrvr: NYDS  
  
# Name of the database where the Replication Server  
# system tables will be stored. Default is<rs_name>_RSSD  
rs.rs_rssd_db: USE_DEFAULT  
  
# Do you want the RSSD connections to allow HA failover?  
# Default is no  
rs.rs_rssd_ha_failover: no  
  
# Do you want rs_init to create the system database ?  
#Default is no  
rs.rs_create_rssd: no  
  
# sa login for the system Adaptive Server - default is sa  
rs.rs_rssd_sa_login: USE_DEFAULT  
  
# sa password for the system Adaptive Server. This is a required  
# field.  
rs.rs_rssd_sa_pass:  
  
# Name of the RSSD primary user. Default is  
# <rs_rssd_db>_prim  
rs.rs_rssd_prim_user: USE_DEFAULT  
  
# Password for the RSSD primary user. This is a required field.  
rs.rs_rssd_prim_pass:  
  
# Name of the RSSD maintenance user. Default is  
# <rs_rssd_db>_maint  
rs.rs_rssd_maint_user: USE_DEFAULT  
  
# Password for the RSSD maintenance user. This is a required field.  
rs.rs_rssd_maint_pass:  
  
# The dbo_user and dbo_password attributes are not used  
# by default. They should be used only if the RSSD  
# requires an LTM and the log should be scanned by  
# someone other than rs_rssd_sa_login. This user should  
# already exist in the database.  
  
# Name of the Database Owner for the RSSD  
rs.rs_rssd_dbo_user: USE_DEFAULT
```



```
# Password for the database owner
rs.rs_rssd_dbo_pass:

#####

# REPLICATION SERVER SYSTEM DATABASE DEVICE INFORMATION

# The following only applies if embedded RSSD is not
# chosen
# (USED ONLY IF RS_INIT IS TO CREATE THE RSSD)

# Size of the system database in MB. Default and minimum
# is 40
rs.rs_rsddb_size: 40

# Size of the log for the system database in MB. Default
# and minimum is 32
rs.rs_rssd_log_size:32

# Name of the device on which the system database is to
# be created Default is master
rs.rs_rssd_db_device_name: dbdev

# Do you want rs_init to create this device for the
# system database ? Default is no
rs.rs_create_rssd_database_dev: no

# Physical pathname of the device for the system
# database
rs.rs_rssd_db_device_path: c:\sybase\data\dev1.dat

# Size of the device for the system database
rs.rs_rsddb_device_size: 40

# Name of the device on which the log for the system
# database is to be created
rs.rs_rssd_log_device_name: logdev

# Do you want rs_init to create this device for the log
# for the system database ? Default is no
rs.rs_create_rssd_log_dev: no

# Physical pathname of the device for the log for the
# system database
rs.rs_rssd_log_device_path: c:\sybase\data\dev2.dat

# Size of the device for the log for the system database
rs.rs_rssd_log_device_size:32

#####

# DISK PARTITION INFORMATION
#
```

Configure SAP Replication Server and Add Databases Using rs_init

```
# Full path name of a raw disk partition for the
# Replication Server
rs.rs_diskp_name: c:\sybase\data\dev3.dat

# Logical identifier name for the raw disk partition for
# the Replication Server
rs.rs_diskp_lname: part1

# Size, in megabytes, of the raw disk partition.Default
# is 20.
rs.rs_diskp_size: 20

# The offset, in megabytes, at which the Replication
# Server should begin writing in the raw disk partition.
# Default is 0
rs.rs_diskp_vstart: 0

#####

# REMOTE SITE CONNECTION INFORMATION
#
# Replication Server login name that other Replication
# Servers will use to connect with this Replication
# Server

# Default is <rs_name>_rsi
rs.rs_rs_user: USE_DEFAULT

# Password for the Replication Server login name. This is a required
# field.
rs.rs_rs_pass:

#####

# SYSTEM DATABASE LOG TRANSFER MANAGER INFORMATION
# (IF RSSD NEEDS LTM)

# Name of the RSSD LTM. Default is
# <rs_rssd_sqlsrvr>_<rs_name>_RSSD_ltm.
rs.ltm_name: NY_LTM

# Replication Server login name that the log transfer
# manager will use when connecting to the Replication
# Server
# Default is <rs_name>_ltm
rs.rs_ltm_rs_user: USE_DEFAULT

# Password for the login name for the log transfer
# manager.
# This is a required field.
rs.rs_ltm_rs_pass:
```

Configure SAP Replication Server and Add Databases Using rs_init

```
# Login name for the user who will start and shutdown
# the log transfer manager for the Replication Server
# system database
# Default is sa
rs.rs_ltm_admin_user: USE_DEFAULT

# Password for the admin user
rs.rs_ltm_admin_pass:

#####

# ID SERVER INTERFACES INFORMATION

# These attributes are valid only for Unix platforms.
# On PC platforms, adding interface file entries through
# resource files is not supported.
# rs.do_add_id_server must be no on these platforms.
#
# Add ID Server to interfaces file? Default is no
rs.do_add_id_server: USE_DEFAULT

# Connect retry count; number of times client tries to
# connect to ID Server before giving up
rs.rs_id_server_connect_retry_count: USE_DEFAULT

# Connect retry delay time (in seconds); amount of time
# client waits between each connection attempt
rs.rs_id_server_connect_retry_delay_time: USE_DEFAULT

# Notes associated with ID Server interfaces file entry
rs.rs_id_server_notes: Default Sybase Configuration

# Protocol for ID Server network listener
rs.rs_id_server_network_protocol_list: tcp

# Name of host for ID Server
rs.rs_idserver_hostname: herbie

# Port numbers for network listener
rs.rs_idserver_port: 5002

#####

# REPLICATION SERVER INTERFACES INFORMATION
# These attributes are valid only for Unix platforms.
# On PC platforms, adding interface file entries through
# resource files is not supported.

# rs.do_add_replication_server must be no on these
# platforms.
#
# Add Replication Server to interfaces file?
rs.do_add_replication_server: no

# Connect retry count; number of times client tries to
# connect to Replication Server before giving up
```

Configure SAP Replication Server and Add Databases Using rs_init

```
rs.rs_rs_connect_retry_count: USE_DEFAULT

# Connect retry delay time (in seconds); amount of time
# client waits between each connection attempt
rs.rs_rs_connect_retry_delay_time: USE_DEFAULT

# Notes associated with Replication Server interfaces
# file entry
rs.rs_rs_notes: Default Sybase Configuration

# Protocol for Replication Server network listener
rs.rs_rs_network_protocol_list: tcp

# Name of host for Replication Server
rs.rs_rs_hostname: herbie

# Port numbers for network listener
rs.rs_rs_port: 5005

#####

# LOG TRANSFER MANAGER INTERFACES INFORMATION - IF RSSD
HAS LTM

# These attributes are valid only for Unix platforms.
# On PC platforms, adding interface file entries through
# resource files is not supported.
# rs.do_add_ltm must be no on these platforms.

# Add Log Transfer Manager to interfaces file?
rs.do_add_ltm: no

# Connect retry count; number of times client tries to
# connect to Log Transfer Manager before giving up
rs.rs_ltm_connect_retry_count: USE_DEFAULT

# Connect retry delay time (in seconds); amount of time
# client waits between each connection attempt
rs.rs_ltm_connect_retry_delay_time: USE_DEFAULT

# Notes associated with Log Transfer Manager interfaces
# file entry
rs.rs_ltm_notes: Default Sybase Configuration

# Protocol for Log Transfer Manager network listener
rs.rs_ltm_network_protocol_list: tcp

# Name of host for Log Transfer Manager
rs.rs_ltm_hostname: herbie

# Port numbers for network listener
rs.rs_ltm_port: 5000

#####

# REPLICATION SERVER SECURITY INFORMATION
```

```
# These attributes apply to the security features
# available for the replication server. This option is
# only available on Solaris and NT.
# Enable external network security
rs.rs_network_security_enable: no

# Type of network security for the Replication Server,
# choices are "dce" or "csfkrb5",
rs.rs_network_security_system: USE_DEFAULT

# Login name for the user who will principle user, this
# login name will be used for all secure connections,
# SAP recommends the name of the Replication Server
# as the principle user name.
rs.rs_principal_user_name: USE_DEFAULT

# Full path to the location of keytab file
rs.rs_keytab_file: USE_DEFAULT

# Use Secure Socket Layer(ssl) security
rs.rs_use_ssl: no

# Full path to the location of the ssl identity file
rs.rs_ssl_identity_file: USE_DEFAULT

# Password for the ssl private key
rs.rs_ssl_pkey_password:

# end of resource file
```

rs_init Command Line Options

Familiarize yourself with the available **rs_init** command line options for a resource file. You can use some of these options in an interactive **rs_init** session.

You can also start **rs_init** with other command line options for your replication environment:

```
rs_init -r resource_file_name [-option] [parameter]
```

where:

- *option* – is the letter specifying a command line option.
- *parameter* – is any valid parameter for that option.

You can specify more than one command line option. For a resource file session, you must specify the **-r** option and the resource file name.

Configure SAP Replication Server and Add Databases Using rs_init

Flags	Parameters	Explanation
-a	none	Validates the resource file and exits without performing the configuration task. Without the -a flag, rs_init validates the resource file and continues the product configuration. You must use the -r flag with the -a flag.
-c	See the list of supported character sets.	Specifies the character set used for all messages and prompts. The -c flag forces rs_init to use a particular character set. Otherwise, rs_init uses your system's default character set.
-e	none	Records information about the user's environment and exits. Information is written to the log file. Without the -e flag, rs_init records user environment information and continues the product configuration.
-h	none	Prints out usage message (help) and exits.
-I	none	<p>Allows you to specify the interfaces file that rs_init should use instead of using the default file located in \$SYBASE directory.</p> <p>For example, rs_init -I /tmp/interfaces</p> <p>If you do not specify the interfaces file, the default file located in \$SYBASE directory is used.</p>
-l	French, German, Japanese, Spanish, Chinese, Korean	Specifies the language used for all messages and prompts. The -l flag forces rs_init to use a particular language. Without this option, rs_init uses U.S. English.
-log	Path and file name of log file	Lets the user specify location of the session log file. Without the -log flag, rs_init uses the default log location (%SYBASE%\init\log).

Flags	Parameters	Explanation
-r	Path and file name of resource file	Specifies that rs_init is to take input from the listed resource file. Use this flag in noninteractive sessions to configure new server products, upgrade existing server products, or modify existing server products.
-s	Path of the release directory	Specifies the release directory. If you do not use the -s flag, rs_init assumes that the release directory is the current directory.
-T IGNORE_WARNINGS	none	Entering certain values for some attributes causes rs_init to exit with a warning. (rs_init exits, for instance, if you specify an operating system file for the location of the master device.) Invoking an rs_init resource file session with the -T IGNORE_WARNINGS flag allows the rs_init session to continue.
-T SKIP_WINDOWS_SERVICE	none	Skips the creation of Windows services, and skips the updates to the Windows registry.
-v	none	Prints the rs_init version string and exits.

See also

- *Supported Character Sets* on page 15

Configuring a New Replication Server

Configure a new Replication Server in your replication environment using **rs_init**.

Prerequisites

Complete the Replication Server installation worksheet.

Task

1. In the RS_Init dialog box, select **Configure a Server Product**, then choose **Continue**. You see the Configure Server Products dialog box.
2. Select **Replication Server**.
3. Select **Install a New Replication Server**. You see a list of tasks you must complete to install a new Replication Server.

Note: The Install a New Replication Server option only lets you configure a new Replication Server; it does not allow you to install additional software.

Select each task and complete the windows until the status of each task is “Complete.”

Entering Replication Server Information

Enter the configuration information for the Replication Server using **rs_init**.

1. In the New Replication Server window, select Replication Server Information.
You see the Replication Server Name window.
2. Enter the name you recorded in the “Replication Server Information” section of the worksheet, then click **Continue**. You see the Replication Server Information window.
3. Select each item on the Replication Server Information window and enter the value you recorded on your worksheet. If you use a default value, record it on your worksheet.

Note: For more information on the character sets and sort orders, see *Adaptive Server Enterprise Configuration Guide > Customizing Localization for Adaptive Server*.

To change a default value, select it and click **Continue**.

In some configurations, if you set Replication Server language before you set its character set, you receive an error message. To avoid this, set the character set before you set the language.

If the Replication Server Interfaces Information item is “Incomplete,” select it and click **Continue**. You see an interfaces file editor dialog box. Follow the instructions provided in Editing the interfaces file, to add a listener service for Replication Server.

4. Click **Continue** to save the information and return to the New Replication Server window.

Editing the Interfaces File

Modify the interfaces file. The interfaces file contains network address information for each Adaptive Server and Replication Server in your replication system.

1. To reach the `interfaces` file window, select Replication Server Interfaces Information from the Replication Server Information window
2. Select **Start > Programs > Sybase > Connectivity > Open Client Directory Service Editor**. Using **dsedit**, edit the `interfaces` file.

Note: SAP recommends that if you are using Replication Server with network-based security, you use the directory services of your network security mechanism to register Replication Servers, Adaptive Servers, and gateway software. See the documentation that comes with your network security mechanism for details.

See the *Open Client and Open Server Configuration Guide* for more information on **dsedit**.

Entering ID Server Information

Complete the ID Server Information dialog box.

Prerequisites

- Ensure that you have the login name and password (ID Server User/Password) that all Replication Servers use to log in to the ID Server when you configure the ID Server.
- When you install a Replication Server that is not the ID Server, copy the ID Server Name, ID Server User, and ID Server Password from the “ID server “ section of the worksheet.

Task

1. From the New Replication Server window, select ID Server Information.
 - If the Replication Server you are installing is not the ID Server, you see the ID Server Name window. Enter the name of the ID Server for the replication system, then click **Continue**. You see the ID Server Information window.
 - If the Replication Server you are configuring is the ID Server, the ID Server Information window appears.

The Starting Replication Server ID and Starting Database ID appear only when you configure the ID Server.

2. Complete the ID Server Information window with the information from the “ID Server” section of your worksheet.

If you do not make entries for the Starting Replication Server ID and starting database ID, the default ranges are used, as shown in "Default ID Number Ranges and ID Number Allocation for ID Server Domains" section.

3. Click **Continue** to save your changes and return to the New Replication Server windows.

See also

- *ID Server* on page 7
- *Default ID Number Ranges and ID Number Allocation for ID Server Domains* on page 21

Selecting the RSSD Type

Determine the RSSD type that you want for your replication system.

Before you can enter your Replication Server System Database (RSSD) information, you must determine if you want an RSSD or an embedded Replication Server System Database (ERSSD).

In the Replication Server System Database Choice window, select:

Configure SAP Replication Server and Add Databases Using rs_init

- **Yes** – if you want an ERSSD using SQL Anywhere. The text on the second line changes to:
2. Embedded Replication Server System
Database INCOMPLETE
Select the **Embedded Replication Server System Database** option, to go to the ERSSD Name window, and then follow the steps to enter information for your ERSSD.
- **No** – if you do not want an ERSSD. This is the default value, and assumes you are creating a regular Replication Server System Database with Adaptive Server Enterprise. The second line on the window appears as:
2. Replication Server Database on ASE INCOMPLETE
Select the Replication Server System Database on ASE option, to go to the Replication Server System Database window, and then follow the steps to enter information for your RSSD.

See also

- *Entering Embedded Replication Server System Database Information* on page 50
- *Entering Replication Server System Database Information* on page 51

Entering Embedded Replication Server System Database Information

Complete the ERSSD information dialog box.

1. If you selected an ERSSD in “Selecting RSSD type”, enter the name of your SQL Anywhere server in the ERSSD Name window, and click **Continue** to accept the name. The Embedded Replication Server System Database window appears.

Note: If you are configuring a Replication Server that previously existed, you must delete the previous ERSSD database (*.db), the previous transaction log file (*.log), and the previous transaction log mirror file (*.mlg) before you start **rs_init**.

2. You see the following options, each filled with a default value:

- ERSSD Database Directory
- ERSSD Transaction Log Directory
- ERSSD Backup Directory
- ERSSD Error Log Directory
- ERSSD Interface Information

Select each item to change the default value to the value you recorded in the Replication Server installation worksheet. See *Manage a Replication System* in the *Administration Guide Volume 1* for more information on value requirements for ERSSDs.

3. Choose **Continue** to accept the values and return to the Replication Server System Database Choice window. You see the New Replication Server window.
4. Choose **Continue** to return to the New Replication Server window.

Entering Replication Server System Database Information

Complete the Replication Server System Database Information dialog box.

1. In the New Replication Server window, select **Replication Server System Database**, then click **Continue**.

Note: If you are configuring a Replication Server that previously existed, you must delete the previous RSSD before you start **rs_init**.

2. Complete the window with the information from your worksheet. If you use a default value, copy it from the window to your worksheet.

For “RSSD will be replicated,” select Yes if you will have more than one Replication Server in your environment.

3. Choose **Continue** to accept the values. You see the New Replication Server window.

Entering RSSD Device Information

Complete the RSSD device information dialog box.

If you selected Yes for the Create RSSD option in the Replication Server System Database window, the “RSSD Device Information” option appears in the New Replication Server window.

Warning! If you selected No for Create RSSD in the Replication Server System Database window, you must already have created the RSSD. Skip this section and go to “Entering disk partition information”.

1. From the New Replication Server window, select RSSD Device Information, then choose **Continue**.
2. Complete the window using information from your worksheet. If you use a default value, copy it from the window to your worksheet.
3. Click **Continue** to save your entries and return to the New Replication Server window.

Entering RSSD RepAgent Information

Complete the RSSD RepAgent information dialog box.

If you selected Yes for the “RSSD will be replicated” option in the Replication Server System database window, the “Database Replication Agent” option appears in the New Replication Server window.

1. Select Database Replication Agent. Enter the RSSD Replication Server user name, and the Replication Server password from your worksheet.

Note: Where necessary, **rs_init** uses the settings established for the Replication Server when configuring an RSSD RepAgent.

2. Click **Continue** to save this information.

Entering Disk Partition Information

Complete the disk partition information dialog box.

In Windows, disk partitions use operating system files for stable queues. If such a file does not already exist, **rs_init** creates it. In Windows, you must not use a raw device to create a partition.

1. From the New Replication Server window, select Disk Partition.
Click **Continue**.
2. Complete the window using the information you recorded on your worksheet.
You can add more partitions after Replication Server is installed. See the *Design Guide* for help in determining how much space you need.
3. Click **Continue** to accept the values and return to the New Replication Server window.

Entering Remote Site Connections Information

Modify the default values in the Remote Site Connections window, which **rs_init** provided based on the Replication Server name you entered.

1. From the New Replication Server window, select **Remote Site Connections**.
Click **Continue**.
2. Complete the window using the information on your worksheet. If you use a default value, copy it to the “Remote site connections” section of the worksheet.
3. Click **Continue** to save your changes and return to the New Replication Server window.

Adding a Database to the Replication System

Add a database to the replication system. Each primary or replicate database in a replication system is managed by a Replication Server.

Prerequisites

Complete the Database Setup Worksheet.

Task

1. From the RS_INIT menu, select **Configure a Server Product**.
Click **Continue**.
2. Select **Replication Server**. You see the Configure Replication System window.
3. Select **Add a Database to the Replication System**, then click **Continue**.

You see the status of each part of the installation with “Incomplete” or “Complete.”

4. Select Replication Server Information.

Click **Continue**.

5. Enter the name of the Replication Server from your worksheet. Click **Continue to save your changes.**

6. Complete the window, using the information you recorded on your worksheet, then click **Continue.**

If the status of Replication Server Interfaces Information is “Incomplete,” select it, then click **Continue**. You see an interfaces file editor window. Edit the interfaces file to add an entry for the Replication Server.

7. Click **Continue to save your changes and return to the Add Database to Replication System window.**

See also

- *Database Setup Worksheet Sample* on page 27
- *Editing the Interfaces File* on page 48

Completing Database Information

Finalize the database information.

1. In the Add Database to Replication System window, select Database Information, then click **Continue**.
2. Complete the window using the information you recorded on the worksheet. If you use a default value, copy it from the window to your worksheet. The label refers to Adaptive Server as “SQL Server.”

Note: The password you specify in this step must be valid to log in to Adaptive Server as “sa”. You cannot change the password in **rs_init** by specifying a different password in this window. To change the Adaptive Server “sa” password, log in to the Adaptive Server after installation and change the password using the alter user command.

3. Choose Yes for “Will the Database Be Replicated?” if:
 - It contains primary data.
 - It is part of a warm standby application.
 - Applications execute replicated stored procedures in it.
4. If you are adding the active or standby database for a warm standby application:
 - a) Choose Yes for “Is This a Physical Connection for Existing Logical Connection?”
 - b) Specify the additional information in the Logical DB Setup window.
5. Click **Continue** to save your changes, then go to “Completing the Configuration”.

Completing Logical Connection Information

Finalize the information you entered in the Logical Connection information window.

Prerequisites

- Set up a warm standby application between Adaptive Server databases. See *Manage Warm Standby Applications* in the *Administration Guide Volume 2*.
- Set up a warm standby application between Oracle databases. See *Heterogeneous Warm Standby for Oracle* in the *Heterogeneous Replication Guide*.

Note: Before you add a database for a warm standby application, you must create the logical connection in the Replication Server.

Task

1. If you selected Yes to “Is This a Physical Connection for Existing Logical Connection?” in the Database Information window, Logical Database Setup selections appear. You must specify logical connection parameters.

In the Database Information window, select Logical DB Setup, then choose **Continue**.

The Logical Connection Information window appears. When you choose “active” for the first item, only these options appear:

- Logical DS Name
 - Logical DB Name
2. Complete the Logical Connection Information window, using the information you recorded on your worksheet. If you use a default value, copy it from the window to your worksheet.
 3. Click **Continue** to save your changes, and **rs_init** returns you to the Database Information window.

Completing the Configuration

Complete the replication system configuration.

1. If the Database Information window indicates that there are incomplete tasks on the Add Database to Replication System window, select each one and complete the required information.

When all tasks are “Complete,” click **Continue**. A message is displayed asking you if you want to execute the configuration.

2. Messages appear on the window as the configuration progresses; these messages require no action.

Do not interrupt the configuration. Most configurations require several minutes (sometimes longer) to complete.

Configure SAP Replication Server and Add Databases Using rs_init

When the configuration is complete, **rs_init** displays “Configuration completed successfully.”

3. Click **OK** to return to the Configure Replication System window.

Note: To add other databases to the replication system, go to “Adding a database to the replication system” section, and repeat the procedure for each database.

4. Click **Exit** to quit **rs_init**.

You can find out more about the progress of the installation by looking at the current **rs_init** log file. **rs_init** log files are stored in the `init\logs` subdirectory of the `%SYBASE_REP%` directory.

Upgrade or Downgrade SAP Replication Server

Upgrade or downgrade SAP Replication Server, or migrate to 64-bit platforms.

Warning! Do not modify the secondary truncation point of Replication Agent, truncate the transaction log, or increase the generation number while upgrading.

See also

- *Required Replication Servers* on page 6

Requirements for Upgrading

There are several requirements for the site, route, and system versions, mixed-version environments, and different platforms, when you upgrade Replication Server.

Site, Route, and System Version

If a replication system domain has Replication Server 15.7.1 SP200 and later, then the system version and route versions in the replication system domain must be version 12.6 and later.

If the Replication Server version, the site version, and the route version are earlier than 12.6, you must upgrade Replication Server to version 12.6 or later, set site version to 12.6 or later, and upgrade routes to 12.6 or later, before you can install Replication Server 15.7.1 SP200.

Mixed-Version Environments

For Replication Server 15.7.1 SP200 and later, mixed-version environments containing versions earlier than 12.6 are not supported. You can upgrade directly to Replication Server 15.7.1 SP200 from versions 12.6 and later, including any ESDs for versions 12.6 and later.

Note: To create a database subscription from a primary Replication Server with version 15.7.1 SP200, the replicate Replication Server must be version 15.7.1 SP200 or later.

SQL Anywhere Version for ERSSD

ERSSD requires SQL Anywhere. SAP Replication Server 15.7.1 SP200 includes SQL Anywhere version 16.0 on 32-bit and 64-bit Windows platforms.

Version 15.7.1 SP200 also includes SQL Anywhere version 12 for upgrading an ERSSD database format if you have installed an earlier version of SQL Anywhere.

See also

- *Commit a Local Site to a New Version Level* on page 71
- *Replication Server Site Version* on page 72

- *Replication Server Route Version* on page 73

Preparing to Upgrade

Prepare the Replication Server for upgrade.

1. Back up the RSSD or ERSSD. The upgrade process makes changes to the RSSD or ERSSD that you cannot roll back if the upgrade fails. Restore the RSSD or ERSSD from the backup if the upgrade fails.
2. Determine where you want to install Replication Server.
If you plan to install the Replication Server software in a directory that:
 - Does not contain your existing Replication Server installation – verify that the `sql.ini` file is accessible and see *Upgrading Replication Server* on page 59
 - Contains your existing Replication Server installation – see *Upgrades and Downgrades Using Existing Directories* on page 87
3. Read the release bulletin for any special installation instructions about mixed-version environments, installing, or upgrading.
4. Use **rs_helpsub** and **rs_helpdbsub** to check that all subscriptions are valid. The upgrade fails if there are subscriptions that are not in a valid state before upgrading.
5. Install Replication Server, following the instructions in the *Installation Guide*.
6. Verify the system-wide and route versions and upgrade to version 12.6 if necessary:
 - a) Execute **sysadmin system_version** on the current Replication Server. If the system version is 1260 or later, you can upgrade your Replication Server now. If the system version is earlier than 12.6, proceed to step 6b.

```
sysadmin system_version  
go
```

An example of the output is:

```
The current system version is 1102.
```

- b) Set the system version on the ID Server to 1260:

```
sysadmin system_version,1260  
go
```

If setting the system version is unsuccessful, this message appears and you must proceed to step 6c:

```
The system version could not be set. The specified  
version '1260' is higher than the lowest Replication  
Server version in the system '1250'
```

If setting the system version is successful, this message appears and you can proceed to step 6d:

The system version has been reset from 1102 to 1260

- c) Upgrade Replication Server to 12.6 and set the site version to 12.6 for any Replication Server in the domain that has a version earlier than 12.6. Repeat step 6b.
- d) Execute **sysadmin system_version** again on the current Replication Server. If the system version is 12.6 or later, proceed to step 6e.
- e) Execute **admin show_route_versions** to verify all route versions are 1260 or later. If the route version is lower than 12.6, see *Upgrade Routes* in the *Administration Guide Volume 1* for information in upgrading the route version. After you upgrade the routes, you can upgrade the current Replication Server.

Upgrading Replication Server

Upgrade Replication Server from version 12.6 and later.

1. *Stopping Replication Agent and Quiescing Replication Server*

Stop Replication Agent and quiesce Replication Server to purge all inbound queues.

2. *Deciding the Upgrade Method to Use*

Decide whether you want to upgrade Replication Server and associated databases using the simplified upgrade method with repserver or continue to upgrade with rs_init.

3. *Upgrades to RSSD or ERSSD and User Databases*

After you upgrade the Replication Server RSSD or ERSSD, you must apply upgrades to a primary, replicate, or standby database in the replication system to accommodate changes, such as installing new stored procedures, that support the new version of Replication Server to which you are upgrading, and features such as Multi-Path Replication™.

4. *Upgrading RSSD or ERSSD and User Databases with repserver*

Use the repserver utility to upgrade the Replication Server RSSD or ERSSD, and user databases in one step.

5. *Upgrading RSSD or ERSSD with rs_init*

(Optional) Use rs_init to upgrade the RSSDs or ERSSDs to be compatible with the executable programs in the Replication Server version to which you are upgrading.

6. *Fixing a Failed Replication Server Upgrade*

Retry the upgrade process at this point if it fails.

7. *Fixing User Database Upgrades with sysadmin upgrade, "database"*

Apply upgrades to SAP ASE, Oracle, or SAP® IQ, primary, replicate, or standby databases in the replication system that failed to upgrade during the automatic upgrade process, or to databases that you excluded from the automatic upgrade process.

8. *Upgrading an SAP ASE User Database with rs_init*

If you use rs_init to upgrade SAP Replication Server and the RSSD or ERSSD, you must apply upgrades to a primary, replicate, or standby database in the replication system to accommodate changes, such as installing new stored procedures, that support the new

version of SAP Replication Server to which you are upgrading, and features such as Multi-Path Replication.

9. *Upgrading Non-SAP ASE User Databases and User Databases Not Supported by sysadmin upgrade*

Use the corresponding upgrade scripts for databases such as IBM DB2 UDB, and Microsoft SQL Server that are not supported by the sysadmin upgrade, database command and rs_init.

10. *Commit a Local Site to a New Version Level*

After you upgrade a Replication Server and its user databases, you must decide whether to commit to the new Replication Server version level. Decide whether to set the replication site version to the new version and whether to upgrade the route version to the new version.

11. *Backing Up the RSSD or ERSSD*

Back up the RSSD or ERSSD after upgrading the Replication Server, setting its site version, and performing route upgrades to the relevant routes.

Stopping Replication Agent and Quiescing Replication Server

Stop Replication Agent and quiesce Replication Server to purge all inbound queues.

Replication Server 15.7.1 SP100 is available on 64-bit and 32-bit platforms for Windows. Therefore, upgrading to version 15.7.1 SP100 may include upgrading from a 32-bit platform which requires a purge of inbound queues. See the *Release Bulletin* for supported 64-bit platforms.

1. On Replication Server, stop Replication Agent for all primary databases and system databases:

```
suspend log transfer from all
```

2. If you are using Adaptive Server as the RSSD, stop RepAgent for the RSSD:

```
sp_stop_rep_agent RSSD_name
```

3. If there are incoming routes to the Replication Server you are upgrading, log in to the source Replication Server and suspend all routes to the Replication Server, *dest_rs*, you are upgrading:

```
suspend route to dest_rs
```

4. Verify that the Replication Server queues have been drained out and the Replication Server you are upgrading has been quiesced by executing this command on the Replication Server:

```
admin quiesce_check
```

If Replication Server is not yet quiesced, retry with **admin quiesce_force_rsi**.

Warning! You may lose data if you proceed with the upgrade process and Replication Server is not quiesced.

Deciding the Upgrade Method to Use

Decide whether you want to upgrade Replication Server and associated databases using the simplified upgrade method with **repserver** or continue to upgrade with **rs_init**.

1. Use the **repserver** utility to upgrade the Replication Server RSSD or ERSSD, and user databases in one step.
 Optionally, continue to use **rs_init** to upgrade the Replication Server RSSD or ERSSD, and user databases in several steps.
2. Upgrade user databases in the replication system only if they failed to upgrade during seamless upgrade or if you excluded them from the upgrade process.
 To upgrade the user databases, use one of:
 - *Fixing User Database Upgrades with sysadmin upgrade, "database"* on page 68
 - *Upgrading an SAP ASE User Database with rs_init* on page 68
 You can use **sysadmin upgrade, "database"** or **rs_init** to upgrade the user databases.

Upgrades to RSSD or ERSSD and User Databases

After you upgrade the Replication Server RSSD or ERSSD, you must apply upgrades to a primary, replicate, or standby database in the replication system to accommodate changes, such as installing new stored procedures, that support the new version of Replication Server to which you are upgrading, and features such as Multi-Path Replication™.

Upgrading an RSSD or ERSSD may add new Replication Server system tables, add new rows or columns to existing tables, or install new stored procedures. To accommodate changes that support the new version of Replication Server to which you are upgrading, **repserver** or **rs_init** applies upgrades to user databases such as a primary, replicate, or standby database in the replication system.

If you do not apply the upgrades to replicate databases such as:

- SAP ASE – you cannot use Multi-Path Replication for replication to SAP ASE databases after you upgrade Replication Server to 15.7 and later.
- SAP® IQ – Replication Server suspends replicate connections to the SAP IQ replicate databases after you upgrade Replication Server to 15.7.1 or later, and you see a "Awaiting Upgr" status if you use **admin who**. You can upgrade the SAP IQ database using one of:
 - **repserver -upgr** – upgrades Replication Server at the same time
 - **sysadmin upgrade,'database'** – after upgrading Replication Server with **rs_init** or **repserver** with the **-nodb** option
- Oracle – Replication Server suspends replicate connections to the Oracle replicate databases after you upgrade Replication Server to 15.7.1 SP101 or later, and you see a "Awaiting Upgr" status if you use **admin who**. You can upgrade the Oracle database using one of:
 - **repserver -upgr** – upgrades Replication Server at the same time

- **sysadmin upgrade,'database'** – after upgrading Replication Server with **rs_init** or **repserver** with the **-nodb** option

See also

- *Upgrading Oracle User Databases Manually* on page 70

Upgrading RSSD or ERSSD and User Databases with repserver

Use the **repserver** utility to upgrade the Replication Server RSSD or ERSSD, and user databases in one step.

1. If the Replication Server uses Adaptive Server for the RSSD, grant **sa_role** to the primary user at the RSSD:

```
sp_role 'grant', sa_role, primary_user
```

You can revoke the “sa” role after the upgrade process is finished, by executing:

```
sp_role 'revoke', sa_role, primary_user
```

Note: The *RSSD_primary_user* in the *.cfg* file must have a replication role or “sa” role. The *RSSD_primary_user* may not necessarily be the sa user ID or the user that has been entered in the **rs_init** pane.

2. Grant **sa_role** to the maintenance user for each user database.
3. Shut down the preupgrade version of Replication Server.
 - a) Use **isql** to log in to the Replication Server as the system administrator:

```
isql -Usa -Psa_password - Srs_name  
go
```

- b) Enter:

```
shutdown  
go
```

4. Start the new version of Replication Server in upgrade mode. Enter:

```
repsrvr -upgr -S rs_name -A erssd_release_dir  
-C config_file -I interfaces_file -E errorlog_file
```

In upgrade mode, Replication Server upgrades the ERSSD or RSSD it is using, automatically connects to each user database to which it has maintenance user access, and where a connection exists, applies the upgrade scripts to the database.

The full syntax is:

```
repsrvr [-C config_file] [-i id_server]  
[-S rs_name] [-I interfaces_file]  
[-E errorlog_file] [-M] [-v] [-K keytab_file]  
[-upgr] [-A erssd_release_dir] [-purgeq]  
[-nodb {all|dbid_1[,dbid_2[,dbid_3[,...]]]}]  
[-e]
```

where:

- **-upgr** – instructs Replication Server to start the upgrade
- **-A *erssd_release_directory*** – specifies the location of the release directory of the ERSSD you are going to upgrade if Replication Server is using an ERSSD, for example:
`c:\sybase\REP-15_5\ASA11`
 If you do not include the **-A** option, Replication Server obtains the release directory location from the configuration file if the configuration file contains the information. Replication Server ignores the release directory location in the configuration file if you specify the **-A** option because what you specify manually in the **repsrvr** command overrides configuration file settings.
- **-purgeq** – purges transactions from the inbound queue. You must use this option if you are upgrading from a version of Replication Server earlier than 15.5.
- **-nodb all** – excludes all user databases from the upgrade process
- **-nodb *dbid_1[,dbid_2[,dbid_3,...]]*** – excludes specific databases from the upgrade process. Separate multiple database IDs with a comma and do not include a space between the IDs. For example:

```
repsrvr -upgr . . . -A . . . -nodb 101,102,105
```
- **-e** – records the SQL statements that Replication Server sends to data servers when you enter the **-upgr** parameter for upgrading. Without the **-e** option, there is no record of the SQL statements generated. With or without the **-e** option, the upgrade process uses the Replication Server error log file to record any errors that occur during the upgrade process, and why any user database was not upgraded.

You can use only the **-A**, **-purgeq**, **-nodb**, and **-e** options when you use **-upgr**. See **repsrvr** in the *Reference Manual* for descriptions of the other **repsrvr** parameters.

For example, if you are upgrading the NY_RS Replication Server from version 15.5 to 15.7.1 SP200, and before the upgrade, NY_RS is using the `c:\sybase\REP-15_5\ASA11` ERSSD release directory location, the `ny_rs.cfg` configuration file, the `sql.ini` file, and the `ny_rs_errorlog` error log file, enter:

```
repsrvr -upgr -SNY_RS -Ac:\sybase\REP-15_5\ASA11 -Cny_rs.cfg -
Isql.ini -E ny_rs_errorlog
```

If the upgrade is successful, the upgrade mode shuts down Replication Server and you do not see any warning or error messages.

5. Restart Replication Server using the appropriate executables for the new version.

Warning! Some Replication Server configuration options with newer versions may have a wider valid range. If you increase any of these configuration options after upgrading, you must reinstate the old values before downgrading. Otherwise, the Replication Server may not start or may behave incorrectly.

6. If you installed the new Replication Server software in a different directory than the earlier version, modify the `runserver` files for the Replication Server to replace the old binary with new binary in the new version directory.

Upgrade or Downgrade SAP Replication Server

7. If you are using Adaptive Server as the RSSD, and it has a RepAgent, restart the RepAgent for the RSSD:

```
sp_start_rep_agent RSSD_name
```

8. Resume log transfer to Replication Server from all Replication Agents for primary databases, and RSSD or ERSSD:

```
resume log transfer from all
```

9. If there are incoming routes to *dest_rs*, the Replication Server you upgraded and now restarted, log in to the source Replication Server and resume all routes to *dest_rs* to allow the source Replication Server to begin sending queued messages to *dest_rs*. At the source Replication Server, execute:

```
resume route to dest_rs
```

10. Check the upgraded Replication Server:

- a) Verify that the RSSD or ERSSD version of the upgraded Replication Server is correct. You can check one of:

- Replication Server error log – you see:

```
Upgraded RSSD successfully. The current RSSD version is '1571200'.
```

- `rs_config` table – log in to **isql** and enter:

```
select * from rs_config where  
optionname='current_rssd_version'
```

- b) Check that the Replication Server modules are running by executing **admin who** with the relevant options.

11. If you have more Replication Servers to upgrade, repeat steps 1 to 12.

Upgrading RSSD or ERSSD with `rs_init`

(Optional) Use **rs_init** to upgrade the RSSDs or ERSSDs to be compatible with the executable programs in the Replication Server version to which you are upgrading.

Upgrading an RSSD or ERSSD may add new Replication Server system tables, add new rows or columns to existing tables, or install new stored procedures. Upgrade an RSSD based on the information from the Replication Server installation worksheet for the Replication Server you are upgrading. You must separately use **rs_init** to upgrade any primary, replicate, or standby user databases in the replication system to accommodate changes, such as installing new stored procedures, that support the new version of Replication Server to which you are upgrading.

SAP Replication Server Version to Upgrade From	Supported SAP SQL Anywhere and dbsrv Binary Version
12.6 and pre12.6	8
15.0 – 15.1	9

SAP Replication Server Version to Upgrade From	Supported SAP SQL Anywhere and dbsrv Binary Version
15.2 – 15.6	11
15.7 – 15.7.1 SP120	12
15.7.1 SP200	16

1. Verify that the RSSD and Replication Servers that you are upgrading are running.
2. If the Replication Server uses Adaptive Server for the RSSD, grant `sa_role` to the primary user at the RSSD:

```
sp_role 'grant', sa_role, primary_user
```

You can revoke the `sa_role` after the upgrade process is finished, by executing:

```
sp_role 'revoke', sa_role, primary_user
```

Note: The `RSSD_primary_user` in the `.cfg` file must have a replication or `sa` role. The `RSSD_primary_user` may not necessarily be the `sa` user ID or the user who has been entered in the `rs_init` pane.

3. If the Replication Server uses an ERSSD, edit the `rs_name.cfg` file, where `rs_name` is your Replication Server:

- a) Add the **`erssd_release_dir`** parameter to specify the location of the SQL Anywhere ERSSD database you are going to upgrade. For example:

```
erssd_release_dir=c:\sybase\REP-15_5\ASAx
```

where `xx` is the version of SQL Anywhere being upgraded.

- b) Add the **`erssd_start_cmd`** parameter to specify the command to start the previous version of ERSSD.

You can find an example of the parameter in the Replication Server error log file by searching for “ERSSD start command”. You see an entry similar to:

```
ERSSD start command:=c:\sybase\REP-15_5\ASAx
\bin\dbspawn
-f -q c:\sybase\REP-15_5\ASAx
\bin\dbsrvxx
-s none -ti 0 -x "tcip(PORT=15501;DOBROAD=NO;BLISTENER=NO)"
-o c:\sybase\REP-15_5\errorlog\rs157_prs_ERSSD.out
c:\sybase\REP-15_5\dbfile\rs157_prs_ERSSD.db
```

where `xx` is the version of SQL Anywhere and `dbsrv` being upgraded.

- c) From the `sql.ini` file, obtain the name and location of the Replication Server you are upgrading, and the port number of the Replication Server RSSD.
4. If the Replication Server uses an ERSSD, and is performing routing, edit the `rs_name.cfg` file, where `rs_name` is your Replication Server:
 - a) Add the **`erssd_ra_release_dir`** parameter to specify the location of the SQL Anywhere ERSSD database you are going to upgrade. For example:

```
erssd_ra_release_dir=c:\sybase\REP-15_5\ASAx
```

where *xx* is the version of SQL Anywhere being upgraded.

- b) Add the **erssd_ra_start_cmd** parameter to specify the command to start the previous version of ERSSD.

Obtain the name of the ERSSD Replication Agent and the location of the `sql.ini` file from the Replication Server log file by searching for “Starting embedded RSSD Replication Agent” and using the same command format from the next line: “Executing command.” For example:

```
erssd_ra_start_cmd=c:\sybase\REP-15_5\ASAx\bin\dbltm
-ud -S SAMP_RS_ERSSD_ra
-C c:\sybase\REP-15_5\samp_repserver\SAMP_RS_ERSSD_ra.cfg
-ot c:\sybase\REP-15_5\samp_repserver\SAMP_RS_ERSSD_ra.out
-I c:\sybase\sql.ini
```

where *xx* is the version of SQL Anywhere and `dbsrv` being upgraded.

5. If you are upgrading from Replication Server version 12.6 to version 15.7.1 SP200 and if the Replication Server uses an ERSSD, include the `win32` subdirectory of the `ASA` directory in the `PATH` environment variable:

```
set PATH=%PATH%;C:\work\RS126\REP-12_6\ASA8\win32
```

6. Select **Start > Programs > Sybase > rs_init**.
7. Select **Configure a Server Product**, then **Continue**.
8. Select **Replication Server**.

Then choose **Continue**.

9. Select **Upgrade an Existing Replication Server**.

Then choose **Continue**.

10. Complete the Upgrade Existing Replication Server window with the information from the Replication Server installation worksheet for the Replication Server you are upgrading.
 - a) Enter the name of the Replication Server with the RSSD you are upgrading.
 - b) Enter the login name for the Replication Server `sa` user. The default value is “`sa`”
 - c) Enter the password for the `sa` user on the Replication Server.
 - d) Enter the path name of the Replication Server configuration file.
 - e) Choose **Continue** to save your changes. You see:
Execute the Replication Server tasks now?

11. Choose **Continue**. If the Replication Server is running, **rs_init** shuts it down.

rs_init displays informational messages as it loads the upgrade script into the RSSD. When the upgrade is complete, you see:

```
RSSD successfully upgraded from old_rel_no to new_rel_no.
Replication Server 'rs_name' can now be restarted. Task to
upgrade the RSSD succeeded. Configuration completed
successfully.
```

where:

- *old_rel_no* – is the Replication Server version from which you are upgrading.
 - *new_rel_no* – is the new Replication Server version.
 - *rs_name* – is the name of the Replication Server.
12. If you installed the new Replication Server software in a different directory than the earlier version, modify the runserver files for the Replication Servers so they use the programs in the new version directory.
 13. Restart Replication Server using the appropriate executables for the new version.

Warning! Some Replication Server configuration options with newer versions may have a wider range of valid value. If you increase any of these configuration options after upgrading, you must reinstate the old values before downgrading. Otherwise, the Replication Server may not start or may behave incorrectly. The Replication Server upgrade process prints all the current configuration option values in **rs_config** to **rs_init** log, so that you can restore the former settings before downgrading.

- a) Modify the old runserver file, *run_servername.bat*, where *servername* is your Replication Server name, to replace the old binary with the new binary in %SYBASE%\REP-15_5\bin\repserver, then start Replication Server from %SYBASE%\REP-15_5\bin\repserver.
- b) If you are using Adaptive Server as the RSSD, restart the RepAgent for the RSSD:

```
sp_start_rep_agent RSSD_name
```
- c) Resume log transfer to Replication Server from all Replication Agents for primary databases, and the RSSD or ERSSD:

```
resume log transfer from all
```
- d) If there are incoming routes to *dest_rs*, the Replication Server you upgraded and have now restarted, log in to the source Replication Server and resume all routes to *dest_rs* to allow the source Replication Server to begin sending queued messages to *dest_rs*. At the source Replication Server, execute:

```
resume route to dest_rs
```

14. If you have more Replication Servers to upgrade, repeat the upgrade procedures.

Fixing a Failed Replication Server Upgrade

Retry the upgrade process at this point if it fails.

1. Restart the old Replication Server against the RSSD and fix any problem that may have caused the error.
2. Re-run the upgrade process after you fix the error.
 You can do this multiple times until the upgrade succeeds.

Note: You cannot start a new Replication Server against a partially upgraded RSSD if you used **rs_init**. However, you can start a new Replication Server in upgrade mode as many

times as needed, using the **-upgr** option with **repserver**, against a partially upgraded RSSD to continue the upgrade process or to fix upgrade problems.

Fixing User Database Upgrades with `sysadmin upgrade, "database"`

Apply upgrades to SAP ASE, Oracle, or SAP® IQ, primary, replicate, or standby databases in the replication system that failed to upgrade during the automatic upgrade process, or to databases that you excluded from the automatic upgrade process.

The upgrades are required to accommodate changes, such as installing new stored procedures, that support the new version of Replication Server to which you are upgrading.

1. Enter **admin version, "connection"** at the upgraded Replication Server to identify the user databases that you must upgrade.
- You see a list of the user databases and data servers, the database IDs, the corresponding Replication Server, and the status of the database. For example:

dbid	Name	Controller RS	Status
-----	-----	-----	-----
101	pds.pdb01	rs_12	Database needs upgrade
102	pds.pdb02	rs_12	Database is not accessible
103	rds.rdb01	rs_12	Database has been upgraded

The “Not accessible” status means that Replication Server cannot connect to this user database because the database is unavailable, or because the maintenance user ID that Replication Server uses to connect to the database has insufficient privileges to connect.

2. Enter **sysadmin upgrade, "database"** at the upgraded Replication Server to upgrade the user databases served by the Replication Server:

```
sysadmin upgrade, "database" {,data_server, database | all}
```

where:

- *dataserver_name, database_name* – specifies a database to upgrade. You must enter a separate command for each database.
- **all** – upgrades all databases served by the Replication Server. Replication Server displays error messages if a database does not meet the conditions for upgrade.

For example, to upgrade the pdb01 database in the pds data server, enter:

```
sysadmin upgrade, database, pds, pdb01
```

If any of the databases fail to upgrade, see the Replication Server error log for the reasons such as:

```
Database data_server.database is not accessible.  
Fail to upgrade data_server.database.
```

Upgrading an SAP ASE User Database with `rs_init`

If you use **rs_init** to upgrade SAP Replication Server and the RSSD or ERSSD, you must apply upgrades to a primary, replicate, or standby database in the replication system to accommodate changes, such as installing new stored procedures, that support the new version

of SAP Replication Server to which you are upgrading, and features such as Multi-Path Replication.

If you do not apply the upgrades to replicate databases such as:

- SAP ASE – you cannot use Multi-Path Replication for replication to SAP ASE databases after you upgrade SAP Replication Server to 15.7 and later.
- SAP IQ – SAP Replication Server suspends replicate connections to the SAP IQ replicates after you upgraded SAP Replication Server to version 15.7.1 or later, and you see a "Awaiting Upgr" status if you use **admin who**.

1. Start **rs_init**.
2. Select **Upgrade an existing database in the replication system** from the Configure Replication System window, then choose **Continue**.
3. Enter the information from the "Database Setup Worksheet" for the upgraded Replication Server:
 - Name of the Adaptive Server that manages the database you are upgrading.
 - Name of the database you are upgrading.
 - Login name for the "sa" user on the Adaptive Server that manages the database that you are upgrading. The default value is "sa."
 - Adaptive Server "sa" user password.
 - Login name for the maintenance user on the Adaptive Server that manages the database that you are upgrading. The default is "database_maint," where "database" is the name of the database you are upgrading.
4. Select **Continue**. **rs_init** performs the upgrade.
5. If you have more Replication Servers or databases to upgrade, repeat the procedures to stop Replication Agent and quiesce Replication Server, upgrade RSSD or ERSSD, and upgrade Adaptive Server databases.

Upgrading Non-SAP ASE User Databases and User Databases Not Supported by sysadmin upgrade

Use the corresponding upgrade scripts for databases such as IBM DB2 UDB, and Microsoft SQL Server that are not supported by the **sysadmin upgrade, database** command and **rs_init**.

1. Use the maintenance user login ID to connect to the user database.
See the SAP Replication Server Options documentation to configure a connection to a non-SAP ASE database.
2. Find the relevant script in the `scripts` subdirectory of your SAP Replication Server installation directory.
The scripts are named `hds_dataserver_make_upgradedb.sql` where `dataserver_make` is the replicate data server type.

3. Run the script to upgrade the user database.

Modify or run the script unchanged depending on the way SAP Replication Server connects to the user database.

If the connection is through, Enterprise Connect™ Data Access (ECDA) runs the script unchanged. For example, to upgrade an IBM DB2 UDB user database, use ECDA for ODBC with the **isql -i** option to run the **hds_db2_upgradedb.sql** script on the user database.

See also

- *Commit a Local Site to a New Version Level* on page 71

Upgrading Oracle User Databases Manually

Use **hds_oracle_upgradedb.sql** to upgrade an Oracle user database manually or if the database upgrade with **sysadmin upgrade** failed.

1. Use the maintenance user login ID to connect to the user database.
See the SAP Replication Server Options documentation to configure a connection to a non-SAP ASE database.
2. Locate the **hds_oracle_upgradedb.sql** in the `scripts` subdirectory of your SAP Replication Server installation directory.
3. Run the script to upgrade the user database.
4. Check the status of the upgrade with **admin who**.

If you see "Awaiting Upgr", you must reset the connection to the database.

5. To reset the connection, log in to the RSSD and execute:

```
set replication off
go
set triggers off
go
update rs_databases set dist_status = dist_status &
~hextoint("0x400")
  where ltype='P'
  and connid=xxxx
go
set replication on
go
set triggers on
go
```

6. Restart SAP Replication Server.

Commit a Local Site to a New Version Level

After you upgrade a Replication Server and its user databases, you must decide whether to commit to the new Replication Server version level. Decide whether to set the replication site version to the new version and whether to upgrade the route version to the new version.

The system version is the version of the replication system. Set the system version at the ID Server with **sysadmin system_version**.

In a replication system that includes Replication Server versions 12.6 through 15.7.1 SP200, and for which the site version is set to its software release level and the system version is 1260 or higher, each Replication Server can use all the features of its release. Such a system is called a mixed-version system.

However, in a mixed-version system, interaction between Replication Servers of different version levels is limited, and information associated with new features may not be available to Replication Servers of earlier versions. Replication Servers of the same version can exchange full information about the software features they support.

If, for example, you are upgrading to version 15.7.1 SP200, you can use new Replication Server features that interact with other Replication Servers only if all these conditions are true:

- The system version has been set to 1260 or higher.
- The site version for both Replication Servers has been set to the current site version, such as 1571200.
- The routes between the Replication Servers have been upgraded.

See **sysadmin system_version** in the *Reference Manual*.

See also

- *Preparing to Upgrade* on page 58
- *Upgrading Non-SAP ASE User Databases and User Databases Not Supported by sysadmin upgrade* on page 69
- *Backing Up the RSSD or ERSSD* on page 76

System Version and Software Version Relationship

You can use the full capabilities of software version 15.5 and later when the system version is at 1260 or later.

SAP Replication Server Software Version	System Version 1260 and Later
15.7.1 SP200	Full capability when site version is set to 1571200
15.7.1 SP100	Full capability when site version is set to 1571100

SAP Replication Server Software Version	System Version 1260 and Later
15.7.1	Full capability when site version is set to 1571
15.7	Full capability when site version is set to 1570
15.6 and 15.5	Full capability when site version is set to 1550
15.2	Full capability when site version is set to 1520
15.1	Full capability when site version is set to 1510
15.0 and 15.0.1	Full capability when site version is set to 1500
12.6	Full capability when site version is set to 1260

For example, new features of version 15.7.1 SP200 are available only when the system version is at least 1260 and the site version is set to 1571200.

If a software version is supported with full capability at a given system version, you can install new SAP Replication Servers of that software version.

Replication Server Site Version

The site version determines which Replication Server features you can use.

If, for example, you have Replication Servers with a site version set to version 15.0, you can create replication definitions for tables containing the `bigint` datatype. Such replication definitions are distributed to other Replication Servers with site versions that are at the same version level or higher. Replication Servers of earlier versions do not receive information about these replication definitions.

After you upgrade Replication Server and its user databases, and set the system version to the new version, you must set the Replication Server site version to the new software version level before you can use the new Replication Server features.

You cannot downgrade after you set the site version. You must set the site version for all Replication Servers that require it, and upgrade the routes. Information needed for the new features cannot be propagated to other sites until the corresponding routes are upgraded.

See also

- *Replication Server Route Version* on page 73

Setting the Replication Server Site Version to the New Version

Set the Replication Server site version to the new version to use the new features of Replication Server.

1. Log in to the current Replication Server and execute **sysadmin site_version, new_site_version** to complete the upgrade.

For example, to set the site version to 1570:

```
sysadmin site_version, 1570
```

The *Release Bulletin* may instruct you to set the site version to a more recent version level.

See **sysadmin site_version** in the *Reference Manual*.

2. If the Replication Server uses an ERSSD, remove the **erssd_release_dir** and **erssd_start_cmd** parameters, and all options and values you entered earlier for these parameters from the `rs_name.cfg` file of the new version of Replication Server.

Replication Server Route Version

The route version is the earlier of the two site version numbers of the source and destination Replication Servers of the route. After you upgrade the source and destination Replication Servers on either end of a route and also set their site versions to a higher Replication Server version, you must upgrade the route.

Upgrading the route allows the Replication Servers to exchange information about newer software features. Upgrading a route rematerializes the data in the system tables in the RSSD and makes information associated with new features available to a newly upgraded Replication Server. After upgrading, new types of information that were not previously allowed can be exchanged.

Replication Server version 11.5 and later uses route version information to determine which feature set you can use with the route and which data to propagate to other sites. If the route version is lower than the earliest site version, you must perform a route upgrade. For example, information necessary for version 15.7.1 SP200 features is not propagated to other sites until the corresponding route versions are upgraded to 1571200.

After you upgrade to Replication Server 15.7.1 SP200 and set the site version to 1571200, you must upgrade each route for which this Replication Server is a source or destination, and the site versions of the source and destination are at 1571200 or later. Set the new site version and upgrade the routes only to use new features across multiple Replication Servers that support the new features.

How you upgrade routes depends on how you use Replication Server, and whether you are using a mixed-version system.

If the source Replication Server is version 15.7 or later, you can use **sysadmin upgrade, "route"** to upgrade a route regardless of the destination Replication Server version.

Upgrading Routes

Set the route version to the new version.

1. Execute **admin version, "route"** to report the routes that you need to upgrade that start from and go to the Replication Server you are upgrading. An example of the report:

Source	Destination	Route	Proposed	Status
		Version	Version	

```
-----
NY_RS   LON_RS           1500   1571200   Need route upgrade
```

2. Execute **sysadmin upgrade, "route"**, *dest_rs_name* on the Replication Server that originates the route you want to upgrade where *dest_rs_name* is the destination Replication Server of the route you are upgrading.

The user ID and password you use to execute the command must also exist at the destination Replication Server, and the RSSD of the destination Replication Server. This user ID must have sa permission at the destination Replication Server and dbo permission at the RSSD of the destination Replication Server.

For example, to upgrade the route from NY_RS to LON_RS in the example replication system in step 1, execute:

```
sysadmin upgrade, "route", LON_RS
```

When you execute the command, you see:

```
Route upgrade for route 'NY_RS.LON_RS' is in progress in the
background"
```

In the background, NY_RS starts a routing thread that performs these procedures:

- NY_RS determines if the route upgrade requires RSSD materialization. If it does, NY_RS proceeds to the next step. Otherwise, NY_RS places a commit marker in the RSSD of LON_RS to alter the route version and completes the route upgrade.
- NY_RS places a begin marker in the RSSD of NY_RS.
- NY_RS checks every two seconds for the arrival of the begin marker at the RSSD of LON_RS. If the begin marker does not arrive at the RSSD of LON_RS within the defined threshold of one minute, NY_RS terminates the upgrade process.
- When the begin marker arrives at the RSSD of LON_RS, NY_RS instructs LON_RS to enter hibernation mode.
- The command instructs NY_RS to process the set of route upgrade scripts.
- NY_RS places a commit marker in the RSSD of LON_RS to alter the route version and then NY_RS completes the route upgrade.
- NY_RS instructs LON_RS to leave the hibernation mode.

3. Execute **admin version, "route"** to check the status of the route upgrade.

If:

- The route upgrade succeeds, the route should not be listed in the output.
- The route upgrade fails and you need to recover the route from the upgrade, you see something similar to:

Source	Destination	Route Version	Proposed Version	Status
-----	-----	-----	-----	-----
NY_RS	LON_RS	1500	1571200	need route upgrade recovery

- If the route upgrade did not proceed and if there are still routes that you need to upgrade, you see something similar to:

Source	Destination	Route Version	Proposed Version	Status
-----	-----	-----	-----	-----
NY_RS	ROM_RS	1500	1571200	need route upgrade

You can also check the error log of *source_rs_name*, the Replication Server where the route starts, for the status of the route upgrade. In a:

- Successful route upgrade that includes materialization to make information associated with new features available to a newly upgraded Replication Server:
Upgrade for route '*source_rs_name.dest_rs_name*' is complete.
- Successful route upgrade that does not need rematerialization:
Upgrade for route '*source_rs_name.dest_rs_name*' is complete. no copying of RSSD information is necessary.
- Failed route upgrade:
Route upgrade/upgrade recovery fails due to error. The upgrade procedure is not completed. This routing thread will in turn exit.

4. To recover the route upgrade if the route upgrade fails:

- a) Execute **sysadmin upgrade,"route", *dest_rs*, "recovery"** at the source Replication Server.

For example, at NY_RS, execute:

```
sysadmin upgrade, "route", LON_RS, "recovery"
```

- b) Execute **admin version,"route"** at NY_RS to verify that the route upgrade is completed.

5. Restart the primary Replication Server distributor thread connection from the primary database after you upgrade the route to support the replication of features included with the new version of Replication Server.

For example, to restart the thread from the *pdb* primary database in the PDS primary data server, enter:

```
suspend distributor PDS.pdb
go
resume distributor PDS.pdb
go
```

Backing Up the RSSD or ERSSD

Back up the RSSD or ERSSD after upgrading the Replication Server, setting its site version, and performing route upgrades to the relevant routes.

1. Use the Adaptive Server commands **dump database** or **dump transaction** to back up the RSSD, and the Replication Server **sysadmin erssd, backup** command to back up the ERSSD.

2. (Optional) You can restore the RSSD with the Adaptive Server commands **load database** or **load transaction**, or restore the ERSSD using the ERSSD recovery procedure.

See the *Administration Guide Volume 1 > Manage a Replication System > > Manage the Embedded Replication Server System Database* for information on recovery procedures.

3. (Optional) If you have a current backup, you can avoid potential problems that can occur if you load an RSSD that corresponds to an earlier version level.

After you load the backup, all queued messages from other Replication Servers can be recognized by this Replication Server and RSSD.

If you restore the RSSD from a backup performed before you set the site version, Replication Server may receive messages that the RSSD cannot accept.

See also

- *Commit a Local Site to a New Version Level* on page 71

Upgrading Adaptive Server in a Replication System

You can separately upgrade Adaptive Server in your replication system.

Prerequisites

SAP strongly recommends you perform a dump database and dump transaction before upgrading Adaptive Server.

Task

1. *Suspend Replication and Transaction Activity in the Database*

Suspend replication and transaction activity in the database. Replication activity includes creating and dropping both routes and subscriptions.

2. *Drain the Transaction Logs of the Primary Databases*

Ensure that the Replication Server completely processes the preupgrade log for each primary database you are upgrading.

3. *Drain the RSSD Transaction Log*

Create a replication definition to manually drain the RSSD transaction log. This ensures that Replication Server processes all transactions in the RSSD log before you upgrade databases if Replication Server has routes to other Replication Servers.

4. *Disable the Secondary Transaction Point*

Turn off the secondary truncation point for the duration of the upgrade and when you upgrade a primary database, the Replication Agent cannot be running.

5. *Upgrade Adaptive Server*

See the Adaptive Server Enterprise Installation Guide for upgrade instructions.

6. *Update the Adaptive Server System Catalog*

To ensure that replication proceeds correctly for objects with quoted identifiers created in versions of Adaptive Server earlier than 15.7, update the Adaptive Server system catalog after you upgrade Adaptive Server, but before you restore replication.

7. *Restore Replication*

Restore replication after you perform the upgrade procedure.

Suspending Replication and Transaction Activity in the Database

Suspend replication and transaction activity in the database. Replication activity includes creating and dropping both routes and subscriptions.

1. Verify that the subscriptions you have created with primary data in the databases being upgraded, have reached a “valid” state at the primary Replication Server.

Do not upgrade while the subscriptions are being created.

Make sure no users create subscriptions for the data in the database you are upgrading until the upgrade procedure is finished.

2. Run **rs_helproute** in each RSSD being upgraded to determine its status.

The status of all routes should be “Active.” See *Managing Routes* in the *Administration Guide Volume 1* to resolve route problems.

3. Shut down the applications that are using the databases you are upgrading.

4. Use the **admin who** command in Replication Server to identify the existing Data Server Interface (DSI) connections to the data server being upgraded.

5. Suspend all DSI connections to databases you are upgrading. For each database, issue:

```
suspend connection to dataserver.database
```

Draining Transaction Logs for Primary Databases

Ensure that the Replication Server completely processes the preupgrade log for each primary database you are upgrading.

1. Wait for all remaining transactions to be replicated.

2. Execute:

```
admin who, sqm
```

Find the entry that corresponds to the inbound queue for this database by looking in the Info field for the *queue_number* and *queue_type* entry. For an inbound queue, the queue type is 1. Note the last segment: block entry for the queue.

3. Open the queue dump file:

```
sysadmin dump_file, "file_name"
```

where *file_name* is the file to which you are dumping.

4. Create a dummy table to check that the Replication Server has received the latest log record written in the log. You can drop this table later.

```
create table dummy (c1 int, c2 char(255))
go
sp_setreptable dummy, true
go
begin tran
go
insert dummy values (1,'hello')
go 10
commit tran
go
```

5. In the primary Replication Server, execute the **admin who, sqm** command until the last segment: block entry for the inbound queue changes.
6. In Replication Server, dump the last block of the inbound queue to the dump file you created in step 3:

```
sysadmin dump_queue, queue_number, queue_type,
last_seg, block, 1
```

Use the *queue_number*, *queue_type*, *last_seg*, and *block* values found in the output of the **admin who, sqm** command in step 5.

7. Use a text editor to examine the dump file to make sure it contains the transaction corresponding to the inserts you performed in step 4.
8. Repeat steps 5 through 7 until the transaction corresponding to the update is in the dump file. After draining the transaction logs, do not allow any other activity in the databases. If activity does occur, you must redrain the transaction logs.

Draining the RSSD Transaction Log

Create a replication definition to manually drain the RSSD transaction log. This ensures that Replication Server processes all transactions in the RSSD log before you upgrade databases if Replication Server has routes to other Replication Servers.

To make sure the transaction log is completely processed, create a replication definition in the primary Replication Server and verify that it appears in the replicate Replication Server RSSD. When the replication definition is in the replicate RSSD, the log is fully processed.

1. Log in to the primary Replication Server.
2. Create a temporary replication definition:

```
create replication definition rep_def_name
with primary at dataserver.database
```

```
with all tables named 'table_name' (column_name datatype)
primary key (column_name)
```

Provide the names for the data server, database, table, and column, and the datatype of the column. See the *Replication Server Reference Manual* for the complete syntax.

3. Log in to the replicate RSSD.
4. See whether the replication definition has arrived from the primary RSSD:

```
rs_helprep rep_def_name
```

When the replication definition has arrived in the replicate RSSD, the RSSD transaction log has been drained.

Disabling the Secondary Truncation Point

Turn off the secondary truncation point for the duration of the upgrade and when you upgrade a primary database, the Replication Agent cannot be running.

1. Shut down the Replication Agents, or make sure that **dbcc logtransfer** is not running for the databases that are being upgraded.
2. Shut down Replication Servers for the RSSDs you are upgrading.
3. In each primary database including RSSDs, turn off the secondary truncation point:

```
use database
go
dbcc settrunc ("ltm", "ignore")
go
```

Repeat step 3 for each primary database and each primary RSSD.

Upgrading Adaptive Server

See the *Adaptive Server Enterprise Installation Guide* for upgrade instructions.

Updating the Adaptive Server System Catalog to Support Quoted Identifiers

To ensure that replication proceeds correctly for objects with quoted identifiers created in versions of Adaptive Server earlier than 15.7, update the Adaptive Server system catalog after you upgrade Adaptive Server, but before you restore replication.

1. Log in to **isql** at the primary Adaptive Server database.
2. Update the system catalog. Enter:

```
set nocount on
declare @cmd varchar(200)
        ,@cmdstat int
        ,@count int
        ,@dbid int
        ,@dbname varchar(30)
        ,@total int
```

Upgrade or Downgrade SAP Replication Server

```
select @cmdstat = config_admin(1, 102, 1, 1, NULL, NULL)
select @dbid = 1, @count = 0, @total = 0
while @dbid is not null
begin
    select @dbname = db_name(@dbid)
    select @cmd = 'select @count = count(1) from ' + @dbname
                + '.dbo.sysobjects'
                + 'where (sysstat2 & 134217728) = 0 '
                + 'and type = 'U''
    exec (@cmd)
    if @count > 0
    begin
        print 'Object count in %1! is %2!', @dbname, @count
        select @total = @total + @count
        select @cmd = 'update ' + @dbname + '.dbo.sysobjects '
                    + 'set sysstat2 = sysstat2 | 134217728 '
                    + 'where (sysstat2 & 134217728) = 0 '
                    + ' and type = 'U''
        exec (@cmd)
    end
    select @dbid = min(dbid) from sysdatabases where dbid > @dbid
end
if @total > 0
    print 'You must restart ASE for changes to take effect.'
select @cmdstat = config_admin(1, 102, 0, 1, NULL, NULL)
```

Restoring Replication

Restore replication after you perform the upgrade procedure.

1. Zero out the locator in the RSSD for each replicated primary.

Use **isql** to connect to the RSSD and execute:

```
use RSSD
go
rs_zeroltm dataserver, database_name
go
```

2. Set the secondary truncation point to “valid” in each primary database. Use **isql** to connect to the replicated primary database and execute:

```
use database
go
dump tran database with truncate_only
go
dbcc settrunc("ltm","valid")
go
```


Downgrading Replication Server

Revert to an earlier version of the software. You cannot downgrade an RSSD to a version below the site version.

Prerequisites

- Read the release bulletin for any information about downgrading your software. In particular, find out if an RSSD downgrade is required to return to the earlier version. When you downgrade to an earlier software version, you must install the earlier software. Read the release bulletin for the earlier version of Replication Server. Then refer to the installation or configuration guide for that version for installation instructions.

Note: If an RSSD downgrade is not required, you do not have to perform these steps. Reinstall the earlier software version following the instructions in the *Installation Guide*.

- Back up your system.
If you are downgrading to a directory other than the existing version directory, verify that the appropriate `sql.ini` file is accessible.
- Back up the RSSD for the Replication Server you plan to downgrade.

Warning! Some Replication Server configuration options with newer versions may have a wider valid range. If you increase any of these configuration options after upgrading, you must reinstate the old values before downgrading. Otherwise, the Replication Server may not start or may behave incorrectly. The Replication Server upgrade process prints all the current configuration option values in **rs_config** to **rs_init** log, so that you can restore the former settings before downgrading.

Task

- Stop Replication Agent for all primary databases and system databases by executing this command on Replication Server:

```
suspend log transfer from all
```

- If you are using Adaptive Server as your RSSD, stop RepAgent for the RSSD:

```
sp_stop_rep_agent RSSD_name
```

- If you are going to downgrade a replicate Replication Server, log in to the primary Replication Server and suspend all the routes to the replicate Replication Server:

```
suspend route to replicate_Replication_Server
```

- Verify that the Replication Server queues have been drained and that Replication Server has been quiesced:

```
admin quiesce_check
```

Retry with **admin quiesce_force_rsi** if Replication Server is not yet quiesced.

Warning! You may lose data if you proceed with the downgrade process without quiescing Replication Server.

5. Log in as a system administrator.
6. Verify that the RSSDs and the Replication Servers you plan to downgrade are running.

Note: The downgrade process purges all the Replication Server inbound queues.

7. In the Windows group window, double-click the **Replication Server Configuration** icon.
8. Select **Configure a Server Product**, then choose **Continue**.
9. Select **Replication Server**, then choose **Continue**.
10. Select **Downgrade RSSD for an Existing Replication Server**, then choose **Continue**.
11. Enter information from the “Replication Server Installation Worksheet” section for the Replication Server you are downgrading:
 - Name of the Replication Server for which you are downgrading the RSSD.
 - Login name for the Replication Server “sa” user. The default value is “sa.”
 - Password for the Replication Server “sa” user.
 - Path name of the Replication Server configuration file.
12. Select **Continue** to save your changes. You see:
Execute the Replication Server tasks now?
13. Select **Yes** to continue.

Informational messages appear as **rs_init** loads the downgrade script into the RSSD. When the downgrade is complete, you see these messages:

```
RSSD successfully downgraded to rel_no. Replication Server
'rs_name' can now be restarted. Task to downgrade the RSSD
succeeded. Configuration completed successfully.
```

where:

- *rel_no* – is the Replication Server version from which you are downgrading.
- *rs_name* – is the name of your Replication Server.

14. Select **OK**. You see:
Replication Server “rs_name” can now be restarted
15. Select **OK**. You see:
Configuration completed successfully.
16. Select **OK**. You see the Setup window.
17. Select **Exit**.
18. Shut down all Replication Servers and Replication Agents on this machine.
19. Restart the Replication Servers and Replication Agents.
20. If you are using Adaptive Server as the RSSD, restart the RepAgent for the RSSD:

```
sp_start_rep_agent RSSD_name
```

Downgrade Restrictions

After you set the replication site version to a new level, you cannot downgrade any Replication Servers in the replication system below that version level, or install a Replication Server below that version level.

For example, if you upgrade to version 15.7.1 SP200, Replication Server may write some version 15.7.1 SP200 commands to the inbound queue after the upgrade. Versions of Replication Server earlier than 15.7.1 SP200 cannot recognize the version 15.7.1 SP200 commands.

To return to an earlier software version, reinstall all Replication Servers and re-create your replication applications.

If you do not want to use new features that depend on the site version, do not set the Replication Server site version after the upgrade. You can then downgrade to an earlier version if needed.

If you plan to downgrade in a directory other than the existing version directory, verify that the `sql.ini` file is accessible.

If necessary, downgrade the RSSD for each Replication Server you are downgrading. You must downgrade the RSSD using the predowngrade—that is, the most recent—version of `rs_init`.

If the Replication Server uses an ERSSD, verify that the Replication Server configuration file contains the `erssd_release_dir` and `erssd_start_cmd` parameters. Ensure the values for these parameters should be the same as the values before upgrading.

Migrating Between 32-Bit and 64-Bit Platforms

Replication Server is available on 32-bit and 64-bit platforms for Windows.

Prerequisites

- Back up your replication system. The migration process makes changes to the system databases that you cannot roll back if the migration fails. Restore the system databases if the migration fails.
- If you plan to install the software in a directory other than an existing version directory, verify that the `sql.ini` file is accessible.

Task

Note: This migration procedure applies only for migration in the same RSSD version and platform. If you have migrated to a Replication Server version that is available only on 64-bit platforms, you cannot migrate back to a 32-bit platform. See the release bulletin for supported 64-bit platforms.

Upgrade or Downgrade SAP Replication Server

1. Stop Replication Agent for all primary databases and system databases by executing this command on Replication Server:

```
suspend log transfer from all
```

2. If you are using Adaptive Server as your RSSD, stop RepAgent for the RSSD:

```
sp_stop_rep_agent RSSD_name
```

3. If you are going to migrate a Replication Server, log in to each upstream Replication Server and suspend all the routes to the Replication Server you are migrating:

```
suspend route to replicate_Replication_Server
```

4. Verify that the Replication Server queues have been drained and that Replication Server has been quiesced:

```
admin quiesce_check
```

If Replication Server has not yet quiesced, use **admin quiesce_force_rsi**.

Warning! You may lose data if you proceed with the migration process without quiescing Replication Server.

5. Stop Replication Server.

- a) Log in to the Replication Server as the system administrator:

```
isql -Usa -Psa_password -Sservername
```

- b) Enter:

```
1> shutdown
2> go
```

6. If you are using an ERSSD, manually restart it:

- a) Set the LD_LIBRARY_PATH environment variable:

```
$ export
LD_LIBRARY_PATH=$SYBASE/REP-15_5/ASA16/
lib:$SYBASE/REP-15_5/lib64:$SYBASE/REP-15_5/
lib:$SYBASE/REP-15_5/lib3p64/log4cxx/lib:$SYBASE/
OCS-16_0/lib:$SYBASE/OCS-16_0/lib3p64:$SYBASE/OCS-16_0/
lib3p
```

- b) Start the ERSSD:

```
C:\sybase\REP-15_5\ASA16\win32\dbspawn.exe -f -q
C:\sybase\REP-15_5\ASA16\win32\dsrv16.exe -ti 0 -x
"tcpip(PORT=11751;DOBROAD=NO;BLISTENER=NO)" -o
C:\sybase\REP-15_5\errorlog\SAMPLE_RS_ERSSD.out
C:\sybase\REP-15_5\dbfile\SAMPLE_RS_ERSSD.db
```

In your Replication Server log file, search for “ERSSD start command”, to see the actual commands for starting the ERSSD.

7. Load the migration script file into the ERSSD or RSSD. For example:

- ERSSD – load %SYBASE%\REP-15_5\scripts\rs_migration_asa.sql into the ERSSD.

- RSSD – load %SYBASE%\REP-15_5\scripts\rs_migration_ase.sql into the RSSD.

8. Start Replication Server from the new Replication Server executable.

See also

- *Start or Stop a Replication Server* on page 101

Upgrades and Downgrades Using Existing Directories

You can upgrade and downgrade SAP Replication Server if you install the software into existing directories.

By default, the installation process installs versions 15.5 to 15.7.1 SP200 in directories under the `REP-15_5` directory. SAP recommends that you do not install and upgrade versions 15.5 to 15.7.1 SP200 using existing directories that contain any preupgrade versions between 15.5 and 15.7.1 SP200. You must back up the files and directories of the preupgrade version of SAP Replication Server before you install the newer version in the same directories.

The *Upgrading Using Existing Directories* on page 87 procedure applies only between these Replication Server versions:

From\To	15.5	15.6	15.7	15.7.1	15.7.1 SP100	15.7.1 SP200
15.5	NA	NA	Yes	Yes	Yes	Yes
15.6	NA	NA	Yes	Yes	Yes	Yes
15.7	NA	NA	NA	Yes	Yes	Yes
15.7.1	NA	NA	NA	NA	Yes	Yes
15.7.1 SP100	NA	NA	NA	NA	NA	Yes

Upgrading Using Existing Directories

Upgrade using the existing directories.

1. Shut down the preupgrade version of Replication Server.

See *Start or Stop a Replication Server* on page 101.

2. Back up the entire set of files and directories under `%SYBASE%`.

Note: Keep this backup in case you need to downgrade from Replication Server version 15.7.1 SP200 to an earlier version.

3. Use the relevant version of the *Installation Guide* to install your new version of Replication Server into the existing version directories under `%SYBASE%`.

Note: Do not install the `SAMPLE_RS` sample Replication Server from the new version if you are using the `SAMPLE_RS` from the earlier version.

The installation process:

- Updates all subdirectories of %SYBASE% that share directory names in both versions.
 - Backs up existing SYBASE.* files, where * can be .env or .bat, by adding a "save" suffix to the file. For example, Sybase.env is backed up as Sybase.env.save
4. Set the relevant environment variables in the SYBASE.env file in the Replication Server 15.7.1 SP200 installation directory.
See Environment Variables on UNIX in the Installation Guide. See Environment Variables on Windows in the Installation Guide.
 5. You can use the **repsvr** or **rs_init** utilities to upgrade Replication Server from versions 15.5 and later to version 15.7.1 SP200.

However, to upgrade from versions 15.5, 15.6 and later to version 15.7, you can only use **rs_init**.

For example, to upgrade the tokyo_rs Replication Server from version 15.6 to 15.7.1 SP200 using **repsrvr**, enter:

```
C:\sybase\rs1560esd1\REP-15_5\bin\repsrvr.exe -upgr -Stokyo_rs
-CC:\sybase\rs1560esd1\REP-15_5\install\toky_rs.cfg
-EC:\sybase\rs1560esd1\REP-15_5\install\tokyo_rs.log
-IC:\sybase\rs1560esd1\ini\sql.ini
-A C:\sybase\rs1560esd1\REP-15_5\ASA11
```

After the upgrade, you see a new entry in the configuration file. For example after upgrading tokyo_rs, you see:

```
erssd_release_dir=C:\sybase\rs1560esd1\REP-15_5\ASA11
erssd_start_cmd=C:\sybase
\rs1560esd1\REP-15_5\ASA11\win32\dbspawn.exe
-f -q C:\sybase\rs1560esd1\REP-15_5\ASA11\win32\dsrv11.exe
-ti 0 -x "tcpip(PORT=11753;DOBROAD=NO;BLISTENER=NO)"
-o C:\sybase\rs1560esd1\REP-15_5\errorlog\tokyo_rs_erssd.out
C:\sybase\rs1560esd1\REP-15_5\dbfile\tokyo_rs_erssd.db
RS_random=b6BADgNj4GOgnJ47vYwkgcPoQf1YvQOxidN0sgnrqCgIk6tmrvYrWmF
20hcV/SnPRH
```

Note: You see the **RS_random** encryption attribute only if you upgrade to version 15.7.1 and later either with **repsvr** or **rs_init**. As earlier versions of Replication Server cannot use the attribute, you can leave it in the configuration file or delete it if you downgrade from versions 15.7.1 and later.

6. Change the runserver file you copied from the backup to use the upgraded Replication Server executable, and then start Replication Server.

See Runserver File in the Configuration Guide.

Downgrading to an Earlier Version in Existing Directories

You can revert to an earlier Replication Server version in the existing directories if you backed up your earlier version before upgrading to same directories.

1. Back up the entire set of files and directories under %SYBASE%.
These contain the current Replication Server version files.
2. Downgrade Replication Server using the procedure in *Downgrading Replication Server* on page 81.
3. Back up the Replication Server ERSSD or RSSD after completing the downgrade procedure in step 2.
4. To overwrite the directory structure under %SYBASE%, restore the files and directories from the backup you made before you upgraded to the current Replication Server version.
5. Verify that the .cfg, sql.ini, and run_repservername runserver files are configured to run the version of Replication Server you are downgrading to.
6. If there was replication activity on the upgraded version of Replication Server prior to the downgrade process, verify that you are using the downgraded version of RSSD files, otherwise restore the ERSSD or RSSD from the backup you have made in step 3.
If you use an ERSSD, copy the dbfile, translog, errorlog, and backup directories to the corresponding locations. If you use SAMPLE_RS, copy all files and directories under %SYBASE%\REP-15_5\samp_repserver to the corresponding locations.
7. Set the relevant environment variables in the SYBASE.env file.
See *Environment Variables on Windows* in the *Installation Guide*.
8. Start the downgraded Replication Server version with the runserver file.
See *Runserver File* in the *Configuration Guide*.

Password Encryption

Replication Server encrypts all passwords, and stores and transmits passwords in encrypted format.

Replication Server uses password encryption instead of clear text when storing all passwords for new Replication Server installations.

Set the site version to 1571 or later before you use **rs_init** to change existing encrypted passwords when you are upgrading Replication Server. To change the passwords if you do not set the site version to 1571 or later, you must use **rs_init** from the version of Replication Server that you are upgrading from. You should manually remove the **RS_random** attribute in the configuration file if you downgrade Replication Server.

To regenerate the password encryption key, see *Password Encryption* in the *Administration Guide Volume 1*.

Enabling Password Encryption for a Replication Server

Enable password encryption for a Replication Server using **rs_init**.

rs_init creates a new configuration file that contains encrypted passwords for the Replication Server. **rs_init** encrypts the passwords in the `rs_users` and `rs_maintusers` system tables.

1. Select **Start > Programs > Sybase > rs_init**.
You see the RS_INIT menu.
2. Select **Configure a Server Product**, then choose **Continue**. You see the Configure Server Products window.
3. Select **Replication Server** and choose **Continue**. You see the Configure Replication System window.
4. Select **Enable Password Encryption for a Replication Server**, then choose **Continue**.
5. Enter:
 - Name of the Replication Server for which you want to enable password encryption.
 - Login name for the Replication Server with “sa” user.
 - Password for the Replication Server “sa” user.
 - Full path for the Replication Server configuration file.
6. Choose **Continue** to save your changes. You see:
Execute the Replication Server tasks now?
7. Select **Yes** to enable encryption.

rs_init shuts down the Replication Server and encrypts the passwords in the Replication Server configuration file and in the `rs_users` and `rs_maintusers` system tables.

Replication Server '`rs_name`' can now be restarted.

8. Choose **OK**. **rs_init** displays:
Configuration tasks completed successfully.
9. Choose **OK**. You see the Configure Replication System dialog box.
10. Choose **Exit** to quit **rs_init**.
11. Restart the Replication Server and any connected Replication Agents.
12. Delete the backup of the Replication Server configuration file.

Note: The backup file contains unencrypted passwords, so you should remove that file to protect your replication system security. However, you may first want to make a hard copy or offline backup of the file and store it in a safe place.

The backup file has the same name as the Replication Server configuration file, but the extension is changed to a three-digit number such as “001.” The file with the highest extension number is the most recent backup file.

Altering an Encrypted Password for a Replication Server

Change an encrypted password in a Replication Server configuration file using **rs_init**.

Do not use **rs_init** to change the passwords stored in the RSSD. To change the Replication Server password, use the **alter user** command. To change the maintenance user password, use **alter connection** or **alter route**.

1. Select **Start > Programs > Sybase > rs_init**.
You see the RS_INIT menu.
2. Select **Configure a Server Product**, then select **Continue**.
3. Select **Replication Server**, then select **Continue**.
4. Select **Alter a Replication Server Configuration File Password**, then select **Continue**.
5. Enter:
 - Name of the Replication Server whose configuration file you want to update.
 - Login name for the Replication Server “sa” user.
 - Password for the Replication Server “sa” account.
 - Full path name for the Replication Server configuration file.
 - Parameter for the password you want to alter:
 - *RSSD_primary_pw_enc* – for the RSSD primary user.
 - *RSSD_maint_pw_enc* – for the RSSD maintenance user.

- *ID_pw_enc* – for the *ID Server* user name.
 - New password you want to use.
6. Select **Continue** to save your changes. **rs_init** displays:
Execute the Replication Server tasks now?
 7. Select **Yes**.
rs_init shuts down the Replication Server, then records the new password in the Replication Server configuration file. When that process is complete, **rs_init** shows:
Configuration completed successfully.
 8. Choose **OK**. You see the Configure Replication System window.
 9. Choose **Exit** to quit **rs_init**.
 10. Restart the Replication Server.

Secure Sockets Layer

Secure Sockets Layer (SSL) is an industry standard for sending wire- or socket-level encrypted data over secure network connections.

See *Manage Replication Server Security* in the *Administration Guide Volume 1* for detailed information on the SSL security option.

See also

- *Replication Server Security Information* on page 17

Setting Up SSL Services

Set up SSL services on Replication Server.

Prerequisites

Review the SSL Plus user documentation and documentation for any third-party SSL security software you are using.

Task

1. *Include Trusted CA certificates*

Modify the SAP® Open Client™/SAP® Open Server™ trusted roots file to include trusted CA certificates.

2. *Obtain a Certificate for Each SSL-Enabled Replication Server*

Obtain a certificate from a trusted certificate authority (CA) for each Replication Server accepting SSL connections.

3. *Create an Identity File*

Create the identity file that contains the concatenation of a certificate and its corresponding encrypted private key, and that is understood by the SSL Plus software.

4. *Add an Encrypted Password to the Configuration File*

Use `rs_init` to enable SSL on Replication Server and to add or change an encrypted SSL password.

5. *Create SSL Entries in the Directory Service*

Create SSL entries in the Replication Server directory service—such as the `sql.ini` file, the Windows Registry, or an LDAP server, which defines the server address and port numbers, and determines security protocols that are enforced for client connections.

6. *Enable or Disable SSL on Replication Server*

You can enable SSL using Replication Server commands or `rs_init`.

7. *Restart Replication Server After SSL Changes*

Stop and start Replication Server for SSL configuration changes to take effect.

Include Trusted CA certificates

Modify the SAP® Open Client™/SAP® Open Server™ trusted roots file to include trusted CA certificates.

The list of known and trusted CAs is maintained in the trusted roots file: `%SYBASE%\ini\trusted.txt`

The system administrator adds and deletes CAs using a standard ASCII-text editor. The trusted roots file is similar in format to a certificate file.

By default, Replication Server recognizes these third-party CAs:

- Thawte
- Entrust
- Baltimore
- VeriSign
- RSA

Obtain a Certificate for Each SSL-Enabled Replication Server

Obtain a certificate from a trusted certificate authority (CA) for each Replication Server accepting SSL connections.

The system administrator installs server certificates and private keys for the Replication Server installation. The system administrator can get a server certificate using third-party tools provided with an existing public-key infrastructure (PKI) already in use in the customer environment. Each Replication Server acting as a server in an SSL-enabled connection must have a certificate issued by a trusted CA.

Most third-party PKI vendors have utilities to generate certificates and private keys.

If you request a certificate from a third-party vendor, and that certificate is in PKCS #12 format, use the **certpk12** utility to convert the certificate into a format understood by Replication Server.

Adaptive Server Enterprise provides the **certreq** and **certauth** utilities to test the certificate request tool and to verify that the authentication methods are working on your server. See *Security Administration* in the *Adaptive Server Enterprise System Administration Guide*.

Creating an Identity File

Create the identity file that contains the concatenation of a certificate and its corresponding encrypted private key, and that is understood by the SSL Plus software.

Prerequisites

Verify that you have the system administrator role before performing this task.

Task

The name and default location of the identity file is the following, where *servername* is the name of the server as specified at start-up:

```
%SYBASE%\%SYBASE_REP%\certificates\servername.crt
```

1. To place the identity file in a different location, specify the alternate location in the **RS_ssl_identity** entry in the configuration file.
2. To make a successful connection, the common name in the certificate must match the Replication Server name in the directory service.

Client certificates are not supported.

Adding an Encrypted Password to the Configuration File

Use **rs_init** to enable SSL on Replication Server and to add or change an encrypted SSL password.

The SSL password decodes the identity file private keys. This password is stored as the **RS_ssl_pw** entry in the Replication Server configuration file where it will not be sent over the network.

Note: You can enable and disable SSL on Replication Server using **configure replication server** and the **use_ssl** option.

Creating SSL Entries in the Directory Service

Create SSL entries in the Replication Server directory service—such as the `sql.ini` file, the Windows Registry, or an LDAP server, which defines the server address and port numbers, and determines security protocols that are enforced for client connections.

Replication Server implements the SSL protocol as a filter that is appended to master and query lines in the directory service.

1. Verify that all attempts to connect to a master or query entry in a directory service with an SSL filter supports the SSL protocol.

For example, suppose a primary Replication Server (SYBSRV1) and a replicate Replication Server (SYBSRV2) use the Transmission Control Protocol (TCP) and the SSL protocol for communication.

Entries in the `sql.ini` file might look like this:

```
[SYBSRV1]
query=tcp,myserver,sybasehost1,5001,ssl
master=tcp,myserver,sybasehost1,5001,ssl
```

```
[SYBSRV2]
query=tcp,myserver,sybasehost2,4001,ssl
master=tcp,myserver,sybasehost2,4001,ssl
```

2. You can also configure Replication Server to accept SSL connections and, at the same time, have other connections that accept clear text or use security mechanisms such as DCE and Kerberos.

To support both SSL and other connection protocols, you must use multiple `sql.ini` files.

For example, a typical `sql.ini` file entry that supports the TCP and both SSL and clear text connections looks like this:

```
[SYBSRV1]
query=tcp,myserver,sybasehost1,5001,ssl
master=tcp,myserver,sybasehost1,5001,ssl
master=tcp,myserver,sybasehost1,5001
```

3. The `sql.ini` file master line entries allow SYBSRV1 to listen for both SSL and clear text connections. To make sure that SYBSRV1 sends queries to SYBSRV2 using SSL, there must be a single query entry in the `sql.ini` file for SYBSRV1.

To allow SYBSRV1 to send queries to other servers using a different protocol, use a separate `sql.ini` file.

Enabling or Disabling SSL on Replication Server

You can enable SSL using Replication Server commands or `rs_init`.

Note: Replication Server does not require the REP_SSL license, as SSL comes as a part of the basic REP_SERVER license.

Enable or disable SSL using **configure replication server** with the **use_ssl** option.

To use **configure replication server**, enter:

```
configure replication server
set use_ssl to 'on'
```

Set **use_ssl** to off to disable SSL. By default, SSL is not enabled on Replication Server. When **use_ssl** is off, Replication Server does not accept SSL connections.

use_ssl is a static option. You must restart Replication Server after you change its value.

Restarting Replication Server After SSL Changes

Stop and start Replication Server for SSL configuration changes to take effect.

See also

- *Start or Stop a Replication Server* on page 101

Start or Stop a Replication Server

You can start or stop a Replication Server using the Services Manager and `runserver` file created by `rs_init` or using `isql`.

Start-up Sequence for Servers

In a production system, you must start Adaptive Servers and Replication Servers, whenever your machine reboots. See your system administrator to do this.

Start servers in this order:

1. If the Replication Server uses RSSD in Adaptive Server Enterprise, start the Adaptive Server first.
2. Replication Servers.

Starting or Stopping a Server Using the Services Manager

Use the Services Manager to start and stop Replication Servers and Adaptive Servers. The Services Manager provides a visual indication of the server status.

Prerequisites

Before you can use the Services Manager, you must shut down the server using `isql` and restart it using the Services Manager.

Task

1. Select **Start > Programs > Services Manager**.
You see the Services Manager window.
2. From the Services list box, select the type of server you want to view.
The available choices depend on the SAP products you have installed.
3. From the Server list box, select the name of the server you want to view.
4. To start the server, double-click **Start/Continue**, or the green light.
To shut down the server, double-click **Stop**, or the red light.

Note: Pause, the yellow (center) light, is not currently implemented.

See also

- *Stopping a Replication Server Using isql* on page 103

Runserver File

The runserver file is an executable script that contains the complete command line required to start an SAP Replication Server. When you install a new SAP Replication Server to your replication system, **rs_init** creates a runserver file in the installation directory.

The runserver file name is constructed based on the name of the server, truncated to eight characters, if necessary, and a `.bat` extension. For example, for an SAP Replication Server named `ROME_RS`, the runserver file is named `run_rome.bat`.

Starting Replication Server with Sufficient Memory

Configure Replication Server or the operating system to provide sufficient memory when Replication Server starts up.

With sufficient memory, Replication Server can avoid failure when there is heavy memory consumption by Replication Server caches and buffers.

1. Modify the **ulimit** option settings in the `runserver` file to:

```
ulimit -d 'unlimited'  
ulimit -c 'unlimited'  
ulimit -m 'unlimited'
```

2. (Optional) Modify the operating system memory limits.

For example, on IBM AIX, change the default settings in the `/etc/security/limits` file:

- `fsize – 1`
- `core – 2097151`
- `cpu – 1`
- `data – 1`
- `rss – 1`
- `stack – 65536`
- `nofiles – 2000`

See your operating system documentation for similar implementations

Configuring a New Server to Start at System Start-up

Configure a new server to start at system start-up.

1. Choose **Start > Settings > Control Panel**.

2. From the Control Panel, double-click the **Services** icon.
3. From the Server list box, select the server that you want to start at system start-up.
4. Click **Startup**.
5. In the Server dialog box, select Automatic in the Startup Type box.
6. Choose **OK**.

The server you selected will start at system start-up.

Stopping a Replication Server Using isql

Stop a Replication Server using the **isql** utility.

When you shut down a Replication Server, it refuses additional connections, terminates threads, and exits.

1. Use **isql** to log in to the Replication Server as the System Administrator:

```
isql -Usa -Psa_password -Sservername
```

2. Enter:

```
shutdown  
go
```


Install and Implement Non-SAP ASE Support Features

There are several requirements for the installation and implementation of non-SAP ASE support features.

Replication Server support for replication into a non-SAP ASE replicate database requires:

- Replication Server system tables—`rs_lastcommit` and `rs_info`—created in the non-SAP ASE database, and Replication Server support functions such as `rs_get_lastcommit` and `rs_get_charset`.
- Function strings that:
 - Replace certain language command and stored procedure invocations from the replicate Replication Server, then,
 - Produce operations in the replicate database that emulate the behavior of the commands and stored procedures that would exist in a SAP ASE replicate database.
- Heterogeneous datatype support for non-SAP ASE datatypes that do not map directly to Replication Server datatypes (or SAP ASE datatypes), which must be translated to the appropriate datatypes for replication into the replicate database.

Components for Non-SAP ASE Support Installed with Replication Server

The components included in the Replication Server default installation are connection profiles that contain function-string classes and error classes for each actively supported database, datatypes class, Replication Server native datatype literal descriptor row in the RSSD `rs_datatype` table, and Replication Server datatype translation engine.

Replication Server includes connection profiles that you use to connect to non-SAP ASE data servers. Connection profiles contain or install these components:

- Datatype definitions – assign a unique datatype ID to each datatype, and describe the attributes of each non-SAP ASE datatype, such as delimiters, length, scale, precision, minimum and maximum values, how it is represented using native Replication Server datatypes. Replication Server uses datatype definitions to:
 - Identify datatypes
 - Convert datatypes into native datatypes for internal handling (if necessary)
 - Translate datatypes
- Replication Server support objects in the replicate database – Replication Server relies on a replicate database to maintain some of the operational data that Replication Server needs to replicate to that database.

Non-SAP ASE support accommodates the Replication Server replicate database requirements by creating two tables in the replicate database:

- `rs_info` – stores the character set and sort order used by the database. The Replication Server maintenance user ID must have select permission on this table.
- `rs_lastcommit` – is used by the replicate Replication Server to record information about the most recent replicated operations committed in the replicate database. Because this table is both read and updated by the replicate Replication Server, the Replication Server maintenance user ID must have both insert and update permission on this table.
- Replication Server function strings – allow users to customize the database operations sent by the replicate Replication Server to the replicate database. Non-SAP ASE support uses function strings to replace invocations of stored procedures and certain database commands that the replicate Replication Server sends to the replicate database. The function strings required to support connections to non-SAP ASE data servers are installed in the RSSD of the replicate Replication Server. For functions-string classes, see *Customize Database Operations* in the *Administration Guide Volume 2* and for datatype classes, see *Topics* in the *Reference Manual*.
- Class-level translations for non-SAP ASE datatypes – default datatype-to-datatype mappings, provided by connection profiles. Connection profiles provide a function-string class for each supported database server. The class-level translations are specific to each function-string class that supports a non-SAP replicate database.

Setting Up and Configuring Non-SAP ASE Support

Set up and configure non-SAP ASE support in Replication Server.

1. Create a replicate database connection – use the **using profile** clause with the **create connection** command to create a connection to a non-SAP ASE replicate database. See **create connection using profile** in the *Reference Manual*.
2. Create replicate definitions – see *Create Replication Definitions* in the *Administration Guide Volume 1*.
3. Mark tables for replication – see *Mark Tables for Replication* in the *Administration Guide Volume 1*.
4. Create subscriptions – see *Manage Subscriptions* in the *Administration Guide Volume 1*.

Once you complete all these steps, you can begin replicating transactions to a non-SAP ASE replicate database. See the *Heterogeneous Replication Guide* for information specific to supported non-SAP ASE databases.

Sample Replication System

The sample replication system replicates the changes made to two tables in the `pubs2` database from one Adaptive Server to another Adaptive Server.

You can set up this example as an introduction to using Replication Server or to test your replication system installation.

Note: The application architecture for this example is similar to the decision-support model described in the *Design Guide*.

The goal of this replication system is to replicate all changes made to the `authors` and `titles` tables in the `pubs2` database in one Adaptive Server to the same tables in the `pubs2` database in another Adaptive Server.

The replication system has two Adaptive Servers:

- A primary Adaptive Server, named `TOKYO_DS`, holds the RSSD for the primary Replication Server and the primary `pubs2` database.
- The replicate Adaptive Server, named `SYDNEY_DS`, holds the RSSD for the replicate Replication Server and the replicate `pubs2` database.

The replication system has two Replication Servers:

- A primary Replication Server named `TOKYO_RS` manages the primary `pubs2` database.
- A replicate Replication Server named `SYDNEY_RS` manages the replicate `pubs2` database.

The replication system has two RepAgents, which are the Replication Agents for Adaptive Server:

- A RepAgent for the primary RSSD runs in the ASE `TOKYO_RSSD` and transfers the RSSD log to the primary Replication Server.
- A RepAgent for the primary `pubs2` database runs in the ASE `TOKYO_PUBS2` and transfers the `pubs2` log to the primary Replication Server.

Setting Up the Sample Replication System

Use the Adaptive Servers or Replication Servers that you have already installed in setting up the sample replication system. Substitute the names of your servers throughout the instructions.

Prerequisites

Choose the machines where each server will execute and locate disk space for Adaptive Server database devices and Replication Server partitions. See the *Installation Guide* for disk space and system requirements.

Task

1. Install the primary Adaptive Server, TOKYO_DS.
2. Install the replicate Adaptive Server, SYDNEY_DS.
3. Install the pubs2 database in the primary Adaptive Server:

```
isql -Usa -Psa_passwd -STOKYO_DS < \
%SYBASE%\%SYBASE_ASE%\scripts\installpubs2
```
4. Install the pubs2 database in the replicate Adaptive Server:

```
isql -Usa -Psa_passwd -SSYDNEY_DS < \
%SYBASE%\%SYBASE_ASE%\scripts\installpubs2
```
5. Complete the Replication Server Installation worksheet for the primary Replication Server (TOKYO_RS).
 - Create the RSSD for TOKYO_RS in the TOKYO_DS Adaptive Server.
 - The RSSD requires a RepAgent.
6. Complete the Replication Server Installation worksheet for the replicate Replication Server (SYDNEY_RS).
 - Create the RSSD for SYDNEY_RS in the SYDNEY_DS Adaptive Server.
 - The RSSD does not require a RepAgent.
7. Complete the Database Setup worksheet for the primary pubs2 database.
 - The database is in Adaptive Server TOKYO_DS.
 - The database is managed by the TOKYO_RS Replication Server.
 - The database requires a RepAgent.
8. Complete the Database Setup worksheet for the replicate pubs2 database.
 - The database is in Adaptive Server SYDNEY_DS.
 - The database is managed by the SYDNEY_RS Replication Server.
 - The database does not require a RepAgent.

9. Log in to the machine where the primary Replication Server will execute. Run **rs_init** and install Replication Server TOKYO_RS using the worksheet you completed in step 5.
10. Log in to the machine where you installed the primary Replication Server. Run **rs_init** and add the primary pubs2 database to the replication system using the worksheet you completed in step 7.
11. Log in to the machine where the replicate Replication Server will execute. Run **rs_init** and install Replication Server SYDNEY_RS using the worksheet you completed in step 6.
12. Log in to the machine where you installed the replicate Replication Server. Run **rs_init** and add the replicate pubs2 database to the replication system using the worksheet you completed in step 8.

See also

- *Replication Server Installation Worksheet Sample* on page 10
- *Database Setup Worksheet Sample* on page 27

Establishing the Sample Replication

Create a route from the primary Replication Server to the replicate Replication Server to establish a sample replication.

1. Log in to the primary Replication Server as “sa”:

```
isql -Usa -STOKYO_RS
```

2. Enter the **create route** command:

```
create route to SYDNEY_RS
set username SYDNEY_RS_rsi
set password SYDNEY_RS_rsi_ps
go
```

Note: Find the user name and password for the **create route** command in the “Remote site connections” section of the Replication Server Installation Worksheet for the replicate Replication Server.

3. Create a login account in the primary Adaptive Server for the user who will create the replication definitions and subscriptions. In this example, the login name is “repsys.” Add the user to the pubs2 databases and grant the user select permissions for the tables to replicate.

```
isql -Usa -STOKYO_DS
sp_addlogin repsys, repsys_ps
go

use pubs2
go

sp_adduser repsys
go
```

```
grant select on authors to repsys
grant select on titles to repsys
go
quit
```

4. Add the “repsys” user to the two Replication Servers and grant create object permission to the user. The “repsys” user must have the same login name and password in the two Replication Servers and the primary Adaptive Server:

```
isql -Usa -STOKYO_RS
create user repsys
set password repsys_ps
go

grant create object to repsys
go
quit

isql -Usa -SSYDNEY_RS
create user repsys
set password repsys_ps
go

grant create object to repsys
go
quit
```

5. Create replication definitions for the authors and titles tables:

```
isql -Urepsys -Prepsys_ps -STOKYO_RS
create replication definition authors
with primary at TOKYO_DS.pubs2
with all tables named 'authors'
(
    au_id varchar(11),
    au_lname varchar(40),
    au_fname varchar(20),
    phone char(12),
    address varchar(40),
    city varchar(20),
    state char(2),
    country varchar(12),
    postalcode char(10)
)
primary key (au_id)
searchable columns (state, postalcode)
go
create replication definition titles
with primary at TOKYO_DS.pubs2
with all tables named 'titles'
(
    title_id varchar(6),
    title varchar(80),
    type char(12),
    pub_id char(4),
    price money,
    advance money,
```

```

        total_sales int,
        notes varchar(200),
        pubdate datetime,
        contract bit
    )
    primary key (title_id)
    searchable columns (type, pub_id)
go

```

6. Set replication to on for the authors and titles tables in the primary pubs2 database:

```

isql -Usa -STOKYO_DS
use pubs2
go

sp_setreptable authors, true
go

sp_setreptable titles, true
go

```

7. In the replicate pubs2 database, grant permissions on the authors and titles tables to the maintenance user:

```

isql -Usa -SSYDNEY_DS
use pubs2
go

grant select, insert, delete, update
on authors to pubs2_maint
grant select, insert, delete, update
on titles to pubs2_maint
go

```

Note: You can find the maintenance user in the “Database information” section of the Database setup worksheet you completed for the replicate pubs2 database.

8. In the replicate Replication Server, create subscriptions for the authors and titles tables:

```

isql -Urepsys -Prepsys_ps -SSYDNEY_RS
create subscription authors_sub
for authors
with replicate at SYDNEY_DS.pubs2
without materialization
go

create subscription titles_sub
for titles
with replicate at SYDNEY_DS.pubs2
without materialization
go

```

Note: Since there is already data at the replicate database, this example uses the **create subscription** with the **without materialization** option. For other methods, see *Replication Server Commands* in the *Reference Manual*.

Troubleshooting and Testing the Replication System

Troubleshoot and test replication for the `authors` and `titles` tables once it has been established.

If you created a subscription with materialization, log in to the replicate `pubs2` database and select the data from the `titles` and `authors` tables:

- If the rows exist in the replicate tables – it indicates that the subscriptions were created and materialized successfully.
- If the rows do not appear in the replicate tables – execute **check subscription** in each of the Replication Servers:

```
check subscription authors_sub
for authors
with replicate at SYDNEY_DS.pubs2
```

check subscription reports the status of the subscription. If the status is not “valid” in both the primary and replicate Replication Servers, then either the subscription has not finished materializing or an error has occurred.

The `authors` and `titles` tables are very small. If there are no configuration problems, they should not take more than a few seconds to materialize. If you do not see the results quickly, you can assume that an error has occurred.

If you created a subscription without materialization or the subscription has completed materializing, log in to the primary `pubs2` database and execute some **insert**, **update**, and **delete** SQL commands against the `authors` and `titles` tables. Then log in to the replicate `pubs2` database and verify that your modifications appear in the replicate tables. If the rows do not appear in the replicate tables:

- Execute **check subscription** in each of the Replication Servers.
- Check the error logs for the primary and replicate Replication Servers for error messages. The most common problems are:
 - Failure to log in to the primary Adaptive Server. The user who creates the subscription in the replicate Replication Server must have the same login name and password in the primary Adaptive Server and the primary Replication Server.
 - Missing permissions in the primary database. The user who creates the subscription must be a user in the primary database and must have select permission in the primary table.
 - Missing permissions in the replicate database. The maintenance user must have select, insert, update, and delete permissions on the tables in the replicate database.

- A Replication Server or Adaptive Server has stopped running. Try logging in to each of the servers. Restart any servers that are not running.

Index

A

- active databases, warm standby applications 30
- Adaptive Server
 - updating system catalog after upgrade from 15.7 to 15.7 ESD #2 and later 79
- Adaptive Server Enterprise
 - for RSSD 21
 - RSSD device information 23
 - upgrading 76
 - upgrading user database in replication system 68
- Adaptive Server system catalog
 - updating after upgrade from 15.7 to 15.7 ESD #2 and later 79
- admin version, "route" 73
- alter user command, specifying passwords with 91
- altering passwords 92
- attribute format for resource files 35

B

- backing up RSSD 76
- backup configuration file 91

C

- certauth utility 96
- certificate authority 96
- certpk12 utility 96
- certreq utility 96
- changing encrypted password 92
- character set
 - Replication Server 15
- character sets
 - Chinese 15
 - cp437 15
 - cp850 15
 - deckanji 15
 - eucgb 15
 - eucjis 15
 - eucksc 15
 - German 15
 - iso_1 15
 - iso15 15

- Japanese 15
- Korean 15
- mac 15
- Replication Server 15
- roman8 15
- roman9 15
- sjis 15
- Spanish 15
- utf8 15
- command line options in rs_init 45
- commands
 - alter user 91
 - create replication definition 109
 - create route 109
 - create subscription 109
 - create user 109
 - sysadmin site_version 72
- communication protocol
 - TCP, Transmission Control Protocol 97
- components
 - non-SAP ASE support 105
- configuration files
 - backup 91
 - Replication Server 14
- configuring
 - non-SAP ASE support 106
 - Replication Server 47
- connection profiles 105
- connections
 - information syntax 18
 - physical 30
 - remote site 26, 52
- conventions
 - style 1
 - syntax 1
- copying resource file templates 34
- create replication definition command example 108
- create route command example 109
- create subscription command example 109
- create user command
 - example 109
 - specifying passwords with 91
- creating
 - identity file 97

Index

- partitions 52
- resource file from templates 34

D

- database setup worksheet 27
 - completing 27
 - template 27
- databases
 - adding to replication system 52
 - log, for RSSD 21
 - primary 5
 - replicate 5
 - requiring warm standby 9
- dates, formatting 16
- deckanji character set 15
- definitions
 - installation directory 13
 - release directory 13
 - runserver 102
- descriptions
 - ERSSD 6
 - rs_init resource file 34
 - RSSD 6
- device information, Adaptive Server Enterprise for RSSD 23
- directory services 48
- disabling
 - secondary truncation point 79
 - SSL 98
- disk partitions 7, 25
- distributor thread
 - restarting 75
- downgr.rs resource file template 35
- downgrade
 - existing directories 89
- downgrading 81
 - restrictions 83
- draining
 - transaction logs for primary database 77
- dsedit, editing interfaces file with 48

E

- editing
 - interfaces file with dsedit 48
 - resource files 34
- eers.rs resource file template 35
- enabling password encryption for Replication Server 91

- encrypted password
 - adding to the configuration file 97
 - changing 92
 - ERSSD 92
- encryption, password 14
- entering RSSD or ERSSD information 49
- error log in Replication Server 14
- ERSSD
 - backing up 76
 - described 6
 - encrypted password 92
 - entering information 50
 - SQL Anywhere database 23
 - system database 23
 - upgrades 61
 - upgrading 62, 64
- executing rs_init with resource files 34
- existing directories
 - downgrade to 89
 - upgrade and downgrade to 87
 - upgrade to 87

F

- files
 - identity for SSL 97
 - Replication Server configuration file 14
 - Replication Server error log 14
 - resource file templates 35
 - runserver 102
 - sql.ini 9
- French character sets 15

G

- gb18030 character set 15
- German character sets 15

H

- heterogeneous data servers 105

I

- ID Server
 - information screen 49
 - installing 14
 - login name 7
 - name 19

- password 19
- requirements 7
- user 19
- identity file
 - creating 97
 - for SSL 97
- install worksheet
 - Replication Server 10
- install.rs resource file template 35
- installation directory 92
- installation worksheet 9
- interactive command keys 34
- interactive mode in rs_init 33
- interfaces file
 - editing 48, 83
 - modifying 48
- IPX/SPX 18, 29
- iso_1 character set 15
- iso15 character set 15
- isql program 83, 103

J

- Japanese character sets 15

K

- Korean character sets 15

L

- languages for Replication Server 16
- list of values, resource file
 - attributes 35
- listener service 18, 29
- log files and rs_init 45
- logical connections 27
- logical DB setup 53
- login name
 - Replication Server 26
- login names
 - ID Server 7

M

- mac character set 15
- maintenance password 30
- maintenance user
 - permissions 30

- RSSD, for 21
- memory, start with sufficient 102
- menus in rs_init 9
- migrating
 - 32-bit to 64-bit 83
- mixed-version requirements 57
- modifying
 - interfaces file 48
- multiple release directories 13
 - interfaces file and 13

N

- name of servers 14
- named pipes 18, 29
- network drivers 18, 29
- network-based security 48
- non-SAP ASE support
 - components 105
 - configuring 106
 - connection profiles 105
 - datatype definitions 105
 - Replication Server class-level translations for
 - non-SAP ASE datatypes 105
 - Replication Server function strings 105
 - Replication Server support objects 105
 - setting up 106
- non-SAP ASE support features 105
- NULL default values, resource file 35
- NWLink IPX/SPX 18, 29

O

- Oracle
 - upgrading user database in replication system
 - 70

P

- partitions
 - creating 52
 - Replication Server 7, 25
- password administration in rs_init 91
- password encryption
 - enabling for Replication Server 14, 91
- passwords
 - Adaptive Server "sa" user 21
 - altering 92
 - changing encrypted 92

Index

- ERSSD 92
 - maintenance user 30
 - primary user 21
 - specifying with alter user command 91
 - specifying with create user command 91
- permissions for maintenance user 30
- physical connections 30
- planning
 - replication system 5
- planning replication systems
 - required Replication Servers 6
- preparing
 - Replication Server installation 5
- preparing to start rs_init 33
- preparing to upgrade 58
- primary data 5
- primary data and RepAgent 8
- primary database
 - draining transaction logs 77
- primary user for RSSD 21

Q

- quiescing Replication Server 60
- quoted identifiers
 - updating Adaptive Server system catalog 79

R

- raw disk partitions, protecting start sectors 25
- RCL commands
 - shutdown command 103
- release directory
 - choosing 13
 - defined 13
 - environment variables and 13
 - using more than one 13
- remote site connections 26, 52
 - for Replication Server 26
- RepAgent
 - database information 32
 - primary data and 8
 - replicated stored procedure execution and 8
 - RSSD and 8
 - warm standby applications and 8
- replicate data 5
- replicated database
 - restoring 80
- replicated stored procedure execution
 - RepAgent and 8

- replication
 - restoring after upgrade 80
- Replication Agent
 - database information 27
 - stopping 60
- Replication Server
 - configuration file 14
 - configuring 47
 - enabling SSL 98
 - entering information 48
 - error log 14
 - information 29
 - install worksheet 10
 - interfaces information 17
 - language 16
 - login name 26
 - name 14
 - partitions 25, 52
 - password encryption, enabling 91
 - quiescing 60
 - remote site connections 26
 - resource templates 35
 - security information 17
 - shutting down 103
 - site version 72
 - site version, setting 72
 - sort order 17
 - stopping 103
 - upgrading 59
- Replication Server ID, starting 19
- Replication Server installation worksheet 9
- Replication Server System Database 6
- replication systems
 - adding a database 52
 - planning 5
 - sample 107
 - testing 112
 - troubleshooting 112
- report routes 73
- reserved words 9
- resource file templates
 - downgr.rs 35
 - eers.rs 35
 - install.rs 35
 - setupdb.rs 35
 - upgr.rs 35
 - upgrdb.rs 35
 - uprscf.rs 35

- resource files
 - attribute format 35
 - copying templates 34
 - creating 34
 - editing 34
 - preparing for rs_init 34
 - sample 37
 - templates 35
 - restarting
 - distributor thread 75
 - restoring
 - replicated database 80
 - replication after upgrade 80
 - restrictions
 - downgrading 83
 - roman8 character set 15
 - roman9 character set 15
 - routes
 - creating 109
 - reporting routes to upgrade 73
 - upgrading 73
 - rs_get_charset system function 105
 - rs_get_lastcommit system function 105
 - rs_info system table 105
 - rs_init
 - command line options 45
 - commands, list of 34
 - enter information 49
 - executing with resource files 34
 - interactive mode 33
 - log file 45
 - menus 9
 - online help 34
 - password administration 91
 - preparing for, with resource files 34
 - preparing to start 33
 - quitting 34
 - resource file 34
 - resource file, description of 34
 - starting 33
 - usage 33
 - version number 45
 - writing to a resource file 34
 - rs_lastcommit system table 105
 - RSSD
 - Adaptive Server Enterprise device information 23
 - backing up 76
 - described 6
 - device 23, 25, 51
 - draining transactions manually 78
 - enter information 51
 - log device 23
 - maintenance user 21
 - primary user 21
 - RepAgent and 8
 - screen 51
 - upgrades 61
 - upgrading 59, 62, 64
 - using Adaptive Server Enterprise 21
 - runserver
 - ulimit option 102
- ## S
- sample replication system
 - establishing 109
 - setting up 108
 - troubleshooting 112
 - sample resource files 37
 - secondary truncation point
 - disabling 79
 - Secure Sockets Layer 95
 - security information
 - Replication Server 17
 - server names 13
 - servers
 - configuring to start at system start-up 102
 - names 13
 - Services Manager
 - using, to start and stop Replication Server 101
 - setting basic configurations for Replication Server 47
 - setting up
 - non-SAP ASE support 106
 - sample replication system 108
 - SSL services 95
 - setupdb.rs resource file template 35
 - shutdown RCL command 103
 - shutting down
 - Replication Server 103
 - site connections, remote 26, 52
 - site version
 - Replication Server 72
 - setting for Replication Server 72
 - site version setting 71
 - site version, setting for Replication Server 72
 - sjisi character set 15

Index

- software version 71
- sort order
 - Replication Server 17
- sort order for Replication Server 14
- sp_setreptable system procedure example 109
- Spanish character sets 15
- SQL Anywhere
 - used for ERSSD 6
- SQL Anywhere and ERSSD 23
- sql.ini interfaces file 9
- SSL 95
 - certificate authority 96
 - disabling on Replication Server 98
 - enabling on Replication Server 98
 - identity file, creating 97
 - master and query entries 97
 - setting up services 95
- starting
 - database ID 19
 - Replication Server ID 19
 - rs_init 33
 - sessions with resource files 34
 - using Services Manager 101
- stopping
 - Replication Agent 60
 - rs_init 34
 - using Services Manager 101
- suspending
 - replication 77
 - transaction activity 77
- SYBASE environment variable 13, 62, 64
- sysadmin site_version command 72
- sysadmin upgrade route 73
- system catalog
 - updating after Adaptive Server upgrade from 15.7 to 15.7ESD #2 and later 79
- system version 71

T

- TCP/IP 18
- templates
 - downgr.rs resource file 35
 - eers.rs resource file 35
 - resource files, copying 34
- transaction logs for primary database
 - draining 77
- transactions, asynchronous 8
- troubleshooting
 - sample replication system 112

U

- ulimit option of runserver 102
- UNCHANGED value, resource file attributes 35
- upgr.rs resource file template 35
- upgrade
 - existing directories 87
- upgrade and downgrade
 - existing directories 87
- upgrade failure 67
- upgrade method 61
- upgrades
 - RSSD and ERSSD 61
 - user databases 61
- upgrading
 - Adaptive Server in a replication system 76
 - ERSSD 62, 64
 - fails 62, 64
 - preparing 58
 - routes 73
 - RSSD 62, 64
- upgrdb.rs resource file template 35
- uprscf.rs resource file template 35
- USE_DEFAULT value, resource file attributes 35
- user databases
 - upgrading, in replication system 68, 70
- using
 - rs_init 33
- utf8 character set 15
- utilities
 - certauth 96
 - certpk12 96
 - certreq 96
 - rs_init 33

V

- version number
 - Replication Server 72
 - rs_init 45
- version restrictions, when upgrading 57

W

- warm standby
 - active database 30
 - adding active or standby database 53

- dump marker for initializing standby database
 - 30
- logical connection information 30
- RepAgent and 8
 - standby database 30
- Windows socket 18, 29
- worksheets
 - database setup 27
 - Replication Server installation 9, 10
 - Replication Server interfaces information 18, 29

