Release Bulletin EAServer 6.2 for Linux

Document ID: DC37793-01-0620-01

Last revised: June 23, 2008

Торіс	Page
1. Accessing current release bulletin information	2
2. Product summary	2
2.1 Version contents	3
3. Special upgrade instructions	3
4. Changed functionality in this version	4
5. Known issues	4
5.1 Security risk	4
5.2 Upgrading ignores existing listeners	4
5.3 Failure to obtain correct license file	4
5.4 Log files in Eclipse plug-in Management Console	5
5.5 Ant version 1.6.5	5
5.6 Obsolete HTTP server properties	5
5.7 Configuring a database type	6
5.8 Data source contents	6
5.9 SQL Anywhere database issues	7
5.10 Adaptive Server Enterprise 12.5.x	7
5.11 PowerBuilder issue	8
5.12 Migration tool issue	8
5.13 Web Services Toolkit issues	8
5.14 Miscellaneous issues	9
6. Documentation updates and clarifications	9
6.1 Automated Configuration Guide	10
6.2 CORBA Components Guide	13
6.3 Enterprise JavaBeans User's Guide	15
6.4 New Features Guide	15
6.5 Security Administration and Programming Guide	16
6.6 System Administration Guide	16

Copyright 2008 by Sybase, Inc. All rights reserved. Sybase trademarks can be viewed at the Sybase trademarks page

at http://www.sybase.com/detail?id=1011207. Sybase and the marks listed are trademarks of Sybase, Inc. (1) indicates registration in the United States of America. Java and all Java-based marks are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. Unicode and the Unicode Logo are registered trademarks of Unicode, Inc. All other company and product names mentioned may be trademarks of the respective companies with which they are associated.

Торіс	Page
6.7 Troubleshooting Guide	18
6.8 Web Services Toolkit User's Guide	20
7. Technical support	20
8. Other sources of information	20
8.1 Sybase certifications on the Web	21
8.2 Sybase EBFs and software maintenance	22
9. Accessibility features	22

1. Accessing current release bulletin information

A more recent version of this release bulletin may be available on the Web. To check for critical product or document information added after the product release, use the Sybase® Product Manuals Web site.

* Accessing release bulletins at the Sybase Product Manuals Web site

- 1 Go to Product Manuals at http://www.sybase.com/support/manuals/.
- 2 Select a product and language and click Go.
- 3 Select a product version from the Document Set list.
- 4 Select the Release Bulletins link.
- 5 From the list of individual documents, select the link to the release bulletin for your platform. You can either download the PDF version or browse the document online.

2. Product summary

Enclosed is Sybase EAServer version 6.2, which is compatible with these platform and operating system configurations:

- RedHat Advanced Server 4.0, Kernel version 2.6.9-22.ELsmp
- SuSE Professional 9.0, Kernel version 2.6.5-7.97-smp
- SuSE Linux Enterprise Server 10.0, Kernel version 2.6.16.21-0.8-smp

2.1 Version contents

Enclosed is Sybase EAServer version 6.2, Build 62012. You may have a later build number if you have installed ESD patches for this release. If so, the cover letters provided with each patch contain the build number and additional documentation.

The EAServer 6.2 software is provided on a DVD, rather than a CD.

Table 1 describes the products that EAServer 6.2 supports.

Product	Supported versions/builds
Adaptive Server® Enterprise	12.5.4 and 15.2
C++ compiler	GNU GCC 3.x
Eclipse	3.2.1
Java Development Kits (JDK):	Versions:
1.5	1.5.0_12
1.6	1.6.0_02
Jetty	6.1
Oracle client	9.2.01 and 10g
PowerBuilder® Virtual Machine (PBVM)	10.5.1 and 11.0
Web server redirector plug-ins:	Versions:
Apache	2.0.55
Sun Java System	6.1
SQL Anywhere®	10.0.1
Web browser	Firefox 1.5

3. Special upgrade instructions

You can install EAServer 6.2 as a new installations, or as an upgrade to an EAServer 6.0, 6.0.1, 6.0.2, or 6.1 installation.

The EAServer migration tool enables you to migrate a subset of entity types from a 5.x repository to the 6.2 repository, saving time by scanning only those entity types in which you are interested. For details, see these books on the SyBooks Online Web site:

• The EAServer Migration Guide at:

 $http://infocenter.sybase.com/help/index.jsp?topic=/com.sybase.dc00485_0600/html/easmig/title.htm/lineasm$

• The EAServer 6.0.2 New Features Guide at:

http://infocenter.sybase.com/help/index.jsp?topic=/com.sybase.dc38032_0602/html/new602/title.htm

"Migration tool issue" on page 8 in this release bulletin describes problems that are known to occur during migration.

4. Changed functionality in this version

The *EAServer 6.2 New Features Guide* describes features added in this version. You can view this book on the SyBooks Online Web site at http://infocenter.sybase.com/help/index.jsp. Browse to the EAServer 6.2 collection, then select this title.

5. Known issues

This section describes known problems in this version of EAServer.

5.1 Security risk

(CR #434293) Do not use HTTP to connect to the Management Console; the administrative user ID and password are passed in plain-text format during the login process, thus posing a security risk.

Workaround: Use HTTPS to log in to the Management Console. To use HTTPS, you first need to obtain a certificate. If you use the sample (test) certificate that is included with EAServer, anyone with EAServer 6.0 has access to your private (test) key. Therefore, Sybase recommends that you use your own certificate.

5.2 Upgrading ignores existing listeners

(CR #481946) When you upgrade EAServer, the installer does not detect the current server listeners, and uses the default ports.

5.3 Failure to obtain correct license file

(CR #430720) If you start EAServer using a remote desktop connection, the server does not obtain the correct license file.

Workaround: To enable the server to obtain the correct license file when you connect from a remote desktop, use a Virtual Network Computing (VNC) system, such as VMWare or RealVNC.

5.4 Log files in Eclipse plug-in Management Console

(CR #497641) The Eclipse plug-in Management Console does not allow you to view the log files remotely.

5.5 Ant version 1.6.5

(CR #439259) EAServer 6.2 is certified to run with Ant version 1.6.5, which is installed with EAServer. If another version of Ant is installed on the same machine, problems can occur when you run EAServer, because the configuration files that Ant uses for setup may be incompatible with EAServer 6.2.

Workaround:

- 1 In the EAServer *bin* subdirectory, create a file named *set-ant-opts-local.sh*.
- 2 To prevent Ant from using incompatible setup information, enter the following lines:

DJC_ANT_ARGS=--noconfig export DJC_ANT_ARGS

To pass command line options to Ant, set the value of DJC_ANT_ARGS to the list of options; for example:

DJC_ANT_ARGS= -debug -logfile Ant.log export DJC_ANT_ARGS

Save and close set-ant-opts-local.sh.

3 Restart the server.

5.6 Obsolete HTTP server properties

(CR #452369) Beginning in version 6.2, EAServer no longer supports these HTTP properties:

- httpUseCustomGetServerInfo
- httpProxyProtocol

- httpProxyPort
- httpGetServerInfoFrom

Instead, EAServer reads these HTTP header fields:

- host to determine the host and port the client used to connect.
- sybaseredirectorheader to determine the protocol that was used to connect to a Web redirector.

If you call any of the HttpRequest methods, getServerName, getServerPort, or getProtocol, the values are retrieved from the browser. This is the same behavior that was achieved by setting httpGetServerInfoFrom to "source" in versions of EAServer earlier than 6.2.

5.7 Configuring a database type

If you specify values for both the dataSourceClass and driverClass properties when you configure a database type, the system uses the class defined by dataSourceClass, and ignores these properties:

- driverClass
- databaseURL, because it is used only by the driver class

5.8 Data source contents

(CR #496672) When you select the Data Sources folder on the left hand side of the Management Console, data source entries do not appear on the right side of the window. Other contents such as Welcome frame, Context Menu frame, and so forth appear on the right window.

Workaround: Set the Management Console as a trusted site. From the Internet browser:

- 1 Select Tools | Internet Options.
- 2 Select the Security tab.
- 3 Select Trusted sites and click Sites.
- 4 Click Add.

5.9 SQL Anywhere database issues

When you upgrade to EAServer 6.2, Adaptive Server® Anywhere (ASA) version 9.0.2 is upgraded to version 10.0, and the name of the database server changes from ASA to SQL Anywhere.

5.9.1 Database must be running before starting server

(CR #482776) If you are using a JCM_ODBCU SQL Anywhere 10 data source, the database must be running before you start the server, or the server may crash.

Workaround: You can either:

- Set the databaseStartCommand and databaseStopCommand properties, or
- Start the database manually.

5.9.2 DBProxy client may crash EAServer

(CR #471417) Connecting to EAServer from a DBProxy client may cause EAServer to crash. This is a jConnect[™] bug.

Workaround: To avoid this problem, either:

- Run the jConnect script *jcatalog.sql*, or
- Install a version of SQL Anywhere later than 10.0.

5.9.3 ODBC driver version

(CR #470030) The ODBC driver that you use with EAServer must be either the driver packaged with EAServer or a later version.

5.10 Adaptive Server Enterprise 12.5.x

(CR #447543) If you are using Adaptive Server Enterprise (ASE) version 12.5.*x* with EAServer, you may see this error:

"SELECT INTO command not allowed within multi-statement transaction"

Workaround: On the machine where Adaptive Server is installed, run:

\$DJC_HOME/extras/jconnect-6.05/sp/sql_server12.5.sql

5.11 PowerBuilder issue

(CR #442234) If you migrate a PowerBuilder Web application from EAServer version 5.*x* to 6.*x*, the migration tool replaces the EAServer 5.*x* profile values that are defined in *WEB-INF/classes/jaguar.properties* with the EAServer 6.*x* values. When you run the migration tool, if the value that you specify for the 5.*x* host is different from the value you initially defined in the PowerBuilder IDE, the profile properties are not migrated correctly. For example, if you initially defined the 5.*x* host as "myhost," specifying either "myhost.sybase.com" or the machine's IP address causes the migration to fail.

Workaround: When you run the migration tool, set the EAServer 5.*x* host name to the same value that you initially defined using the PowerBuilder IDE.

5.12 Migration tool issue

(CR #437181) When you are migrating EAServer entities from version 5.*x* to version 6.2, the migrate tool does not migrate *sql.ini* content for Open ClientTM Client-LibraryTM connections.

Workaround: Manually copy Open Client Client-Library connection information from the 5.*x* version of *sql.ini* to the 6.2 version.

5.13 Web Services Toolkit issues

5.13.1 Activating and deactivating Web services

(CR #448806) The wstool commands for activating and deactivating Web services, wstool activate and wstool deactivate, do not work.

5.13.2 Datatype mapping

(CR #449109) In EAServer 6.0, the Web services datatype-mapping version is set to 1.3, so xsd:short may be mapped to either the short or unsignedByte Java datatype. This causes some Web service tests to fail.

Workaround: Set the datatype-mapping version to 1.2, so xsd:short will always be mapped to the short datatype:

- 1 Start EAServer, and connect to the server using the Management Console.
- 2 Expand the Servers folder, and select the server.

- 3 On the General tab, find the WebServices Type Mapping Version field. The default value is 1.3.
- 4 Change the value to 1.2, and click Save.

5.13.3 Apache Scout

(CR #448380) The Apache Scout client method BusinessLifeCycleManager.saveAssociations fails, and a null pointer exception is returned.

5.13.4 Web services display in random order

(CR #422161) Selecting the Management Console options to display Web services either alphabetically or in descending order by date fail. Web services display in random order.

5.14 Miscellaneous issues

5.14.1 Permission required to use JIT data sources

(CR #465348) You can use a JIT (just-in-time) data source to access a database only if you have permission to create tables in the database.

5.14.2 SSLServiceProvider.getGlobalProperty

(CR #436638) The SSLServiceProvider method for checking the status of FIPS, SSLServiceProvider.getGlobalProperty("fips140"), has not been implemented in EAServer 6.2.

6. Documentation updates and clarifications

This section contains updates and clarifications for the EAServer product manuals.

6.1 Automated Configuration Guide

6.1.1 Chapter 3, "Using Scheduled Tasks"

(CR #477285) "Predefined tasks" does not include CleanupPBCookies task, which you can schedule to remove unwanted PowerBuilder cookies from your machine.

6.1.2 Chapter 4, "Creating Service Components"

(CR #500334) In Table 4-1 of "Service component entity properties," the Component property that specifies how to define the remote interface for a service component is incorrect. The corrected text is:

ejb.components.mypackage.MyComponentRemote

or, for a local interface for a service component:

ejb.components.mypackage.MyComponentLocal

Writing a Java class as a service component

This procedure shows how to write a Java class as a service component using these methods:

- start()
- run()
- stop()
- 1 Use a text editor to write a Java file that includes the three Java methods. For example:

```
package serviceTest;
public class oneService {
    boolean bstop = false;
    public void start()
    {
        System.out.println("oneService start!");
        bstop = false;
}
    public void run()
    {
        while(!bstop)
        {
        System.out.println("oneService runing...");
    }
}
```

}

```
try {
                          Thread.sleep(1000);
            }catch (InterruptedException e) {
              }
      }
}
 public void stop()
       bstop = true;
       System.out.println("oneService stop!");
 }
           2
                Save and compile this Java file to a class file.
           3
                Create a JAR file for the class file.
           4
                Place the JAR file in $EAServer/lib/ext/.
           5
                Log in to the Management Console.
           6
                Select the Service Components folder, right-click, and select Add.
                а
                    Type the name of the service component, for example, oneservice.
                b
                    Choose Finish.
           7
                Select oneservice from the Service Components subfolders.
                    Type the name of the component in the Component property field on
                а
                    the right side of the Management Console window. For example,
                    serviceTest.oneService.
                b
                    Select the Start Before Binding check box.
                    Select Apply to save the new settings.
                с
           8
                Select the Servers folder.
                    Select the server where EAServer is running. For example, zeus-
                а
                    deskwxp.
                b
                    Select the Services tab.
                с
                    Select the service component that you have just created, for example,
                    oneservice from the list.
                    Select Apply to save the new settings.
                d
           9
                Restart EAServer.
```

When you run the service component, the log file or console displays these messages:

```
oneService start!
```

```
oneService runing...",
```

If you stop EAServer, the log file or console displays this message:

```
oneService stop!"
```

6.1.3 Chapter 6, "Using jagtool and jagant"

Obsolete jagtool commands

(CR #465796 and #447432) These jagtool commands are documented in the *Automated Configuration Guide*, but the commands are not supported in EAServer 6.0 and later:

- configure
- export
- exportconfig
- grantroleauth
- mergeprops
- props
- removeroleauth
- set_props

Generating stubs

(CR #462838) To generate stubs for a package or component, you can use the jagtool gen_stubs command. See the *Automated Configuration Guide* for more information about jagtool commands.

gen_stubs [-javastubs true|false] [-cppstubs true|false] [-javastubjarname *file-name*] [-javastubcodebase *path*] [-cppstubcodebase *path*] [-compilejavastubs true|false] [-verbose true|false] *entity*

Option	Description
javastubs	Whether to generate Java stubs; the default is true.
cppstubs	Whether to generate C++ stubs; the default is true.

Syntax

Option	Description
javastubjarname	If specified, the Java stubs are placed in a JAR file of the specified name. The file name must include the full path.
	If not specified, Java files are generated (the default).
javastubcodebase	The location of the code base for Java stubs; the default is \$DJC_HOME/genfiles/java/stubs.
cppstubcodebase	The location of the code base for C++ stubs; the default is <i>\$DJC_HOME/include</i> .
compilejavastubs	Whether to compile the generated Java stubs; the default is true.
verbose	Whether to produce verbose output while generating stubs; the default is false.
entity	The name of the entity for which stubs are being generated, in the form <i>EntityType:EntityName</i> , where <i>EntityType</i> is either "Package" or "Component."

Return values

Return value	Indicates
0	The command ran successfully; the result is true/success.
2	The command did not run successfully; an exception was thrown.

6.2 CORBA Components Guide

6.2.1 Chapter 4, "Managing CORBA Packages and Components"

(CR #437366) You cannot use hyphens ("-") in CORBA-component package names. CORBA-component packages are those that contain CORBA/C++, CORBA/Java, or PowerBuilder components.

6.2.2 Chapter 5, "Developing and Deploying PowerBuilder Components"

(CR #405138) You cannot use a hyphen ("-") in the name of a PowerBuilder NVO method or variable. EAServer wraps NVOs as EJBs, and Java does not support method or variable names that contain hyphens.

Accessing data sources

(CR #533120) When accessing these predefined EAServer data sources from PowerBuilder components, set the default transaction object (SQLCA) to use the appropriate database type as shown in Table 2 on page 14.

Database type	Description
JCM_Sybase	For ASE database:
	sqlca.dbms="SYJ"
JCM_Oracle or	Oracle database which corresponds to the
JCM_Oracle_Unicode	EAServer 5.x Oracle Call Interface (OCI) 9 and
	OCI10 native connection caches.
	sqlca.dbms="090", or
	sqlca.dbms="010"
JCM_Odbc or	For any databases using ODBC driver:
JCM_Odbc_Unicode	sqlca.dbms="ODBC"
JCM_non-JCM JDBC-	For any non-JCM JDBC-compliant database type:
compliant	sqlca.dbms ="JDBC"

Table	2:	Database	type
-------	----	----------	------

Implementing method-level security for PowerBuilder components

(CR #488947) You can implement method-level security after deploying PowerBuilder components. To implement method-level security for a PowerBuilder component:

- 1 Add two users. For example, "Pass" and "Fail".
- 2 Change the role of the user "Pass" to admin-role. You can also define and use your role.
- 3 Deploy the *final_test* NVO into EAServer from PowerBuilder.
- 4 Deploy *final_test.jar* into EAServer from Web console or command line.
- 5 Run PowerBuilder client and click the Pass and Fail buttons.
- 6 Modify the *\$EAServer/config/ejbjar-final_test-user.xml* file, as follows:

- 7 Run the Ant Refresh followed by the Run Ant Recompile from the Management Console.
- 8 Run the PowerBuilder client.

If the implementation is successful, the Pass button works.

If you click Fail, the NO_PERMISSION exception occurs.

6.3 Enterprise JavaBeans User's Guide

6.3.1 Chapter 3, "Developing EJB Clients"

(CR #498818) In the "Client runtime requirements" section, include this:

When using JDK 1.6, add this option in \$JAVA_HOME/bin/java:

-Dsun.lang.ClassLoader.allowArraySyntax=true

This is because the JDK 1.6 on the client side provides the allowArraySyntax option to convert array from the server result data.

If clients run with a JRE, instead of a full JDK, you can prevent the client from trying to generate and compile stubs by setting the system property djc.allowRuntimeCompile to false for the Java command that starts the client application.

6.3.2 Chapter 4, "Creating Application Clients"

(CR #472302) In the section "Starting the runtime container," this example for starting an application client's runtime container is incorrect:

```
runclient.sh -client my_appclient -login true
```

The correct syntax is:

run-appclient.sh -client my_appclient -login true

6.4 New Features Guide

(CR #493619) The introduction in the ".NET client support" section in the *EAServer 6.1 New Features Guide* is incorrect. The corrected introduction is:

EAServer 6.1 includes .NET client support, and enables IIOP/IIOPS communication between .NET and J2EE distributed objects in EAServer.

6.5 Security Administration and Programming Guide

6.5.1 Chapter 6, "Using TLS and FIPS"

(CR #474337) The section "SSL/TLS and FIPS Support" describes how to enable FIPS support, "Enabling FIPS using the Certicom Java libraries." Step 2 says to set the com.sybase.ejb.fips connection property to specify FIPS usage, but fails to specify the value. To enable FIPS support, set the value of com.sybase.ejb.fips to true; to disable, set the value to false.

6.6 System Administration Guide

6.6.1 Chapter 3, "Creating and Configuring Servers"

(CR #500334) The configuration property name for the Component property in Table 3-7 is incorrect. The correct property name is serviceComponents, as indicated below:

Property	Description
Component	The name of the component that implements the service.
	For a user-defined service component, enter either:
	• The class name of a simple Java class (must be in the server class path), or
	• The fully-qualified name of an EJB local or remote interface; for example,
	ejb.components.mypackage.MyCompLocal Or
	ejb.components.mypackage.MyCompRemote.
	The configuration property name is serviceComponents.

(CR #487210) By default, multiple users can start EAServer. However, to allow single user to start EAServer, configure EAServer with the shared-data-protection-off option. For example:

```
cd $EAServer/bin
configure.sh shared-data-protection-off
```

To allow multiple users to start EAServer, use the shared-data-protection-on option. For example:

```
cd $EAServer/bin
configure.sh shared-data-protection-on
```

(CR #473658) "Configuring system logging" describes how to customize the location of the system log files, but the name of the variable (DJC_JVM_ARGS) is incorrect. The correct variable is DJC_JVM_USER_ARGS; for example:

set DJC_JVM_USER_ARGS=\$DJC_JVM_USER_ARGS -Ddjc.logFile=/myserver/myserver.log
-Ddjc.logFileMaxSize=5m -Ddjc.logFileRotation=true

Note If you customize the location of the system log files, only the HTTP log is rotated; the server log is not.

6.6.2 Chapter 4, "Database Access"

The section that describes how to configure a database type fails to explain that if you define both a dataSourceClass and a driverClass, EAServer uses only the dataSourceClass value—see "Configuring a database type" on page 6 in this release bulletin.

Configuring data sources

(CR #531900) When using servers in a cluster, make sure these predefined data sources are all connected to the same database:

- cluster.db
- message.db
- tx_manager

You can change the data sources using the Management Console.

6.6.3 Chapter 12, "Command Line Tools"

deploy	(CR #475510) The documentation that states the deploy.sh command line tool includes an eas5naming option is incorrect. This option is not supported.
	(CR #475511) EAServer 6.2 does not support the -jsr154filter option for the deploy.sh command line tooljsr154filter may be supported in a later version of EAServer.
wlogin and wlogout	(CR #443144) The command line tools wlogin and wlogout support only this syntax:
	<pre>wlogin.sh <host:port> wlgout.sh <host:port></host:port></host:port></pre>

Chapter 12 incorrectly states that you can pass the server name if it is defined in the local repository.

6.6.4 Chapter 13, "JNI Compiler"

(CR #472818) Before calling a generated proxy class, standalone clients must call either:

- JNICC_CreateJavaVM to initialize the JVM, or
- JNICC_SetJavaVM(JavaVM* vm) if the JVM has already been initialized.

6.6.5 Chapter 14, "Systems Management"

(CR #437261) EAServer supports Simple Network Management Protocol (SNMP) features that conform to the Java Specification Request JSR 77. The status of a server and its components are reported as Management Information Base objects, which can be polled, and can also be reported as SNMP traps.

6.7 Troubleshooting Guide

6.7.1 Chapter 1, "Monitoring Techniques"

This example shows how to configure the *log4j.properties* file.

Configuring Log4j

1 Use a text editor to create a *log4j.properties* file.

```
# Set root category priority to INFO and its only appender to CONSOLE.
#log4j.rootCategory=FATAL, CONSOLE
log4j.rootCategory=DEBUG, LOGFILE
# Set the enterprise logger category to FATAL and its only appender to CONSOLE.
```

```
# Set the enterprise logger category to FATAL and its only appender to CONSOLE
# log4j.logger.org.apache.axis.enterprise=DEBUG, LOGFILE
```

```
# CONSOLE is set to be a ConsoleAppender using a PatternLayout.
log4j.appender.CONSOLE=org.apache.log4j.ConsoleAppender
log4j.appender.CONSOLE.Threshold=DEBUG
log4j.appender.CONSOLE.layout=org.apache.log4j.PatternLayout
log4j.appender.CONSOLE.layout.ConversionPattern=- %m%n
```

```
# LOGFILE is set to be a File appender using a PatternLayout.
log4j.appender.LOGFILE=org.apache.log4j.FileAppender
log4j.appender.LOGFILE.File=<install_directory>/axisserver.log
log4j.appender.LOGFILE.Append=true
log4j.appender.LOGFILE.Threshold=DEBUG
```

```
log4j.appender.LOGFILE.layout=org.apache.log4j.PatternLayout
log4j.appender.LOGFILE.layout.ConversionPattern=%-4r [%t] %-5p %c %x - %m%n
```

- 2 Put the *log4j.properties* file into *\$EAServer_Home/lib*.
- 3 Change to *\$EAServer_Home/bin* and execute:

```
run-server -
```

Dorg.apache.commons.logging.Log=org.apache.commons.logging.impl.Log4JLogger

4 Write a class named "Hello":

package sayhello;

```
public class Hello {
  public String hello() {
      return "hello";
    }
}
```

- 5 Use Sybase Web Services Toolkit to deploy this class as a Web service and generate a client.
- 6 Run Hello_ServiceTestClient.java.
- 7 Find the log file in *<install_directory>\aixsserver.log* and view the contents which should look similar to:

```
953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle -
loadBundle: Ignoring MissingResourceException: Can't find bundle for
base name org.apache.axis.resource, locale zh CN
953
    [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle
Created org.apache.axis.i18n.resource, linked to parent null
953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle -
getBundle(org.apache.axis,org.apache.axis.utils,resource,null,...)
953
    [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle -
loadBundle: Iqnoring MissingResourceException: Can't find bundle for
base name org.apache.axis.utils.resource, locale zh CN
953
    [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle
loadBundle: Iqnoring MissingResourceException: Can't find bundle for
base name org.apache.axis.resource, locale zh CN
953
    [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle - Root
package not found, cross link to org.apache.axis.i18n.resource
953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle - Root
package not found, cross link to org.apache.axis.i18n.resource
953 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle -
org.apache.axis.i18n.resource::handleGetObject(engineFactory)
1047 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle -
org.apache.axis.i18n.resource::handleGetObject(attachEnabled)
1063 [main] DEBUG org.apache.axis.i18n.ProjectResourceBundle -
org.apache.axis.i18n.resource::handleGetObject(oddDigits00)
```

6.8 Web Services Toolkit User's Guide

6.8.1 Chapter 9, "Using wstool and wstant"

(CR #464242) The Ant build example for the exposeComponent command is incorrect:

<wst_antTask command="exposeComponent"
entity="component:myPackage/myComponent"/>

The correct command is:

<wst_antTask command="exposeComponent"
entity="myPackage/myComponent"/>

7. Technical support

Each Sybase installation that has purchased a support contract has one or more designated people who are authorized to contact Sybase Technical Support. If you have any questions about this installation or if you need assistance during the installation process, ask the designated person to contact Sybase Technical Support or the Sybase subsidiary in your area.

8. Other sources of information

Use the Sybase Getting Started CD, the SyBooksTM CD, and the Sybase Product Manuals Web site to learn more about your product:

- The Getting Started CD contains release bulletins and installation guides in PDF format, and may also contain other documents or updated information not included on the SyBooks CD. It is included with your software. To read or print documents on the Getting Started CD, you need Adobe Acrobat Reader, which you can download at no charge from the Adobe Web site using a link provided on the CD.
- The SyBooks CD contains product manuals and is included with your software. The Eclipse-based SyBooks browser allows you to access the manuals in an easy-to-use, HTML-based format.

Some documentation may be provided in PDF format, which you can access through the PDF directory on the SyBooks CD. To read or print the PDF files, you need Adobe Acrobat Reader.

Refer to the *SyBooks Installation Guide* on the Getting Started CD, or the *README.txt* file on the SyBooks CD for instructions on installing and starting SyBooks.

The Sybase Product Manuals Web site is an online version of the SyBooks CD that you can access using a standard Web browser. In addition to product manuals, you will find links to EBFs/Maintenance, Technical Documents, Case Management, Solved Cases, newsgroups, and the Sybase Developer Network.

To access the Sybase Product Manuals Web site, go to Product Manuals at http://www.sybase.com/support/manuals/.

8.1 Sybase certifications on the Web

Technical documentation at the Sybase Web site is updated frequently.

Finding the latest information on product certifications

- 1 Point your Web browser to Technical Documents at http://www.sybase.com/support/techdocs/.
- 2 Click Certification Report.
- 3 In the Certification Report filter select a product, platform, and timeframe and then click Go.
- 4 Click a Certification Report title to display the report.
- * Finding the latest information on component certifications
 - 1 Point your Web browser to Availability and Certification Reports at http://certification.sybase.com/.
 - 2 Either select the product family and product under Search by Base Product; or select the platform and product under Search by Platform.
 - 3 Select Search to display the availability and certification report for the selection.

Creating a personalized view of the Sybase Web site (including support pages)

Set up a MySybase profile. MySybase is a free service that allows you to create a personalized view of Sybase Web pages.

- 1 Point your Web browser to Technical Documents at http://www.sybase.com/support/techdocs/.
- 2 Click MySybase and create a MySybase profile.

8.2 Sybase EBFs and software maintenance

- * Finding the latest information on EBFs and software maintenance
 - 1 Point your Web browser to the Sybase Support Page at http://www.sybase.com/support.
 - 2 Select EBFs/Maintenance. If prompted, enter your MySybase user name and password.
 - 3 Select a product.
 - 4 Specify a time frame and click Go. A list of EBF/Maintenance releases is displayed.

Padlock icons indicate that you do not have download authorization for certain EBF/Maintenance releases because you are not registered as a Technical Support Contact. If you have not registered, but have valid information provided by your Sybase representative or through your support contract, click Edit Roles to add the "Technical Support Contact" role to your MySybase profile.

5 Click the Info icon to display the EBF/Maintenance report, or click the product description to download the software.

9. Accessibility features

This document is available in an HTML version that is specialized for accessibility. You can navigate the HTML with an adaptive technology such as a screen reader, or view it with a screen enlarger.

EAServer and the HTML documentation have been tested for compliance with U.S. government Section 508 Accessibility requirements. Documents that comply with Section 508 generally also meet non-U.S. accessibility guidelines, such as the World Wide Web Consortium (W3C) guidelines for Web sites.

The online help for this product is also provided in HTML, which you can navigate using a screen reader.

For information on using EAServer without a mouse, see "Keyboard navigation" in Chapter 2, "Management Console Overview," in the *EAServer System Administration Guide*.

Note You might need to configure your accessibility tool for optimal use. Some screen readers pronounce text based on its case; for example, they pronounce ALL UPPERCASE TEXT as initials, and MixedCase Text as words. You might find it helpful to configure your tool to announce syntax conventions. Consult the documentation for your tool.

For information about how Sybase supports accessibility, see Sybase Accessibility at http://www.sybase.com/accessibility. The Sybase Accessibility site includes links to information on Section 508 and W3C standards.

For a Section 508 compliance statement for EAServer, go to Voluntary Product Assessments at http://www.sybase.com/detail_list?id=52484, and click the link for EAServer.